

How to mount a File share of your Azure Storage Account to your Virtual Machine or in Enterprise Product to your Nucleus Laptop

For Voyager (without cnDTAG Connect)

- Create Storage Account
- Create private Endpoint with an IP out of your cnDTAG IP Range (Networking)
- In the Settings of your private Endpoint, create an Application Security Group (e.g. <asg-storage>)
- Create the File share
- Add Inbound NSG Rule
Add a NSG rule to your <nsg-defaultnetworking> - Allow Inbound from VNet to ASG <asg-storage> Port 445 TCP.
- Mount the Azure File share with File Explorer:

<https://learn.microsoft.com/en-us/azure/storage/files/storage-how-to-use-files-windows>

- Map Network drive on your VM
path to mount the File share to an Azure VM can be find in the properties of your File share in the Storage Account
- Copy the URL without <https:> and change slashes '/' to backslashes '\'
\\storageAccountName>.file.core.windows.net\<fileShareName>
- Use different Account
- Username: Storage Account Name
Password: Storage Account Access Key (key1 or key2)

Enterprise (with cnDTAG connection):

In addition to mentioned steps for Voyager, File share can also be mounted to the Nucleus Company Laptop.

- Add an A-Record to your private DNS zone <dtit_cidxxxx.azcloud.telekom.de>. It is located in the resource group rg-ci-vnet.
Name of the Storage Account and IP of the private Endpoint
- Reach out for the Azure Landingzone Team to add a CNAME entry in the centralized private DNS zone for file <privatelink.file.core.windows.net>.
- Open Pannet Firewall with the Excel Template. Rule for Inbound from Source 10.0.0.0/8 to Target IP private Endpoint of Storage Account, Port 445 TCP.
- Add Inbound NSG rule to your <nsg-defaultnetworking> - Allow Inbound from Source 10.0.0.0/8 to Target ASG <asg-storage> Port 445 TCP.

- Map Network drive on your VM
path to mount the File share to your Nucleus Laptop:
\\storageAccountName.dtitcidxxxx.azcloud.telekom.de\<fileShareName>
- Use different Account
- Username: Storage Account Name
 Password: Storage Account Access Key (key1 or key2)

[#azure](#) [#azurecloud](#) [#storage](#) [#storageaccount](#) [#mountfileshare](#)