Physikalisches Grundpraktikum 1 für Bachelor in Gruppen: Zustandsgleichung realer Gase

Leon Heiß, Paul Hildebrandt Kurs 5, Gruppe 7, Team 19

Technische Universität München 10. Mai 2022

Abstract

This experiment deals with the properties of real gases, which depend on the temperature, the exerted pressure and the volume and can be represented visually in the form of isotherms. The critical point and the vapor pressure of a gas can then be determined by examining the graphs of the isotherms. In this experiment, this is done using sulfur hexafluoride as an example.

Contents

1	Theory Real gases	2 2 2 3
2	Experiment Setup	3 3 4
3	Measurements for determining amount of substance	4
	Calculating amount of substance Principle Error Propagation Extrapolation	4 4 5 5
J	Molar Volume	5 6 6
6	State of aggregation	6
7	Van der Waals equation	6
8	Vapor pressure	8
9	Comparison with literature	9
10	Fluctuation of pressure	10
11	Attachments	10

1 Theory

Gases under standard conditions can be described using simple linear relations. By using the equation of state for ideal gases:

$$p \cdot V = n \cdot R \cdot T = N \cdot k_b \cdot T,\tag{1}$$

with pressure p [Pa], volume V [m³], temperature T [K], amount of substance n [mol], molar gas constant R = 8,314462618... $\frac{\text{J}}{\text{mol K}}$, number of particles N [1] and Boltzmann constant $k_B = 1,380649 \cdot 10^{-23} \frac{\text{J}}{\text{K}}$, we can describe the behaviour of gases, where molecular interactions and the individual sizes of the atoms and molecules can be neglected. We also define the molar volume V_m , which is the volume occupied by one mole of a substance:

$$V_m = \frac{V}{n} = \frac{R \cdot T}{p}.\tag{2}$$

At higher temperature and pressure, these approximations become insufficiently precise and therefore real gases must be described using a different approach, focusing more on microscopic effects.

Real gases If a gas cannot be approximated as an ideal gas, the Van der Waals equation can be used:

$$\left(p + \left(\frac{n}{V}\right)^2 \cdot a\right) \cdot (V - n \cdot b) = n \cdot R \cdot T,\tag{3}$$

or

$$\left(p + \frac{a}{V_m^2}\right) \cdot (V_m - b) = R \cdot T. \tag{4}$$

The so-called internal pressure $(\frac{n}{V})^2 \cdot a$ takes into account the (dipole) interaction between the particles through the variable a. The variable b denotes the so-called co-volume, i.e. the volume that one mole of a gas would occupy in its densest spherical form. This gives the effectively compressible volume V_{eff} :

$$V_{eff} = V - n \cdot b. (5)$$

The effective pressure on the particles in the gas interior is calculated with:

$$p_{eff} = p + \left(\frac{n}{V}\right)^2 \cdot a. \tag{6}$$

Isotherms The curves obtained by plotting the pressure against the corresponding volume for a certain temperature are called isotherms. Figure 1 shows the course of several such Isotherms shown. According to




Figure 1: Van-der-Waals Isotherms, taken from the instructions [4]

Equation 3, the curves at low temperatures have two extremes and an inflection point. In reality, however,

the pressure in the area around the extrema remains constant. At the so-called critical point, the maximum, minimum and turning point coincide. The measurements at this point are called critical pressure p_{crit} , critical volume V_{crit} and critical temperature T_{crit} . Here both the first and second derivatives of pressure with respect to volume are equal to zero:

$$\left(\frac{\delta p}{\delta V}\right)_{T_{krit}, V_{krit}, p_{krit}} = 0,$$
(7)

$$\left(\frac{\delta p}{\delta V}\right)_{T_{krit}, V_{krit}, p_{krit}} = 0,$$

$$\left(\frac{\delta^2 p}{\delta V^2}\right)_{T_{krit}, V_{krit}, p_{krit}} = 0.$$
(8)

Applying equations 7 and 8 to the Van der Waals equation 3 gives the following relationships for the critical volume and p_{crit} :

$$V_{krit} = 3 \cdot b \cdot n \tag{9}$$

$$p_{krit} = \frac{a}{27 \cdot b^2}. ag{10}$$

Vapor pressure The area under the dashed function in Figure 1 is called the coexistence region, where gas and liquid both coexist. Its boundary values are called gas volume V_q and liquid volume V_{lq} . In the coexistence region, with a temperature-dependent constant vapor pressure p_d , more and more gas is converted into liquid with decreasing volume. In contrast, at $T > T_{crit}$ no more liquid is produced, no matter the pressure, and the gas can be assumed to be ideal. The slope of the dashed vapor pressure curve $p_d(T)$ in Figure 1 depends on the so-called vaporization enthalpy L:

$$\frac{dp_d}{dT} = \frac{L}{T \cdot (V_g - V_{lq})}. (11)$$

2 Experiment

Setup The gas under study is sulfur hexafluoride. It is filled inside a cylinder and can be compressed with mercury, that is forced into the cylinder from the bottom. The detailed experimental setup is depicted in Figure 2. The pressure put on the mercury can be read using a pressure gauge which has an estimated resolution of




Figure 2: Experimental setup, taken from the instructions [4]

25000 Pa. The level of mercury can be read from a scale with an estimated resolution of 0.05 cm³. As shown in figure 3, the surface of the mercury is not flat. With both rising and falling level, a dome shaped surface forms. Because of this, the level can not be measured directly at the upper edge (1) of the mercury. Instead it is measured at roughly $\frac{1}{3}$ the distance (3) between the upper edge touching the cylinder (1) and the top of the




Figure 3: Error resulting from round surface

dome (2) since

$$\frac{1}{4}V_{sphere}(r) = V_{Cylinder}(r,h) \cdot h \tag{12}$$

$$\frac{1}{3}r^3 = h^2 \cdot h \tag{13}$$

$$h = \frac{1}{3}r\tag{14}$$

This error is only taken into account during the experiment. It is not discussed any further during calculation. As implied in figure 1, the cylinder filled with gas and mercury is surrounded by a cylinder filled with water. The water, and thereby the gas and mercury can be tempered using a thermostat with an accuracy of 0.1°C.

Measurement The same experiment is performed for different temperatures. Our group measured values for 30°C , 40°C and $52,5^{\circ}\text{C}$. First, the water is brought to the target temperature. Next, the volume is decreased in $0.25~\text{cm}^3$ steps. After each reduction, and especially with low volume, the pressure needs a few seconds to settle at a value. When decreasing the volume, the pressure is initially higher than the final value and vice versa with increasing volume. The decrease of volume is stopped before the pressure reaches the maximum pressure of the gauge at $5 \cdot 10^6 Pa$. After reaching maximum pressure, the volume is increased in $0.25~\text{cm}^3$ steps. This produces two values for the pressure at a certain volume and temperature. All further calculations use the arithmetic mean of the two measured pressures whenever pressure is needed for some calculation.

3 Measurements for determining amount of substance

Using the same setup as described before, we perform some measurements in order to determine the amount of substance later on. With some data from the data sheet [1] of sulfur hexafluoride, we can estimate, what temperature we need to choose in order to measure within a reasonably linear relation between pressure and volume. In this case, the temperature 52,5°C was chosen since we already performed a measurement at this temperature and it is above the critical point. In order to receive good data, the measurements for this task are performed at big volumes with small changes of volume (0,1 ml) between each measurement.

No separate measurement was performed. Instead, the measurements at 52,5°C from the previous task were performed with smaller changes in said interval.

4 Calculating amount of substance

Principle In order to determine the molar amount of gas inside the test tube, we assume an ideal gas for further evaluation. With lower density of the gas, this approximation is more accurate. As previously stated, an ideal gas is described by

$$N = \frac{p \cdot V}{k_B \cdot T},\tag{15}$$

where N describes the number of particles. Since we can only experiment with a finite volume, we extrapolate values for $p \cdot V$ by letting $V \to \infty$, thus calculating with an infinitely low density. We can determine an approximation for $p \cdot V$ by plotting $\frac{1}{V}$ against $p \cdot V$ and extrapolating the curve to $\frac{1}{V} = 0$.

Error Propagation The value of $p \cdot V$ cannot be measured directly. Its uncertainty must be calculated by combining the uncertainties of measured values into a total uncertainty

$$u(p,V) = \sqrt{\frac{\delta(p \cdot V)^2}{\delta p} \cdot (\Delta p)^2 + \frac{\delta(p \cdot V)^2}{\delta V} \cdot (\Delta V)^2} = \sqrt{V^2 \cdot (\Delta p)^2 + p^2 \cdot (\Delta V)^2}$$
(16)

where Δp and ΔV are the uncertainties needed to be combined and u(p, V) is the resulting uncertainty. Note that the uncertainty now also depends on the values p and V of the measurement.

The uncertainty of the inverse volume must also be determined. In general, uncertainty for a function of the form f(x) at a distance of Δx from x is given by

$$|\Delta f| = \left| \frac{df}{dx} \right| \cdot |\Delta x| \tag{17}$$

For $f(x) = x^{-1}$, this results in

$$\left|\frac{d}{dx}x^{-1}\right| \cdot |x| = \left|\frac{1}{x}\right| \tag{18}$$

Thereby, the ratio of uncertainty is the same for V and V^{-1} .

$$u_r(\frac{1}{V}) = u_r(V) = \frac{V + \Delta V}{V} - 1 = \frac{\Delta V}{V}$$

$$\tag{19}$$

For the uncertainty of the measurement value follows

$$u(\frac{1}{V}) = u_r(\frac{1}{V}) \cdot V^{-1} = \frac{\Delta V}{V^2}$$
 (20)

Extrapolation In this case, the values for $\frac{1}{V}$ are represented by the x-axis. Performing a linear fit, for $x \to 0$ we receive $y \to 7.316(0.028)$ [Pa·m³]

Using the relation

$$n = \frac{N}{N_A} \tag{21}$$

with n being the the molar amount and $N_A = 6.02214076 \cdot 10^{23} \cdot \frac{1}{\text{mol}}$ being the Avogadro-constant, we can calculate

$$n = \frac{7.316(0.028) \text{Pa} \cdot \text{m}^3}{\frac{1.380649 \cdot 10^{-23} \frac{\text{J}}{\text{K}} \cdot 325.65 \text{K}}{6.02214076 \cdot 10^{23} \cdot \frac{1}{\text{mol}}}} \approx 2.702(0.010) \text{ mmol}$$
(22)

5 Isotherms

Molar Volume In order to compare measurements from different set-ups, the molar volume is useful since measurements with different amounts of gas can be directly compared. The molar volume can be calculated from the amount of substance n and the volume V at a certain pressure p.

$$V_m(p) = \frac{V(p)}{n} \tag{23}$$




Figure 4: Linear fit for extrapolation of volume $\rightarrow \infty$

Error Propagation The already known errors for V and n are combined using the known formula from equation (2).

$$u(V,n) = \sqrt{(\frac{1}{n})^2 \cdot (\Delta V)^2 + (\frac{V}{n^2})^2 \cdot (\Delta n)^2}$$
 (24)

The resulting values and errors fit the expected curves. Unfortunately, there is no recorded data available for when liquid starts forming unless for the dataset of 40°C. This is partly due to lack of documentation and partly due to missing data from other groups.

Graph The data in Figure 4 roughly looks as expected. At closer inspection, one can see that some of the lines cross each other, which is unexpected. Higher temperature should always result in a higher positioned line. This anomaly is probably due to calculation or measurement error.

6 State of aggregation

As stated, no sufficient data about when the probe became a liquid was collected or handed out by the other groups. It can only be estimated by analyzing the slope of the lines. For figure 3, the points where the graph changes slope drastically, are used to define the transition of state of aggregation.

7 Van der Waals equation

Figure 6 shows the isotherms for sulfur hexafluoride SF6 with the limit curve for the coexistence region. We can observe that only at T = 50°C no constant pressure ranges occur. We can conclude that T_{crit} for SF6 is somewhere between 43°C and 50°C. In fact, the literature value for T_{crit} is 45.55°C.[1] We then approximated




Figure 5: Pressure of molar volume at different temperatures




Figure 6: State of aggregation at different pressures and temperatures

a limit curve for the mixed region and found a maximal, giving us the critical molar volume $V_{m,crit}=0,25(0,05)$ l/mol and critical pressure $p_{crit}=3,55(0,05)\cdot 10^6$ Pa. With the critical values we can

now calculate the co-volume \mathbf{b} and variable \mathbf{a} of the internal pressure for a single particle and 1 mol. By rearranging the following two formulas from earlier:

$$V_{krit} = 3 \cdot b \cdot n$$
$$p_{krit} = \frac{a}{27 \cdot b^2}$$

and remembering that V_{krit} is a molar volume we get

	amount [mol]	particles [1]
$a \left[\text{Pa} \cdot \text{l}^2/\text{mol}^2 \right]$	$(6,13\pm0,09)\cdot10^5$	$(1,79\pm0,12)\cdot10^{-47}$
b [l/mol]	$0,08 \pm 0,02$	$(1,38\pm0,28)\cdot10^{-25}$

8 Vapor pressure

In order to calculate the vapor pressure from the measured isotherms, the mean value of all pressures that lie in between the coexistence region of gas and liquid shown in Figure 6 is calculated for each temperature. If you now plot the vapor pressure $p_d(T)$ on a logarithmic scale against the reciprocal of the temperature 1/T and fit an exponential function, you get Figure 8.




Figure 7: Vapor pressure against the reciprocal of temperature

The semi logarithmically fitted exponential function is of the form

$$p_d(T) = e^{k-A \cdot \frac{1}{T}} \tag{25}$$

which, plotted semi-logarithmically results in

$$A = -\frac{dp_d}{d\frac{1}{T}} \tag{26}$$

with $A=-576\pm231$. Inserting this value into

$$L = \frac{-A \cdot p_d \cdot (V_g - V_{fl})}{T} \tag{27}$$

, derived from formula 9 of the instructions [4], we obtain

T[K]	$p_d[MPa]$	$V_g - V_{fl}[dm^3]$	$L[\frac{kJ}{mol}]$	$u(l)[\frac{kJ}{mol}]$
298,25	2,42	0,431	2014	809
303,15	2,45	0,426	1983	796
308,35	2,81	0,380	1994	801
310,75	2,95	0,357	1952	784
313,15	2,99	0,311	1710	687
316,05	2,79	0,268	1362	548

The uncertainty u(L) is calculated using

$$u(L) = \sqrt{\frac{p_d \cdot \Delta V^2}{T} \cdot u(A)^2 + \frac{A \cdot \Delta V^2}{T} \cdot u(p_d)^2 + \frac{A \cdot p_u^2}{T} \cdot u(\Delta V)^2 + \frac{A \cdot p_d \cdot \Delta V^2}{T^2} \cdot u(T)^2}$$
(28)

Looking at Figure 8, one observes that enthalpy becomes lower with higher temperature.




Figure 8: Enthalpy of vaporization at different temperatures

9 Comparison with literature

•	Literature	Our result
V_{krit}	0,198 l/mol [3]	0,25(0,05) l/mol
p_{krit}	$3,7590 \cdot 10^6 \text{ Pa}$	$3,55(0,05) \cdot 10^6 \text{Pa}$
a	$7.857 \cdot 10^5 \text{ Pa} \cdot \text{l}^2/\text{mol}^2 [2]$	$6.13(0.09) \cdot 10^5 \text{ Pa} \cdot \text{ l}^2/\text{mol}^2$
b	0,0879 l/mol [2]	0.08(0.02) l/mol
L	22,37 kJ/mol [2]	see above

Taking into account the uncertainty, the critical volume is slightly above the literature value. Since the measurement quality of all groups effect this value, an error is hard to spot. During the measurements hardly any notes were taken about the aggregation state of the substance. This lead us to guess it based on the graphs. Obviously, this renders the according calculations inaccurate. These inaccuracies propagate through the values a and b. For L, no real explanations for results in another order of magnitude are obvious to us. Nevertheless, Figure 8 looks as expected: with higher temperature, the enthalpy of vaporization becomes lower.

10 Fluctuation of pressure

After every change of volume, pressure fluctuations continued to occur for a short time. Therefore we waited a few seconds after each change before reading the final pressure on the manometer. The reason for this anomaly is that the gas is no longer in thermal equilibrium after the pressure change. The increase in volume not only increases the pressure but also the temperature of the gas. It then takes a short time for the gas to be cooled down or heated up again by the water, which is kept at the target temperature by the thermostat. When changing temperature at constant volume, the pressure also changes.

11 Attachments

Protocol

References

- [1] Messer Schweiz AG, Datenblatt Schwefelhexafluorid URL: https://www.messer.ch/documents/2227840/4121563/Schwefelhexafluorid.pdf/ 47b9120b-e052-966e-3b35-527e7df3ed04?t=1595841860760
- [2] Ph.D. W.M. Haynes, Handbook of Chemistry and Physics, CRC Press., ISBN: 978-1-4822-0868-9.
- [3] U.S. Secretary of Commerce, NIST Chemistry WebBook, Sulfur hexafluoride datasheet **URL:** https://webbook.nist.gov/cgi/cbook.cgi?ID=C2551624&Mask=4
- [4] Fakultät für Physik. Zustandsgleichung realer Gase (ZUS. Technische Universität München. 10.05.2022) URL: https://www.ph.tum.de/academics/org/labs/ap/ap1/ZUS.pdf

Physikalisches Grondpraktikum I: ZUS

1 308 (+0,1)			
Volumen [m] (+0,05)	Druck [bar] (+)	0,25) 0	105 Gas
4,00	14,00	14,00	- 06ese Konte
3,75	14,75	15,00	/ Quecksiber
3,50	15,75	15,75	Hohe Eylinder:
3,25	16,75	16,75	
300	17,75	18,00	Bei sinkenden Pagel nahe 20 Warne Wolsong
2,75	19,00	19,00	Laurie Worsong
\$2,50	20,50	20,50	liblea Soulla
2.25	21,75	22,00	linke Spalle Druck: aufsleiged
2,00	23,50	23,00	Messing teelts
1,75	25,00	23,50	
1,50	25,00	24,00	
1,40	25,00	24,00	
1,30	25,00	24,25	
1,20	25,00	24.50	
1,10	25,00	24,50	
1,00	25,00	24,25	
0,90	25,00	24,25	
0,80	25,50	24,50	
0,70	25,50	24,50	
0,60	25,75	24,50	
0,50	26,00	25,00	
0,40	20,25		25,50

12 400 (±0,1) Valuer [m] (±0,05) 4,00 3,75 3,50 2,25 2,00 1,75 1,50 1,40 1,30 1,20 1,10 1,00 0,90 0,8 0,7 0,8 0,9	Droda [6as 14, 75 15, 75 16, 75 19, 00 20,50 21, 75 23, 50 25, 50 27, 50 29, 50 30, 25 31, 60 31, 75 31, 75 31, 75 32,00 32,00 32,00 32,00 32,25 40,00	(10 00)	Schickt Flussicheit 30,75

21 24 21 127 62 620 (+0		Huget Hock	n-runter cedrent damit	
51,8:01 3 32,3 6010,1)			
volumen Em	13(±0,05)	Druck [b	par] (±0,25)	
4,00 3,90 3,80 3,60 3,60 3,40 3,30 3,20 3,10 3,00 2,90 2,80		0 ruck [b	16,00 16,50 16,75 17,25 17,75 18,25 18,50 19,00 19,50 20,00 20,75 21,25 21,75	estent