Understanding IAM Custom Roles

Cloud IAM also provides the ability to create customized Cloud IAM roles. You can create a custom Cloud IAM role with one or more permissions and then grant that custom role to users. Cloud IAM provides a UI and API for creating and managing custom roles.

Key Point: Custom roles enable you to enforce the principle of least privilege, ensuring that the user and service accounts in your organization have only the permissions essential to performing their intended functions.

Note: You can create a custom role at the organization level and at the project level. However, you cannot create custom roles at the folder level.

You create a custom role by combining one or more of the available Cloud IAM permissions. Permissions allow users to perform specific actions on Google Cloud resources.

In the Cloud IAM world, permissions are represented in the form:

<service>.<resource>.<verb>

content copy

For example, the compute.instances.list permission allows a user to list the Compute Engine instances they own, while compute.instances.stop allows a user to stop a VM.

Permissions usually, but not always, correspond 1:1 with REST methods. That is, each Google Cloud service has an associated permission for each REST method that it has. To call a method, the caller needs that permission. For example, the caller of topic.publish() needs the pubsub.topics.publish permission.

Custom roles can only be used to grant permissions in policies for the same project or organization that owns the roles or resources under them. You cannot grant custom roles from one project or organization on a resource owned by a different project or organization.

Required permissions and roles

To create a custom role, a caller must have the iam.roles.create permission.

Users who are not owners, including organization administrators, must be assigned either the Organization Role Administrator role (roles/iam.organizationRoleAdmin) or the IAM Role Administrator role (roles/iam.roleAdmin). The IAM Security Reviewer role (roles/iam.securityReviewer) enables the ability to view custom roles but not administer them.

The custom roles user interface is in the Cloud Console under IAM Roles. It is only available to users who have permissions to create or manage custom roles. By default, only project owners can create new roles. Project owners can control access to this feature by granting IAM Role Administrator role to others on the same project; for organizations, only Organization Administrators can grant the Organization Role, Administrator role.

Preparing to create a custom role

Before you create a custom role, you might want to know:

- •What permissions can be applied to a resource
- •What roles are grantable on a resource
- •What a role's metadata is

Viewing the available permissions for a resource

Before you create a custom role, you might want to know what permissions can be applied to a resource. You can get all permissions that can be applied to a resource, and the resources below that in the hierarchy, using the gcloud command-line tool, the Cloud Console, or the IAM API. For example, you can get all permissions that you can apply on an organization and on projects in that organization.

Run the following to get the list of permissions available for your project.

```
gcloud iam list-testable-permissions
//cloudresourcemanager.googleapis.com/projects/$DEVSHELL_PROJECT_ID
content_copy
(Output)
```

```
name: appengine.applications.create
stage: GA
---
name: appengine.applications.get
stage: GA
---
name: appengine.applications.update
stage: GA
---
name: appengine.instances.delete
stage: GA
---
name: appengine.instances.get
stage: GA
---
name: appengine.instances.get
stage: GA
---
customRolesSupportLevel: TESTING
name: appengine.memcache.addKey
```

stage: BETA
--customRolesSupportLevel: TESTING
name: appengine.memcache.flush
stage: BETA
--content_copy

Getting the role metadata

Before you create a custom role, you might want to get the metadata for both predefined and custom roles. Role metadata includes the role ID and permissions contained in the role. You can view the metadata using the Cloud Console or the IAM API.

To view the role metadata, use command below, replacing [ROLE_NAME] with the role. For example: roles/viewer or roles/editor

gcloud iam roles describe [ROLE_NAME] content_copy

Example Outptut (for roles/viewer):

```
description: Read access to all custom roles in the project.
etag: AA==
includedPermissions:
- iam.roles.get
- iam.roles.list
- resourcemanager.projects.get
- resourcemanager.projects.getlamPolicy
...
...
name: roles/iam.roleViewer
stage: GA
```

title: Role Viewer content copy

Viewing the grantable roles on resources

Use the gcloud iam list-grantable-roles command to return a list of all roles that can be applied to a given resource.

Execute the following gcloud command to list grantable roles from your project:

gcloud iam list-grantable-roles //cloudresourcemanager.googleapis.com/projects/\$DEVSHELL_PROJECT_ID content_copy

Your output will look something like this:

```
description: Full management of App Engine apps (but not storage).

name: roles/appengine.appAdmin

title: App Engine Admin

description: Ability to view App Engine app status.

name: roles/appengine.appViewer

title: App Engine Viewer

description: Ability to view App Engine app status and deployed source code.

name: roles/appengine.codeViewer

title: App Engine Code Viewer

title: App Engine Code Viewer

...

...

content_copy
```

Creating a custom role

To create a custom role, a caller must possess iam.roles.create permission. By default, the owner of a project or an organization has this permission and can create and manage custom roles.

Users who are not owners, including organization admins, must be assigned either the Organization Role Administrator role, or the IAM Role Administrator role.

Use the gcloud iam roles create command to create new custom roles. You can use this command in two ways:

- •By providing a YAML file that contains the role definition
- •By using flags to specify the role definition When creating a custom role, you must specify whether it applies to the organization level or project level by using the --organization [ORGANIZATION_ID] or --project [PROJECT_ID] flags. Each example below creates a custom role at the project level. In the exercises to follow you'll create custom roles at the project level.

To create a custom role using a YAML file

Create a YAML file that contains the definition for your custom role. The file must be structured in the following way:

title: [ROLE_TITLE]
description: [ROLE_DESCRIPTION]
stage: [LAUNCH_STAGE]
includedPermissions:
- [PERMISSION_1]
- [PERMISSION_2]
content_copy

Each of the placeholder values is described below:

- •[ROLE TITLE] is a friendly title for the role, such as **Role Viewer**.
- •[ROLE_DESCRIPTION] is a short description about the role, such as **My custom** role description.
- •[LAUNCH_STAGE] indicates the stage of a role in the launch lifecycle, such as ALPHA, BETA, or GA.
- •includedPermissions specifies the list of one or more permissions to include in the custom role, such as **iam.roles.get**.

Time to get started! Create your role definition YAML file by running:

nano role-definition.yaml

content copy

Add this custom role definition to the YAML file:

title: "Role Editor"

description: "Edit access for App Versions"

stage: "ALPHA"

includedPermissions:

- appengine.versions.create
- appengine.versions.delete

content copy

Then save and close the file by pressing Ctrl+X, Y and then Enter.

Execute the following gcloud command:

gcloud iam roles create editor --project \$DEVSHELL PROJECT ID \

--file role-definition.yaml

content copy

If the role was created successfully, the following response is returned:

Created role [editor].

description: Edit access for App Versions

etag: BwVs4O4E3e4= includedPermissions:

appengine.versions.create

- appengine.versions.delete

name: projects/[PROJECT ID]/roles/editor

stage: ALPHA title: Role Editor content copy

Click Check my progress to verify the objective.

Create a custom role using flags

Now you'll use the flag method to create a new custom role. The flags take a similar form to the YAML file, so you'll recognize how the command is being built.

Execute the following gcloud command to create a new role using flags:

gcloud iam roles create viewer --project \$DEVSHELL_PROJECT_ID \
--title "Role Viewer" --description "Custom role description." \
--permissions compute.instances.get,compute.instances.list --stage ALPHA
content_copy
sample output:

Created role [viewer].

description: Custom role description.

etag: BwVs4PYHqYI= includedPermissions:

- compute.instances.get

- compute.instances.list

name: projects/[PROJECT_ID]/roles/viewer

stage: ALPHA title: Role Viewer <u>cont</u>ent copy

Click Check my progress to verify the objective.

Listing the custom roles

Execute the following gcloud command to list custom roles, specifying either project-level or organization-level custom roles:

content copy

Example Output:

description: Edit access for App Versions

etag: BwVxLgrnawQ=

name: projects/[PROJECT_ID]/roles/editor

title: Role Editor

description: Custom role description.

etag: BwVxLg18IQg=

name: projects/[PROJECT_ID]/roles/viewer

title: Role Viewer content copy

To list deleted roles, you can also specify the --show-deleted flag.

Execute the following gcloud command to list predefined roles:

gcloud iam roles list content copy

Editing an existing custom role

A common pattern for updating a resource's metadata, such as a custom role, is to read its current state, update the data locally, and then send the modified data for writing. This pattern could cause a conflict if two or more independent processes attempt the sequence simultaneously.

For example, if two owners for a project try to make conflicting changes to a role at the same time, some changes could fail.

Cloud IAM solves this problem using an etag property in custom roles. This property is used to verify if the custom role has changed since the last request. When you make a request to Cloud IAM with an etag value, Cloud IAM

compares the etag value in the request with the existing etag value associated with the custom role. It writes the change only if the etag values match.

Use the gcloud iam roles update command to update custom roles. You can use this command in two ways:

- •By providing a YAML file that contains the updated role definition
- •By using flags to specify the updated role definition

When updating a custom role, you must specify whether it applies to the organization level or project level by using the --organization [ORGANIZATION_ID] or --project [PROJECT_ID] flags. Each example below creates a custom role at the project level.

The describe command returns the role's definition and includes an etag value that uniquely identifies the current version of the role. The etag value should be provided in the updated role definition to ensure that any concurrent role changes are not overwritten.

To update a custom role using a YAML file

Get the current definition for the role by executing the following gcloud command, replacing [ROLE ID] with **editor**.

gcloud iam roles describe [ROLE_ID] --project \$DEVSHELL_PROJECT_ID
content copy

The describe command returns the following output:

description: [ROLE_DESCRIPTION]
etag: [ETAG_VALUE]
includedPermissions:
- [PERMISSION_1]
- [PERMISSION_2]
name: [ROLE_ID]
stage: [LAUNCH_STAGE]
title: [ROLE_TITLE]
content_copy

You'll create a new YAML file with the outputted value. Copy the output from this command.

Create a new-role-definition.yaml file with your editor.

nano new-role-definition.yaml

content copy

Paste in the outputted value from the last command and add these two permissions under includedPermissions:

- storage.buckets.get
- storage.buckets.list

content copy

Your YAML file will look like this when you're finished:

description: Edit access for App Versions

etag: BwVxIAbRq_I= includedPermissions:

- appengine.versions.create

- appengine.versions.delete
- storage.buckets.get
- storage.buckets.list

name: projects/[PROJECT ID]/roles/editor

stage: ALPHA title: Role Editor content copy

Save and close the file **Ctrl+X**, **Y** and then **Enter**.

Now you'll use the update command to update the role. Execute the following gcloud command, replacing [ROLE_ID] with **editor**:

gcloud iam roles update [ROLE_ID] --project \$DEVSHELL_PROJECT_ID \

--file new-role-definition.yaml

content_copy

If the role was updated successfully, the following response is returned:

description: Edit access for App Versions

etag: BwVxIBjfN3M= includedPermissions:

- appengine.versions.create
- appengine.versions.delete
- storage.buckets.get

- storage.buckets.list

name: projects/[PROJECT_ID]/roles/editor

stage: ALPHA title: Role Editor content copy

Click Check my progress to verify the objective.

To update a custom role using flags

Each part of a role definition can be updated using a corresponding flag. See the <u>gcloud iam roles update</u> topic for a list of all possible flags.

You can use the following flags to add or remove permissions:

- •--add-permissions: Adds one or more comma-separated permissions to the role.
- •--remove-permissions: Removes one or more comma-separated permissions from the role.

Alternatively, you can simply specify the new permissions using the -permissions [PERMISSIONS] flag and providing a comma-separated list of permissions to replace the existing permissions list.

Execute the following gcloud command to add permissions to the **viewer** role using flags:

--add-permissions storage.buckets.get,storage.buckets.list

content copy

If the role was updated successfully, the following response is returned:

description: Custom role description.

etag: BwVxLi4wTvk=

includedPermissions:

- compute.instances.get
- compute.instances.list

- storage.buckets.get

- storage.buckets.list

name: projects/[PROJECT_ID]/roles/viewer

stage: ALPHA title: Role Viewer content copy

Click Check my progress to verify the objective.

Disabling a custom role

When a role is disabled, any policy bindings related to the role are inactivated, meaning that the permissions in the role will not be granted, even if you grant the role to a user.

The easiest way to disable an existing custom role is to use the --stage flag and set it to DISABLED.

Execute the following gcloud command to disable the **viewer** role:

gcloud iam roles update viewer --project \$DEVSHELL_PROJECT_ID \
--stage DISABLED
content_copy

If the role was updated successfully, the following response is returned:

description: Custom role description.

etag: BwVxLkIYHrQ=

includedPermissions:

- compute.instances.get
- compute.instances.list
- storage.buckets.get
- storage.buckets.list

name: projects/[PROJECT_ID]/roles/viewer

stage: DISABLED

title: Role Viewer
content copy

Click Check my progress to verify the objective.

Deleting a custom role

Use the gcloud iam roles delete command to delete a custom role. Once deleted the role is inactive and cannot be used to create new IAM policy bindings.

gcloud iam roles delete viewer --project \$DEVSHELL_PROJECT_ID content copy

Example Output:

description: Custom role description.

etag: BwVxLkf_epw=

includedPermissions:

- compute.instances.get
- compute.instances.list
- storage.buckets.get
- storage.buckets.list

name: projects/[PROJECT_ID]/roles/viewer

stage: DISABLED title: Role Viewer content copy

After the role has been deleted, existing bindings remain, but are inactive. The role can be undeleted within 7 days. After 7 days, the role enters a permanent deletion process that lasts 30 days. After 37 days, the Role ID is available to be used again.

Note: If a role is being phased out, change its **role.stage** property to **DEPRECATED**, and set the deprecation_message to let users know what alternative roles should be used or where to get more information.

Undeleting a custom role

Within the 7 days window you can undelete a role. Deleted roles are in a **DISABLED** state. You can make it available again by updating the -- stage flag:

gcloud iam roles undelete viewer --project \$DEVSHELL_PROJECT_ID content copy

Click Check my progress to verify the objective.

Congratulations



Finish Your Quest

This self-paced lab is part of the Qwiklabs <u>Security & Identity</u>

<u>Fundamentals</u> Quest. A Quest is a series of related labs that form a learning path. Completing this Quest earns you the badge above, to recognize your achievement. You can make your badge (or badges) public and link to them in your online resume or social media account. <u>Enroll in this Quest</u> and get immediate completion credit if you've taken this lab. <u>See other available</u> Owiklabs Quests.

Take Your Next Lab

Continue your Quest with **Getting Started with Cloud KMS** or try one of these:

- •Service Accounts and Roles: Fundamentals
- VPC Network Peering

Next Steps / Learn More

•Read more about Cloud Identity and Access

Management: https://cloud.google.com/iam/

Google Cloud Training & Certification

...helps you make the most of Google Cloud technologies. <u>Our classes</u> include technical skills and best practices to help you get up to speed quickly and continue your learning journey. We offer fundamental to advanced level training, with on-demand, live, and virtual options to suit your busy schedule. <u>Certifications</u> help you validate and prove your skill and expertise in Google Cloud technologies.

Manual Last Updated September 02, 2021 Lab Last Tested September 02, 2021

Copyright 2021 Google LLC All rights reserved. Google and the Google logo are trademarks of Google LLC. All other company and product names may be trademarks of the respective companies with which they are associated.