Spacetime coercive wave equation tests

Notes for the wave equation coercive formulation numerical tests

Paolo Bignardi

June 3, 2022

Introduction

Local operators

To construct the operators of the bilinear form, introduce the local operators for the space and time component, S is for space, T is for time. Apices will be used to denote the order of derivation for the trial and test functions: for example, S^{00} is the **local mass matrix** for the space component. In general S^{ij} is the local matrix associated to the local operator

$$\int_{\hat{R}} \partial_i u \cdot \partial_j v dx,$$

letting u and v vary among all the space local basis functions, where \hat{R} is the reference space element. Similarly T^{ij} is associated to the local operator

$$\int_0^1 \partial_i u \cdot \partial_j v dt,$$

letting u and v vary among all the time local basis functions.

$H^1(Q)$ terms

Scalar terms of the $H^1(Q)$ space are easy to compute.

$$\int_{Q} u_{t} v_{t} = S^{00} \otimes T^{11}$$
$$\int_{Q} \nabla u \cdot \nabla v = S^{11} \otimes T^{00}$$

Least square term

Least square term comes from the integral $\int_Q WuWv$. Expanding, we get

$$\int_{O} \left[u_{tt}v_{tt} - c^{2}u_{tt}\Delta v - c^{2}v_{tt}\Delta v + c^{4}\Delta u\Delta v \right],$$

Each terms is

$$\int_{Q} u_{tt}v_{tt} = S^{00} \otimes T^{22}$$

$$\int_{Q} u_{tt}\Delta v = S^{20} \otimes T^{02}$$

$$\int_{Q} v_{tt}\Delta u = S^{02} \otimes T^{20}$$

$$\int_{Q} \Delta u \Delta v = S^{22} \otimes T^{00}$$

$$\int_{Q} ZuWv$$
 term

Expanding all terms we get

$$\int_{Q} ZuWv = \dots$$

$$\int_{Q} tu_{t}v_{tt} = S^{00} \otimes T_{t}^{12}$$

$$\int_{Q} tu_{t}\Delta v = S^{02} \otimes T_{t}^{10}$$

$$\int_{Q} u_{t}v_{tt} = S^{00} \otimes T^{12}$$


$$\int_{Q} u_{t}\Delta v = S^{02} \otimes T^{10}$$

$$\int_{Q} x \cdot \nabla uv_{tt} = S_{x}^{10} \otimes T^{02}$$

$$\int_{Q} x \cdot \nabla u\Delta v = S_{x}^{12} \otimes T^{00}$$

Appendix A: FEM matrix assembly

Consider $\Omega = [0,1]^2$ as the domain, and the following subdivision:



Assume we have a local matrix called A, which is easy to compute. Now construct the *connectivity matrix* which has in each column the list of vertices of

the element.

$$T = \begin{pmatrix} 1 & 2 & 4 & 5 \\ 2 & 3 & 5 & 6 \\ 4 & 5 & 7 & 8 \\ 5 & 6 & 8 & 9 \end{pmatrix}$$

Now, assembly the global matrix by

```
for e = 1:n_elems
    el_nodes = T[:,e]
    K[el_nodes,el_nodes] = K[el_nodes,el_nodes] + A
end
```

How do we treat more general elements? ...

Suppose we have a finite element that has k local degree of freedom, then we assemble the stiffness matrix we would generally

Appendix B: Load vector assembly