6/8/2016 t Operation

t operation

Synopsis

```
t(tx, ty, tz)
```

Parameters

tx (float), ty float), tz (float)
 Amount to translate in each direction.

The t operation translates the scope by the vector (tx, ty, tz), i.e. the vector is added to scope.t. If the scope rotation is non-zero, then the passed translation vector is rotated around the pivot, with angles (scope.rx, scope.ry, scope.rz), first. In other words, the translation is relative to the scope axes.

The relative operator 'permits a convenient notation relative to the scope size: t('tx,0,0) is equivalent to t(tx*scope.sx,0,0).


Note: t(x,y,z) is the same as translate (rel, scope, x, y, z).

Related

- scope attribute
- r operation
- rotate operation
- s operation
- translate operation

Examples


Translate - Rotation Concatenation





This is the initial shape we start with.

```
A-->
i("builtin:cube")
t(2,0,0)
```


First a translation of two units along the x-axis.







Then a rotation of 30 degrees around the y-axis.



```
A-->
i("builtin:cube")
t(2,0,0)
r(0,30,0)
t('2,0,0)
```

And another translation of 2 units along the x-axis. Note:

- translations are along the scope's x-axis, i.e. the rotation changes the global translation direction!
- the relative operator ' is used here it does not make a difference because scope.sx is 1

Copyright ©2008-2015 Esri R&D Center Zurich. All rights reserved.