Week 4 - MAC Sub-Layer

COMP90007

Internet Technologies

Chien Aun Chan


Outline

- The MAC Sub-layer
- Channel Allocation Problems
- Multiple Access Protocols

Introduction

- On point to point networks, there are only singular sender and receiver pairs, eliminating transmission contention
- On broadcast networks, determining right to transmit is a complex problem
- Medium Access Control (MAC) sublayer is used to assist in resolving transmission conflicts

The MAC Sub-layer



Types of Channel Allocation Mechanisms


- Various methods exist for allocating a single broadcast channel amongst competing users
 - Static Channel Allocation
 - Dynamic Channel Allocation

Static Channel Allocation

- Arbitrary division of a channel into segments and each user allocated a dedicated segment for transmission
- Frequency Division Multiplexing (FDM) is typically used
- Significant inefficiencies arise when:
 - Number of senders > allocated segments
 - Number of senders is not static
 - Traffic is bursty


Time Division Multiplexing

Users take turns on a fixed schedule



Frequency Division Multiplexing

FDM (Frequency Division Multiplexing) shares the channel by placing users on different frequencies:



Down falls

- Usually good for fixed number of users
- Network traffic is bursty
 - TDM and FDM try to give consistent access to the network leading to inefficiency in the use of network resources
- Where?
 - TV and Radio (FDM)
 - 2G uses TDM

Dynamic Channel Allocation

- Channel segmentation is dynamic, segment allocation is dynamic
- Assumptions for dynamic channel allocation:
 - Independent transmission stations
 - Single channel for all communication
 - Simultaneous transmission results in damaged frames

Time

- Transmission can begin at any time
- Transmission can begin only within discrete intervals

Carrier Sense

- Detection of channel use prior to transmission
- No detection of channel use prior to transmission

Multiple Access Protocols


- ALOHA
- Carrier Sense Multiple Access
- Collision Free
- Limited Contention
- MACA/MACAW (for Wireless LANs)

ALOHA

- Users transmit frames whenever they have data; users retry after a random time if there are collisions (or no Ack is arrived)
- Requires no central control mechanism
- Efficient under low load but inefficient under high traffic loads
- Slotted ALOHA: Allows the users to start sending only at the beginning of defined slots.
 Increase efficiency of pure ALOHA by reducing possibility of collisions


Carrier Sense Multiple Access (CSMA) Protocols

- In networks which require transmission state detection to determine transmission rights dynamically, there are specific protocols which are used
 - Persistent and Non-Persistent CSMA
 - CSMA with Collision Detection




Persistent and Non-Persistent CSMA


- When a sender has data to transmit, first check channel to detect other active transmission
- 1-persistent CSMA
 - Wait until channel idle; transmit one frame and check collisions; if collision, wait for a random time and repeat
- Non-persistent CSMA
 - If channel busy, wait random period and check again; if not, start transmitting
- p-persistent CSMA
 - If channel idle, transmit with probability p, or wait with probability (1-p) and check again



Persistent and Non-Persistent CSMA




CSMA Variants



CSMA outperforms ALOHA, and being less persistent is better under high load


CSMA with Collision Detection

- Principle that transmission aborted when collision detected
- After collision detected, abort, wait random period, try again
- Channel must be continually monitored
- Used in half-duplex system (e.g., with Hub or repeater)
 Reduced contention times improve performance




Classic Ethernet Minimum Packet Size

- Collisions can occur and take as long as 2τ to detect
 - \Box τ is the time it takes to propagate over the Ethernet
 - Leads to minimum packet size for reliable detection



Collision Free Protocols

- Bit Map Protocol
 - Reservation-based protocol
 - 1 bit per station overhead
 - Division of transmission right, and transmission event - no collisions as this is a reservation based protocol




Collision Free Protocols

Binary Countdown Protocol

- Avoid the 1 bit per station scalability problem by using binary station addressing
- No collisions as higher-order bit positions are used to arbitrate between stations wanting to transmit
- Higher numbered stations have a higher priority


Binary Countdown Protocol

- Stations send their address in contention slot (log N bits instead of N bits)
- Channel medium ORs bits; stations give up when they send a "0" but see a "1"
- Station that sees its full address is next to send




Limited Contention Protocols

- 2 strategies contention and collision free both become inefficient at different points
- Under low loads, collision free is less attractive because of a higher delay between transmissions
- Under higher loads, contention is less attractive because overhead associated with channel arbitration becomes greater
- Limited Content Protocols increase the probability of stations acquiring transmission rights by arbitrarily dividing stations and using a binary algorithm to determine rights allocation
 - Idea is to divide stations into groups within which only a very small number are likely to want to send
 - Avoids wastage due to idle periods and collisions



Adaptive Tree Walk Protocol

- All stations compete for right to transmit, if a collision occurs, binary division is used to resolve contention
- Tree divides stations into groups (nodes) to poll
 - Depth first search under nodes with poll collisions
 - Start search at lower levels if >1 station expected





Wireless LAN Protocols

- Wireless Complications: when a station is in the range of two transmitters or relays, interference affects signal reception
- Leads to hidden and exposed terminal problems
- Require detection of transmissions to receiver, not just carrier sensing
- Transmission Protocols for Wireless LANs (802.11)
 - Multiple Access with Collision Avoidance for Wireless (MACAW)

Hidden and Exposed terminals

- Hidden terminals are senders that cannot sense each other but nonetheless collide at intended receiver
- Want to prevent; loss of efficiency
- A and C are hidden terminals when sending to B
- Exposed terminals are senders who can sense each other but still transmit safely (to different receivers)
 - Desirably concurrency; improves performance
 - □ B → A and C → D are exposed terminals






Multiple Access with Collision Avoidance (MACA)

- Sender asks receiver to transmit short control frame
- Stations near receiver hear control frame
- Sender can then transmit data to receiver


MACA

MACA protocol grants access for A to send to B:

- A sends RTS to B [left]; B replies with CTS [right]
- A can send with exposed but no hidden terminals



A sends RTS to B; C and E hear and defer for CTS




B replies with CTS; D and E hear and defer for data

A MAC Sub-Layer Case Study: Ethernet

- Ethernet Frame Format
- MAC Addressing
- Ethernet Performance
- Switched Ethernet
- Fast Ethernet
- Gigabit Ethernet
- Ethernet in Retrospect

Classic Ethernet

- Each type of Ethernet has a maximum cable length per segment.
- Multiple cable lengths can be connected by repeaters - a physical device which receives, amplifies and retransmits signals in both directions.



Ethernet Frame Format

- MAC protocol is 1-persistent CSMA/CD (earlier)
 - □ Random delay (backoff) after collision is computed with BEB
 (Binary Exponential Backoff, i.e., random number 0 and 2ⁱ 1)
 - Frame format is still used with modern Ethernet.

Preamble S Destination Source address

Check-ss Length Data Pad Sum

Preamble (7B) – synchronisation between sender and receiver Start of Frame (1B) – FLAG bytes

Dest. & Source addresses – to identify who send, who receive

Type & Length (2B) – specifies which process to give the frame to (0x0800 means data contains IPv4)

Pad(0~46B) – Minimum size of the message of the Ethernet – 64 Bytes CRC (4B) – 32 bits checksum

MAC ADDRESSING

- Source and Destination Addressing can be done at a local or global levels
- The MAC Address provides the unique identifier for a physical interface
- MAC Address is a 48-bit number encoded in the frame
 - □ eg 00:02:2D:66:7C:2C

Ethernet Performance


Definition

Channel Efficiency =
$$\frac{1}{1 + 2BLe/cF}$$

- F: frame length
- B : bandwidth
- L : cable length
- o c : speed of light
- optimal case of e contention slots per frame
- When cF is large, the channel efficiency will be high.
- Increasing network bandwidth or distance (BL) reduces the efficiency for a given frame size

Switched Ethernet

- Hubs wire all lines into a single CSMA/CD domain
- Switches isolate each port to a separate domain
 - Much greater throughput for multiple ports
 - No need for CSMA/CD with full-duplex lines



Summary

- MAC Sub-layer
 - Compare different CSMA schemes
 - Summarise collision free protocols
 - Explain for Wireless protocols
- Ethernet
 - Explain key features of Ethernet
 - Evaluate factors affecting Ethernet performance