# Distributed Systems COMP90015 2019 SM1 OS Support Lectures by Aaron Harwood © University of Melbourne 2019

#### **Overview**

- operating system layer
- protection
- processes and threads
- communication and invocation
- operating system architecture

## **Networking versus Distributed OS**


A *networked operating system* provides support for networking operations. The users are generally expected to make intelligent use of the network commands and operations that are provided. Each host remains autonomous in the sense that it can continue to operate when disconnected from the networking environment.

A *distributed operating system* tries to abstract the network from the user and thereby remove the need for the user to specify how the networking commands and operations should be undertaken. This is sometimes referred to as providing a *single system image*. Each host may not have everything that would be required to operate on its own, when disconnected from the network.

The term "single system image" is often discussed in the context of cluster computing. The MOSIX operating system provides a single system image over a cluster and has proven to be quite successful.

In general, consumer operating systems are networked. Many home consumers use only a single machine anyway, and users in organizations tend to prefer autonomy.

The figure depicts two different hosts, each with its own hardware and operating system, or platform, but conceptually supporting a consistent middleware that supports distributed applications and services.



The figure is depicting network operating systems as opposed to distributed operating systems, since there is no implied commonality between the OSes or the hardware. The operating system includes the kernel,

If the operating system is divided into *kernel* and *server* processes then they:

- *Encapsulate* resources on the host by providing a useful service interface for clients. Encapsulation hides details about the platform's internal operations; like its memory management and device operation.
- *Protect* resources from illegitimate access, from other users and other clients that are using resources on that host. Protection ensures that users cannot interfere with each other and that resources are not exhausted to the point of system failure.
- *Concurrently process* client requests, so that all clients receive service. Concurrency can be achieved by sharing time -- a fundamental resource -- called time sharing.

E.g. a client may allocate memory using a kernel system call, or it may discover an network address by using a server object. The means of accessing the encapsulated object is called an *invocation method*.

#### The core OS components are:

- *Process manager* -- Handles the creation of processes, which is a unit of resource management, encapsulating the basic resources of memory (address space) and processor time (threads).
- *Thread manager* -- Handles the creation, synchronization and scheduling of one or more threads for each process. Threads can be scheduled to receive processor time.
- *Communication manager* -- Handles interprocess communication, i.e. between threads from different processes. In some cases this can be across different hosts.
- *Memory manager* -- Handles the allocation and access to physical and virtual memory. Provides translation from virtual to physical memory and handles paging of memory.
- Supervisor -- Handles privileged operations, i.e. those that directly affect shared resources on the host, e.g. to and from an I/O device. The supervisor is responsible for ensuring that host continues to provide proper service to each client.

In a number of systems that are emerging today, there is also a *hypervisor* that sits beneath the supervisor. The hypervisor allows a host to concurrently execute multiple kernels. There is typically multiple levels of virtual memory and additional overheads for managing access to I/O devices, etc.

#### **Protection**

Resources that encapsulate space, such as memory and files, typically are concerned with *read* and *write* operations. Protecting a resource requires ensuring that only legitimate read and write operations take place.

Legitimate operations are those carried out only by clients who have the right to perform them. A legitimate operation should also conform to resource policies of the host, e.g. a file should never exceed 1 GB in size or at most 100MB of memory can be allocated.

In some cases the resource may also be protected by giving it the property of *visible* versus *invisible*. A visible resource can be discovered by listing a directory contents or searching for it. An invisible resource should be known a priori to the client; it can be guessed though.

Resources that encapsulate time, i.e. processes, are concerned with *execute* operations. In this case a client may or may not have the right to create a process. Again, host based policies should be enforced.

Protection 2

Files in the UNIX operating system have the three fundamental access privileges of read, write and execute. The execute privilege is used on directories to determine if the contents can be listed or not; since a directory is not executable.

The kernel is that part of the operating system which assumes full access to the host's resources. The kernel begins execution soon after the host is powered up and continues to execute while the host is operational. The kernel has access to all resources and shares access to all other processes that executing on the host. To do this securely requires hardware support at the machine instruction level, which is supplied by the processor using two fundamental operating modes:

- *supervisor* mode -- instructions that execute while the processor is in supervisor (or privileged) mode are capable of accessing and controlling every resource on the host,
- *user* mode -- instructions that execute while the processor is in user (or unprivileged) mode are restricted, by the processor, to only those accesses defined or granted by the kernel.

Most processors have a register that determines whether the processor is operating in user or supervisor mode.

Before the kernel assigns processor time to a user process, it puts the processor into user mode.

A user process accesses a kernel resource using a *system call*. The system call is an *exception* that puts the processor into supervisor mode and returns control to the kernel.

Other kinds of exceptions can occur, such as when an illegal instruction has been issued, a resource is trying to be accessed that is not allowed, or when I/O is pending.

In theory, a well designed, error-free kernel, that uses proper hardware level security, cannot "loose control" of the host. Implementing such a kernel is a very challenging task.

On systems with supervisor mode there is typically a user, e.g. the superuser or root user, that can execute any desired processes in supervisor mode, which is necessary to maintain and administer the host. Such a user is a trusted user. Other users are typically limited to what processes they can execute in supervisor mode.

Of course, supervisor mode can only access and control every resource on the host if there is no active hypervisor.

#### **Processes and threads**

A process encapsulates the basic resources of memory and processor time. It also encapsulates other higher level resources.

#### Each process:

- has an address space and has some amount of allocated memory,
- consists of one or more threads that are given processor time, including thread synchronization and communication resources.
- higher-level resources like open files and windows.

Threads have equal access to the resources encapsulated within the process.

Resource sharing or interprocess communication is required for threads to access resources in other processes.

Processes and threads 3

E.g. shared memory or socket communication.

The allocation of a resource does not come for "free". E.g., each process requires a process table entry and each open file requires a file descriptor to be recorded in memory.

## **Address spaces**

Most operating systems allocate a *virtual* address space for each process. The virtual address space is typically byte addressable and on a 32 bit architecture will typically have 2^32 byte addresses.

The virtual address space can be divided into *regions* that are contiguous and do not overlap.


A *paged* virtual memory scheme divides the address space into fixed sized blocks that are either located in physical memory (RAM) or located in swap space on the hard disk drive.

A *page table* is used by the processor and operating system to map virtual addresses to real addresses. The page table also contains access control bits for each page that determine, among other things, the access privileges of the process on a per page basis.

The operating system manages the pages, swapping them into and out of memory, in response to process memory address accesses.

The size of memory address register in the CPU determines the size of the address space. While it is possible to have 2^64 bytes of addressable memory on a 64 bit architecture, in most cases the extra bits are used for other purposes.

## **Example virtual address space mappings**



## **Shared memory**

Two separate addresses spaces can share parts of real memory. This can be useful in a number of ways:

- *Libraries*: The binary code for a library can often be quite large and is the same for all processes that use it. A separate copy of the code in real memory for each process would waste real memory space. Since the code is the same and does not change, it is better to share the code.
- *Kernel*: The kernel maintains code and data that is often identical across all processes. It is also often located in the same virtual memory space. Again, sharing this code and data can be more efficient than having several copies.
- Data sharing and communication: When two processes want access to the same data or want to communicate then shared memory is a possible solution. The processes can arrange, by calling appropriate system functions, to share a region of memory for this purpose. The kernel and a process can also share data or communicate using this approach.

Examples of each of these shared memory uses are shown in the previous figure.

## Creation of a new process

The operating system usually provides a way to create processes. In UNIX the fork system call is used to duplicate the caller's address space, creating a new address space for a new process. The new process is identical to the caller, apart from the return value of the fork system call is different in the caller. The caller is called the parent and the new process is called the child.

Creation of a new process 5

In UNIX a exec system call can be used to replace the caller's address space with a new address space for a new process that is named in the system call.


A combination of fork and exec allows new processes to be allocated.


## Copy on write

When a new process is created using fork, the address space is copied. The new process' code is identical and is usually read-only so that it can be shared in real memory and no actual copying of memory bytes is required. This is faster and more efficient than making a copy.

However the data and other memory regions may or may not be read-only. If they are writable then the new process will need its own copy when it writes to them.

Copy on write is a technique that makes a copy of a memory region only when the new process actually writes to it. This saves time when allocating the new process and saves memory space since only what is required to be copied is actually copied.





Copy on write 6

## New processes in a distributed system

In a distributed system there is a choice as to which host the new process will be created on. In a distributed operating system this choice would be made by the operating system.

The decision is largely a matter of policy and some categories are:

- transfer policy -- determines whether the new process is allocated locally or remotely.
- *location policy* -- determines which host, from a set of given hosts, the new process should be allocated on.

The policy is often transparent to the user and will attempt to take into account such things as relative load across hosts, interprocess communication, host architectures and specialized resources that processes may require.

When the user is programming for explicit parallelism or fault tolerance then they may require a means for specifying process location. However, it is desirable to make these choices automatic as well.

Process location policies may be *static* or *adaptive*. Static policies do not take into account the current state of the distributed system. Adaptive policies receive feedback about the current state of the distributed system.

A *load manager* gathers information about the current state of the distributed system. Load managers may be:

- centralized -- a single load manager receives feedback from all other hosts in the system.
- hierarchical -- load managers are arranged in a tree where the internal nodes are load managers and the leaf nodes are hosts.
- *decentralized* -- there is typically a load manager for every host and load managers communicate with all other load managers directly.

In a *sender-initiated* or push policy, the local host is responsible for determining the remote host to allocate the process. In the *receiver-initiated* or pull policy, remote hosts advertises to other hosts that new processes should be allocated on it.

Sometimes it is more efficient to use push over pull and vice versa.

## **Process migration**

Processes can be *migrated* from one host to another by copying their address space. Depending on the platform and on the resources that are in current use by the process, process migration can be more or less difficult.


Process code is often CPU dependent, e.g. x86 versus SPARC. This can effectively prohibit migration. Ensuring that hosts are homogeneous can eliminate this problem. Using virtual machines can also help, by avoiding CPU dependent instructions.

Even if the host platforms are such that a process can migrate, the process may be using host resources such as open files and sockets that further complicates the migration.

The Condor library is used by the Department's P2P research group to migrate Linux processes in an x86 environment.

Process migration 7

#### **Threads**



Typically there is significant use of threads in a distributed system.

#### Performance bottleneck

Consider a server than handles client requests. Handling the request requires a disk access of 8ms and 2ms of processor time. A process with a single thread takes 10ms of time and the server can complete 100 requests/second.

If we use two threads, where each thread independently handles a request then while the first thread is waiting for the disk access to complete the second thread is executing on the processor. In general if we have many threads then the server becomes bottlenecked at the disk drive and a request can be completed every 8ms which is 125 requests/second.

Consider when disk accesses are cached with a 75% hit rate and an increase in processor time to 2.5ms (the increase is due to the cache access). The disk access is now completed in 0.75x0 + 0.25x8 = 2ms. Hence the requests are bottlenecked at the processor and the maximum rate is 1000/2.5=400 requests/second.

Some multi-processor operating systems do not schedule threads of a processes on different processors; though most do.

## Worker pool architecture

Creating a new thread incurs some overhead that can quickly become the bottleneck in a server system. In this case it is preferable to create threads in advance.

It is okay to have a single I/O thread to receive the requests since the I/O is the bottleneck.

In the *worker pool* architecture the server creates a fixed number of threads called a worker pool. As requests arrive at the server, they are put into a queue by the I/O thread and from there assigned to the next available worker thread.


Worker pool architecture 8

Request priority can be handled by using a queue for each kind of priority. Worker threads can be assigned to high priority requests before low priority requests.

If the number of workers in a pool is too few too handle the rate of requests then a bottleneck forms at the queue. Also, the queue is shared and this leads to an overhead.

The Common Object Request Broker Architecture uses the worker pool architecture.

## **Alternative Threading**



## a. Thread-per-request

b. Thread-per-connection

c. Thread-per-object

## Thread-per-request architecture

In the *thread-per-request* architecture a separate thread is created by the I/O thread for each request and the thread is deallocated when the request is finished.

This allows as many threads as requests to exist in the system and avoids accessing a shared queue. Potential parallelism can be maximized.

However, thread allocation and deallocation incurs overheads as mentioned earlier. Also, as the number of threads increases then the advantages from parallelism decreases (for a fixed number of processors) and the overhead incurred in context switching between threads can outweigh the benefit. Managing large numbers of threads can be more expensive than managing a large queue.

## Thread-per-connection architecture

A single client may make several requests. In the previous architectures, each request is treated independently of the client connection.

In the *thread-per-connection* architecture, a separate thread is allocated for each *connection* rather than for each *request*. This can reduce the overall number of threads as compared to the thread-per-request architecture.

The client can make several requests over the single connection.

## Thread-per-object architecture

In the *thread-per-object* architecture, a worker thread is associated for each remote object or resource that is being accessed. An I/O thread receives requests and queues them for each worker thread.

The thread-per-connection and thread-per-object architectures generally use less threads, however bottlenecks can still occur. For example the thread-per-connection can leave a client waiting on many requests, even though there are idle processors at the server; similarly for the thread-per-object architecture.

#### Threads within clients

Threads are useful within clients in the case when the request to the server takes considerable time. Also, communication invocations often block while the communication is taking place.

E.g., in a web browser the user can continue to interact with the current page while the next page is being fetched from the server. Multiple threads can be used to fetch each of the images in the page, where each image may come from a different server.

## Threads versus multiple processes

It is possible to use multiple processes instead of multiple threads. However the threaded approach has the advantages of being cheaper to allocate/deallocate and of being easy to share resources via shared memory.

One study showed that creating a new process took about 11ms while creating a new thread took 1ms. While these times may be decreasing as as technology improves, the relative difference is likely to remain.

This is because, e.g., processes require a new address space which leads to a new page table, while threads require in comparison only a new processor context.

If the kernel does not schedule threads across processors then it can be preferable to use multiple processes rather than multiple threads.

In some Java implementations, the Java threads are not scheduled across different processors. They are in Solaris' Java implementation.

Context switching between threads is also cheaper than between processes because of cache behavior concerned with address spaces. Some processors are optimized to switch between threads (hyper-threading) and so this can lead to greater advantages for the threading model; though it has caveats as well.

A *processor context* comprises the values of the processor registers such as the program counter, the address space identifier and the processor protection mode (supervisor or user).

Context switching involves saving the processor's original state and loading the new state. When changing from a user context to a kernel context it also involves changing the protection mode which is a called a *domain transition*.

One study showed that context switching between processes took 1.8ms while switching between threads belonging to the same process took 0.4ms. Again, it is the relative difference that is of interest here.

A danger with the use of threads is that their memory space is not protected from each other and so an errant thread can easily corrupt the data of other threads.

## Thread programming

Thread programming is largely concerned with the study of concurrency, including:

- race condition,
- critical section,
- monitor,
- condition variable, and
- semaphore.

In Java, the Thread class is used to implement threads.

Typically, each OS provides its own kind of thread model. Recently the POSIX thread model, known as pthreads, has become standard.

For parallel programming there is the OpenMP programming model. It provides an abstraction on top of the threading model that is particularly suited for parallel processing but that can also be used for general processing.

### Java thread methods

- Thread (ThreadGroup group, Runnable target, String name) -- Creates a new thread in the SUSPENDED state, which will belong to group and be identified as name; the thread will execute the run () method of target.
- setPriority (int newPriority), getPriority () -- Set and return the thread's priority.
- run () -- A thread executes the run () method of its target object, if it has one, and otherwise its own run () method.
- start () -- Change the state of the thread from SUSPENDED to RUNNABLE.
- sleep (int millisecs) -- Cause the thread to enter the SUSPENDED state for the specified time.
- yield() -- Enter the READY state and invoke the scheduler.
- destroy() -- Destroy the thread.

#### Thread lifetime

A new thread is created on the Java virtual machine (JVM) as its creator.

It is created in the SUSPENDED state.

It is made RUNNABLE using the start () method and executes the run () method (either designated or its own).

Threads can be assigned priorities for scheduling purposes and can be managed in groups.

Groups provide protection of threads within a group from threads in other groups.

Thread lifetime 11

## Java thread synchronization

- thread.join(int millisecs) -- Blocks the calling thread for up to the specified time until thread has terminated.
- thread.interrupt() -- Interrupts thread: causes it to return from a blocking method call such as sleep().
- object.wait(long millisecs, int nanosecs) -- Blocks the calling thread until a call made to notify() or notifyAll() on object wakes the thread, or the thread is interrupted, or the specified time has elapsed.
- object.notify(), object.notifyAll() -- Wakes, respectively, one or all of any threads that have called wait() on object.

Consider a shared function to generate unique identifiers:

This code doesn't work when several threads call it concurrently.

Consider when there is exactly one element on the stack. The condition to check whether the stack is empty may be tested concurrently by two or more threads. All threads will assume that the stack contains a value to be popped and will attempt to pop it. In fact there are a lot of problems with executing this code concurrently.

One way to avoid these problems is to allow only one thread to be executing the function at a time. This eliminates concurrency for this function which reduces the parallelism but avoids the concurrent access problem.

Using a stack is a good way to keep track of which integers have been returned for reuse. The value for greatest is only decremented when the (greatest-1) identifier is returned.

The POSIX standard defines a pthread\_mutex\_t data type and functions such as pthread\_mutex\_init(), pthread\_mutex\_lock(), pthread\_mutex\_unlock() and pthread\_mutex\_trylock() for blocking and non-blocking mutual exclusion operation.

Among other things, Java provides the synchronized keyword to indicate methods for which only one thread may be executing at any one time.

Monitors allow a higher level thread synchronization control by providing wait and signal primitives.

Mutual exclusion can lead to deadlock, livelock and starvation.

## Thread scheduling

Some thread scheduling is *preemptive*. In this case a running thread is suspended at any time, usually periodically, to allow processor time for other threads.

Other the thread scheduling is *non-preemptive*. In this case a running thread will continue to receive processor time until the thread *yields* control back to the thread scheduler.

Non-preemptive scheduling has the advantage that concurrency issues, such as mutual exclusion to a shared variable, are greatly simplified.

However, non-preemptive scheduling does not guarantee that other threads will receive processor time since an errant thread can run for an arbitrarily long time before yielding. This can have negative effects on performance and usability.

Real time scheduling of threads is not support by vanilla Java. Real time imposes another set of constraints on thread scheduling.

## Thread implementation

Depending on the kernel, the threads of a process may or may not be schedulable across different processors.

Some kernels provide system calls only to allocate processes. Some kernels provide system calls to allocate threads as well; they can be call *kernel threads*. This can depend on whether the kernel itself is threaded. Most modern OSes have threaded kernels.

If the kernel does not provide thread allocation (and even if it does), it is possible for the user to manage *user threads* within a process.

In the case of user threads, the kernel gives processor time to the process and the process is responsible for scheduling the threads.

In ANSI C, user threads can be implemented using library functions such as set jmp () and long jmp ().

In UNIX the ps command lists the currently running processes. Usually, the -M option lists threads. Some kernels allocate separate process numbers to each thread. Some kernels do not.

#### User versus kernel threads

User threads within a process cannot take advantage of multiple processors.

A user thread that causes a page fault will block the entire process and hence all of the threads in that process.

User threads within different processes cannot be scheduled according to a single scheme of relative prioritization.

Context switching between user threads can be faster than between kernel threads.

A user thread scheduler can be customized by the user, to be specific for a given application.

User versus kernel threads

Usually the kernel places limits on how many kernel threads can be allocated, a user thread scheduler can usually allocate more threads than this.

It is possible to combine kernel level threads with user level threads.

#### Communication and invocation

An invocation such as a remote method invocation, remote procedure call or event notification is intended to bring about an operation on a resource in a different address space.

- What communication primitives are available?
- Which protocols are supported and how open are they?
- What is done to make the communication efficient?
- What additional support is provided, e.g. for high-latency communication and issues such as disconnection?

The kernel can provide communication primitives such as TCP and UDP, and it can also provide higher level primitives. In most cases the higher level primitives are provided by middleware because it become too complex to develop them into the kernel and because standards are not widely accepted at the higher level.

## **Protocols and openness**

Using open protocols, as opposed to closed or proprietary protocols, facilitates interoperation between middleware implementations on different systems.

Experience has shown that kernels which implement and require their own network protocols do not become popular.

A design choice of some new kernels is to leave the implementation of networking protocols to servers. Hence a choice of networking protocol can be more easily made.

The kernel is still required to provide device drivers for new networking devices such as infrared and BlueTooth. Either the kernel can transparently select the appropriate device driver or middleware should be able to dynamically select the appropriate driver. In either case, standard protocols such as TCP and UDP allow the middleware and application to make use of the new devices without significantly changes.

## **Invocation performance**


The performance of an invocation can be categorized into three kinds, depending on what is required to invoke the resource:

- User space procedure -- minimal overhead, allocating stack space.
- System call -- if a system call is required then the overhead is characterized by a domain transition two and from the kernel.
- Interprocess on the same host -- in this case there is a domain transition to the kernel, to the other process, back to the kernel and back to the calling process.
- Interprocess on a remote host -- this case includes the same overheads as the previous case, plus the overhead of network communication between the two kernels.

Invocation performance 14


One study showed that the time for a null RPC between user processes on two 500MHz PCs across a 100Mbps LAN is in the order of tenths of a millisecond. By comparison an equivalent user space procedure call takes a small fraction of a microsecond.

Consider printing lots of information to a log file. Using several calls to the system print function is less efficient than buffering the information in user space and making a single call to the system print function. In part this is also due to combining several disk accesses into a smaller number of larger accesses.



## **RPC Delay versus size**

RPC Delay versus size



The following are the main factors contributing to delay for RMI, apart from actual network delay:

- marshalling -- copying and converting data becomes significant as the amount of data grows.
- data copying -- after marshalling, the data is typically copied several times, from user to kernel space, and to different layers of the communication subsystem.
- packet initialization -- protocols headers and checksums take time, the cost is proportional to the size of the data.
- thread scheduling and context switching -- system calls and server threads.
- waiting for acknowledgments -- above the network level acknowledgments.

## **Communication via shared memory**

Shared memory can be used to communicate between user processes and between a user process and the kernel.


Data is communicated by writing to and reading from the shared memory, like a "whiteboard".

In this case, when communicating between user processes the data is not copied to and from kernel space.

However the processes will typically need to use some synchronization mechanism to ensure that communication is deterministic.

In UNIX, a shared memory area can be obtained using <code>shmget()</code>, the area can be attached to a process using <code>shmat()</code>, detached using <code>shmdt()</code> and controlled (e.g. specifying read/write permissions) using <code>shmctl()</code>. The <code>shmget()</code> is a system call that returns an identifier and the identifier must be communicated to other processes. Thus there is some overhead in setting up a shared memory area.

## **Lightweight RPC**



## **Choice of protocol**

Connection-oriented protocols like TCP are often used when the client and server are to exchange information in a single session for a reasonable length of time; e.g. telnet or ssh. These protocols can suffer if the end-points are changing their identity, e.g. if one of the end-points is mobile and roaming from one IP address to another, or e.g. if a DHCP based wireless base station experiences a lot of contention and the clients to the base station are continually having their IP address change.

Connection-less protocols like UDP are often used for request-reply applications, that do not require a session for any length of time. E.g., finding the time from a time server. Because these protocols often have less overhead, they are also used for applications that require low latency, e.g. in streaming media and online games.

In many cases, cross address space communication happens between processes on the same host and so it is preferable to (transparently) choose a communication mechanism (such as using shared memory) that is more efficient. Lightweight RPC is an example of this.


Choice of protocol 17

## Concurrent and asynchronous operation

In many applications it is possible to have a number of outstanding or *concurrent* requests. In other words it is not necessary to wait for the response to a request before moving on to another request. This was exemplified in the use of threads for the client, where e.g. several requests to different web servers could be undertaken concurrently.

The telnet client/server is an example of *asynchronous* operation. In this case, whenever a key is typed at the keyboard the client sends the key to the server. Whenever output is available from the server it is sent to the client and received data from the server is printed on the terminal by the client whenever it arrives. Sends and receives are not synchronized in any particular way.

An asynchronous invocation returns without waiting for the invocation request to be completed. Either the caller must periodically check whether the request has completed or the caller is notified when the request has completed. The caller is required to take appropriate action if the request fails to complete.



## Persistent asynchronous invocations

With usual networking circumstances it is possible to automatically retry a nonresponsive request after a timeout, retrying some number of times before the request is considered to have failed. Usually the timeout period is some number of seconds and is sufficient for example when making a request from a client on the Internet to a server on the Internet.

However, with the use of mobile devices that can experience excessively long disconnection times it is preferable to handle asynchronous invocations in a different way. A *persistent asynchronous invocation* is placed in a queue at the client and attempts are made to complete the request as the client roams from network to network. At the server side, the response to the request is put into a "client mailbox" and the client is required to retrieve the response when it can.

Persistent invocations allow the user to select which kind of network (e.g. GSM or Internet) will be used to service the request. Queued RPC is an example of this.

## **Operating system architecture**

An open distributed system should make it possible to:


- Run only that system software that is specifically required by the hosts hardware, e.g. specific software for a mobile phone or personal digital assistant. This leaves as much resources as possible available for user applications.
- Allow the software (and the host) implementing any particular service to be changed independently of other facilities.
- Allow for alternatives of the same service to be provided, when this is required to suit different users or applications.
- Introduce new services without harming the integrity of existing ones.

## Monolithic and Micro kernel design


The UNIX operating system is described as having a *monolithic kernel*. In this case there is significantly detailed and diverse functionality supplied by the kernel. Changing kernel functionality is more difficult than changing a server functionality. Same implementations use *kernel modules* to load and unload functionality into the kernel.

In contrast, the Mach operating system is described as a *micro kernel*. In this case the kernel provides only the fundamental functionality such as address space management, threads and local interprocess communication. All other functionality is provided by servers.

Monolithic kernels can sometimes be more efficient because complex functionality can be provided through a smaller number of system calls and interprocess communication is minimized. However micro kernels allow a greater extensibility and have a better ability to enforce modularity behind memory protection boundaries. A small kernel is also more likely to be free of bugs.



#### **Role of Microkernel**



The microkernel supports middleware via subsystems

#### **Emulation and virtualization**


The adoption of microkernels is hindered in part because they do not run software that a vast majority of computer users want to use. Microkernels can use binary *emulation* techniques, e.g. emulating another operating system like UNIX, to overcome this. The Mach OS emulates both UNIX and OS/2.

Virtualization can also be used and can be achieved in different ways. Virtualization can be used to run multiple instances of virtual machines on a single real machine. The virtual machines are then capable of running different kernels. Another approach is to implement an OS' application programming interface, which

Emulation and virtualization 20


Today, two prominent research systems that use virtualization are Xen and PlanetLab.

#### **Xen Architecture**




## **Privileges**

Privileges 21




## **Virtual Memory**



Virtual Memory 22

# **Split Device Drivers**



Split Device Drivers 23