# 1. 과제 개요

이 과제의 목표는 pthread 라이브러리를 이용한 쓰레드 프로그래밍을 통해 다중 쓰레드 프로그래밍의 기본 개념을 이해하는 것이다. 1번 문제에서는 lock과 조건변수를 이용하여 간단한 마스터-워커 쓰레드 풀을 구현한다. 2번 문제에서는 두가지 종류의 읽기-쓰기 lock을 구현한다. 3번 문제에서는 pthread 라이브러리를 이용하여 세마포어를 구현하고, 구현한 세마포어를 이용해 쓰레드간 동기화를 구현한다.

#### - 구현 방법

#### 1. Master-Worker Thread Pool 구현

master 쓰레드가 수행하는 generate\_requests\_loop() 함수를 다음과 같이 구현하였다. 무한 루프를 수행하며 mutex lock을 건 뒤 버퍼에 남은 공간이 있으면 다음 아이템을 집어넣는다. 아이템은 mutex lock을 건 뒤에만 접근해 쓰레드간 동기화 문제가 발생하지 않도록 했다. 버퍼에 공간이 없는 경우에는 pthread\_cond\_wait()으로 버퍼에 공간이생길 때를 기다린다. 반복문의 마지막에는 다른 쓰레드에 signal을 보낸 뒤 wait을 호출해 다음 순서를 기다린다. 모든 아이템을 생성한 경우에는 다른 쓰레드에 signal을 보낸 뒤 반복을 종료하고 쓰레드를 종료한다.

worker 쓰레드가 수행하는 consume\_requests\_loop() 함수는 다음과 같이 구현하였다. 무한 루프를 수행하며 버퍼에 소비해야 할 아이템이 있는 경우에는 해당 아이템을 소비한다. 이 때에도 mutex를 이용하여 쓰레드간 동기화 문제가 발생하지 않도록 하였다. 버퍼가 비어서 소비할 아이템이 없을 경우에는 wait 상태로 들어가 대기한다. 모든 아이템을 소비했을 때에는 다른 쓰레드에 signal을 보낸 뒤 반복을 종료한다. 반복문의 마지막에는 다른 쓰레드에게 signal을 보낸 뒤 wait 상태로 들어간다.

위와 같이 master 쓰레드와 worker 쓰레드를 구현하여 master-worker thread pool을 구현하였다.

## 2. Reader-Writer Locks 쓰레드 프로그램 구현

두가지 종류의 read/write lock을 구현한다. 첫번째는 쓰기 쓰레드가 lock을 요청한 뒤에도 읽기, 쓰기 쓰레드가 모두 lock을 획득할 수 있는 lock이다. 이 경우에는 쓰기 쓰레드의 대기시간이 매우 길어질 수 있다. 두번째는 쓰기 쓰레드가 lock을 요청했으면 읽기 쓰레드는 lock을 획득할 수 없는 lock이다. 첫번째 lock은 rw\_lock-r-test.c에, 두번째 lock은 rw lock-w-test.c에 구현하였다.

```
struct rw_lock을 다음과 같이 정의하였다.
struct rw_lock
{
    pthread_rwlock_t rwlock;
    pthread_spinlock_t lock;
    int num_of_readers;
```

```
int num_of_writers;
int num_of_write_requests;
```

**}**;

여기에서 pthread\_rwlock\_t rw\_lock은 첫번째 lock에, pthread\_spinlock\_t lock은 두번째 lock에 사용한다. num\_of\_readers는 읽기 lock을 획득한 쓰레드의 수, num\_of\_writers는 쓰기 lock을 획득한 쓰레드의 수, num\_of\_write\_requests는 쓰기 lock을 요청한 쓰레드의 수이다. 이 중 num\_of\_write\_requests는 두번째 lock에서만 사용하고, 나머지 변수들은 두 lock에서 모두 사용한다.

첫번째 lock은 pthread\_rwlock\_t를 이용하여 구현하였다. pthread의 rwlock은 스케줄러의 종류에 따라 다르게 작동한다고 man page에 나와있다. 리눅스의 기본 스케줄러(CFS)에서는 우리가 구현해야 하는 첫번째 스케줄러와 동일하게 작동하기 때문에 pthread\_rwlock\_t를 그대로 가지고 구현하였다. 스케줄러를 RR 스케줄러 등으로 바꾸면 두번째 스케줄러와 같은 방식으로 작동하게 되지만, 두번째 스케줄러를 구현하는 데에는 pthread\_rwlock\_t를 사용하지 않고 그냥 spinlock을 이용하여 구현하였다.

두번째 스케줄러는 다음과 같이 구현하였다. 우선 lock 관리 구조체인 struct rw\_lock에 접근할 때에는 쓰레드간 동기화 문제가 일어나지 않도록 하기 위하여 spinlock을 이용에 한번에 한 쓰레드만 접근할 수 있도록 하였다. r\_lock() 함수에서는 쓰기 lock을 갖고 있는 쓰레드가 없고, 쓰기 lock을 요청한 쓰레드가 없을 때에만 읽기 lock을 획득할 수 있도록 구현하였다. w\_lock() 함수에서는 일단 num\_of\_write\_requests를 1 증가시켜 쓰기 lock 획득을 요청한 쓰레드가 있음을 표시하였다. 그 다음 읽기, 쓰기 lock을 갖고 있는 쓰레드가 하나도 없을 때 쓰기 lock을 획득하도록 하였다.

lock의 획득 및 해제의 상대적 순서를 확인하기 위하여 새로운 테스트 프로그램을 원래 테스트 용으로 주어졌던 테스트 프로그램과, 셸 스크립트를 일부 수정하여 작성하였다. 해당 테스트 프로그램에서는 쓰레드가 lock을 요청한 시점, 획득한 시점, 반납한 시점에 메시지를 출력한다. 출력된 메시지를 통해 제대로 동작하고 있는지 확인할 수 있다. 테스트 결과는 보고서의 "2.결과"에서 확인할 수 있다.

#### 3. pthread를 이용한 사용자 수준 세마포어 (SSU Sem) 구현

pthread 라이브러리를 이용하여 사용자 수준 세마포어를 구현하고, 구현한 세마포어를 이용하여 쓰레드가 차례대로 돌아가며 수행되는 SSU\_Sem\_toggle\_test 프로그램을 구현한다.

```
typedef struct SSU_Sem {
    pthread_mutex_t lock;
    pthread_cond_t cond;
    int count;
```

} SSU\_Sem;

세마포어 SSU\_Sem은 위와 같이 정의하여 세마포어의 count값이 정상적으로 증가/감소할 수 있도록 하였다.

SSU\_Sem\_down(), SSU\_Sem\_up() 함수는 위 구조체의 mutex와 조건변수를 이용하여 쓰레드간 동기화 문제없이 counter값을 증가, 감소시키도록 구현하였다.

SSU\_Sem\_toggle\_test.c 에서는 정해진 쓰레드 수만큼 세마포어를 만들어 각각의 쓰레드가 자신만의 세마포어를 갖게 하였고, 그 값을 0으로 초기화 하였다. 쓰레드를 생성하여 justprint() 함수를 수행하게 되면 일단 SSU\_Sem\_down()을 호출하여 대기하게 된다. 메인 쓰레드에서 모든 쓰레드가 생성된 후에 첫번째 세마포어에 대하여 SSU\_Sem\_up()을 호출하여 첫번째 쓰레드가 수행되도록 한다. 각각의 쓰레드는 wait상태에서 깨어나 수행을 한뒤 다음 쓰레드의 세마포어에 대하여 SSU\_Sem\_up()을 호출하여 다음 쓰레드가 수행되도록 한다 (예를 들면 1번 쓰레드가 수행을 마친 뒤에는 2번 쓰레드를 깨우고, 2번 쓰레드가 수행을 마친 뒤에는 3번 쓰레드를 깨운다). 다음 쓰레드를 깨운 뒤에는 본인의 세마포어를 1 감소시켜 대기한다. 이 과정을 반복하며 모든 쓰레드가 순차적으로 수행되도록 구현하였다.

## 2. 결과

### - 1. Master-Worker Thread Pool 구현 test

```
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/1$ ./test-master_worker.sh 100 100 3 5
OK. All test cases passed!
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/1$ ./test-master_worker.sh 300 200 3 5
OK. All test cases passed!
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/1$ ./test-master_worker.sh 100 10 3 5
OK. All test cases passed!
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/1$ ./test-master_worker.sh 500 20 2 6
OK. All test cases passed!
```

여러 상황에서 정상적으로 작동하는 것 확인.

# - 2. Reader-Writer Locks 쓰레드 프로그램 구현 test

```
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/2$ ./rw_lock_test.sh
TESTSET: Running Testcases with reader test
CASE1: Reader Test with 5 reader and 1 writer
PASSED
CASE2: Reader Test with 5 reader and 3 writer
PASSED
CASE3: Reader Test with 5 reader and 5 writer
PASSED
TESTSET: Running Testcases with writer test
CASE1: Writer Test with 5 reader and 1 writer
PASSED
CASE2: Writer Test with 5 reader and 3 writer
PASSED
CASE3: Writer Test with 5 reader and 5 writer
PASSED
Test Cases Passed: 6
Test Cases Total: 6
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/2$ ./rw_lock_test.sh
TESTSET: Running Testcases with reader test
CASE1: Reader Test with 5 reader and 1 writer
PASSED
CASE2: Reader Test with 5 reader and 3 writer
PASSED
CASE3: Reader Test with 5 reader and 5 writer
PASSED
TESTSET: Running Testcases with writer test
CASE1: Writer Test with 5 reader and 1 writer
PASSED
CASE2: Writer Test with 5 reader and 3 writer
PASSED
CASE3: Writer Test with 5 reader and 5 writer
PASSED
Test Cases Passed: 6
Test Cases Total: 6
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/2$ ./rw_lock_test.sh
TESTSET: Running Testcases with reader test
CASE1: Reader Test with 5 reader and 1 writer
PASSED
CASE2: Reader Test with 5 reader and 3 writer
PASSED
CASE3: Reader Test with 5 reader and 5 writer
PASSED
TESTSET: Running Testcases with writer test
CASE1: Writer Test with 5 reader and 1 writer
PASSED
CASE2: Writer Test with 5 reader and 3 writer
PASSED
CASE3: Writer Test with 5 reader and 5 writer
PASSED
Test Cases Passed: 6
Test Cases Total: 6
```

테스트를 위해 세번 연속으로 실행했을 때 정상적으로 작동하는 것 확인.

### ● lock의 획득 및 해제의 상대적 순서 확인



```
Writer: 3 has acquired the lock & Writer: 3 has released the lock Reader: 5 has acquired the lock Reader: 4 has acquired the lock Reader: 7 has acquired the lock
                                                                      → 모든 쓰기 쓰레드가 요청했던 write lock
                                                                               을 획득, 반납하고 나서야 읽기 쓰레드
Reader: 8 has acquired the
                                              lock
            6 has acquired the
  eader:
                                              lock
Reader: 9 has acquired the
Reader: 5 has released the
Reader: 7 has released the
                                                                              가 lock을 획득함.
                                              lock
Reader: 9 has released the
Reader: 6 has released the
                                              lock
                                                                              또한 읽기 쓰레드들은 동시에 read lock
                                              lock
 Reader: 8 has released the lock
Reader: 4 has released the lock
Reader 0 Lock Time: 0 Unlock Time:
                                                                               을 획득하고 있음.
Reader 1 Lock Time: 1 Unlock Time: 7
Reader 2 Lock Time: 2 Unlock Time: 5
Reader 3 Lock Time: 3 Unlock Time: 6
Reader 4 Lock Time: 22 Unlock Time: 28
Reader 5 Lock Time: 21 Unlock Time: 24
Reader 6 Lock Time: 20 Unlock Time:
Reader 7 Lock Time: 23 Unlock Time:
Reader 8 Lock Time: 19 Unlock Time:
Reader 9 Lock Time: 18 Unlock Time:
Writer 0 Lock Time: 10 Unlock Time:
Writer 1 Lock Time: 12 Unlock Time: 13
Writer 2 Lock Time: 14 Unlock Time: 15
Writer 3 Lock Time: 16 Unlock Time: 17
Writer 4 Lock Time: 8 Unlock Time: 9
18
PASSED
********** TEST END ********
```

위와 같이 요구사항 대로 두 종류의 read/write lock을 구현한 것을 확인함.

# - 3. pthread를 이용한 사용자 수준 세마포어(SSU\_Sem) 구현 test

```
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/3$ ./SSU_Sem_test.sh
Running SSU_Sem_test.c
This is main thread. This should print first
This is thread 1
One thread has printed
This is thread 2
Second thread has printed
Running SSU_Sem_toggle_test.c
This is thread 0
This is thread 1
This is thread
     is thread
     is thread
This is thread
This is thread 0
This is thread 1
This is thread
This is thread
This is thread
     is thread
This is thread
This is thread
This is thread
This is thread 0
This is thread
This is thread
This is thread
This is thread
This is thread 2
shlee@shlee-virtual-machine:~/workspace/ssuos/project4/3$
```

SSU\_Sem\_test에서 메인 쓰레드가 먼저 출력되는 것, SSU\_Sem\_toggle\_test에서 차례대로 돌아가며 출력되는 것 확인.

# 3. 소스코드 (수정된 부분만)

1. Master-Worker Thread Pool 구현

#### master-worker.c

```
pthread_mutex_t lock = PTHREAD_MUTEX_INITIALIZER; // mutex 선언, 초기화
pthread cond t cond = PTHREAD COND INITIALIZER; // 조건변수 선언, 초기화
//produce items and place in buffer
//modify code below to synchronize correctly
void *generate_requests_loop(void *data)
{
       int thread_id = *((int *)data);
       while(1)
       {
                pthread_mutex_lock(&lock); // mutex lock
                if(item_to_produce >= total_items) { // 아이템 모두 만들었으면
                        pthread_cond_signal(&cond); // send signal
                        pthread_mutex_unlock(&lock); // mutex unlock
                        break;
               }
               if (curr_buf_size < max_buf_size) { // 버퍼에 빈 공간이 있을 때
                        buffer[curr_buf_size++] = item_to_produce; // 새로운 아이템을 버퍼에 넣음
                        print_produced(item_to_produce, thread_id);
                        item_to_produce++;
               }
```

```
pthread_cond_signal(&cond); // send signal
                pthread_cond_wait(&cond, &lock); // wait
                pthread_mutex_unlock(&lock); // mutex unlock
        }
        return 0;
}
void *consume_requests_loop(void *data)
        int thread_id = *((int *)data);
        while(1)
        {
                pthread_mutex_lock(&lock); // mutex lock
                if(item_to_consume >= total_items) { // 모든 아이템을 소비했으면
                        pthread_cond_signal(&cond); // send signal
                        pthread_mutex_unlock(&lock); // mutex unlock
                        break;
                }
                if (0 < curr_buf_size) { // 버퍼가 비어있지 않다면
                        print_consumed(buffer[--curr_buf_size], thread_id); // 아이템 하나 소비
                        ++item_to_consume;
                }
```

```
pthread_cond_signal(&cond); // send signal
                 pthread_cond_wait(&cond, &lock); // wait
                 pthread_mutex_unlock(&lock); // mutex unlock
        }
        return 0;
}
//write function to be run by worker threads
//ensure that the workers call the function print_consumed when they consume an item
int main(int argc, char *argv[])
{
        int *master_thread_id;
        int *worker_thread_id;
        pthread_t *master_thread;
        pthread_t *worker_thread;
        item_to_produce = 0;
        curr_buf_size = 0;
        int i;
        if (argc < 5) {
                 printf("./master-worker #total_items #max_buf_size #num_workers #masters e.g. ./exe 10000 1000 4 3\pm\n");
                 exit(1);
        }
        else {
                 num_masters = atoi(argv[4]);
```

```
num_workers = atoi(argv[3]);
         total_items = atoi(argv[1]);
         max_buf_size = atoi(argv[2]);
}
buffer = (int *)malloc (sizeof(int) * max_buf_size);
//create master producer threads
master_thread_id = (int *)malloc(sizeof(int) * num_masters);
master_thread = (pthread_t *)malloc(sizeof(pthread_t) * num_masters);
for (i = 0; i < num\_masters; i++)
        master_thread_id[i] = i;
for (i = 0; i < num\_masters; i++)
         pthread_create(&master_thread[i], NULL, generate_requests_loop, (void *)&master_thread_id[i]);
//create worker consumer threads
worker_thread_id = (int *)malloc(sizeof(int) * num_workers);
worker_thread = (pthread_t *)malloc(sizeof(pthread_t) * num_workers);
for (i = 0; i < num\_workers; i++)
        worker_thread_id[i] = i;
for (i = 0; i < num\_workers; i++)
         pthread_create(&worker_thread[i], NULL, consume_requests_loop, (void *)&worker_thread_id[i]);
//wait for all threads to complete
```

```
for (i = 0; i < num_masters; i++)
{
        pthread_join(master_thread[i], NULL);
        printf("master %d joined₩n", i);
}
for (i = 0; i < num\_workers; i++)
{
        pthread_join(worker_thread[i], NULL);
        printf("worker %d joined₩n", i);
}
/*----Peallocating Buffers-----*/
free(buffer);
free(master_thread_id);
free(master_thread);
free(worker_thread_id);
free(worker_thread);
pthread_mutex_destroy(&lock);
pthread_cond_destroy(&cond);
return 0;
```

```
- 2. Reader-Writer Locks 쓰레드 프로그램 구현
```

```
rw_lcok.h
struct rw_lock
       pthread_rwlock_t rwlock; // 첫 번째 방법에 사용할 rwlock - pthread_rwlock을 그대로 사용한다
       pthread_spinlock_t lock; // 두 번째 방법에 사용할 spinlock
       int num_of_readers; // 읽기 작업 하고있는 쓰레드의 개수
       int num_of_writers; // 쓰기 작업 하고있는 쓰레드의 개수
       int num_of_write_requests; // 쓰기 lock 요청한 쓰레드의 개수 - 두 번째 방법에 사용
};
   rw lock-r-test.c
void init_rwlock(struct rw_lock * rw)
       //
               Write the code for initializing your read-write lock.
       pthread_rwlock_init(&(rw->rwlock), NULL); // rwlock 초기화
       rw->num_of_readers = 0; // 멤버 변수 초기화
       rw->num_of_writers = 0; // 멤버 변수 초기화
       return;
}
void r_lock(struct rw_lock * rw)
{
               Write the code for aquiring read-write lock by the reader.
       //
       pthread_rwlock_rdlock(&(rw->rwlock)); // read lock
```

```
return;
}
void r_unlock(struct rw_lock * rw)
        //
                 Write the code for releasing read-write lock by the reader.
         pthread_rwlock_unlock(&(rw->rwlock)); // read unlock
        return;
}
void w_lock(struct rw_lock * rw)
{
                 Write the code for aquiring read-write lock by the writer.
        //
        pthread_rwlock_wrlock(&(rw->rwlock)); // write lock
         return;
}
void w_unlock(struct rw_lock * rw)
        //
                 Write the code for releasing read-write lock by the writer.
        pthread_rwlock_unlock(&(rw->rwlock)); // unlock rwlock
        return;
}
   rw_lock-w-test.c
void init_rwlock(struct rw_lock * rw)
```

```
Write the code for initializing your read-write lock.
       //
        pthread_spin_init(&(rw->lock), 0); // spinlock 초기화
       rw->num_of_readers = 0; // 멤버 변수 초기화
       rw->num_of_writers = 0; // 멤버 변수 초기화
       rw->num_of_write_requests = 0; // 멤버 변수 초기화
}
void r_lock(struct rw_lock * rw)
               Write the code for aquiring read-write lock by the reader.
       //
       while (1) {
                if (rw->num_of_writers <= 0 && rw->num_of_write_requests <= 0) { // 쓰기 중인 쓰레드, 쓰기 요청한
쓰레드 없다면
                        pthread_spin_lock(&(rw->lock)); // lock
                        ++(rw->num_of_readers); // 읽기 중인 쓰레드 개수 + 1
                        pthread_spin_unlock(&(rw->lock)); // unlock
                       break; // 반복 종료
               }
               sched_yield(); // 다른 쓰레드에게 넘김
       }
}
void r_unlock(struct rw_lock * rw)
       //
               Write the code for releasing read-write lock by the reader.
```

```
pthread_spin_lock(&(rw->lock)); // lock
        --(rw->num_of_readers); // 읽기 중인 쓰레드 개수 - 1
        pthread_spin_unlock(&(rw->lock)); // unlock
}
void w_lock(struct rw_lock * rw)
       //
                Write the code for aquiring read-write lock by the writer.
        pthread_spin_lock(&(rw->lock)); // lock
        ++(rw->num_of_write_requests); // 쓰기 요청한 쓰레드 개수 + 1
        pthread_spin_unlock(&(rw->lock)); // unlock
       while (1) {
                if (rw->num_of_readers <= 0 && rw->num_of_writers <= 0) { // 읽기, 쓰기 중인 쓰레드가 없다면
                        pthread_spin_lock(&(rw->lock)); // lock
                        --(rw->num_of_write_requests); // 쓰기 요청한 쓰레드 개수 - 1
                        ++(rw->num_of_writers); // 쓰기 작업중인 쓰레드 개수 + 1
                        pthread_spin_unlock(&(rw->lock)); // lock
                        break; // 반복 종료
               }
                sched_yield(); // 다른 쓰레드에게 넘김
       }
}
void w_unlock(struct rw_lock * rw)
       //
                Write the code for releasing read-write lock by the writer.
```

```
pthread_spin_lock(&(rw->lock)); // lock
        --(rw->num_of_writers); // 쓰기 작업 중인 쓰레드 개수 - 1
        pthread_spin_unlock(&(rw->lock)); // unlock
}
   my_rw_lock_test.sh
echo "******* TESTSET: Running Testcases with READER TEST *********
gcc my_reader_test.c rw_lock-r-test.c rw_lock.c -o rw_lock-r-test -lpthread
echo "Reader Test with 5 reader and 5 writer"
out=`./rw_lock-r-test 5 5`
echo -e $out
echo "******* TESTSET: Running Testcases with WRITER TEST ********* "
gcc my_writer_test.c rw_lock-w-test.c rw_lock.c -o rw_lock-w-test -lpthread
echo "Writer Test with 5 reader and 5 writer"
out=`./rw_lock-w-test 5 5`
echo -e $out
echo "******** TEST END ********* "
● my_reader_test.c (reader_test.c에서 수정한 부분만)
void *Reader(void* arg)
```

```
int threadNUmber = *((int *)arg);
        // Occupying the Lock
        printf("Reader: %d has requested the lock₩₩n", threadNUmber);
        r_lock(&rwlock);
        pthread_spin_lock(&spinlock);
        readerAcquireTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
        printf("Reader: %d has acquired the lock\\n", threadNUmber);
        usleep(10000);
        pthread_spin_lock(&spinlock);
        readerReleaseTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
        // Releasing the Lock
        r_unlock(&rwlock);
        printf("Reader: %d has released the lock₩₩n",threadNUmber);
void *Writer(void* arg)
        int threadNUmber = *((int *)arg);
```

}

```
// Occupying the Lock
        printf("Writer: %d has requested the lock ^₩₩n", threadNUmber);
        w_lock(&rwlock);
        pthread_spin_lock(&spinlock);
        writerAcquireTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
        printf("Writer: %d has acquired the lock &\₩n",threadNUmber);
        usleep(10000);
        pthread_spin_lock(&spinlock);
        writerReleaseTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
        // Releasing the Lock
        w_unlock(&rwlock);
        printf("Writer: %d has released the lock₩₩n",threadNUmber);
int main(int argc, char *argv[])
        int *threadNUmber;
```

}

```
pthread_t *threads;
       setbuf(stdout, NULL); // 정확한 결과 확인을 위해 버퍼링 없이 바로 출력.
  my_writer_test.c (writer_test.c에서 수정한 부분만)
void *Reader(void* arg)
       int threadNUmber = *((int *)arg);
       // Occupying the Lock
       printf("Reader: %d has requested the lock₩₩n", threadNUmber);
       r_lock(&rwlock);
       pthread_spin_lock(&spinlock);
       readerAcquireTime[threadNUmber] = indx;
       indx++;
       pthread_spin_unlock(&spinlock);
       printf("Reader: %d has acquired the lock₩₩n", threadNUmber);
        usleep(100000);
       pthread_spin_lock(&spinlock);
       readerReleaseTime[threadNUmber] = indx;
       indx++;
```

```
pthread_spin_unlock(&spinlock);
        // Releasing the Lock
        r_unlock(&rwlock);
        printf("Reader: %d has released the lock₩₩n",threadNUmber);
}
void *Writer(void* arg)
        int threadNUmber = *((int *)arg);
        // Occupying the Lock
        printf("Writer: %d has requested the lock ^₩₩n", threadNUmber);
        w_lock(&rwlock);
        pthread_spin_lock(&spinlock);
        writerAcquireTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
        printf("Writer: %d has acquired the lock &₩₩n",threadNUmber);
        usleep(100000);
        pthread_spin_lock(&spinlock);
        writerReleaseTime[threadNUmber] = indx;
        indx++;
        pthread_spin_unlock(&spinlock);
```

```
// Releasing the Lock
w_unlock(&rwlock);
printf("Writer: %d has released the lock\\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb{\pi}\mathbb
```

- 3. pthread를 이용한 사용자 수준 세마포어(SSU\_Sem) 구현
- SSU\_Sem.h

#include <pthread.h>

```
typedef struct SSU_Sem {
       pthread_mutex_t lock; // count 변수 접근 시에 사용할 mutex
       pthread_cond_t cond; // count 변수 접근 시에 사용할 조건변수
       int count;
} SSU_Sem;
   SSU_Sem.c
void SSU_Sem_init(SSU_Sem *s, int value) {
       pthread_mutex_init(&(s->lock), NULL); // mutex 초기화
       pthread_cond_init(&(s->cond), NULL); // 조건변수 초기화
       pthread_mutex_lock(&(s->lock)); // lock
       s->count = value; // 세마포어의 count 값 초기화
       pthread_mutex_unlock(&(s->lock)); // unlock
}
void SSU_Sem_down(SSU_Sem *s) {
       pthread_mutex_lock(&(s->lock)); // lock
       --(s->count); // count 1 감소시킴
       if (s->count < 0) { // count가 음수라면
               pthread_cond_wait(&(s->cond), &(s->lock)); // wait
       }
       pthread_mutex_unlock(&(s->lock)); // unlock
}
void SSU_Sem_up(SSU_Sem *s) {
```

pthread\_mutex\_lock(&(s->lock)); // lock

```
++(s->count); // count 1 증가시킴
       if (s-> count <= 0) { // 대기중인 쓰레드가 있다면
              pthread_mutex_unlock(&(s->lock)); // unlock
              pthread_cond_signal(&(s->cond)); // send signal
       } else {
              pthread_mutex_unlock(&(s->lock)); // unlock
       }
       return;
  SSU_Sem_toggle_test.c
SSU_Sem *sems; // 쓰레드당 하나씩 사용할 세마포어들을 저장할 배열의 인덱스
void *justprint(void *data)
{
       int thread_id = *((int *)data);
       int next_thread = (thread_id + 1) % NUM_THREADS; // 다음에 실행할 쓰레드의 thread_id를 구함
       for(int i = 0; i < NUM_ITER; i++)
       {
              SSU_Sem_down(sems + thread_id); // 세마포어 1 감소시켜 다른 쓰레드가 깨울 때 까지 wait
              printf("This is thread %d\n", thread_id); // 현재 쓰레드 id 출력
              SSU_Sem_up(sems + next_thread); // 다음 쓰레드의 세마포어 1 증가시켜 다음 쓰레드를 수행하도록 함
       }
       return 0;
```

```
}
int main(int argc, char *argv[])
{
       pthread_t mythreads[NUM_THREADS];
       int mythread_id[NUM_THREADS];
       sems = (SSU_Sem *) malloc (sizeof(SSU_Sem) * NUM_THREADS); // 쓰레드 개수만큼의 세마포어를 동적 할당한다
       for (int i = 0; i < NUM THREADS; ++i) { // 쓰레드 총 개수만큼 반복하며 세마포어를 초기화
              SSU_Sem_init(sems + i, 0); // 세마포어 count 0으로 초기화
       }
       for(int i =0; i < NUM THREADS; i++)
       {
               mythread_id[i] = i;
               pthread_create(&mythreads[i], NULL, justprint, (void *)&mythread_id[i]);
       }
       SSU_Sem_up(sems); // 첫번째 세마포어의 count를 1 증가시켜 첫번째 쓰레드를 동작시킨다
       for(int i =0; i < NUM_THREADS; i++)</pre>
       {
               pthread_join(mythreads[i], NULL);
       }
       return 0;
```

}