
Chapter 7

INERTANCE



INERTANCE RELATES THE PRESSURE DROP WITH THE RATE OF CHANGE OF FLOW. This figure shows that when blood is subjected to pressure difference the velocity will change. Assuming no friction, the relation between the pressure drop and the rate of change of blood flow, depends on the density of the blood, ρ , the cross-sectional area, A, and the length, I, of the blood vessel. We call this combined effect the inertance, $L = \rho I/A$. Inertance plays a dominating role in large blood vessels, where the viscous resistance is small and pulsatility is considerable. Inertance and Poiseuille resistance form the basis of the Oscillatory Flow Theory. The inertance and compliance in combination determine the wave speed and the characteristic impedance of a blood vessel.

Description

Blood is accelerated and decelerated with every heartbeat, and therefore the mass of the blood plays a role. The mass is density times volume, and the volume depends on the geometry of the blood vessel or heart. Blood density is a material property and is about 1.06 g/cm³. In hemodynamics, we calculate the effective mass and call it inertance. Inertance connects the oscillatory pressure drop with the rate of change of blood flow.

We can derive inertance by using Newton's law relating force, F, mass, m, and the rate of change of velocity, dv/dt, which is the acceleration, a:

$$F = m \cdot a = m \cdot dv/dt$$

For a vessel, with length l, the net force $F = \Delta P \cdot A$, A being the luminal cross-sectional area. The mass in the segment equals blood density, ρ , times the volume (length times area): $\rho \cdot (l \cdot A)$. The acceleration is the rate of change of velocity with time, i.e., dv/df. In terms of volume flow this is $(1/A) \cdot dQ/dt$. With Newton's equation this gives:

$$\Delta P \cdot A = \rho \cdot l \cdot A \cdot (1/A) \cdot dQ/dt = \rho \cdot l \cdot dQ/dt$$

SO

$$\Delta P = \rho \cdot l/A \cdot (dQ/dt) = L \cdot dQ/dt$$

Where $L = \rho \cdot l/A$ is called inertance. We recall that resistance is inversely proportional to r^4 (Chapter 2) while inertance is inversely related to r^2 . Thus, in large vessels the inertance plays a larger role than resistance while in very small arteries and arterioles it is the resistance that plays a larger role.

The inertance in combination with the compliance of a vessel segment determines the characteristic impedance and the wave speed (see Chapter 20 and Appendix 3).


Addition of series and parallel inertances

The principal rules for addition of inertance of vessels in parallel and in series are as for resistances (see Chapter 6).


Physiological and clinical relevance

The inertance is determined by the cross-sectional area and length of the blood vessel, and by blood density. Blood density varies little, even in pathologic conditions. Inertance is therefore primarily a geometrical parameter.

An example where effect of the inertance can be seen is when left ventricular and aortic pressures measured simultaneously. This is shown in the figure on the right. During the ejection phase aortic flow is first accelerating (early and then ejection) decelerating. When the blood is accelerated the left ventricular pressure higher than aortic pressure. When the



INERTANCE PLAYS A ROLE IN ACCELERATING AND DECELERATING the blood. In early systole, when left ventricular pressure is higher than aortic pressure the blood accelerates, i.e., flow increases. In late systole, aortic pressure is higher than ventricular pressure the blood still flows forward but the velocity decreases (deceleration). Adapted from [1], used by permission.



BLOOD FLOW MAY BE REVERSED, or negative, during part of the cardiac cycle. This results from inertia and reflections. With vasodilation the reflections decrease and flow reversal disappears (example from femoral artery). Adapted from [2], used by permission.

blood is decelerated the pressure difference reverses, as in the later phase of ejection. It may be seen that the pressure difference and the time derivative of flow are almost proportional in systole, suggesting inertance effects.

Inertance in combination with reflections (see Chapter 21) can result in flow reversal, i.e., negative flow during part of the cardiac cycle. This negative flow is therefore physiologic. The mean flow is, of course, always in the direction of the periphery.

Another example (see figure on the next page) is the diastolic filling of the ventricle through the mitral valve. As a