

The Live Textbook of Physical Chemistry

Volume 1: Classical Thermodynamics and Chemical Kinetics



Roberto Peverati

Contents

| | |
|--|-----------|
| Preface | vi |
| How to use this book | vii |
| 1 Systems and Variables | 1 |
| 1.1 Thermodynamic Systems | 1 |
| 1.2 Thermodynamic Variables | 5 |
| 2 Zeroth Law of Thermodynamics | 11 |
| 2.1 What is Thermodynamics? | 11 |
| 2.2 The Zeroth Law of Thermodynamics | 12 |
| 2.3 Calculation of Work | 13 |
| 2.4 Calculation of Heat | 16 |
| 3 First Law of Thermodynamics | 19 |
| 3.1 Calculation of Internal Energy Changes | 19 |
| 3.2 The First Law of Thermodynamics | 23 |
| 3.3 Reversible and Irreversible processes | 24 |
| 4 Thermochemistry | 31 |
| 4.1 Reaction Enthalpies | 31 |

| | | |
|----------|---|-----------|
| 4.2 | Standard Enthalpies of Formation | 33 |
| 4.3 | Hess's Law | 34 |
| 4.4 | Calculations of Enthalpies of Reaction at $T \neq 298\text{ K}$ | 36 |
| 5 | Thermodynamic Cycles | 39 |
| 5.1 | Carnot Cycle | 41 |
| 5.2 | Energy, Heat, and Work in the Carnot Cycle | 45 |
| 5.3 | Efficiency of a Carnot Cycle | 48 |
| 6 | Second Law of Thermodynamics | 51 |
| 6.1 | Entropy | 51 |
| 6.2 | Irreversible Cycles | 53 |
| 6.3 | The Second Law of Thermodynamics | 54 |
| 7 | Third Law of Thermodynamics | 57 |
| 7.1 | Calculation of ΔS^{sys} | 57 |
| 7.2 | Calculation of ΔS^{surr} | 60 |
| 7.3 | Clausius Theorem | 63 |
| 7.4 | The Third Law of Thermodynamics | 64 |
| 8 | Thermodynamic Potentials | 67 |
| 8.1 | Fundamental Equation of Thermodynamics | 67 |
| 8.2 | Thermodynamic Potentials | 68 |
| 8.3 | Free Energies | 71 |
| 8.4 | Maxwell Relations | 73 |
| 9 | Gibbs Free Energy | 79 |
| 9.1 | Gibbs Equation | 79 |
| 9.2 | Temperature Dependence of ΔG | 81 |
| 9.3 | Pressure Dependence of ΔG | 83 |
| 9.4 | Composition Dependence of ΔG | 84 |

| | |
|---|------------|
| 10 Chemical Equilibrium | 89 |
| 10.1 Reaction Quotient and Equilibrium Constant | 89 |
| 10.2 Temperature Dependence of K_{eq} | 92 |
| 10.3 Pressure and Composition Dependence of K_{eq} | 94 |
| 11 Ideal and Non-Ideal Gases | 99 |
| 11.1 The Ideal Gas Equation | 99 |
| 11.2 Behaviors of Non-Ideal Gases | 103 |
| 11.3 Critical Phenomena | 108 |
| 11.4 Fugacity | 112 |
| 12 Phase Equilibrium | 115 |
| 12.1 Phase Stability | 115 |
| 12.2 Gibbs Phase Rule | 119 |
| 12.3 PT Phase Diagrams | 120 |
| 12.4 The Clausius–Clapeyron Equation | 123 |
| 13 Multi-Component Phase Diagrams | 125 |
| 14 Solutions | 127 |
| 14.1 Activity | 127 |
| 14.2 Colligative Properties | 127 |
| 14.3 Binding Equilibria | 127 |
| 15 Chemical Kinetics | 129 |
| 16 Appendix | 131 |
| 16.1 Thermodynamic Data of Inorganic Substances at 298 K | 131 |
| 16.2 Thermodynamic Data of Organic Substances at 298 K | 141 |

Preface



This textbook is the official textbook for the Physical Chemistry 1 Course (CHM 3001) at Florida Tech.

The instructor for this course and author of this textbook is Dr. Roberto Peverati.

Contacts: rpeverati@fit.edu, Office: OPS 333, (321) 674-7735

Chemistry Program, Department of Biomedical and Chemical Engineering
and Science Florida Institute of Technology, Melbourne, FL.

This live open textbook is distributed under the CC-BY-SA 4.0 License and it was funded by the Florida Tech Open Educa-

tional Resources Grant Program: A Collaboration of the Teaching Council, eEducation, and the Evans Library.

How to use this book

Please read this book carefully, since everything that will be in your exams is explained here. Since this book is specifically tailored for the CHM 3001 course at Florida Tech, there are no superfluous parts. In other words, everything in it might be subject to question in the quizzes and the final exam.

Definitions and exercises are usually numbered and are highlighted in the text in this format (lighter grey, indented, and following a grey vertical bar). Please study the definitions carefully since they are fundamental concepts that will be used several times in the remainder of the text, and they will be subject to quizzes and exams. Exercises are essential for cementing the concepts, and you should attempt to execute them first without looking at the solution. Even if you were able to solve an exercise on your own, always read the solution after, since it might contain additional explanations expanding the main concepts in the text.

Navigating the book should be straightforward. On each page, there is a useful sidebar on the left that gives you an overview of all chapters, and a toolbar at the top with important tools. Arrows to shift between chapters might also be present, depending on your browser. If you are old-school and prefer a pdf, you can download a printout by clicking on the toolbar's corresponding icon. If you are *really* old-school and prefer a printed book, the best solution is to download the pdf and print it yourself. It is a LaTeX book, and I can promise you it will look good on paper. However, I cannot provide physical copies to each student. In the toolbar, you will find a useful search box that is capable of searching the entire book. The most adventurous will find in the toolbar a link to the raw GitHub source code. Feel free to head on over there and fork the book.

Each chapter of this book represents one week of work in the classroom and at home. The sidebar on the left will reflect your syllabus, as well as the main structure of the class on Canvas. The book is a live document, which means it will be updated throughout the semester with new material. While

you are not required to check it every day, you might want to review each week's chapter before the lecture on Friday.

If you spot a mistake or a typo, contact Dr. Peverati via email and you will receive a credit of up to three points towards your final score, once the typo has been verified and corrected.

Chapter 1

Systems and Variables

1.1 Thermodynamic Systems

A thermodynamic system—or just simply a system—is a portion of space with defined boundaries that separate it from its surroundings (see also the title picture of this book). The surroundings may include other thermodynamic systems or physical systems that are not thermodynamic systems. A boundary may be a real physical barrier or a purely notional one. Typical examples of systems are reported in Figure 1.1 below.¹

In the first case, a liquid is contained in a typical Erlenmeyer flask. The boundaries of the system are the glass walls of the beaker. The second system is represented by the gas contained in a balloon. The boundary is a physical barrier also in this case, being the plastic of the balloon. The third case is that of a thunder cloud. The boundary is not a well-defined physical barrier, but rather some condition of pressure and chemical composition at the interface between the cloud and the atmosphere. Finally, the fourth case is the case of an open flame. In this case, the boundary is again non-physical, and possibly even harder to define than for a cloud. For example, we can choose to define the flame based on some temperature threshold, color criterion, or even some chemical one. Despite the lack of physical boundaries, the cloud and the flame—as portions of space containing matter—can be defined as a thermodynamic system.

¹The photos depicted in this figure are taken from Wikipedia and distributed under CC-BY-SA license.



Figure 1.1: Examples of Thermodynamic Systems.

A system can exchange exclusively mass, exclusively energy, or both mass and energy with its surroundings. Depending on the boundaries' ability to transfer these quantities, a system is defined as open, closed, or isolated. An open system exchanges both mass and energy. A closed system exchanges only energy, but not mass. Finally, an isolated system does not exchange mass nor energy.

When a system exchanges mass or energy with its surroundings, some of its parameters (variables) change. For example, if a system loses mass to the surroundings, the number of molecules (or moles) in the system will decrease. Similarly, if a system absorbs some energy, one or more of its variables (such as its temperature) increase. Mass and energy can flow into the system or out of the system. Let's consider mass exchange only. If some molecules of a substance leave the system, and then the same amount of molecules flow back into the system, the system will not be modified. We can count, for example, 100 molecules leaving a system and assign them the value of -100 in an outgoing process, and then observe the same 100 molecules going back into the system and assign them a value of $+100$. Regardless of the number of molecules present in the system in the first place, the overall balance will be -100 (from the outgoing process) $+100$ (from the ingoing process) $= 0$, which brings the system to its initial situation (mass has not changed). However, from a mathematical standpoint, we could have equally assigned the label $+100$ to the outgoing process and -100 to the ingoing one, and the overall total would have stayed the same: $+100 - 100 = 0$. Which of the two labels is best? For this case, it seems natural to define a mass going

out of the system as negative (the system is losing it), and a mass going into the system as positive (the system is gaining it), but is it as straightforward for energy?

| Type of System | Mass | Energy (either heat or work) |
|-----------------|------|------------------------------|
| Open | Y | Y |
| Closed | N | Y |
| Isolated | N | N |

Here is another example. Let's consider a system that is composed of your body. When you exercise, you lose mass in the form of water (sweat) and CO₂ (from respiration). This mass loss can be easily measured by stepping on a scale before and after exercise. The number you observe on the scale will go down. Hence you have lost weight. After exercise, you will reintegrate the lost mass by drinking and eating. If you have reinstated the same amount you have lost, your weight will be the same as before the exercise (no weight loss). Nevertheless, which label do you attach to the amounts that you have lost and gained? Let's say that you are running a 5km race without drinking nor eating, and you measure your weight dropping 2 kg after the race. After the race, you drink 1.5 kg of water and eat a 500 g energy bar. Overall you did not lose any weight, and it would seem reasonable to label the 2 kg that you've lost as negative (-2) and the 1.5 kg of water that you drank and the 500 g bar that you ate as positive ($+1.5 + 0.5 = +2$). But is it the only way? After all, you didn't gain nor lose any weight, so why not calling the 2 kg due to exercise $+2$ and the 2 that you've ingested as -2 ? It might seem silly, but mathematically it would not make any difference, the total would still be zero. Now, let's consider energy instead of mass. To run the 5km race, you have spent 500 kcal, which then you reintegrate precisely by eating the energy bar. Which sign would you put in front of the kilocalories that you "burned" during the race? In principle, you've lost them, so if you want to be consistent, you should use a negative sign. But if you think about it, you've put quite an effort to "lose" those kilocalories, so it might not feel bad to assign them a pos-

itive sign instead. After all, it's perfectly OK to say, "I've done a 500 kcal run today", while it might sound quite awkward to say, "I've done a -500 kcal run today." Our previous exercise with mass demonstrates that it doesn't really matter which sign you put in front of the quantities. As long as you are consistent throughout the process, the signs will cancel out. If you've done a +500 kcal run, you've eaten a bar for -500 kcal, resulting in a total zero loss/gain. Alternatively, if you've done a -500 kcal run, you would have eaten a +500 kcal bar, for a total of again zero loss/gain.

These simple examples demonstrate that the sign that we assign to quantities that flow through a boundary is arbitrary (i.e., we can define it any way we want, as long as we are always consistent with ourselves). There is no best way to assign those signs. If you ask two different people, you might obtain two different answers. But we are scientists, and we must make sure to be rigorous. For this reason, chemists have established a convention for the signs that we will follow throughout this course. If we are consistent in following the convention, we are guaranteed to never make any mistake with the signs.

Definition 1.1. *The chemistry convention of the sign is system-centric:²*

- *If something (energy or mass) goes **into** the system it has a **positive** sign (the system is gaining)*
- *If something (energy or mass) goes **out of** the system it has a **negative** sign (the system is losing)*

If you want a trick to remember the convention, use the weight loss/gain during the exercise example above. You are the system, if you lose weight, the kilograms will be negative (-2 kg), while if you gain weight, they will be

²Notice that physicists use a different sign convention when it comes to thermodynamics. To eliminate confusion, I will not describe the physics convention here, but if you are reading thermodynamics on a physics textbook, or if you are browsing the web and stumble on thermodynamics formula (e.g., on Wikipedia), please be advised that some quantity, such as work, might have a different sign than the one that is used in this textbook. Obviously, the science will not change, but you need to be *always* consistent, so if you decide that you want to use the physics convention, make sure to *always* use the physics convention. In this course, on the other hand, we will *always* use the chemistry one, as introduced above.

positive (+2 kg). Similarly, if you eat an energy bar, you are the system, and you will have increased your energy by +500 kcal (positive). In contrast, if you burned energy during exercise, you are the system, and you will have lost energy, hence -500 kcal (negative). If the system is a balloon filled with gas, and the balloon is losing mass, you are the balloon, and you are losing weight; hence the mass will be negative. If the balloon is absorbing heat (likely increasing its temperature and increasing its volume), you are the system, and you are gaining heat; hence heat will be positive.

1.2 Thermodynamic Variables

The system is defined and studied using parameters that are called variables. These variables are quantities that we can measure, such as pressure and temperature. However, they don't be surprised if, on some occasions, you encounter some variable that is a little harder to measure directly, such as entropy. The variables depend only on the current state of the system, and therefore they define it. If I know the values of all the "relevant variables" of a system, I know the state of the system. The relationship between the variables is described by mathematical functions called state functions, while the "relevant variables" are called natural variables.

What are the "relevant variables" of a system? The answer to this question depends on the system, and it is not always straightforward. The simplest case is the case of an ideal gas, for which the natural variables are those that enter the ideal gas law and the corresponding equation:

$$PV = nRT \tag{1.1}$$

Therefore, the natural variables for an ideal gas are the pressure P, the volume V, the number of moles n, and the temperature T, with R being the ideal gas constant. Recalling from the general chemistry courses, R is a universal dimensional constant which has the values of $R = 8.31 \text{ kJ/mol}$ in SI units.

We will use the ideal gas equation and its variables as an example to discuss variables and functions in this chapter. We will analyze more complicated cases in the next chapters. Variables can be classified according to numerous criteria, each with its advantages and disadvantages. A typical classification is:

- **Physical variables** (P , V , T in the ideal gas law): independent on the chemical composition of the system.

- **Chemical variables** (n in the ideal gas law): dependent on the chemical composition of the system.

Another useful classification is:

- **Intensive variables** (P, T in the ideal gas law): independent on the physical size (extension) of the system.
- **Extensive variables** (V, n in the ideal gas law): dependent on the physical size (extension) of the system.

When we deal with thermodynamic systems, it is more convenient to work with intensive variables. Luckily, it is relatively easy to convert extensive variables into intensive ones by just taking the ratio between the two of them. For an ideal gas, by taking the ratio between V and n , we obtained the intensive variable called molar volume:

$$\bar{V} = \frac{V}{n}. \quad (1.2)$$

We can then recast eq. (1.1) as:

$$P\bar{V} = RT, \quad (1.3)$$

which is the preferred equation that we will use for the remainder of this course. The ideal gas equation connects the 3 variables pressure, molar volume, and temperature, reducing the number of independent variables to just 2. In other words, once 2 of the 3 variables are known, the other one can be easily obtained using these simple relations:

$$P(T, \bar{V}) = \frac{RT}{\bar{V}}, \quad (1.4)$$

$$\bar{V}(T, P) = \frac{RT}{P}, \quad (1.5)$$

$$T(P, \bar{V}) = \frac{P\bar{V}}{R}. \quad (1.6)$$

These equations define three state functions, each one expressed in terms of two independent natural variables. For example, eq. (1.4) defines the

state function called “pressure”, expressed as a function of temperature and molar volume. Similarly, eq. (1.5) defines the “molar volume” as a function of temperature and pressure, and eq. (1.6) defines the “temperature” as a function of pressure and molar volume. When we know the natural variables that define a state function, we can express the function using its total differential, for example for the pressure $P(T, \bar{V})$:

$$dP = \left(\frac{\partial P}{\partial T} \right) dT + \left(\frac{\partial P}{\partial \bar{V}} \right) d\bar{V} \quad (1.7)$$

Recalling Schwartz’s theorem, the mixed partial second derivatives that can be obtained from eq. 1.2.7 are the same:

$$\frac{\partial^2 P}{\partial T \partial \bar{V}} = \frac{\partial}{\partial \bar{V}} \frac{\partial P}{\partial T} = \frac{\partial}{\partial T} \frac{\partial P}{\partial \bar{V}} = \frac{\partial^2 P}{\partial \bar{V} \partial T} \quad (1.8)$$

Which can be easily verified considering that:

$$\frac{\partial}{\partial \bar{V}} \frac{\partial P}{\partial T} = \frac{\partial}{\partial \bar{V}} \left(\frac{R}{\bar{V}} \right) = -\frac{R}{\bar{V}^2} \quad (1.9)$$

and

$$\frac{\partial}{\partial T} \frac{\partial P}{\partial \bar{V}} = \frac{\partial}{\partial T} \left(\frac{-RT}{\bar{V}^2} \right) = -\frac{R}{\bar{V}^2} \quad (1.10)$$

While for the ideal gas law, all the variables are “well-behaved” and always satisfy Schwartz’s theorem, we will encounter some variable for which Schwartz’s theorem does not hold. Mathematically, if the Schwartz’s theorem is violated (i.e., if the mixed second derivatives are not equal), then the corresponding function cannot be integrated, hence it is not a state function. The differential of a function that cannot be integrated cannot be defined exactly. Thus, these functions are called path functions; that is, they depend on the path rather than the state. The most typical examples of path functions that we will encounter in the next chapters are heat (Q) and work (W). For these functions, we cannot define exact differentials dQ and dW , and we must introduce a new notation to define their “inexact differentials” dQ and dW .

We will return on exact and inexact differential when we discuss heat and work, but for this chapter, it is crucial to notice the difference between a state function and a path function. A typical example to understand the difference between state and path function is to consider the distance between two geographical locations. Let's, for example, consider the distance between New York City and Los Angeles. If we fly straight from one city to the other, there are roughly 4,000 km between them. This "air distance" depends exclusively on the geographical location of the two cities. It stays constant regardless of the method of transportation that I have accessibility to travel between them. Since the cities' positions depend uniquely on their latitudes and longitudes, the "air distance" is a state function, i.e., it is uniquely defined from a simple relationship between measurable variables. However, the "air distance" is not the distance that I will practically have to drive when I go from NYC to LA. Such "travel distance" depends on the method of transportation that I decide to take (airplane vs. car vs. train vs. boat vs. . . .). It will depend on a plentiful amount of other factors such as the choice of the road to be traveled (if going by car), the atmospheric conditions (if flying), and so on. A typical "travel distance" by car is, for example, about 4,500 km, which is about 12% more than the "air distance." Indeed, we could even design a very inefficient road trip that avoids all highways and will result in a "travel distance" of 8,000 km or even more (200% of the "air distance"). The "travel distance" is a clear example of a path function because it depends on the specific path that I decide to travel to go from NYC to LA. See Figure 1.2.




Figure 1.2: State Functions vs. Path Functions.

Chapter 2

Zeroth Law of Thermodynamics

2.1 What is Thermodynamics?

Thermodynamics is the branch of science that deals with heat and work, and their relation to energy. As the definition suggests, thermodynamics is concerned with two types of energy: heat and work. A formal definition of these forms of energy is as follow:

- Work is exchanged if external parameters are changed during the process.
- Heat is exchanged if only internal parameters are changed during the process.

As we saw in chapter 1, though, heat and work are not “well-behaved” quantities because they are path functions. On the one hand, it might be simple to measure the amount of heat and/or work experimentally, these measured quantities cannot be used to define the state of a system. Since heat and work are path functions, their values depend directly on the methods used to transfer them (their paths). Understanding and quantifying these energy transfers is the reason why thermodynamics was developed in the first place. The origin of thermodynamics dates back to the seventeenth century when people began to use heat and work for technological applications. These early scientists needed a mathematical tool to understand how heat and work were related to each other, and how they were related to the other variables that they were able to measure, such as temperature and volume.

Before we even discuss the definition of energy and how it relates to heat and work, it is crucial to introduce the essential concept of temperature. Temperature is an intuitive concept that has a surprisingly complex definition at the microscopic level.¹ However, for all our purposes, it is not essential to have a microscopic definition of temperature, as long as we have the guarantee that this quantity can be measured unambiguously. In other words, we need a mathematical definition of temperature that agrees with the physical existence of thermometers.

2.2 The Zeroth Law of Thermodynamics

The mathematical definition that guarantees that the thermal equilibrium is an equivalence relation is called the zeroth law of thermodynamics. The zeroth law of thermodynamics states that if two thermodynamic systems are each in thermal equilibrium with a third one, then they are in thermal equilibrium with each other. The law might appear trivial and possibly redundant, but it is a fundamental requirement for the mathematical formulation of thermodynamics, so it needs to be stated. The zeroth law can be summarized by the following simple mathematical relation:

Definition 2.1. *Zeroth Law of Thermodynamics:* If $T_A = T_B$, and $T_B = T_C$, then $T_A = T_C$.

Notice that when we state the zeroth law, it appears intuitive. However, this is not necessarily the case. Let's, for example, consider a pot of boiling water at $P = 1 \text{ atm}$. Its temperature, T_{H_2O} , is about 373 K. Let's now submerge in this water a coin made of wood and another coin made of metal. After some sufficient time, the wood coin will be in thermal equilibrium with the water, and its temperature $T_W = T_{H_2O}$. Similarly, the metal coin will also be in thermal equilibrium with the water, hence $T_M = T_{H_2O}$. According to the zeroth law, the temperature of the wood coin and that of the metal coin are precisely the same $T_W = T_M$, even if they are not in direct contact with each other. Now here's the catch: since wood and metal transmit heat in different manners if I take the coins out of the water and put them immediately in your hands, one of them will be very hot, but the other will burn you. If you had to guess the temperature of the two coins without

¹In fact, we will not even give a rigorous microscopic definition of temperature within this textbook.

a thermometer, and without knowing that they were immersed in boiling water, would you suppose that they have the same temperature? Probably not.

2.3 Calculation of Work

In thermodynamics, work (W) is the ability of a system to transfer energy by exerting a force on its surroundings. Work can be measured simply by evaluating its effects, such as displacing a massive object by some amount of space. The mathematical treatment of work, however, is complicated because *work is a path function*. In the following sections, we will analyze how work is calculated in some prototypical situations commonly encountered in the thermodynamical treatment of systems.

2.3.1 Free expansion at constant temperature




Figure 2.1: Free Expansion at Constant Temperature of an Ideal Gas.

Let's consider the situation in Figure 2.1, where a special beaker with a piston that is free to move is filled with an ideal gas. The beaker sits in a horizontal position on a desk, so the piston is not subject to any external forces². The piston is initially compressed to a position that is not in equilibrium (i). After the process, the piston reaches a final equilibrium

²For this simple thought experiment, we will ignore any external force that is not significant. In other words, we will not consider the friction of the piston on the beaker walls or any other foreign influence.

position (f). We assume that the only force acting on the piston is the pressure of the ideal gas, P . How do we calculate the work (W) performed by the system?

From basic physics, we recall that the infinitesimal amount of work associated with an object moving in space is given by the force acting on the object (F) multiplied by the infinitesimal amount it gets displaced (dh):

$$dW = -Fdh, \quad (2.1)$$

where the negative sign comes from the chemistry sign convention, Definition 1.1, since the work in Figure 2.1 is *performed* by the system (expansion). What kind of force is moving the piston? It is the force due to the pressure of the gas. Relying upon another definition from physics, the pressure is the ratio between the force (F) and the area (A) that such force acts upon:

$$P = F/A. \quad (2.2)$$

Obtaining F from eq. (2.2) and replacing it in eq. (2.1), we obtain:

$$dW = -P \underbrace{Adh}_{dV}, \quad (2.3)$$

and considering that Adh (area times infinitesimal height) is the definition of an infinitesimal volume dV , we obtain:

$$dW = -PdV, \quad (2.4)$$

If we want to calculate the amount of work performed by a system, W , from eq. (2.4), we need to recall that dW is an inexact differential. As such, we cannot integrate it from initial to final as for the (exact) differential of a state function, because:

$$\int_i^f dW \neq W_f - W_i, \quad (2.5)$$

but rather:

$$\int_{\text{path}} dW = W, \quad (2.6)$$

where the integration is performed along the *path*. Using eq. (2.6), we can integrate eq. (2.4) as:

$$\int dW = W = - \int_i^f P dV, \quad (2.7)$$

where the integral on the left-hand side is taken along the path,³ while the integral on the right-hand side can be taken between the initial and final states, since dV is a state function. How do we solve the integral in eq. (2.7)? The pressure in this process is not constant since it decreases throughout the process. Therefore P cannot be moved outside the integral. However, if our gas is ideal, we can calculate the pressure using the ideal gas law $P = \frac{nRT}{V}$, and solve the integral because n , R , and T are constant:

$$W = -nRT \int_i^f \frac{dV}{V} = -nRT \ln \frac{V_f}{V_i}, \quad (2.8)$$

which, considering that $P_i V_i = P_f V_f$, can be also written as:

$$W = -nRT \ln \frac{P_i}{P_f}. \quad (2.9)$$

2.3.2 Isothermal expansion against a constant external pressure

The process that we are analyzing here (Figure 2.2) is apparently similar to the case we have seen in the previous section, with the noticeable difference that the beaker now sits vertically on the workbench. In this case, when the piston moves upwards, it is no longer moving freely, but it moves against the force due to the constant external pressure P_{ext} .

The integral that describes the work performed by the system in this case involves a transformation at constant external pressure:

$$\int dW = W = - \int_i^f P_{\text{ext}} dV, \quad (2.10)$$

³from here on we will replace the notation \int_{path} with the more convenient \int and we will keep in mind that the integral of an inexact differential must be taken along the path.




Figure 2.2: Isothermal Expansion of an Ideal Gas Against a Constant External Pressure.

which can be easily simplified as:

$$W = - \int_i^f P_{\text{ext}} dV = -P_{\text{ext}} \int_i^f dV = -P_{\text{ext}}(V_f - V_i), \quad (2.11)$$

resulting in the following simple formula to calculate W :

$$W = -P_{\text{ext}} \Delta V, \quad (2.12)$$

Comparing eq. (2.12) with eq. (2.9) shows how different this case is from the previous one.

2.4 Calculation of Heat

Heat (Q) is a property that gets transferred between substances. Similarly to work, the amount of heat that flows through a boundary can be measured, but its mathematical treatment is complicated because *heat is a path function*. As you probably recall from general chemistry, the ability of a substance to absorb heat is given by a coefficient called the heat capacity, which is measured in SI in $\frac{\text{J}}{\text{mol K}}$. However, since heat is a path function, these coefficients are not unique, and we have different ones depending on how the heat transfer happens.

2.4.1 Processes at constant volume (isochoric)

The heat capacity at constant volume measures the ability of a substance to absorb heat at constant volume. Recasting from general chemistry:

The molar heat capacity at constant volume is the amount of heat required to increase the temperature of 1 mol of a substance by 1 K at constant volume.

This simple definition can be written in mathematical terms as:

$$C_V = \frac{dQ_V}{dT} \Rightarrow dQ_V = nC_V dT. \quad (2.13)$$

Given a known value of C_V , the amount of heat that gets transferred can be easily calculated by measuring the changes in temperature, after integration of eq. (2.13):

$$dQ_V = nC_V dT \rightarrow \int dQ_V = n \int_{T_i}^{T_F} C_V dT \rightarrow Q_V = nC_V \int_{T_i}^{T_F} dT, \quad (2.14)$$

which, assuming C_V independent of temperature, simply becomes:

$$Q_V \cong nC_V \Delta T. \quad (2.15)$$

2.4.2 Processes at constant pressure (isobaric)

Similarly to the previous case, the heat capacity at constant pressure measures the ability of a substance to absorb heat at constant pressure. Recasting again from general chemistry:

The molar heat capacity at constant pressure is the amount of heat required to increase the temperature of 1 mol of a substance by 1 K at constant pressure.

And once again, this mathematical treatment follows:

$$C_P = \frac{dQ_P}{dT} \Rightarrow dQ_P = nC_PdT \rightarrow \int dQ_P = n \int_{T_i}^{T_f} C_PdT, \quad (2.16)$$

which result in the simple formula:

$$Q_P \cong nC_P\Delta T. \quad (2.17)$$

Chapter 3

First Law of Thermodynamics

3.1 Calculation of Internal Energy Changes

The internal energy (U) of a system is a thermodynamic state function defined as:

Definition 3.1. *Internal Energy:* Property of a system that can be either transferred or converted.

In the absence of chemical transformations, heat and work are the only two forms of energy that thermodynamics is concerned with. Keeping in mind Definition 1.1, which gives the convention for the signs of heat and work, the internal energy of a system can be written as:

$$U = Q + W, \quad (3.1)$$

which we can write in differential form by considering that the internal energy is a state function, as:

$$dU = dQ + dW, \quad (3.2)$$

which, using eq. (2.4) becomes:

$$dU = dQ - PdV. \quad (3.3)$$

3.1.1 Internal energy in isothermal processes

To study the behavior of the internal energy in a process at constant temperature ($dT = 0$), James Prescott Joule (1818–1889) created the apparatus depicted in Figure 3.1.




Figure 3.1: The Joule Expansion Experiment.

The left side of the Joule apparatus's inner chamber is filled with an ideal gas, while a vacuum is created in the right chamber. Both chambers are immersed in a water bath, to guarantee isolation from the environment. When the communication channel between the chambers is open, the gas expands and equilibrates. The work associated with the transformation is:

$$dW = P_{\text{ext}} dV = 0, \quad (3.4)$$

since the chambers are not in communication with the environment, $P_{\text{ext}} = 0$. Thus, changes in internal energy are associated with the heat transfer of the process, which can be measured by monitoring the temperature of the gas at the beginning, T_i , and at the end of the experiment T_f . Joule noticed experimentally that if he used an ideal gas for this experiment, the temperature would not change $T_i = T_f$. Since the temperature doesn't change, there is no heat transfer, and therefore the internal energy stays constant:

$$dU = dQ = 0. \quad (3.5)$$

Notice that Joule's conclusion is valid only for an ideal gas. If we expand a real gas, we do notice a change in temperature associated with the expansion. A typical example of this behavior is when you use a pressurized spray bottle and release its content for an extended time in the air. The container will typically get

colder. We will discuss this behavior in chapter 11 when we will study non-ideal gases.

From this simple experiment, we can conclude that the internal energy of an ideal gas depends only on its temperature.

3.1.2 Internal energy in adiabatic processes

An adiabatic process is defined as a process that happens without the exchange of heat. As such, $dQ = 0$, and the work associated with an adiabatic process becomes a state function:

$$dU = dW = PdV, \quad (3.6)$$

which can then be calculated using the formulas that we derived in section 2.3. Notice that isothermal and adiabatic are two very different processes. While an adiabatic process happens without the exchange of heat across the system's boundaries, this does not mean that the system's temperature does not change. Isothermal processes are usually associated with a heat transfer across the boundaries to maintain the temperature of the system constant. For adiabatic processes, it is quite the opposite since they are usually associated with a change in temperature.

3.1.3 Internal energy in isochoric processes

An isocoric process is a process in which the volume does not change. Therefore, $dW = 0$, and $dU = dQ_V$, which for 1 mol of substance and using eq. (2.13), becomes:

$$dU = dQ_V = nC_VdT. \quad (3.7)$$

Since no work is performed at these conditions, the heat becomes a state function. Eq. (3.7) also gives a mathematical justification of the concept of heat capacity at constant volume. C_V can now be interpreted as the partial derivative (a coefficient) of a state function (the internal energy):

$$C_V = \left(\frac{\partial U}{\partial T} \right)_{V,n}, \quad (3.8)$$

where we have replaced the total derivative d with a partial one ∂ , and we have specified that the derivation happens at constant volume and number of moles. Eq. (3.8) equation brings a rigorous definition of heat capacity at constant volume for 1 mol of substance:

Definition 3.2. *The heat capacity of a substance, C_V , represents its ability to absorb energy at constant volume.*

3.1.4 Internal energy in isobaric processes

In an isobaric process, the pressure does not change, hence $dP = 0$. Unfortunately, eq. (3.2) for this case does not simplify further, as happened in the two previous cases. However, in section 2.4.2, we have introduced the useful concept of heat capacity at constant P . C_P was used in an adiabatic process in the same manner as C_V was used in the isochoric case. That is, as a coefficient to measure the amount of heat absorbed at constant pressure. Eq. (3.8) gave a mathematical definition of C_V as the partial derivative of a state function (the internal energy). But if heat capacities are coefficients, and coefficients are partial derivatives of state functions, how do we explain C_V ?

In order to do so, we can introduce a new state function, called the enthalpy (H), as:

$$H = U + PV, \quad (3.9)$$

and its differential, calculated as:

$$dH = dU + d(PV) = dU + PdV + \overbrace{VdP}^0, \quad (3.10)$$

which can be rearranged as:

$$dU = dH - PdV, \quad (3.11)$$

Replacing eq. (3.11) into eq. (3.3):

$$dH - PdV = dQ_P - PdV, \quad (3.12)$$

which simplifies to:

$$dH = dQ_P. \quad (3.13)$$

Eq. (3.13) establishes that the heat exchanged at constant pressure is equal to a new state function called the enthalpy, defined by eq. (3.9). It also establishes a mathematical justification of the concept of heat capacity at constant pressure. Similarly to C_V , C_P can now be interpreted as the partial derivative (a coefficient) of the new state function (the enthalpy):

$$C_P = \left(\frac{\partial H}{\partial T} \right)_{P,n}, \quad (3.14)$$

Eq. (3.14) brings also a rigorous definition of heat capacity at constant pressure for 1 mol of substance:

Definition 3.3. *The heat capacity of a substance, C_P , represents its ability to absorb enthalpy at constant pressure.*

3.2 The First Law of Thermodynamics

We finally come to a working definition of the first law. If we take an isolated system—i.e., a system that does not exchange heat nor mass with its surroundings—its internal energy is conserved. If the internal energy is conserved, $dU = 0$. Therefore, for an isolated system:

$$dQ = -dW, \quad (3.15)$$

and heat and work can be easily calculated using any of the appropriate formulas introduced in either section 2.3 or 2.4.


The first law is a conservation law. It is intuitive since it comes directly from Lavoisier's principle of "nothing is lost, nothing is created, everything is transformed." Considering that the only system that is truly isolated is the universe, we can condense the first law in one simple sentence:

Definition 3.4. First Law of Thermodynamics: The energy of the universe is conserved.


3.3 Reversible and Irreversible processes

3.3.1 Calculation of $|W_{\max}|$ and $|W_{\min}|$

Let's go back to the calculation of the work in a process at constant temperature. We can use the formulas obtained in section 2.3 to understand a little bit better the meaning of a *path function*. Let's consider the following PV diagram, obtained from an ideal gas at constant $T = 298$ K:




where the isothermal expansion happens between P_i and P_f . If the expansion happens in a one-step fast process, for example against a constant pressure $P_f = P_{\text{ext}}$, the work is given by eq. (2.12). On the plot, the absolute value of the work¹ is represented by the red area:



¹we use the absolute value to avoid confusions due to the fact that the expansion work is negative according to Definition 1.1.


$$|W_{1\text{-step}}| = P_{\text{ext}}(V_f - V_i) \quad (3.16)$$

However, if the process happens in two steps, by pausing at position (1) until equilibrium is reached, then we should calculate the work by dividing the process into two. The first process is an expansion between P and P_1 , whose absolute value of the work, W_A , is represented by the blue area:




$$|W_A| = P_1(V_1 - V_i) \quad (3.17)$$

The second process is an expansion between P_1 and P_{ext} , whose absolute value of the work is represented by the green area:



$$|W_B| = P_f(V_f - V_1) \quad (3.18)$$

The total absolute value of the work for the 2-step process is given by the sum of the two areas:




$$|W_{2\text{-step}}| = |W_A| + |W_B| = P_i(V_1 - V_i) + P_f(V_f - V_1). \quad (3.19)$$

As can be easily verified by comparing the shaded areas in the plots, $|W_{2\text{-step}}| > |W_{1\text{-step}}|$.

We can easily extend this procedure to consider processes that happens in 3, 4, 5, ..., n steps. What is the limit of this procedure? In other words, what happens when $n \rightarrow \infty$? A simple answer is given by the plots in the next Figure, which clearly demonstrates that the maximum value of the area underneath the curve $|W_{\max}|$ is achieved in an ∞ -step process, for which the work is calculated as:

$$|W_{\infty\text{-step}}| = |W_{\max}| = \sum_n^{\infty} P_n(V_n - V_{n-1}) = \int_i^f P dV. \quad (3.20)$$



The integral on the right hand side of eq. (3.20) is similar to the integral that we already solved for eq. (2.8). Using the same trick, we can solve eq. (3.20) for an ideal gas as:

$$|W_{max}| = nRT \int_i^f \frac{dV}{V} = nRT \ln \frac{V_f}{V_i}. \quad (3.21)$$

This example demonstrates why work is a path function. If we perform a fast 1-step expansion, the system will perform an amount of work that is much smaller than the amount of work it can perform if the expansion between the same points happens slowly in an ∞ -step process.

The same considerations that we made up to this point for expansion processes hold specularly for compression ones. The only difference is that the work associated with compressions will have a positive sign since it must be performed onto the system. As such, the amount of work for a transformation that happens in a finite amount of steps will be an upper bound to the minimum amount of work required to compress the system.² $|W_{min}|$ for compressions is calculated as the area underneath the PV curve, exactly as $|W_{max}|$ for expansions in eq. (3.20).

²In contrast to a lower bound for expansion processes.

3.3.2 Cycles and reversibility

Let's now consider the cycle in Figure 3.2. The process in this case starts from state 1 (system at P_1V_1), expands to state 2 (system at P_2V_2), and compresses back to state 1 (system back to P_1V_1).




Figure 3.2: Expansion/Compression Cycle of an Ideal Gas.

Since the process starts and finishes at the same state, the value of the internal energy at the end of the process will be the same as its value at the beginning, regardless of the path:³

$$\oint dU = 0, \quad (3.22)$$

where the symbol \oint indicates an integral around a cycle. Considering the work associated with the cycle, however, the situation is radically different because it depends on the path that the system is taking, and in general

$$\oint_{\text{path}} dW \neq 0. \quad (3.23)$$

³recall that the internal energy is a state function, so its value depends exclusively from the conditions at the beginning and at the end. In a cycle, we're going back to the same point, so the conditions at the beginning and at the end are equal by definition.

For instance, if we perform the expansion in one step, the work associated with it will be (using eq. (2.12)):⁴

$$W_{\text{1-step}}^{\text{expansion}} = -P_2 \underbrace{(V_2 - V_1)}_{>0} < 0, \quad (3.24)$$

and if we also perform the compression in 1-step:⁵

$$W_{\text{1-step}}^{\text{compression}} = -P_1 \underbrace{(V_2 - V_1)}_{<0} > 0. \quad (3.25)$$

With a little bit of math, it is easy to prove that the total work for the entire cycle is:

$$\begin{aligned} W_{\text{1-step}}^{\text{cycle}} &= W_{\text{1-step}}^{\text{expansion}} + W_{\text{1-step}}^{\text{compression}} \\ &= -P_2(V_2 - V_1) - P_1(V_1 - V_2) \\ &= -P_2(V_2 - V_1) + P_1(V_2 - V_1) \\ &= \underbrace{(V_2 - V_1)}_{>0} \underbrace{(P_1 - P_2)}_{>0} > 0, \end{aligned} \quad (3.26)$$

or, in other words, net work is destroyed.

In practice, if we want to manually perform this cycle by pushing on the piston by hand, we will notice that it requires more energy to push down than the amount it gives back when we release it, and it moves back up.

In contrast, if both the expansion and the compression happen in a slow ∞ -step manner, the work associated with them will be W_{\max} and W_{\min} , respectively, which are calculated using eq. (3.21). The total work related with the cycle will be in this case:

⁴notice that the work for the expansion is negative, as it should be.

⁵notice that the work for the compression is positive, as it should be.

$$\begin{aligned}
 W_{\infty\text{-step}}^{\text{cycle}} &= W_{\max}^{\text{expansion}} + W_{\min}^{\text{compression}} \\
 &= -nRT \ln \frac{V_f}{V_i} - nRT \ln \frac{V_i}{V_f} \\
 &= -nRT \underbrace{\left(\ln \frac{V_f}{V_i} - \ln \frac{V_f}{V_i} \right)}_{=0} = 0,
 \end{aligned} \tag{3.27}$$

which means that, in this case, work is not destroyed nor created.

In practice, if we were able to perform this cycle manually by pushing on the piston down by hand, we will notice that it requires the same amount of energy to push down than the amount it gives back when it moves up.

This process can happen both ways without losses, and is called *reversible*:

Definition 3.5. *Reversible process:* a process whose direction can be returned to its original position by inducing infinitesimal changes to some property of the system via its surroundings.⁶

Reversible processes are ideal processes that are hard to realize in practice since they require transformations that happen in an infinite amount of steps (infinitely slowly).

⁶Definition from: Sears, F.W. and Salinger, G.L. (1986), Thermodynamics, Kinetic Theory, and Statistical Thermodynamics, 3rd edition (Addison-Wesley.)

Chapter 4

Thermochemistry

4.1 Reaction Enthalpies

In the previous chapter, we have discussed thermodynamical changes in energy in the absence of chemical reactions. When a chemical reaction takes place, some bonds break and/or some new one form. This process either absorbs or releases the energy contained in these bonds. For a proper thermodynamic treatment of the system, this extra energy must be included in the net balance.

In this chapter, we will consider the heat associated with chemical reactions. Since most chemical reactions happen at constant atmospheric pressure (isobaric conditions) in the lab, we can use eq. (3.13) to replace the inexact differential of the heat with the exact differential of the state function called enthalpy. The advantage of this transformation is that it allows us to study the heat associated with chemical reactions at constant pressure independently of their path. If we call the molecules at the beginning of the reaction “reactants” and the molecules at the end of the reaction “products,” the heat associated with the reaction (rxn) is defined as:

$$\Delta_{\text{rxn}} H = H_{\text{products}} - H_{\text{reactants}} . \quad (4.1)$$

For example, if we take a simple reaction of the form:



the heat at constant pressure is equal to the enthalpy of reaction, which is calculated as:


$$Q_P = \Delta_{\text{rxn}}H = \underbrace{(H_C + H_D)}_{\text{products}} - \underbrace{(H_A + H_B)}_{\text{reactants}}. \quad (4.2)$$

Using the chemistry sign convention, Definition 1.1, reactions are classified in terms of the sign of their reaction enthalpies as follows:

Definition 4.1.

- $\Delta_{\text{rxn}}H > 0 \Rightarrow$ *Endothermic reaction* (heat is gained by the system).
- $\Delta_{\text{rxn}}H < 0 \Rightarrow$ *Exothermic reaction* (heat is lost by the system).

If we expand the sample reaction to account for its stoichiometry:



where a, b, c, d are the stoichiometric coefficients of species A, B, C, D. Eq. (4.2) can be rewritten as:

$$Q_P = \Delta_{\text{rxn}}H = \underbrace{(cH_C + dH_D)}_{\text{products}} - \underbrace{(aH_A + bH_B)}_{\text{reactants}}, \quad (4.3)$$

while for the most general case we can write it:

$$\Delta_{\text{rxn}}H = \sum_i \nu_i H_i, \quad (4.4)$$

where ν_i is the stoichiometric coefficient of species i with its own sign. The signs of the stoichiometric are defined according to eq. (4.3) as:

Definition 4.2. Signs of the stoichiometric coefficients:

- ν_i is **positive** if i is a **product**.
- ν_i is **negative** if i is a **reactant**.


4.2 Standard Enthalpies of Formation

In principle, we could use eq. (4.3) to calculate the reaction enthalpy associated with any reaction. However, to do so, the absolute enthalpies H_i of reactants and products would be required. Unfortunately, absolute enthalpies are not known—and theoretically unknowable, since this would require an absolute zero for the enthalpy scale, which does not exist.¹ To prevent this problem, enthalpies relative to a defined reference state must be used. This reference state is defined at the constituent elements in their standard state, and the enthalpies of 1 mol of substance in this reference state are called **standard enthalpies of formation**.

Definition 4.3. The *standard enthalpy of formation* of compound i , $\Delta_f H_i^\ominus$, is the change of enthalpy during the formation of 1 mol of i from its constituent elements, with all substances in their standard states.

The standard pressure is defined at $P^\ominus = 100 \text{ kPa} = 1 \text{ bar}$.² There is no standard temperature, but standard enthalpies of formation are usually reported at room temperature, $T = 298.15 \text{ K}$. Standard states are indicated with the symbol \ominus and they are defined for elements as the form in which such element is most stable at standard pressure (for example, for hydrogen, carbon, and oxygen the standard states are $\text{H}_{(g)}$, $\text{C}_{(s,\text{graphite})}$, and $\text{O}_{2(g)}$, respectively).³

For example, the standard enthalpies of formation of some common compounds at $T = 298.15 \text{ K}$ are calculated from the following reactions:



¹An example of a known absolute zero for a scale is the zero of the temperature scale, a temperature that can be approached only as a limit from above. No such thing exists for the enthalpy.


²prior to 1982 the value of $P^\ominus = 1.0 \text{ atm}$ was used. The two values of P^\ominus are within 1% of each other, since $1 \text{ atm} = 101.325 \text{ kPa}$.

³There are some exceptions, such as phosphorus, for which the most stable form at 1 bar is black phosphorus, but white phosphorus is chosen as the standard reference state for zero enthalpy of formation. For the purposes of this course, however, we can safely ignore them.

A comprehensive list of standard enthalpies of formation of inorganic and organic compounds is also reported in appendix 16.

4.3 Hess's Law

The calculation of a standard reaction enthalpy can be performed using the following cycle:



This process is summarized by the simple formula:

$$\Delta_{\text{rxn}} H^\ominus = \Delta_f H^\ominus_{\text{products}} - \Delta_f H^\ominus_{\text{reactants}}. \quad (4.7)$$


Notice how there is a negative sign in front of the enthalpy of formation of the reactants because they are normally defined for the reactions that go from the elements to the reactants and not vice-versa. To close the cycle in eq. (4.6), however, we should go from the reactants to the elements, and therefore we must invert the sign in front of the formation enthalpies of the reactants. Eq. (4.7) can be generalized using the same technique used to derive eq. (4.4), resulting in:

$$\Delta_{\text{rxn}} H^\ominus = \sum_i \nu_i \Delta_f H_i^\ominus, \quad (4.8)$$

which is a mathematical expression of the law that is known as **Hess's Law**. Hess's law is valid at constant pressure because, at those conditions, the heat of reaction—a path function—is equal to the enthalpy of reaction—a state function. Therefore, the enthalpy of a reaction depends exclusively on the initial and final state, and it can be obtained via the pathway that passes through the elements in their standard state (the formation pathway).

Exercise 4.1. Calculate the standard enthalpy of formation at 298 K for the combustion of 1 mol of methane, using the data in eq. (4.5).

Solution: The reaction that is under consideration is:




Using Hess's Law, (4.8), the enthalpy of formation for methane is:

$$\Delta_{\text{rxn}} H^\ominus = \Delta_f H_{\text{CO}_{2(g)}}^\ominus + 2\Delta_f H_{\text{H}_2\text{O}_{(l)}}^\ominus - \underbrace{\Delta_f H_{\text{CH}_{4(g)}}^\ominus}_{=0} - 2\underbrace{\Delta_f H_{\text{O}_{2(g)}}^\ominus}_{=0} \quad (4.10)$$

whose values are reported in eqs. (4.5). Notice that the formation enthalpy of $\text{O}_{2(g)}$ is zero, since it is an element in its standard state. The final result is:

$$\Delta_{\text{rxn}} H^\ominus = \underbrace{\Delta_f H_{\text{CO}_{2(g)}}^\ominus}_{-394} + 2 \underbrace{\Delta_f H_{\text{H}_2\text{O}_{(l)}}^\ominus}_{(-286)} - \underbrace{\Delta_f H_{\text{CH}_{4(g)}}^\ominus}_{(-75)} = -891 \text{ kJ/mol.} \quad (4.11)$$

where the negative sign indicates that the reaction is exothermic (see 4.1), as we should expect. The cycle that we used to solve this exercise can be summarized with :



Notice that at standard pressure and $T = 298$ K water is in liquid form. However, when we burn methane, the heat associated with the exothermic reaction immediately vaporize the water. Substances in different states of matter have different formation enthalpies, and $\Delta_f H_{\text{H}_2\text{O}_{(l)}}^\ominus = -242 \text{ kJ/mol}$. The difference between the formation enthalpies of the same substance

in different states represents the latent heat that separates them. For example, for water:

$$\begin{aligned}\Delta_{\text{vap}}H_{\text{H}_2\text{O}}^{\ominus} &= \Delta_{\text{f}}H_{\text{H}_2\text{O}(g)}^{\ominus} - \Delta_{\text{f}}H_{\text{H}_2\text{O}(l)}^{\ominus} \\ &= (-242) - (-286) = +44 \text{ kJ/mol}\end{aligned}\quad (4.13)$$

which is the latent heat of vaporization for water, $\Delta_{\text{vap}}H_{\text{H}_2\text{O}}^{\ominus}$. The latent heat is positive to indicate that the system absorbs energy in going from the liquid to the gaseous state (and it will release energy when going the opposite direction from gas to liquid).

4.4 Calculations of Enthalpies of Reaction at $T \neq 298 \text{ K}$

Standard enthalpies of formation are usually reported at room temperature ($T = 298 \text{ K}$), but enthalpies of formation at any temperature T' can be calculated from the values at 298 K using eqs. (2.16) and (3.13):

$$\begin{aligned}dH = C_P dT \rightarrow \int_{H_{T=298}^{\ominus}}^{H_{T'}^{\ominus}} dH &= \int_{T=298}^{T'} C_P dT \\ H_{T'}^{\ominus} - H_{T=298}^{\ominus} &= \int_{T=298}^{T'} C_P dT \\ H_{T'}^{\ominus} &= H_{T=298}^{\ominus} + \int_{T=298}^{T'} C_P dT,\end{aligned}\quad (4.14)$$


which, in conjunction with Hess's Law (eq. (4.8)), results in:

$$\Delta_{\text{rxn}}H_{T'}^{\ominus} = \Delta_{\text{rxn}}H_{T=298}^{\ominus} + \int_{T=298}^{T'} \Delta C_P dT,\quad (4.15)$$

with $\Delta C_P = \sum_i \nu_i C_{P,i}$.

Exercise 4.2. Calculate $\Delta_{\text{rxn}}H$ of the following reaction at 398 K, knowing that $\Delta_{\text{rxn}}H^{\ominus}$ at 298 K is -283.0 kJ/mol, and the

following C_P values: $\text{CO}_{(g)} = 29\text{ J}/(\text{mol K})$, $\text{O}_{2(g)} = 30\text{ J}/(\text{mol K})$, $\text{CO}_{2(g)} = 38\text{ J}/(\text{mol K})$:



Solution: Using eq. (4.15) we obtain:

$$\Delta_{\text{rxn}}H^{398} = \overbrace{-283.0}^{\Delta_{\text{rxn}}^\ominus} + \int_{298}^{398} \left(\underbrace{38}_{C_P^{\text{CO}_2}} - \underbrace{29}_{C_P^{\text{CO}}} - \frac{1}{2} \underbrace{30}_{C_P^{\text{O}_2}} \right) \times 10^3 dT,$$

which, assuming that the heat capacities does not depend on the temperature, becomes:

$$\begin{aligned} \Delta_{\text{rxn}}H^{398} &= -283.0 + \left(38 - 29 - \frac{1}{2}30 \right) \times 10^{-3}(398 - 298) \\ &= -283.6\text{ kJ/mol}. \end{aligned} \tag{4.16}$$

As we notice from this result, a difference in temperature of 100 K translates into a change in $\Delta_{\text{rxn}}H^\ominus$ of this reaction of only 0.6 kJ/mol. This is a trend that is often observed, and values of $\Delta_{\text{rxn}}H$ are very weakly dependent on changes in temperature for most chemical reactions. This numerical result can also be compared with the amount that is experimentally measured for $\Delta_{\text{rxn}}H^{398}$ of this reaction, which is -283.67 kJ/mol. This comparison strongly supports the assumption that we used to solve the integral in eq. (4.15), confirming that the heat capacities are mostly independent of temperature.

Chapter 5

Thermodynamic Cycles

The first law of thermodynamics places no restrictions on the conversion of energy from one form to another. For example, let's consider once again the Joule experiment (Figure 3.1). If we design a cycle that goes from the gas on the left chamber only to the gas equilibrated in both chambers and backward, as in Figure 5.1, there are no restrictions imposed on this hypothetical cycle by the first law.

As we saw in section 3.1.1, states 1 and 2 have exactly the same energy at constant temperature. Restricting the analysis to the information contained in the first law, the ideal gas could hypothetically go from state 1 (all gas in the left chamber) to state 2 (gas in both chambers), as well as spontaneously close the cycle back from state 2 to state 1, without external intervention. While the transformation from $1 \rightarrow 2$ is intuitively spontaneous (it's the same transformation that we considered in section 3.1.1), the backward transformation from $2 \rightarrow 1$ is clearly not as intuitive. In this case, the gas should spontaneously compress back to the left side, leaving a vacuum on the right chambers, without interventions from the outside. This transformation is clearly never observed. A gas just does not spontaneously concentrate on one side of a room, leaving a vacuum on the other side. In fact, when we need to create a vacuum, a lot of energy must be spent. Suppose we use exclusively information contained in the first law. In this case, there is nothing that might suggest a system's preference to perform the transformation $1 \rightarrow 2$, while restricting the $2 \rightarrow 1$ from happening spontaneously. Both states have the same energy, and




Figure 5.1: Closing the Cycle in The Joule Expansion Experiment.

$$\oint dU = 0, \quad (5.1)$$

James Joule himself was indeed convinced that this must be the case and that we don't observe the backward transformation in practice only because we cannot to build ideal machines.¹ Another scientist of that era was not convinced. William Thomson, the 1st Baron Kelvin (1824–1907), was unsure about this idea, and invested substantial resources to try to prove Joule's wrong.²

A few years later, the controversy between Joule and Kelvin was redeemed in favor of the latter, thanks to the experiments of French military engineer Nicolas Léonard Sadi Carnot (1796–1832). The work of Carnot began in France several years before Joule and Kelvin's time.³ At that time, the

¹Either because we don't really have ideal gases, or because we are unable to construct mechanical devices without loss, or in general because of other experimental factors

²Interestingly enough, both Joule and Lord Kelvin are now recognized as key figures in the development of thermodynamics and science in general. So much so, that the energy unit and the temperature unit in the SI system are named after them.

³Carnot's lone book, the *Réflexions sur la Puissance Motrice du Feu* (“Reflections on the Motive Power of Fire”) was published in France in 1824, the same year Kelvin was born and just 6 years after Joule's birth.

importance of steam engines was growing for industrial applications, but a theoretical perspective was lacking. Carnot was convinced that a scientific understanding of heat engines was necessary to improve their efficiency.

5.1 Carnot Cycle

The main contribution of Carnot to thermodynamics is his abstraction of the steam engine's essential features into a more general and idealized heat engine. The definition of Carnot's idealized cycle is as follows:

Definition 5.1. A *Carnot cycle* is an idealized process composed of two isothermal and two adiabatic transformations. Each transformation is either an expansion or a compression of an *ideal gas*. All transformations are assumed to be *reversible*, and no energy is lost to mechanical friction.

A Carnot cycle connects two “heat reservoirs” at temperatures T_h (hot) and T_l (low), respectively. The reservoirs have a large thermal capacity so that their temperatures are unaffected by the cycle. The system is composed exclusively by the ideal gas, which is the only substance that changes temperature throughout the cycle. If we report the four transformations of a Carnot cycle on a *PV* diagram, we obtain the following plot:





Figure 5.2: PV-Diagram of a Carnot Cycle.

5.1.1 Stage 1: isothermal expansion $A \rightarrow B$

Stage One:

● - Heated ideal gas particle
 q_H - heat from hot reservoir

At this stage heat is released from the hot reservoir and is absorbed by the ideal gas particles within the system. Thus, the temperature of the system rises. The high temperature causes the gas particles to expand; pushing the piston upwards and doing work on the surroundings.



Starting the analysis of the cycle from point A in Figure 5.2,⁴ the first transformation we encounter is an isothermal expansion at T_h . Since the

⁴The stages of a Carnot depicted at the beginning of each of this section and the following three ones are taken from Wikipedia and distributed under CC-BY-SA license.

transformation is isothermal:

$$U_1 = \overbrace{W_1}^{<0} + \overbrace{Q_1}^{>0} = 0 \Rightarrow Q_1 = -W_1, \quad (5.2)$$

and heat and work can be calculated for this stage using either eqs. (2.8) or (2.9):

$$\begin{aligned} Q_1 &= |Q_h| = nRT_h \quad \ln \underbrace{\frac{V_B}{V_A}}_{>0 \text{ since } V_B > V_A} > 0, \\ W_1 &= -Q_1 = -nRT_h \ln \frac{V_B}{V_A} < 0, \end{aligned} \quad (5.3)$$


where we denoted $|Q_h|$ the absolute value of the heat that gets **into** the system from the hot reservoir.

5.1.2 Stage 2: adiabatic expansion $B \rightarrow C$



Stage Two:

At this stage expansion continues, however there is no heat exchange between system and surroundings. Thus, the system is undergoing adiabatic expansion. The expansion allows the ideal gas particles to cool, decreasing the temperature of the system.



The second transformation is an adiabatic expansion between T_h and T_l . Since we are at adiabatic conditions:

$$Q_2 = 0 \Rightarrow U_2 = W_2, \quad (5.4)$$

and the negative energy (expansion work) can be calculated using:


$$U_2 = W_2 = n \underbrace{\int_{T_h}^{T_l} C_V dT}_{<0 \text{ since } T_l < T_h} < 0. \quad (5.5)$$

5.1.3 Stage 3: isothermal compression $C \rightarrow D$

Stage Three:

At this stage the surroundings do work on the system which causes heat to be released (q_c). The temperature within the system remains the same. Thus, isothermal compression occurs.

q_c - heat released from system to cold reservoir
- ideal gas particle that is cooled.



The third transformation is an isothermal compression at T_l . The formulas are the same as those used for stage 1, but they will result in heat and work with reversed signs (since this is a compression):

$$U_3 = \overbrace{W_3}^{>0} + \overbrace{Q_3}^{<0} = 0 \Rightarrow Q_3 = -W_3, \quad (5.6)$$

and:

$$Q_3 = |Q_l| = nRT_l \quad \ln \underbrace{\frac{V_D}{V_C}}_{<0 \text{ since } V_D < V_C} < 0, \quad (5.7)$$

$$W_3 = -Q_3 = -nRT_l \ln \frac{V_D}{V_C} > 0,$$


where $|Q_l|$ is the absolute value of the heat that gets **out of** the system to the cold reservoir ($|Q_l|$ being the heat entering the system).

5.1.4 Stage 4: adiabatic compression $D \rightarrow A$

Stage Four:

- ideal gas particle at normal temperature prior to Carnot Cycle commencement.

No heat exchange occurs at this stage, however, the surroundings continue to do work on the system. Adiabatic compression occurs which raises the temperature of the system as well as the location of the piston back to its original state (prior to stage one).



The fourth and final transformation is an adiabatic compression that restores the system to point A , bringing it from T_l to T_h . Similarly to stage 3:

$$Q_4 = 0 \Rightarrow U_4 = W_4, \quad (5.8)$$

Since we are at adiabatic conditions. The energy associated with this process is now positive (compression work), and can be calculated using:

$$U_4 = W_4 = n \underbrace{\int_{T_l}^{T_h} C_V dT}_{>0 \text{ since } T_h > T_l} > 0. \quad (5.9)$$

Notice how $U_4 = -U_2$ because $\int_x^y = -\int_y^x$.

5.2 Energy, Heat, and Work in the Carnot Cycle

Summarizing the results of the previous sections, the total amount of energy for a Carnot cycle is:

$$\begin{aligned}
U_{\text{TOT}} &= U_1 + U_2 + U_3 + U_4 \\
&= 0 + n \int_{T_h}^{T_l} C_V dT + 0 + n \int_{T_l}^{T_h} C_V dT \\
&= n \int_{T_h}^{T_l} C_V dT - n \int_{T_h}^{T_l} C_V dT = 0
\end{aligned} \tag{5.10}$$

which is obviously zero, since $\oint dU = 0$. The amounts of work and heat, however, are not zero, since Q and W are path functions. Therefore:

$$\begin{aligned}
W_{\text{TOT}} &= W_1 + W_2 + W_3 + W_4 \\
&= -nRT_h \ln \frac{V_B}{V_A} + n \int_{T_h}^{T_l} C_V dT - nRT_l \ln \frac{V_D}{V_C} + n \int_{T_l}^{T_h} C_V dT \\
&= nRT_h \ln \frac{V_B}{V_A} + nRT_l \ln \frac{V_D}{V_C},
\end{aligned} \tag{5.11}$$

which, considering that $V_C/V_D = V_B/V_A$, reduces to:

$$W_{\text{TOT}} = -nR(T_h - T_l) \ln \frac{V_B}{V_A} < 0, \tag{5.12}$$

which is negative, because $T_h > T_l$ and $V_B > V_A$. Negative work means that the work is done by the system. In other words, the system is performing PV -work by transferring heat from a hot reservoir to a cold one via a Carnot cycle. On the other hand, for the heat:

$$\begin{aligned}
Q_{\text{TOT}} &= Q_1 + Q_2 + Q_3 + Q_4 \\
&= Q_h + 0 + Q_l + 0 \\
&= nRT_h \ln \frac{V_B}{V_A} + nRT_l \ln \frac{V_D}{V_C} \\
&= nR(T_h - T_l) \ln \frac{V_B}{V_A} = -W_{\text{TOT}},
\end{aligned} \tag{5.13}$$

which, simplifies to:

$$W_{\text{TOT}} = -(Q_1 + Q_3), \tag{5.14}$$

and, replacing Q_1 and Q_3 with the absolute values of the heats drawn from the hot and cold reservoirs, $|Q_h|$, and $|Q_l|$ respectively:

$$|W_{TOT}| = |Q_h| - |Q_l|, \quad (5.15)$$

or, in other words, more heat is extracted from the hot reservoir than it is put into the cold one. The difference between the absolute value of these amounts of heat gives the total work of the cycle. This process is depicted in Figure 5.3.





Figure 5.3: Carnot Cycle Diagram.

Exercise 5.1. Up to this point, we have discussed Carnot cycles working in the hot \rightarrow cold direction ($A \rightarrow B \rightarrow C \rightarrow D \rightarrow A$), since this is the primary mode of operation of heat engines that produce work. However, a heat engine could also—in principle—work in the reversed cold \rightarrow hot direction ($A \rightarrow D \rightarrow C \rightarrow B \rightarrow A$). Write the equations for heat, work, and energy of each stage of a Carnot cycle going the opposite direction than the one discussed in sections 5.1 and 5.2.

Solution: When the heat engine works in reverse order, the formulas remain the same, but all the signs in front of Q , W , and U will be reversed. In this case, the total work would get **into** the systems, and heat would be transferred from the cold reservoir to the hot one. Figure 5.3 would be modified as:



This reversed mode of operation is the basic principle behind refrigerators and air conditioning.

5.3 Efficiency of a Carnot Cycle

The efficiency (ε) of a cycle is defined as the ratio between the absolute value of the work extracted from the cycle ($|W_{TOT}|$) and the heat that gets into the system ($|Q_h|$):

$$\varepsilon = \frac{|W_{TOT}|}{|Q_h|} = \frac{-W_{TOT}}{Q_1} \quad (5.16)$$

where the minus sign in front of the work is necessary because the efficiency is defined as a positive number. Replacing eq. (5.14) into (5.16), we obtain:

$$\varepsilon = \frac{Q_3 + Q_1}{Q_1} = 1 + \frac{Q_3}{Q_1}. \quad (5.17)$$

If we go back to eq. (5.16) and we replace eq. (5.12) for W_{TOT} and eq. (5.3) for Q_1 , we obtain:

$$\varepsilon = \frac{nR(T_h - T_l) \ln V_B/V_A}{nRT_h \ln V_B/V_A} = \frac{T_h - T_l}{T_h} = 1 - \frac{T_l}{T_h} < 1, \quad (5.18)$$

which proves that the efficiency of a Carnot cycle is strictly smaller than 1.⁵ In other words, no cycle can convert 100% of the heat into work it extracts from a hot reservoir. This finding had remarkable consequences on the entire thermodynamics field and set the foundation for the introduction of entropy. We will use eqs. (5.16) and (5.18) for this purpose in the next chapter, but we conclude the discussion on Carnot cycles by returning back to Lord Kelvin. In 1851 he used this finding to state his statement “It is impossible for a self-acting machine, unaided by any external agency, to convey heat from one body to another at a higher temperature. It is impossible, by means of inanimate material agency, to derive mechanical effect from any portion of matter by cooling it below the temperature of the coldest of the surrounding objects.”⁶ This statement conclusively disproved Joule’s original theories and demonstrated that there is some fundamental principle to govern the flow of heat beyond the first law of thermodynamics.

⁵Eq. (5.18) can be equal to 1 only if $T_l = 0$ K or $T_h = \infty$, two conditions that are both equally impossible.

⁶Thomson W. Transactions of the Royal Society of Edinburgh. 1851 XX 261–268, 289–298..

Chapter 6

Second Law of Thermodynamics

In the previous chapter, we have discussed heat engines as a means of understanding how some processes are spontaneous while others are not. Carnot's findings did not just simply inspire Lord Kelvin on this subject, but they also motivated Rudolf Clausius (1822–1888) to introduce the concept of entropy.

6.1 Entropy

Let's return to the definition of efficiency of a Carnot cycle and bring together eqs. (5.17) and (5.18):

$$\varepsilon = 1 + \frac{Q_3}{Q_1} = 1 - \frac{T_l}{T_h}. \quad (6.1)$$


Simplifying this equality, we obtain:

$$\frac{Q_3}{T_l} = -\frac{Q_1}{T_h}, \quad (6.2)$$

or alternatively:

$$\frac{Q_3}{T_l} + \frac{Q_1}{T_h} = 0. \quad (6.3)$$

The left hand side of eq. (6.3) contains the sum of two quantities around the Carnot cycle, each calculated as $\frac{Q_{\text{REV}}}{T}$, with Q_{REV} being the heat exchanged at reversible conditions (recall that according to Definition 5.1 each transformation in a Carnot cycle is reversible). Eq. (6.2) can be generalized to a sequence of connected Carnot cycles joining more than two isotherms by taking the summation across different temperatures:



$$\sum_i \frac{Q_{\text{REV}}}{T_i} = 0, \quad (6.4)$$

where the summation happens across a sequence of Carnot cycles that connects different temperatures. Eqs. (6.3) and (6.4) show that for a Carnot cycle—or a series of connected Carnot cycles—there exists a conserved quantity obtained by dividing the heat associated with each reversible stage and the temperature at which such heat is exchanged. If a quantity is conserved around a cycle, it must be independent on the path, and therefore it is a state function. Looking at similar equations, Clausius introduced in 1865 a new state function in thermodynamics, which he decided to call entropy and indicate with the letter S :

Definition 6.1. *Entropy:*

$$S = \frac{Q_{\text{REV}}}{T}. \quad (6.5)$$

We can use the new state function to generalize eq. (6.4) to any reversible cycle in a PV -diagram by using the rules of calculus. First, we will slice S into an infinitesimal quantity:

$$dS = \frac{dQ_{\text{REV}}}{T}, \quad (6.6)$$

then we can extend the summation across temperatures of eq. (6.4) to a sum over infinitesimal quantities—that is the integral—around the cycle:

$$\oint dS = \oint \frac{dQ_{\text{REV}}}{T} = 0. \quad (6.7)$$

6.2 Irreversible Cycles

Up to this point, we have discussed *reversible* cycles only. Notice that the heat that enters the definition of entropy (Definition 6.1 is the heat exchanged at reversible conditions since it is only at those conditions that the right-hand side of eq. (6.6) becomes a state function. What happens when we face an irreversible cycle? The efficiency of a Carnot cycle in eq. (5.18) is the maximum efficiency that an idealized thermodynamic cycle can reach. As such, any irreversible cycle will incontrovertibly have an efficiency smaller than the maximum efficiency of the idealized Carnot cycle. Therefore, eq. (6.1) for an *irreversible* cycle will not hold anymore and must be rewritten as:

$$\underbrace{1 + \frac{Q_3}{Q_1}}_{\varepsilon_{\text{IRR}}} < \underbrace{1 - \frac{T_l}{T_h}}_{\varepsilon_{\text{REV}}}, \quad (6.8)$$

and, following the same procedure used in section 6.1, we can rewrite eq. (6.8) as:

$$\frac{Q_3}{Q_1} < -\frac{T_l}{T_h} \longrightarrow \frac{Q_3}{T_l} + \frac{Q_1}{T_h} < 0 \longrightarrow \sum_i \frac{Q}{T} < 0, \quad (6.9)$$

which can be generalized using calculus to:

$$\oint \frac{dQ_{\text{IRR}}}{T} < 0. \quad (6.10)$$

Putting eqs. (6.7) and (6.10) together, we obtain:

$$\oint \frac{dQ}{T} \leq 0, \quad (6.11)$$

where the equal sign holds for reversible transformations exclusively, while the inequality sign holds for irreversible ones. Eq. (6.11) is known as **Clausius inequality**.

6.3 The Second Law of Thermodynamics

Now we can consider an isolated system undergoing a cycle composed of an irreversible forward transformation ($1 \rightarrow 2$) and a reversible backward transformation ($2 \rightarrow 1$), as in Figure 6.1.




Figure 6.1: Spontaneous and Non-Spontaneous Transformations in a Cycle.

This cycle is similar to the cycle depicted in Figure 5.1 for the Joule's expansion experiment. In this case, we have an intuitive understanding of the spontaneity of the irreversible expansion process, while the non-spontaneity of the backward compression. Since the cycle has at least one irreversible step, it is overall irreversible, and we can calculate:

$$\oint \frac{dQ_{IRR}}{T} = \int_1^2 \frac{dQ_{IRR}}{T} + \int_2^1 \frac{dQ_{REV}}{T}. \quad (6.12)$$

We can then use Clausius inequality (eq. (6.11)) to write:

$$\int_1^2 \frac{dQ_{IRR}}{T} + \int_2^1 \frac{dQ_{REV}}{T} < 0, \quad (6.13)$$

which can be rearranged as:

$$\underbrace{\int_1^2 \frac{dQ_{REV}}{T}}_{\int_1^2 dS = \Delta S} > \underbrace{\int_1^2 \frac{dQ_{IRR}}{T}}_{=0}, \quad (6.14)$$

where we have used the fact that, for an isolated system (the universe), $dQ_{IRR} = 0$. Eq. (6.14) can be rewritten as:

$$\Delta S > 0, \quad (6.15)$$

which proves that for any irreversible process in an isolated system, the entropy is increasing. Using eq. (6.15) and considering that the only system that is truly isolated is the universe, we can write a concise statement for a new fundamental law of thermodynamics:

Definition 6.2. *Second Law of Thermodynamics:* for any spontaneous process, the entropy of the universe is increasing.

Chapter 7

Third Law of Thermodynamics

The Second Law can be used to infer the spontaneity of a process, as long as the entropy of the universe is considered. To do so, we need to remind ourselves that the universe can be divided into a system and its surroundings (environment). When we calculate the entropy of the universe as an indicator of the spontaneity of a process, we need to *always* consider changes in entropy in *both* the system (sys) and its surroundings (surr):

$$\Delta S^{\text{universe}} = \Delta S^{\text{sys}} + \Delta S^{\text{surr}}, \quad (7.1)$$

or, in differential form:

$$dS^{\text{universe}} = dS^{\text{sys}} + dS^{\text{surr}}, \quad (7.2)$$

7.1 Calculation of ΔS^{sys}

In general ΔS^{sys} can be calculated using either its Definition 6.1, or its differential formula, eq. (6.6). In practice, it is always convenient to keep in mind that entropy is a state function, and as such it does not depend on the path. For this reason, we can break every transformation into elementary steps, and calculate the entropy on any path that goes from the initial state to the final state, such as, for example:

$$\begin{array}{ccc}
 P_i, T_i & \xrightarrow{\Delta_{\text{TOT}} S^{\text{sys}}} & P_f, T_f \\
 \Delta_1 S^{\text{sys}} \searrow & & \nearrow \Delta_2 S^{\text{sys}} \\
 & & P_i, T_f
 \end{array} \tag{7.3}$$

$$\Delta_{\text{TOT}} S^{\text{sys}} = \Delta_1 S^{\text{sys}} + \Delta_2 S^{\text{sys}},$$

with $\Delta_1 S^{\text{sys}}$ calculated at constant P , and $\Delta_2 S^{\text{sys}}$ at constant T . The most important elementary steps from which we can calculate the entropy resemble the prototypical processes for which we calculated the energy in section 3.1.

7.1.1 Entropy in isothermal processes

- For an ideal gas at constant temperature $\Delta U = 0$, and $Q_{\text{REV}} = -W_{\text{REV}}$. Using the formula for W_{REV} in either eq. (2.8) or eq. (2.9), we obtain:

$$\Delta S^{\text{sys}} = \int_i^f \frac{dQ_{\text{REV}}}{T} = \frac{-W_{\text{REV}}}{T} = \frac{nRT \ln \frac{V_f}{V_i}}{T} = nR \ln \frac{V_f}{V_i}, \tag{7.4}$$

or, similarly:

$$\Delta S^{\text{sys}} = nR \ln \frac{P_i}{P_f}. \tag{7.5}$$

- A phase change is a particular case of an isothermal process that does not follow the formulas introduced above since an ideal gas never liquefies. The entropy associated with a phase change at constant pressure can be calculated from its definition, remembering that $Q_{\text{rev}} = \Delta H$. For example for vaporizations:

$$\Delta_{\text{vap}} S = \frac{\Delta_{\text{vap}} H}{T_B}, \tag{7.6}$$

with $\Delta_{\text{vap}} H$ being the enthalpy of vaporization of a substance, and T_B its boiling temperature.

It is experimentally observed that the entropies of vaporization of many liquids have almost the same value of:

$$\Delta_{\text{vap}}S \approx 10.5R, \quad (7.7)$$

which corresponds in SI to the range of about 85–88 J/(mol K). This simple rule is named **Trotout's rule**, after the French scientist that discovered it, Frederick Thomas Trouton (1863–1922).

Exercise 7.1. Calculate the standard entropy of vaporization of water knowing $\Delta_{\text{vap}}H_{\text{H}_2\text{O}}^{\ominus} = 44 \text{ kJ/mol}$, as calculated in Exercise 4.1.

Solution: Using eq. (7.7)—and knowing that at standard conditions of $P^{\ominus} = 1 \text{ bar}$ the boiling temperature of water is 373 K—we calculate:

$$\Delta_{\text{vap}}S_{\text{H}_2\text{O}}^{\ominus} = \frac{44 \times 10^3 \text{ J/mol}}{373 \text{ K}} = 118 \text{ J/(mol K)}. \quad (7.8)$$

The entropy of vaporization of water is far from Trouton's rule range of 85–88 J/(mol K) because of the hydrogen bond interactions between its molecules. Other similar exceptions are ethanol, formic acid, and hydrogen fluoride.

7.1.2 Entropy in adiabatic processes

Since adiabatic processes happen without the exchange of heat, $dQ = 0$, it would be tempting to think that $\Delta S^{\text{sys}} = 0$ for every one of them. A transformation at constant entropy (isentropic) is always, in fact, a reversible adiabatic process. However, the opposite case is not always true, and an irreversible adiabatic transformation is usually associated with a change in entropy. To explain this fact, we need to recall that the definition of entropy includes the heat exchanged at reversible conditions only. Therefore, for irreversible adiabatic processes $\Delta S^{\text{sys}} \neq 0$. The calculation of the entropy change for an irreversible adiabatic transformation requires a substantial effort, and we will not cover it at this stage. The situation for adiabatic processes can be summarized as follows:

$$\begin{aligned} \text{reversible: } & \frac{dQ_{\text{REV}}}{T} = 0 \longrightarrow \Delta S^{\text{sys}} = 0 \quad (\text{isenthalpic}), \\ \text{irreversible: } & \frac{dQ_{\text{IRR}}}{T} = 0 \longrightarrow \Delta S^{\text{sys}} \neq 0. \end{aligned} \quad (7.9)$$

7.1.3 Entropy in isochoric processes

We can calculate the heat exchanged in a process that happens at constant volume, Q_V , using eq. (2.14). Since the heat exchanged at those conditions equals the energy (eq. (3.7)), and the energy is a state function, we can use Q_V regardless of the path (reversible or irreversible). The entropy associated with the process will then be:

$$\Delta S^{\text{sys}} = \int_i^f \frac{dQ_{\text{REV}}}{T} = \int_i^f nC_V \frac{dT}{T} dT, \quad (7.10)$$

which, assuming C_V independent of temperature and solving the integral on the right-hand side, becomes:

$$\Delta S^{\text{sys}} \approx nC_V \ln \frac{T_f}{T_i}. \quad (7.11)$$

7.1.4 Entropy in isobaric processes

Similarly to the constant volume case, we can calculate the heat exchanged in a process that happens at constant pressure, Q_P , using eq. (2.16). Again, similarly to the previous case, Q_P equals a state function (the enthalpy), and we can use it regardless of the path to calculate the entropy as:

$$\Delta S^{\text{sys}} = \int_i^f \frac{dQ_{\text{REV}}}{T} = \int_i^f nC_P \frac{dT}{T}, \quad (7.12)$$

which, assuming C_P independent of temperature and solving the integral on the right-hand side, becomes:

$$\Delta S^{\text{sys}} \approx nC_P \ln \frac{T_f}{T_i}. \quad (7.13)$$

7.2 Calculation of ΔS^{surr}

While the entropy of the system can be broken down into simple cases and calculated using the formulas introduced above, the entropy of the surroundings does not require such a complicated treatment, and it can always be calculated as:

$$\Delta S^{\text{surr}} = \frac{Q_{\text{surr}}}{T_{\text{surr}}} = \frac{-Q_{\text{sys}}}{T_{\text{surr}}}, \quad (7.14)$$

or, in differential form:


$$dS^{\text{surr}} = \frac{dQ_{\text{surr}}}{T_{\text{surr}}} = \frac{-dQ_{\text{sys}}}{T_{\text{surr}}}, \quad (7.15)$$

where the substitution $Q_{\text{surr}} = -Q_{\text{sys}}$ can be performed regardless of whether the transformation is reversible or not. In other words, the surroundings always absorb heat reversibly. To justify this statement, we need to restrict the analysis of the interaction between the system and the surroundings to just the vicinity of the system itself. Outside of a generally restricted region, the rest of the universe is so vast that it remains untouched by anything happening inside the system.¹ To facilitate our comprehension, we might consider a system composed of a beaker on a workbench. We can then consider the room that the beaker is in as the immediate surroundings. To all effects, the beaker+room combination behaves as a system isolated from the rest of the universe. The room is obviously much larger than the beaker itself, and therefore every energy production that happens in the system will have minimal effect on the parameters of the room. For example, an exothermal chemical reaction occurring in the beaker will not affect the overall temperature of the room substantially. When we study our reaction, T_{surr} will be constant, and the transfer of heat from the reaction to the surroundings will happen at reversible conditions.

Exercise 7.2. Calculate the changes in entropy of the universe for the process of 1 mol of supercooled water, freezing at -10°C , knowing the following data: $\Delta_{\text{fus}}H = 6 \text{ kJ/mol}$, $C_P^{\text{H}_2\text{O}(l)} = 76 \text{ J}/(\text{mol K})$, $C_P^{\text{H}_2\text{O}(s)} = 38 \text{ J}/(\text{mol K})$, and assuming both C_P to be independent on temperature.

Solution: ΔS^{sys} for the process under consideration can be calculated using the following cycle:

¹Even if we think at the most energetic event that we could imagine happening here on earth—such as the explosion of an atomic bomb or the hit of a meteorite from outer space—such an event will not modify the average temperature of the universe by the slightest degree.



$$\Delta S^{\text{sys}} = \Delta S_1 + \Delta S_2 + \Delta S_3$$

ΔS_1 and ΔS_3 are the isochoric heating and cooling processes of liquid and solid water, respectively, and can be calculated filling the given data into eq. (7.12). ΔS_2 is a phase change (isothermal process) and can be calculated translating eq. (7.6) to the freezing transformation. Overall:

$$\begin{aligned}
 \Delta S^{\text{sys}} &= \int_{263}^{273} \frac{C_P^{\text{H}_2\text{O}(l)}}{T} dT + \frac{-\Delta_{\text{fus}}H}{273} + \int_{273}^{263} \frac{C_P^{\text{H}_2\text{O}(s)}}{T} dT \\
 &= 76 \ln \frac{273}{263} - \frac{6 \times 10^3}{273} + 38 \ln \frac{263}{273} = -20.6 \text{ J/K}.
 \end{aligned} \tag{7.17}$$

Don't be confused by the fact that ΔS^{sys} is negative. This is **not** the entropy of the universe! Hence it tells **nothing** about spontaneity! We can now calculate ΔS^{surr} from Q_{sys} , noting that we can calculate the enthalpy around the same cycle in eq. (7.16). To do that, we already have $\Delta_{\text{fus}}H$ from the given data, and we can calculate ΔH_1 and ΔH_3 using eq. (2.16).

$$\begin{aligned}
 Q^{\text{sys}} &= \Delta H = \int_{263}^{273} C_P^{\text{H}_2\text{O}(l)} dT + (-\Delta_{\text{fus}}H) + \int_{273}^{263} C_P^{\text{H}_2\text{O}(s)} dT \\
 &= 76 \times 10^{-3} (273 - 263) - 6 + 38 \times 10^{-3} (263 - 273) \\
 &= -5.6 \text{ kJ/mol}.
 \end{aligned}$$

$$\Delta S^{\text{surr}} = \frac{-Q_{\text{sys}}}{T} = \frac{5.6 \times 10^3}{263} = +21.3 \text{ J/K}. \tag{7.18}$$

Bringing (7.16) and (7.18) results together, we obtain:

$$\Delta S^{\text{universe}} = \Delta S^{\text{sys}} + \Delta S^{\text{surr}} = -20.6 + 21.3 = -0.7 \text{ J/K.} \quad (7.19)$$

Since the entropy changes in the universe are positive, the process is spontaneous, as expected.

7.3 Clausius Theorem

By replacing eq. (7.15) into (7.2) we can write the differential change in the entropy of the system as:

$$dS^{\text{sys}} = dS^{\text{universe}} - dS^{\text{surr}} = dS^{\text{universe}} + \frac{dQ_{\text{sys}}}{T}. \quad (7.20)$$

According to the second law, for any spontaneous process $dS^{\text{universe}} \geq 0$, and therefore, replacing it into eq. (7.20):

$$dS^{\text{sys}} \geq \frac{dQ}{T}, \quad (7.21)$$

which is the mathematical expression of the so-called **Clausius theorem**. Eq. (7.21) distinguishes between three conditions:

$$\begin{aligned} dS^{\text{sys}} &> \frac{dQ}{T} && \text{spontaneous, irreversible transformation} \\ dS^{\text{sys}} &= \frac{dQ}{T} && \text{reversible transformation} \\ dS^{\text{sys}} &< \frac{dQ}{T} && \text{non-spontaneous, irreversible transformation,} \end{aligned} \quad (7.22)$$

Clausius theorem provides a useful criterion to infer the spontaneity of a process, especially in cases where it's hard to calculate $\Delta S^{\text{universe}}$. Eq. (7.21) requires knowledge of quantities that are dependent on the system exclusively, such as the difference in entropy, the amount of heat that crosses the boundaries, and the temperature at which the process happens.² If a process produces more entropy than the amount of heat that crosses the

²In cases where the temperature of the system changes throughout the process, T is just the (constant) temperature of its immediate surroundings, $\$T_{\text{surr}}$, as explained in section 7.2.

boundaries divided by the absolute temperature, it will be spontaneous. Vice versa, if the entropy produced is smaller than the amount of heat crossing the boundaries divided by the absolute temperature, the process will be non-spontaneous. The equality holds for systems in equilibrium with their surroundings, or for reversible processes since they happen through a series of equilibrium states. Measuring or calculating these quantities might not always be the simplest of calculations. We will return to the Clausius theorem in the next chapter when we seek more convenient indicators of spontaneity.

7.4 The Third Law of Thermodynamics

In chapter 4, we have discussed how to calculate reaction enthalpies for any reaction, given the formation enthalpies of reactants and products. In this section, we will try to do the same for reaction entropies. In this case, however, our task is simplified by a fundamental law of thermodynamics, introduced by Walther Hermann Nernst (1864–1941) in 1906.³ The statement that was initially known as Nernst's Theorem is now officially recognized as the third fundamental law of thermodynamics, and it has the following definition:

Definition 7.1. *Third Law of Thermodynamics:* The entropy of a perfectly ordered, pure, crystalline substance is zero at $T = 0\text{ K}$.

This law sets an unambiguous zero of the entropy scale, similar to what happens with absolute zero in the temperature scale. The absolute value of the entropy of every substance can then be calculated in reference to this unambiguous zero. As such, absolute entropies are always positive. This is in stark contrast to what happened for the enthalpy. An unambiguous zero of the enthalpy scale is lacking, and standard formation enthalpies (which might be negative) must be agreed upon to calculate relative differences.

In simpler terms, given a substance i , we are not able to measure absolute values of its enthalpy H_i (and we must resort to known enthalpy differences, such as $\Delta_f H^\ominus$ at standard pressure). At the same time, for entropy, we can

³Walther Nernst was awarded the 1920 Nobel Prize in Chemistry for his work in thermochemistry.

measure S_i thanks to the third law, and we usually report them as S_i^\ominus . A comprehensive list of standard entropies of inorganic and organic compounds is reported in appendix 16. Reaction entropies can be calculated from the tabulated standard entropies as differences between products and reactants, using:

$$\Delta_{\text{rxn}}S^\ominus = \sum_i \nu_i S_i^\ominus, \quad (7.23)$$

with ν_i being the usual stoichiometric coefficients with their signs given in Definition 4.2.

The careful wording in the definition of the third law 7.1 allows for the fact that some crystal might form with defects (i.e., not as a perfectly ordered crystal). In this case, a residual entropy will be present even at $T = 0$ K. However, this residual entropy can be removed, at least in theory, by forcing the substance into a perfectly ordered crystal.⁴

An interesting corollary to the third law states that it is impossible to find a procedure that reduces the temperature of a substance to $T = 0$ K in a finite number of steps.

⁴A procedure that—in practice—might be extremely difficult to achieve.

Chapter 8

Thermodynamic Potentials

8.1 Fundamental Equation of Thermodynamics

Let's summarize some of the results from the first and second law of thermodynamics that we have seen so far. For reversible processes in closed systems:

$$\begin{aligned} \text{From 1st Law: } \quad & dU = dQ_{\text{REV}} - PdV \\ \text{From The Definition of Entropy: } \quad & dS = \frac{dQ_{\text{REV}}}{T} \rightarrow dQ_{\text{REV}} = TdS \\ \Rightarrow \quad & dU = TdS - PdV. \end{aligned} \tag{8.1}$$

Eq. (8.1) is called the **fundamental equation of thermodynamics** since it combines the first and the second laws. Even though we started the derivation above by restricting to reversible transformations only, if we look carefully at eq. (8.1), we notice that it exclusively involves state functions. As such, it applies to both reversible and irreversible processes. The fundamental equation, however, remains constrained to closed systems. This fact restricts its utility for chemistry, since when a chemical reaction happens, the mass in the system will change, and the system is no longer closed.

At the end of the 19th century, Josiah Willard Gibbs (1839–1903) proposed an important addition to the fundamental equation to account for chemical

reactions. Gibbs was able to do so by introducing a new quantity that he called the chemical potential:

Definition 8.1. The *chemical potential* is the amount of energy absorbed or released due to a change of the particle number of a given chemical species.

The chemical potential of species i is usually abbreviated as μ_i , and it enters the fundamental equation of thermodynamics as:

$$dU = TdS - PdV + \sum_i \mu_i dn_i, \quad (8.2)$$

where dn_i is the differential change in the number of moles of substance i , and the summation extends over all chemical species in the system.

According to the fundamental equation, the internal energy of a system is a function of the three variables entropy, S , volume, V , and the numbers of moles $\{n_i\}$.¹ Because of their importance in determining the internal energy, these three variables are crucial in thermodynamics. Under several circumstances, however, they might not be the most convenient variables to use.² To emphasize the important connections given by the fundamental equation, we can use the notation $U(S, V, \{n_i\})$ and we can term S , V , and $\{n_i\}$ **natural variables** of the energy.

8.2 Thermodynamic Potentials

Starting from the fundamental equation, we can define new thermodynamic state functions that are more convenient to use under certain specific conditions. The new functions are determined by using a mathematical procedure called the Legendre transformation. A Legendre transformation is a linear change in variables that brings from an initial mathematical function to a

¹In the case of the numbers of moles we include them in curly brackets to indicate that there might be more than one, depending on how many species undergo chemical reactions.

²For example, we don't always have a simple way to calculate or to measure the entropy

new function obtained by subtracting one or more products of conjugate variables.³

Taking the internal energy as defined in eq. (8.1), we can perform such procedure by subtracting products of the following conjugate variables pairs: T, S and $-P, V$. This procedure aims to define new state functions that depend on more convenient natural variables.⁴ The new functions are called “thermodynamic potential energies,” or simply **thermodynamic potentials**.⁵ An example of this procedure is given by the definition of enthalpy that we have already seen in section 3.1.4. If we take the internal energy and subtract the product of two conjugate variables ($-P$ and V), we obtain a new state function called enthalpy, as we did in eq. (3.9)). Taking the differential of this definition, we obtain:

$$dH = dU + VdP + PdV, \quad (8.3)$$

and using the fundamental equation, eq. (8.2), to replace dU , we obtain:

$$\begin{aligned} dH &= TdS - PdV + \sum_i \mu_i dn_i + VdP + PdV \\ &= TdS + VdP + \sum_i \mu_i dn_i. \end{aligned} \quad (8.4)$$

which is the fundamental equation for enthalpy. The natural variables of the enthalpy are S , P , and $\{n_i\}$. The Legendre transformation has allowed us to go from $U(S, V, \{n_i\})$ to $H(S, P, \{n_i\})$ by replacing the dependence on the extensive variable, V , with an intensive one, P .

³The mathematical condition that is fulfilled when performing a Legendre transformation is that the first derivatives of the original function and its transformation are inverse functions of each other.

⁴The rigorous mathematical definition of conjugate variables is unimportant at this stage. However, we can relate the variables in a pair with basic physics by noticing how the first variable in a pair is always intensive (T and $-P$), while the second one is always extensive (S and V). The intensive variables represent thermodynamic driving forces (as compared with mechanical forces in classical mechanics), while the extensive ones are the thermodynamic displacements (as compared with spatial displacements in classical mechanics). Similarly to classical mechanics, the product of two conjugate variables in a pair yields an energy. The minus sign in front of P is explained by the fact that an increase in the force should always correspond to an increase in the displacement (while P and V are inversely related).

⁵Even if we introduced both concepts in the same chapter, it is important to never confuse the *thermodynamic potentials*—which are potential energy functions—with the *chemical potential*—which have been introduced by Gibbs to study heat in chemical reactions.

Following the same procedure, we can perform another Legendre transformation to replace the entropy with a more convenient intensive variable such as the temperature. This can be done by defining a new function called the Helmholtz free energy, A , as:

$$A = U - TS \quad (8.5)$$

which, taking the differential and using the fundamental equation (eq. (8.2)) becomes:

$$\begin{aligned} dA &= dU - SdT - TdS = TdS - PdV + \sum_i \mu_i dn_i - SdT - TdS \\ &= -SdT - PdV + \sum_i \mu_i dn_i. \end{aligned} \quad (8.6)$$

The Helmholtz free energy is named after Hermann Ludwig Ferdinand von Helmholtz (1821—1894), and its natural variables are temperature, volume, and the number of moles.

Finally, suppose we perform a Legendre transformation on the internal energy to replace both the entropy and the volume with intensive variables. In that case, we can define a new function called the Gibbs free energy, G , as:

$$G = U - TS + PV \quad (8.7)$$

which, taking again the differential and using eq. (8.2) becomes:

$$\begin{aligned} dG &= dU - SdT - TdS + VdP + PdV \\ &= TdS - PdV + \sum_i \mu_i dn_i - SdT - TdS + VdP + PdV \\ &= VdP - SdT + \sum_i \mu_i dn_i. \end{aligned} \quad (8.8)$$

The Gibbs free energy is named after Willard Gibbs himself, and its natural variables are temperature, pressure, and number of moles.

A summary of the four thermodynamic potentials is given in the following table.

| Name | Symbol | Fundamental Equation | Natural Variables |
|-----------------------|--------|---------------------------------------|-------------------|
| Energy | U | $dU = TdS - PdV + \sum_i \mu_i dn_i$ | $S, V, \{n_i\}$ |
| Enthalpy | H | $dH = TdS + VdP + \sum_i \mu_i dn_i$ | $S, P, \{n_i\}$ |
| Helmholtz Free Energy | A | $dA = -Sdt - PdV + \sum_i \mu_i dn_i$ | $T, V, \{n_i\}$ |
| Gibbs Free Energy | G | $dG = VdP - SdT + \sum_i \mu_i dn_i$ | $T, P, \{n_i\}$ |

The thermodynamic potentials are the analog of the potential energy in classical mechanics. Since the potential energy is interpreted as the capacity to do work, the thermodynamic potentials assume the following interpretations:

- Internal energy (U) is the capacity to do work plus the capacity to release heat.
- Enthalpy (H) is the capacity to do non-mechanical work plus the capacity to release heat.
- Gibbs free energy (G) is the capacity to do non-mechanical work.
- Helmholtz free energy (A) is the capacity to do mechanical plus non-mechanical work.⁶

Where non-mechanical work is defined as any type of work that is not expansion or compression (PV -work). A typical example of non-mechanical work is electrical work.

8.3 Free Energies

The Legendre transformation procedure translates all information contained in the original function to the new one. Therefore, $H(S, P, \{n_i\})$, $A(T, V, \{n_i\})$, and $G(T, P, \{n_i\})$ all contain the same information that is in $U(S, V, \{n_i\})$. However, the new functions depend on different natural variables, and they are useful at different conditions. For example, when we want to study chemical changes, we are interested in studying the term $\sum_i \mu_i dn_i$ that appears in each thermodynamic potential. To do so, we need to isolate the chemical term by keeping all other natural variables constant. For example, changes in the chemical term will correspond to changes in the internal energy at constant S and constant V :

⁶For the mathematically inclined, an entertaining method to summarize the same thermodynamic potentials is the thermodynamic square.

$$dU(S, V, \{n_i\}) = \sum_i \mu_i dn_i \quad \text{if } dS = dV = 0. \quad (8.9)$$

Similarly:

$$\begin{aligned} dH(S, P, \{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if } dS = dP = 0, \\ dA(T, V, \{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if } dT = dV = 0, \\ dG(T, P, \{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if } dT = dP = 0. \end{aligned} \quad (8.10)$$

The latter two cases are particularly interesting since most of chemistry happens at either constant volume (for example, several industrial processes in chemical plants), or constant pressure (for example, most processes in a chemistry lab). Since $dS = 0$ is not a requirement for both free energies to describe chemical changes, we can apply either of them to study non-isenthalpic processes. If a process is not isenthalpic, it increases the entropy of the universe or decreases it. Therefore—according to the second law—it is either spontaneous or not. Using this concept in conjunction with Clausius theorem, we can devise new criteria for inferring the spontaneity of a process that depends exclusively on the free energies.

Recalling Clausius theorem:

$$dS^{\text{sys}} \geq \frac{dQ}{T_{\text{surr}}} \quad \rightarrow \quad TdS \geq dQ, \quad (8.11)$$

we can consider the two cases: constant V ($dQ_V = dU$, left), and constant P ($dQ_P = dH$, right):

constant V :

$$TdS \geq dU$$

constant P :

$$TdS \geq dH \quad (8.12)$$

$$TdS - dU \geq 0$$

$$TdS - dH \geq 0$$

we can then simplify the definition of free energies, eqs. (8.6) and (8.8):

constant $T, V :$

$$d(A)_{T,V} = dU - TdS$$

$$dU = d(A)_{T,V} + TdS$$

constant $T, P :$

$$d(G)_{T,P} = dH - TdS$$

$$dH = d(G)_{T,P} + TdS$$

(8.13)

and by merging dU and dH from eqs. (8.13) into Clausius theorem expressed using eqs. (8.12), we obtain:

$$TdS - d(A)_{T,V} - TdS \geq 0$$

$$TdS - d(G)_{T,P} - TdS \geq 0$$

$$d(A)_{T,V} \leq 0$$

$$d(G)_{T,P} \leq 0.$$

(8.14)

These equations represent the conditions on dA and dG for inferring the spontaneity of a process, and can be summarized as follows:

Definition 8.2.

- During a spontaneous process at constant *temperature* and *volume*, the *Helmholtz free energy* will decrease ($dA < 0$), until it reaches a stationary point at which the system will be at equilibrium ($dA = 0$).
- During a spontaneous process at constant *temperature* and *pressure*, the *Gibbs free energy* will decrease ($dG < 0$), until it reaches a stationary point at which the system will be at equilibrium ($dG = 0$).

8.4 Maxwell Relations

Let's consider the fundamental equations for the thermodynamic potentials that we have derived in section 8.1:




Figure 8.1: Behavior of Helmholtz (red) and Gibbs (blue) Free Energies for Spontaneous Processes at Constant T, V (left) and Constant T, P (right).

$$\begin{aligned}
dU(S, V, \{n_i\}) &= TdS - PdV + \sum_i \mu_i dn_i \\
dH(S, P, \{n_i\}) &= TdS + VdP + \sum_i \mu_i dn_i \\
dA(T, V, \{n_i\}) &= -SdT - PdV + \sum_i \mu_i dn_i \\
dG(T, P, \{n_i\}) &= -SdT + VdP + \sum_i \mu_i dn_i .
\end{aligned} \tag{8.15}$$

From the knowledge of the natural variable of each potential, we could reconstruct these formulas by using the total differential formula:

$$\begin{aligned}
dU &= \underbrace{\left(\frac{\partial U}{\partial S}\right)_{V, \{n_i\}}}_{T} dS + \underbrace{\left(\frac{\partial U}{\partial V}\right)_{S, \{n_i\}}}_{-P} dV + \sum_i \underbrace{\left(\frac{\partial U}{\partial n_i}\right)_{S, V, \{n_j \neq i\}}}_{\mu_i} dn_i \\
dH &= \underbrace{\left(\frac{\partial H}{\partial S}\right)_{P, \{n_i\}}}_{T} dS + \underbrace{\left(\frac{\partial H}{\partial P}\right)_{S, \{n_i\}}}_{V} dP + \sum_i \underbrace{\left(\frac{\partial H}{\partial n_i}\right)_{S, P, \{n_j \neq i\}}}_{\mu_i} dn_i \\
dA &= \underbrace{\left(\frac{\partial A}{\partial T}\right)_{V, \{n_i\}}}_{-S} dT + \underbrace{\left(\frac{\partial A}{\partial V}\right)_{T, \{n_i\}}}_{-P} dV + \sum_i \underbrace{\left(\frac{\partial A}{\partial n_i}\right)_{T, V, \{n_j \neq i\}}}_{\mu_i} dn_i \\
dG &= \underbrace{\left(\frac{\partial G}{\partial T}\right)_{V, \{n_i\}}}_{-S} dT + \underbrace{\left(\frac{\partial G}{\partial P}\right)_{T, \{n_i\}}}_{V} dP + \sum_i \underbrace{\left(\frac{\partial G}{\partial n_i}\right)_{T, P, \{n_j \neq i\}}}_{\mu_i} dn_i ,
\end{aligned} \tag{8.16}$$

we can derive the following new definitions:

$$\begin{aligned}
T &= \left(\frac{\partial U}{\partial S} \right)_{V, \{n_i\}} = \left(\frac{\partial H}{\partial S} \right)_{P, \{n_i\}} \\
-P &= \left(\frac{\partial U}{\partial V} \right)_{S, \{n_i\}} = \left(\frac{\partial A}{\partial V} \right)_{T, \{n_i\}} \\
V &= \left(\frac{\partial H}{\partial P} \right)_{S, \{n_i\}} = \left(\frac{\partial G}{\partial P} \right)_{T, \{n_i\}} \\
-S &= \left(\frac{\partial A}{\partial T} \right)_{V, \{n_i\}} = \left(\frac{\partial G}{\partial T} \right)_{V, \{n_i\}}
\end{aligned} \tag{8.17}$$

and:

$$\begin{aligned}
\mu_i &= \left(\frac{\partial U}{\partial n_i} \right)_{S, V, \{n_j \neq i\}} = \left(\frac{\partial H}{\partial n_i} \right)_{S, P, \{n_j \neq i\}} \\
&= \left(\frac{\partial A}{\partial n_i} \right)_{T, V, \{n_j \neq i\}} = \left(\frac{\partial G}{\partial n_i} \right)_{T, P, \{n_j \neq i\}} .
\end{aligned}$$

Since T , P , V , and S are now defined as partial first derivatives of a thermodynamic potential, we can now take a second partial derivation with respect to a separate variable, and rely on Schwartz's theorem on c to derive the following relations:

$$\begin{aligned}
\frac{\partial^2 U}{\partial S \partial V} &= + \left(\frac{\partial T}{\partial V} \right)_{S, \{n_j \neq i\}} = - \left(\frac{\partial P}{\partial S} \right)_{V, \{n_j \neq i\}} \\
\frac{\partial^2 H}{\partial S \partial P} &= + \left(\frac{\partial T}{\partial P} \right)_{S, \{n_j \neq i\}} = + \left(\frac{\partial V}{\partial S} \right)_{P, \{n_j \neq i\}} \\
-\frac{\partial^2 A}{\partial T \partial V} &= + \left(\frac{\partial S}{\partial V} \right)_{T, \{n_j \neq i\}} = + \left(\frac{\partial P}{\partial T} \right)_{V, \{n_j \neq i\}} \\
\frac{\partial^2 G}{\partial T \partial P} &= - \left(\frac{\partial S}{\partial P} \right)_{T, \{n_j \neq i\}} = + \left(\frac{\partial V}{\partial T} \right)_{P, \{n_j \neq i\}}
\end{aligned} \tag{8.18}$$

The relations in (8.18) are called **Maxwell relations**,⁷ and are useful in experimental settings to relate quantities that are hard to measure with others that are more intuitive.

⁷Maxwell relations should not be confused with the Maxwell equations of electromagnetism.

Exercise 8.1. Derive the last Maxwell relation in eq. (8.18).

Solution: We can start our derivation from the definition of V and S as a partial derivative of G :

$$V = \left(\frac{\partial G}{\partial P} \right)_{T, \{n_i\}} \quad \text{and:} \quad -S = \left(\frac{\partial G}{\partial T} \right)_{V, \{n_i\}}, \quad (8.19)$$

and then take a second partial derivative of each quantity with respect to the second variable:

$$\begin{aligned} \left(\frac{\partial V}{\partial T} \right)_{P, \{n_i\}} &= \frac{\partial}{\partial T} \left[\left(\frac{\partial G}{\partial P} \right)_{T, \{n_i\}} \right]_{P, \{n_i\}} \\ &\quad - \left(\frac{\partial S}{\partial P} \right)_{T, \{n_i\}} = \frac{\partial}{\partial P} \left[\left(\frac{\partial G}{\partial T} \right)_{P, \{n_i\}} \right]_{T, \{n_i\}}. \end{aligned} \quad (8.20)$$

These two derivatives are mixed partial second derivatives of G with respect to T and P , and therefore, according to Schwartz's theorem, they are equal to each other:

$$\begin{aligned} \frac{\partial}{\partial T} \left[\left(\frac{\partial G}{\partial P} \right)_{T, \{n_i\}} \right]_{P, \{n_i\}} &= \frac{\partial}{\partial P} \left[\left(\frac{\partial G}{\partial T} \right)_{P, \{n_i\}} \right]_{T, \{n_i\}}, \\ \text{hence:} \end{aligned} \quad (8.21)$$

$$\left(\frac{\partial V}{\partial T} \right)_{P, \{n_i\}} = - \left(\frac{\partial S}{\partial P} \right)_{T, \{n_i\}},$$

which is the last of Maxwell relations, as defined in eq. (8.18). This relation is particularly useful because it connects the quantity $\left(\frac{\partial S}{\partial P} \right)_{T, \{n_i\}}$ —which is impossible to measure in a lab—with the quantity $\left(\frac{\partial V}{\partial T} \right)_{P, \{n_i\}}$ —which is easier to measure from an experiment that determines isobaric volumetric thermal expansion coefficients.

Chapter 9

Gibbs Free Energy

In this chapter, we will concentrate on chemical processes that happen at constant T and constant P .¹ As such, we will focus our attention on the Gibbs free energy.

9.1 Gibbs Equation

Recalling from the previous chapter, the definition of G is:

$$G = U - TS + PV = H - TS, \quad (9.1)$$

which, taking the differential at constant T and P , becomes:

$$dG = dH - \underbrace{SdT}_{=0} - TdS = dH - TdS. \quad (9.2)$$

Integrating eq. (9.2) between the initial and final states of a process results in:

¹The majority of chemical reactions in a lab happens at those conditions, and all biological functions happen at those conditions as well.

$$\int_i^f dG = \int_i^f dH - T \int_i^f dS \quad (9.3)$$

$$\Delta G = \Delta H - T\Delta S$$

which is the famous **Gibbs equation** for ΔG . Using Definition 8.2, we can use ΔG to infer the spontaneity of a chemical process that happens at constant T and P using $\Delta G \leq 0$. If we set ourselves at standard conditions, we can calculate the standard Gibbs free energy of formation, $\Delta_{\text{rxn}}G^\ominus$, for any reaction as:

$$\begin{aligned} \Delta_{\text{rxn}}G^\ominus &= \Delta_{\text{rxn}}H^\ominus - T\Delta_{\text{rxn}}S^\ominus \\ &= \sum_i \nu_i \Delta_f H_i^\ominus + T \sum_i \nu_i S_i^\ominus, \end{aligned} \quad (9.4)$$

where $\Delta_f H_i^\ominus$ are the standard enthalpies of formation, S_i^\ominus are the standard entropies, and ν_i are the stoichiometric coefficients for every species i involved in the reaction. All these quantities are commonly available, and we have already discussed their usage in chapters 4 and 7, respectively.²

The following four options are possible for ΔG^\ominus of a chemical reaction:

| ΔG^\ominus | | ΔH^\ominus | ΔS^\ominus | Spontaneous? |
|--------------------|-----------|--------------------|--------------------|---|
| – | <i>if</i> | – | + | <i>Always</i> |
| + | <i>if</i> | + | – | <i>Never</i> |
| -/+ | <i>if</i> | – | – | <i>Depends on T:</i> spontaneous at low T |
| +/- | <i>if</i> | + | + | <i>Depends on T:</i> spontaneous at high T |

²It is not uncommon to see values of $\Delta_f G^\ominus$ tabulated alongside $\Delta_f H^\ominus$ and S_i^\ominus , which simplifies even further the calculation. In fact, a comprehensive list of standard Gibbs free energy of formation of inorganic and organic compounds is reported in the appendix of this book 16. For cases where $\Delta_f G^\ominus$ are not reported, they can always be calculated by their constituents.

Or, in other words:

- Exothermic reactions that increase the entropy are always spontaneous.
- Endothermic reactions that reduce the entropy are always non-spontaneous.
- For the other two cases, the spontaneity of the reaction depends on the temperature:
 - Exothermic reactions that reduce the entropy are spontaneous at low T .
 - Endothermic reactions that increase the entropy are spontaneous at high T .

A simple criterion to evaluate the entropic contribution of a reaction is to look at the total number of moles of the reactants and the products (as the sum of the stoichiometric coefficients). If the reaction is producing more molecules than it destroys ($|\sum_{\text{products}} \nu_i| > |\sum_{\text{reactants}} \nu_i|$), it will increase the entropy. Vice versa, if the total number of moles in a reaction is reducing ($|\sum_{\text{products}} \nu_i| < |\sum_{\text{reactants}} \nu_i|$), the entropy will also reduce.

As we saw in section 8.2, the natural variables of the Gibbs free energy are the temperature, T , the pressure, P , and chemical composition, as the number of moles $\{n_i\}$. The Gibbs free energy can therefore be expressed using the total differential as (see also, last formula in eq. (8.16)):

$$dG(T, P, \{n_i\}) = \underbrace{\left(\frac{\partial G}{\partial T}\right)_{V, \{n_i\}} dT}_{\text{temperature dependence}} + \underbrace{\left(\frac{\partial G}{\partial P}\right)_{T, \{n_i\}} dP}_{\text{pressure dependence}} + \sum_i \underbrace{\left(\frac{\partial G}{\partial n_i}\right)_{T, P, \{n_j \neq i\}} dn_i}_{\text{composition dependence}} \quad (9.5)$$

If we know the behavior of G as we vary each of the three natural variables independently of the other two, we can reconstruct the total differential dG . Each of these terms represents a coefficient in eq. (9.5), which are given in eq. (8.17).

9.2 Temperature Dependence of ΔG

$$\left(\frac{\partial G}{\partial T}\right)_{P, \{n_i\}} = -S$$

Let's analyze the first coefficient that gives the dependence of the Gibbs energy on temperature. Since this coefficient is equal to $-S$ and the entropy is always positive, G must decrease when T increases at constant T and $\{n_i\}$, and vice versa.

If we replace this coefficient for $-S$ in the Gibbs equation, eq. (9.3), we obtain:

$$\Delta G = \Delta H + T \left(\frac{\partial G}{\partial T} \right)_{P, \{n_i\}}, \quad (9.6)$$

and since eq. (9.6) includes both ΔG and its partial derivative with respect to temperature $\left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}}$ we need to rearrange it to include the temperature derivative only. To do so, we can start by evaluating the partial derivative of $\left(\frac{\Delta G}{T} \right)$ using the chain rule:

$$\left[\frac{\partial \left(\frac{\Delta G}{T} \right)}{\partial T} \right]_{P, \{n_i\}} = \frac{1}{T} \left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}} - \frac{1}{T^2} \Delta G, \quad (9.7)$$

which, replacing ΔG from eq. (9.6) into eq. (9.7), becomes:

$$\begin{aligned} \left[\frac{\partial \left(\frac{\Delta G}{T} \right)}{\partial T} \right]_{P, \{n_i\}} &= \frac{1}{T} \left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}} - \frac{1}{T^2} \left[\frac{1}{T} \left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}} - \frac{1}{T^2} \Delta G \right] \\ &= \frac{1}{T} \left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}} - \frac{1}{T} \left(\frac{\partial \Delta G}{\partial T} \right)_{P, \{n_i\}} - \frac{\Delta H}{T^2}, \end{aligned} \quad (9.8)$$

which simplifies to:

$$\left[\frac{\partial \left(\frac{\Delta G}{T} \right)}{\partial T} \right]_{P, \{n_i\}} = -\frac{\Delta H}{T^2}. \quad (9.9)$$

Equation (9.9) is known as the **Gibbs–Helmholtz equation**, and is useful in its integrated form to calculate the Gibbs free energy for a chemical reaction at any temperature T by knowing just the standard Gibbs free energy of formation and the standard enthalpy of formation for the individual species,

which are usually reported at $T = 298$ K. The integration is performed as follows:

$$\int_{T_i=298 \text{ K}}^{T_f=T} \frac{\partial \left(\frac{\Delta_{\text{rxn}}G}{T} \right)}{\partial T} = - \int_{T_i=298 \text{ K}}^{T_f=T} \frac{\Delta_{\text{rxn}}H}{T^2}$$

$$\frac{\Delta_{\text{rxn}}G^\ominus(T)}{T} = \frac{\Delta_{\text{rxn}}G^\ominus}{298 \text{ K}} + \Delta_{\text{rxn}}H^\ominus \left(\frac{1}{T^2} - \frac{1}{(298 \text{ K})^2} \right), \quad (9.10)$$

giving the integrated Gibbs–Helmholtz equation:

$$\frac{\Delta_{\text{rxn}}G^\ominus(T)}{T} = \frac{\sum_i \nu_i \Delta_f G_i^\ominus}{298 \text{ K}} + \sum_i \nu_i \Delta_f H_i^\ominus \left(\frac{1}{T^2} - \frac{1}{(298 \text{ K})^2} \right) \quad (9.11)$$

9.3 Pressure Dependence of ΔG

$$\left(\frac{\partial G}{\partial P} \right)_{T, \{n_i\}} = V$$

We can now turn the attention to the second coefficient that gives how the Gibbs free energy changes when the pressure change. To do this, we put the system at constant T and $\{n_i\}$, and then we consider infinitesimal variations of G . From eq. (8.8):

$$dG = VdP - SdT + \sum_i \mu_i dn_i \xrightarrow{\text{constant } T, \{n_i\}} dG = VdP, \quad (9.12)$$

which is the differential equation that we were looking for. To study changes of G for macroscopic changes in P , we can integrate eq. (9.12) between initial and final pressures, and considering an ideal gas, we obtain:

$$\int_i^f dG = \int_i^f VdP$$

$$\Delta G = nRT \int_i^f \frac{dP}{P} = nRT \ln \frac{P_f}{P_i}. \quad (9.13)$$

If we take $P_i = P^\ominus = 1 \text{ bar}$, we can rewrite eq. (9.13) as:

$$G = G^\ominus + nRT \ln \frac{P_f}{\underbrace{P^\ominus}_{=1 \text{ bar}}}, \quad (9.14)$$

which is useful to convert standard Gibbs free energies of formation at pressures different than standard pressure, using:

$$\Delta_f G = \Delta_f G^\ominus + nRT \ln \frac{P_f}{\underbrace{P^\ominus}_{=1 \text{ bar}}} = \Delta_f G^\ominus + nRT \ln P_f \quad (9.15)$$

For liquids and solids, V is essentially independent of P (liquids and solids are incompressible), and eq. (9.12) can be integrated as:

$$\Delta G = \int_i^f V dP = V \int_i^f dP = V \Delta P. \quad (9.16)$$

The plots in Figure 9.1 show the remarkable difference in the behaviors of $\Delta_f G$ for a gas and for a liquid, as obtained from eqs. (9.13) and (9.16).

9.4 Composition Dependence of ΔG

$$\left(\frac{\partial G}{\partial n_i} \right)_{T,P} = \mu_i$$

The third and final coefficient gives the chemical potential as the dependence of G on the chemical composition at constant T and P . Similarly to the previous cases, we can take the definition of the coefficient and integrate it directly between the initial and final stages of a reaction. If we consider a reaction product, pure substance i , at the beginning of the reaction there will be no moles of it $n_i = 0$, and consequently $G = 0$.³ We can then integrate the left-hand side between zero and the number of moles of product at the end of the reaction, n , and the right-hand side between zero and the Gibbs free energy of the product, G . The integral will become:

³For reactants, the same situation usually applies but in reverse. More complicated cases where the reaction does not consume all reactants are possible, but insignificant for the following treatment.




Figure 9.1: Dependence of the Gibbs Free Energy of Formation of Liquid and Gaseous Ethanol at $T = 310 \text{ K}$. The Curves Cross at the Vapor Pressure of Liquid Ethanol at this Temperature, which is 0.1 bar.

$$\int_0^G dG = \int_0^n \mu^* dn, \quad (9.17)$$

where μ^* indicates the chemical potential of a pure substance, which is independent on the number of moles by definition. As such, eq. (9.17) becomes:

$$\int_0^G dG = \mu^* \int_0^n dn \rightarrow G = \mu^* n \rightarrow \mu^* = \frac{G}{n}, \quad (9.18)$$

which gives a straightforward interpretation of the chemical potential of a pure substance as the molar Gibbs free energy.

We can start from eq. (9.14) and write for a pure substance that is brought from $P_i = P^\ominus$ to $P_f = P$ at constant T :

$$G - G^\ominus = nRT \ln \frac{P}{P^\ominus}, \quad (9.19)$$

dividing both sides by n , we obtain:

$$\frac{G}{n} - \frac{G^\ominus}{n} = RT \ln \frac{P}{P^\ominus}, \quad (9.20)$$

which, for a pure substance at $P^\ominus = 1$ bar, becomes:

$$\mu^* = \mu^\ominus + RT \ln P. \quad (9.21)$$

Notice that, while we use the pressure of the gas inside the logarithm in eq. (9.21), the quantity is formally divided by the standard pressure $P^\ominus = 1$ bar, and therefore it is a dimensionless quantity, as it should be. For simplicity of notation, however, we will omit the division by P^\ominus in the remaining of this textbook, especially wherever it does not create confusion. Let's now consider a mixture of ideal gases, and let's try to find out whether the chemical potential of a pure gas inside the mixture, μ_i^{mixture} , is the same as its chemical potential outside the mixture, μ^* . To do so, we can use eq. (9.21) and replace the pressure P with the partial pressure P_i :

$$\mu_i^{\text{mixture}} = \mu_i^\ominus + RT \ln P_i, \quad (9.22)$$

where the partial pressure P_i can be obtained from the simple relation that is known as **Dalton's Law**:

$$P_i = y_i P, \quad (9.23)$$

with y_i being the concentration of gas i measured as a mole fraction in the gas phase $y_i = \frac{n_i}{n_{\text{TOT}}} < 1$. Replacing eq. (9.23) into eq. (9.22), we obtain:

$$\begin{aligned} \mu_i^{\text{mixture}} &= \mu_i^\ominus + RT \ln(y_i P) \\ &= \underbrace{\mu_i^\ominus + RT \ln P}_{\mu_i^*} + RT \ln y_i, \end{aligned} \quad (9.24)$$

which then reduces to the following equation:

$$\mu_i^{\text{mixture}} = \mu_i^* + RT \ln y_i. \quad (9.25)$$

Analyzing eq. (9.25), we can immediately see that, since $y_i < 1$:

$$\mu_i^{\text{mixture}} < \mu_i^*, \quad (9.26)$$

or, in other words, the chemical potential of a substance in the mixture is always lower than the chemical potential of the pure substance. If we consider a process where we start from two separate pure ideal gases and finish with a mixture of the two, we can calculate the change in Gibbs free energy due to the mixing process with:

$$\Delta_{\text{mixing}}G = \sum n_i (\mu_i^{\text{mixture}} - \mu_i^*) < 0, \quad (9.27)$$

or, in other words, the process is spontaneous under all circumstances, and pure ideal gases will always mix.

Chapter 10

Chemical Equilibrium

10.1 Reaction Quotient and Equilibrium Constant

Let's consider a prototypical reaction at constant T, P :



The Gibbs free energy of the reaction is defined as:

$$\Delta_{\text{rxn}}G = G_{\text{products}} - G_{\text{reactants}} = G^{\text{C}} + G^{\text{D}} - G^{\text{A}} - G^{\text{B}}, \quad (10.2)$$

and replacing the absolute Gibbs free energies with the chemical potentials μ_i , we obtain:

$$\Delta_{\text{rxn}}G = c\mu_{\text{C}} + d\mu_{\text{D}} - a\mu_{\text{A}} - b\mu_{\text{B}}. \quad (10.3)$$

Assuming the reaction is happening in the gas phase, we can then use eq. (9.22) to replace the chemical potentials with their value in the reaction mixture, as:

$$\begin{aligned} \Delta_{\text{rxn}}G &= c(\mu_{\text{C}}^{\ominus} + RT \ln P_{\text{C}}) + d(\mu_{\text{D}}^{\ominus} + RT \ln P_{\text{D}}) + \\ &\quad - a(\mu_{\text{A}}^{\ominus} + RT \ln P_{\text{A}}) - b(\mu_{\text{B}}^{\ominus} + RT \ln P_{\text{B}}) \\ &= \underbrace{c\mu_{\text{C}}^{\ominus} + d\mu_{\text{D}}^{\ominus} - a\mu_{\text{A}}^{\ominus} - b\mu_{\text{B}}^{\ominus}}_{\Delta_{\text{rxn}}G^{\ominus}} + RT \ln \frac{P_{\text{C}}^c \cdot P_{\text{D}}^d}{P_{\text{A}}^a \cdot P_{\text{B}}^b}. \end{aligned} \quad (10.4)$$

We can define a new quantity called the *reaction quotient* as a function of the partial pressures of each substance:¹

$$Q_P = \frac{P_C^c \cdot P_D^d}{P_A^a \cdot P_B^b}, \quad (10.5)$$

and we can then simply rewrite eq. (10.4) using eq. (10.5) as:

$$\Delta_{\text{rxn}}G = \Delta_{\text{rxn}}G^\ominus + RT \ln Q_P. \quad (10.6)$$

This equation tells us that the sign of $\Delta_{\text{rxn}}G$ is influenced by the reaction quotient Q_P . For a spontaneous reaction at the beginning, the partial pressures of the reactants are much higher than the partial pressures of the products, therefore $Q_P \ll 1$ and $\Delta_{\text{rxn}}G < 0$, as we expect. As the reaction proceeds, the partial pressures of the products will increase, while the partial pressures of the reactants will decrease. Consequently, both Q_P and $\Delta_{\text{rxn}}G$ will increase. The reaction will completely stop when $\Delta_{\text{rxn}}G = 0$, which is the chemical equilibrium point. At the reaction equilibrium:

$$\Delta_{\text{rxn}}G = 0 = \Delta_{\text{rxn}}G^\ominus + RT \ln K_P, \quad (10.7)$$

where we have defined a new quantity called **equilibrium constant**, as the value the reaction quotient assumes when the reaction reaches equilibrium, and we have denoted it with the symbol K_P .² From eq. (10.7) we can derive the following fundamental equation on the standard Gibbs free energy of reaction:

$$\Delta_{\text{rxn}}G^\ominus = -RT \ln K_P. \quad (10.8)$$

To extend the concept of K_P beyond the four species in the prototypical reaction (10.1), we can use the product of a series symbol (\prod_i), and write:

$$K_P = \prod_i P_{i,\text{eq}}^{\nu_i}, \quad (10.9)$$

¹Notice that since we used eq. (9.21) to derive the reaction quotient, the partial pressures inside it are always dimensionless since they are divided by P^\ominus .

²The subscript P refers to the fact that the equilibrium constant is measured in terms of partial pressures.

where $P_{i,\text{eq}}$ are the partial pressure of each species at equilibrium. Eq. (10.9) is in principle valid for ideal gases only. However, reaction involving ideal gases are pretty rare. As such, we can further extend the concept of equilibrium constant and write:

$$K_{\text{eq}} = \prod_i a_{i,\text{eq}}^{\nu_i}, \quad (10.10)$$

where we have replaced the partial pressure at equilibrium, $P_{i,\text{eq}}$, with a new concept introduced initially by Gilbert Newton Lewis (1875–1946),³ that he termed **activity**, and represented by the letter a . For ideal gases, it is clear that $a_i = P_i/P^\ominus$. For non-ideal gases, the activity is equal to the fugacity $a_i = f_i/P^\ominus$, a concept that we will investigate in the next chapter. For pure liquids and solids, the activity is simply $a_i = 1$. For diluted solutions, the activity is equal to a measured concentration (such as, for example, the mole fraction x_i in the liquid phase, and y_i in the gas phase, or the molar concentration $[i]/[i]^\ominus$ with $[i]^\ominus = 1 \text{ [mol/L]}$). Finally for concentrated solutions, the activity is related to the measured concentration via an activity coefficient. We will return to the concept of activity in chapter 14, when we will specifically deal with solutions. For now, it is interesting to use the activity to write the definition of the following two constants:

$$K_y = \prod_i (y_{i,\text{eq}})^{\nu_i} \quad K_C = \left(\prod_i [i]_{\text{eq}}/[i]^\ominus \right)^{\nu_i}, \quad (10.11)$$

which can then be related with K_P for a mixture of ideal gases using:

$$P_i = y_i P \quad P_i = \frac{n_i}{V} RT = [i]RT, \quad (10.12)$$

which then results in:

$$K_P = K_y \cdot \left(\frac{P}{P^\ominus} \right)^{\Delta\nu} \quad K_P = K_C \left(\frac{[i]^\ominus RT}{P^\ominus} \right)^{\Delta\nu}, \quad (10.13)$$

with $\Delta\nu = \sum_i \nu_i$.

³Gilber Lewis is the same scientist that invented the concept of Lewis Structures.

Using the general equilibrium constant, K_{eq} , we can also rewrite the fundamental equation on $\Delta_{\text{rxn}}G^{\ominus}$ that we derived in eq. (10.8) to be applicable at most conditions, as:

$$\Delta_{\text{rxn}}G^{\ominus} = -RT \ln K_{\text{eq}}, \quad (10.14)$$

and since $\Delta_{\text{rxn}}G^{\ominus}$ depends on T, P and $\{n_i\}$, it is useful to explore how K_{eq} depends on those variables as well.

10.2 Temperature Dependence of K_{eq}

To study the temperature dependence of K_{eq} we can use eq. (10.14) for the general equilibrium constant and write:

$$\ln K_{\text{eq}} = -\frac{\Delta G^{\ominus}}{RT}, \quad (10.15)$$

which we can then differentiate with respect to dT at constant $P, \{n_i\}$ on both sides:

$$\left(\frac{\partial \ln K_{\text{eq}}}{\partial T} \right)_{P, \{n_i\}} = -\frac{1}{R} \left[\partial \left(\frac{\partial \frac{\Delta F^{\ominus}}{RT}}{\partial T} \right) \right]_{P, \{n_i\}}, \quad (10.16)$$

and, using Gibbs-Helmholtz equation (eq. (9.9)) to simplify the left hand side, becomes:

$$\left(\frac{\partial \ln K_{\text{eq}}}{\partial T} \right)_{P, \{n_i\}} = -\frac{1}{R} \left(-\frac{\Delta H^{\ominus}}{T^2} \right) = \frac{\Delta H^{\ominus}}{RT^2}, \quad (10.17)$$

which gives the dependence of $\ln K_{\text{eq}}$ on T that we were looking for. Eq. (10.17) is also called **van 't Hoff equation**,⁴ and it is the mathematical expression of Le Chatelier's principle. The simplest interpretation is as follows:

- For an exothermic reaction ($\Delta H^{\ominus} < 0$): K_{eq} will decrease as the temperature increases.

⁴named after Jacobus Henricus "Henry" van 't Hoff Jr. (1852–1911).

- For an endothermic reaction ($\Delta H^\ominus > 0$): K_{eq} will increase as the temperature increases.

If we integrate the van 't Hoff equation between two arbitrary points at constant P , and assuming constant ΔH^\ominus , we obtain the following:

$$\int_1^2 d \ln K_{eq} = \frac{\Delta H^\ominus}{R} \int_1^2 \frac{dT}{T^2}, \quad (10.18)$$

which leads to the linear equation:

$$\ln K_{eq}(2) = \ln K_{eq}(1) - \frac{\Delta H^\ominus}{R} \left(\frac{1}{T_2} - \frac{1}{T_1} \right). \quad (10.19)$$

which is the equation that produces the so-called **van 't Hoff plots**, from which ΔH^\ominus can be experimentally determined:




Figure 10.1: Van 't Hoff Plots for an Endothermic (Left, Blue) and an Exothermic (Right, Red) Reactions at Constant P.

10.3 Pressure and Composition Dependence of K_{eq}


While K_P is independent of both temperature and number of moles for an ideal gas, the same is not necessarily true for the other equilibrium constants.

$$\left(\frac{\partial K_P}{\partial P}\right)_{T,\{n_i\}} = 0 \quad \left(\frac{\partial K_P}{\partial n_i} = 0\right)_{T,P}. \quad (10.20)$$

For example, it is easy to look at eq. (10.13) and determine that K_y usually depends on P .⁵ Using Dalton's Law, eq. (9.23), we can also notice that the equilibrium partial pressures of the reactants and products in a gas-phase reaction can be expressed in terms of their equilibrium mole fractions y_i and the total pressure P . As such, we can use K_y to demonstrate that the equilibrium mole fractions will change when P changes,⁶ as it is demonstrated by the following exercise.

Exercise 10.1. Calculate the mole fraction change for the dissociation of $\text{Cl}_{2(g)}$ when the pressure is increased from P^\ominus to $P_f = 2.5$ bar at constant $T = 2298$ K, knowing that $\Delta_f G_{\text{Cl}_{(g)}}^\ominus = 105.3$ kJ/mol and $\Delta_f H_{\text{Cl}_{(g)}}^\ominus = 121.3$ kJ/mol, and remembering that both of these values are tabulated at $T = 298$ K.

Solution: Let's consider the reaction:



We can divide the exercise into two parts. In the first one, we will deal with calculating the equilibrium constant at $T = 2298$ K from the data at $T = 298$ K. In the second one, we will calculate the change in mole fraction when the pressure is increased from $P^\ominus = 1$ bar to $P_f = 2.5$ bar.

- Let's begin the first part by calculating $\Delta_{\text{rxn}}G^\ominus$ and $\Delta_{\text{rxn}}H^\ominus$ from:

$$\begin{aligned} \Delta_{\text{rxn}}G^\ominus &= 2\Delta_f G_{\text{Cl}_{(g)}}^\ominus - \Delta_f G_{\text{Cl}_{2(g)}}^\ominus \\ \Delta_{\text{rxn}}H^\ominus &= 2\Delta_f H_{\text{Cl}_{(g)}}^\ominus - \Delta_f H_{\text{Cl}_{2(g)}}^\ominus, \end{aligned} \quad (10.21)$$

⁵ K_y becomes independent of P in the particular case where $\Delta\nu = 0$, i.e., for reactions where the total number of moles of reactants is the same as the total number of moles of the products.

⁶Keep in mind that K_P will *not* change.

and since $\text{Cl}_{2(g)}$ is an element in its most stable form at $T = 298 \text{ K}$, its standard enthalpy and Gibbs free energy of formation are $\Delta_f H_{\text{Cl}_{2(g)}}^\ominus = \Delta_f G_{\text{Cl}_{2(g)}}^\ominus = 0$. Therefore:⁷

$$\begin{aligned}\Delta_{\text{rxn}}G^\ominus &= 2 \cdot 105.3 - 0 = 210.6 \text{ kJ/mol} \\ \Delta_{\text{rxn}}H^\ominus &= 2 \cdot 121.3 - 0 = 242.6 \text{ kJ/mol.}\end{aligned}\quad (10.22)$$

Using eq. (10.8) to calculate $K_P(P^\ominus, 298 \text{ K})$, we obtain:⁸

$$\ln[K_P(P^\ominus, 298 \text{ K})] = \frac{-\Delta_{\text{rxn}}G^\ominus}{RT} = \frac{-210.6 \times 10^3}{8.31 \cdot 298} = -85.0. \quad (10.23)$$

We can now use the integrated van 't Hoff equation, eq. (10.19), to calculate K_P at $T = 2298 \text{ K}$:

$$\begin{aligned}\ln[K_P(P^\ominus, 2298 \text{ K})] &= \ln[K_P(P^\ominus, 298 \text{ K})] + \\ &\quad - \frac{\Delta_{\text{rxn}}H^\ominus}{R} \left(\frac{1}{2298} - \frac{1}{298} \right),\end{aligned}\quad (10.24)$$

which becomes:

$$\begin{aligned}\ln[K_P(P^\ominus, 2298 \text{ K})] &= -85.0 + \\ &\quad - \frac{242.6 \times 10^3}{8.31} \left(\frac{1}{2298} - \frac{1}{298} \right) = 0.262,\end{aligned}\quad (10.25)$$

which corresponds to:

$$K_P(P^\ominus, 2298 \text{ K}) = \exp(0.262) = 1.30. \quad (10.26)$$

- Let's now move to the second part of the exercise, where we increase the pressure from 1 bar to 2.5 bar at constant $T = 2298 \text{ K}$. We start by writing the definition of K_P and K_y :

$$K_P = \frac{P_{\text{Cl}_{1(g)}}^2}{P_{\text{Cl}_{2(g)}}} \quad K_y = \frac{y_{\text{Cl}_{1(g)}}^2}{y_{\text{Cl}_{2(g)}}}, \quad (10.27)$$

⁷Notice how a positive $\Delta_{\text{rxn}}G^\ominus$ indicates that the dissociation of $\text{Cl}_{2(g)}$ is non-spontaneous at $T = 298 \text{ K}$ and $P = 1 \text{ bar}$. As such, we should expect a very small value for K_P .

⁸The results corresponds to $K_P = 1.2 \times 10^{-37}$, an incredible minuscule number, as we should expect given the data of $\Delta_{\text{rxn}}G^\ominus$.

and using eq. (10.13):

$$\Delta\nu = 2 - 1 = 1$$

$$K_P = K_y \cdot \frac{P}{P^\ominus} \quad \longrightarrow \quad K_y = K_P \left(\frac{P}{P^\ominus} \right)^{-1}, \quad (10.28)$$

we can calculate the initial K_y at $P_i = P^\ominus$, using:

$$K_y(P^\ominus, 2\,298\text{ K}) = 1.30 = \frac{1.30}{1}. \quad (10.29)$$

and calculate the initial concentration of $\text{Cl}_{(g)}$ and $\text{Cl}_{(g)}$ at P^\ominus , recalling that $y_{\text{Cl}_{2(g)}} = 1 - y_{\text{Cl}_{(g)}}$:

$$K_y(P_i, 2\,298\text{ K}) = \frac{\left(y_{\text{Cl}_{(g)}}^i\right)^2}{y_{\text{Cl}_{(g)}}^i} = 1.30. \quad (10.30)$$

Solving the quadratic equation, we obtain one negative answer—which is unphysical—,⁹ and:

$$y_{\text{Cl}_{(g)}}^i = 0.662 \quad \longrightarrow \quad y_{\text{Cl}_{2(g)}}^i = 1 - 0.662 = 0.338. \quad (10.31)$$

At the end of the process, $P_f = 2.5$ bar, and we obtain:

$$K_y(P_f, 2\,298\text{ K}) = 0.520 = K_P \frac{P^\ominus}{P_f} = \frac{1.30}{2.5}, \quad (10.32)$$

and, using the same technique used before to solve the quadratic equation:

$$K_y(P_f, 2\,298\text{ K}) = \frac{\left(y_{\text{Cl}_{(g)}}^f\right)^2}{y_{\text{Cl}_{(g)}}^f} = 0.520, \quad (10.33)$$

gives:

$$y_{\text{Cl}_{(g)}}^f = 0.507 \quad \longrightarrow \quad y_{\text{Cl}_{2(g)}}^f = 1 - 0.507 = 0.493. \quad (10.34)$$

To summarize, when we increase the pressure from 1 bar to 2.5 bar at $T = 2\,298\text{ K}$, the equilibrium constant in terms of the mole fraction decreases from $K_y(P^\ominus, 2\,298\text{ K}) = 1.30$ to $K_y(P_f = 2.5 \text{ bar}, 2\,298\text{ K}) = 0.520$. This reduction is causing a shift of the equilibrium towards the reactants, with

⁹Concentration cannot be negative.

the concentration of $\text{Cl}_{2(g)}$ increasing from $y_{\text{Cl}_{2(g)}}^i = 0.338$ to $y_{\text{Cl}_{2(g)}}^f = 0.493$ and the concentration of $\text{Cl}_{(g)}$ decreasing from $y_{\text{Cl}_{(g)}}^i = 0.662$ to $y_{\text{Cl}_{(g)}}^f = 0.507$.

The dependence of K_{eq} on P highlighted above is another mathematical expression of Le Chatelier's principle, on this occasion, for changes in pressure. The interpretation For a reaction happening in the gas phase is as follows:

- If the total pressure increases, the equilibrium will shift towards the side of the chemical equation that contains the smallest total amount of moles (the equilibrium in exercise 10.1 shifts toward the reactant).

Chapter 11

Ideal and Non-Ideal Gases

11.1 The Ideal Gas Equation

The concept of an ideal gas is a theoretical construct that allows for straightforward treatment and interpretation of gases' behavior. As such, the ideal gas is a simplified *model* that we use to understand nature, and it does not correspond to any real system. The following two assumptions define the ideal gas model:

- Definition 11.1.**
- The particles that compose an ideal gas do not occupy any volume.
 - The particles that compose an ideal gas do not interact with each other.

Because of its simplicity, the ideal gas model has been the historical foundation of thermodynamics and of science in general. The first studies of the ideal gas behavior date back to the seventeenth century, and the scientists that performed them are among the founders of modern science.

11.1.1 Boyle's Law

In 1662 Robert Boyle (1627–1691) found that the pressure and the volume of an ideal gas are inversely related at constant temperature. Boyle's Law has the following mathematical description:

$$P \propto \frac{1}{V} \quad \text{at const. } T, \quad (11.1)$$

or, in other terms:

$$PV = k_1 \quad \text{at const. } T, \quad (11.2)$$

which results in the familiar PV plots of Figure ???. As we already discussed in chapter 2, each of the curves in Figure ??? is obtained at constant temperature, and it is therefore called “*isotherm*.”




Figure 11.1: PV-Diagram of an ideal Gas.

11.1.2 Charles's and Gay-Lussac's Laws

It took scientists more than a century to expand Boyle's work and study the relationship between volume and temperature. In 1787 Jacques Alexandre César Charles (1746–1823) wrote the relationship known as Charles's Law:

$$V \propto T \quad \text{at const. } P, \quad (11.3)$$

or, in other terms:

$$V = k_2 T \quad \text{at const. } P, \quad (11.4)$$

which results in the plots of Figure 11.2. Each of the curves is obtained at constant pressure, and it is termed “*isobar*.”




Figure 11.2: VT-Diagram of an ideal Gas.

The interesting thing about isobars is that each line seems to converge to a specific point along the temperature line when we extrapolate them to $V \rightarrow 0$. This led to the introduction of the absolute temperature scale, suggesting that the temperature will never get smaller than -273.15°C .

It took an additional 21 years to write a formal relationship between pressure and temperature. The following relationships were proposed by Joseph Louis Gay-Lussac (1778–1850) in 1808:

$$P \propto T \quad \text{at const. } V, \tag{11.5}$$

or, in other terms:

$$P = k_3 T \quad \text{at const. } V, \tag{11.6}$$

which results in the plots of Figure 11.3. Each of the curves is obtained at constant volume, and it is termed “*isochor*.”

11.1.3 Avogadro’s Law

Ten years later, Amedeo Avogadro (1776–1856) discovered a seemingly unrelated principle by studying the composition of matter. His Avogadro’s




Figure 11.3: PT-Diagram of an ideal Gas.

Law encodes the relationship between the number of moles in an ideal gas and its volume as:

$$V \propto n \quad \text{at const. } P, T, \quad (11.7)$$

or in other terms:

$$V = k_4 n \quad \text{at const. } P, T, \quad (11.8)$$

11.1.4 The ideal gas Law

Despite all of the ingredients being available for more than 20 years, it's only in 1834 that Benoît Paul Émile Clapeyron (1799–1864) was finally able to combine them into what is now known as the **ideal gas Law**. Using the same formulas obtained above, we can write:

$$PV = \underbrace{k_3 T}_{\text{from Gay-Lussac's}} \cdot \underbrace{k_4 n}_{\text{from Avogadro's}}, \quad (11.9)$$

which by renaming the product of the two constants k_3 and k_4 as R , becomes:

$$PV = nRT \quad (11.10)$$

The value of the constant R can be determined experimentally by measuring the volume that 1 mol of an ideal gas occupies at a constant temperature (e.g., at $T = 0^\circ\text{C}$) and a constant pressure (e.g., atmospheric pressure $P = 1 \text{ atm}$). At those conditions, the volume is measured at 22.4 L, resulting in the following value of R :

$$R = \frac{VP}{nT} = \frac{22.4 \cdot 1}{1 \cdot 273} = 0.082 \frac{\text{L atm}}{\text{mol K}}, \quad (11.11)$$

which a simple conversion to SI units transforms into:

$$R = 8.31 \frac{\text{J}}{\text{mol K}}. \quad (11.12)$$

11.2 Behaviors of Non-Ideal Gases

Non-ideal gases (sometimes also referred to as “real gases”), do not behave as ideal gases because at least one of the assumptions in definition 11.1 is violated. What characterizes non-ideal gases is that there is no unique equation that we can use to describe their behavior. For this reason, we have a plethora of several experimental models, none of which is superior to the other. The van der Waals (vdW) equation is the only model that we will analyze in detail because of its simple interpretation. However, it is far from universal, and for several non-ideal gases, it is severely inaccurate. Other popular non-ideal gases equations are the Clausius equation, the virial equation, the Redlich–Kwong equation and several others.¹

11.2.1 The van der Waals equation

One of the simplest empirical equation that describes non-ideal gases was obtained in 1873 by Johannes Diderik van der Waals (1837–1923). The vdW equation includes two empirical parameters (a and b) with different values for different non-ideal gases. Each of the parameters corresponds to a correction for the breaking of one of the two conditions that define the

¹For more information on empirical equations for non-ideal gases see this Wikipedia page.

ideal gas behavior (definition 11.1). The vdW equation is obtained from the ideal gas equation performing the following simple substitutions:

$$\begin{aligned} P &\rightarrow \left(P + \frac{a}{V^2} \right) \\ \bar{V} &\rightarrow (\bar{V} - b), \end{aligned} \tag{11.13}$$

which results in:

$$\begin{aligned} P\bar{V} = RT &\rightarrow \left(P + \frac{a}{V^2} \right) (\bar{V} - b) = RT \\ P &= \frac{RT}{\bar{V} - b} - \frac{a}{V^2}. \end{aligned} \tag{11.14}$$

The parameter a accounts for the presence of intermolecular interactions, while the parameter b accounts for the non-negligible volume of the gas molecules. Despite the parameters have simple interpretations, their values for each gas must be determined experimentally. Values for these parameters for some significant non-ideal gas are reported below:

| | $a \left[\frac{\text{L}^2 \text{bar}}{\text{mol}^2} \right]$ | $b \left[\frac{\text{L}}{\text{mol}} \right]$ |
|-----------------|---|--|
| Ammonia | 4.225 | 0.0371 |
| Argon | 1.355 | 0.03201 |
| Carbon dioxide | 3.640 | 0.04267 |
| Carbon monoxide | 1.505 | 0.03985 |
| Chlorine | 6.579 | 0.05622 |
| Freon | 10.78 | 0.0998 |
| Helium | 0.0346 | 0.0238 |
| Hydrogen | 0.2476 | 0.02661 |
| Mercury | 8.200 | 0.01696 |
| Methane | 2.283 | 0.04278 |
| Neon | 0.2135 | 0.01709 |
| Nitrogen | 1.370 | 0.0387 |
| Oxygen | 1.382 | 0.03186 |
| Radon | 6.601 | 0.06239 |
| Xenon | 4.250 | 0.05105 |

11.2.2 Joule–Thomson effect




Figure 11.4: The Joule–Thomson Experiment.

We have already met William Thomson, also known as Lord Kelvin, and his seminal work on the second law of thermodynamics. In conjunction with that work, Thomson is famous for developing a sensitive method for measuring the temperature changes related to the expansion of a gas. These experiments improved on the earlier work by James Joule, and Lord Kelvin's improved instrument depicted in Figure 11.4 is named the Joule–Thomson apparatus. The apparatus is composed of two chambers, each with its own mobile piston. The chambers are connected via a valve or a porous plug. The entire equipment is also thermally isolated from the surroundings. This instrument is a more sensitive version of the Joule expansion apparatus that we already described in section 3 (compare with Figure 3.1).

Thomson realized that a gas flowing through an obstruction experience a drop in pressure. If the entire apparatus is insulated, it will not exchange heat with its surroundings ($Q = 0$), and each transformation will happen at adiabatic conditions. Let's consider an initial condition with 1 mol of gas in the left chamber, occupying a volume V_l , and a completely closed left chamber, for which $V_r^i = 0$. After the process completes, the volume of the right chamber will reduce to $V_r^f = 0$, while the volume of the right chamber will be V_r . Using the first law of thermodynamics, we can write:

$$\Delta U = U_r - U_l = \underbrace{Q}_{=0} + W = W_l + W_r, \quad (11.15)$$

with:

$$\begin{aligned} W_l &= - \int_{V_l}^0 P_l dV = P_l V_l \\ W_r &= - \int_0^{V_r} P_r dV = -P_r V_r. \end{aligned} \quad (11.16)$$

Replacing (11.16) into eq. (11.15), results in:

$$\begin{aligned} U_r - U_l &= P_l V_l - P_r V_r \\ \underbrace{U_r + P_r V_r}_{H_r} &= \underbrace{U_l + P_l V_l}_{H_l}, \end{aligned} \quad (11.17)$$

which, replacing the definition of enthalpy $H = U + PV$, we obtain:

$$\begin{aligned} H_r &= H_l \\ \Delta H &= 0, \end{aligned} \quad (11.18)$$

or, in other words, the process is **isenthalpic**. Using the total differential of H :

$$dH = \left(\frac{\partial H}{\partial T} \right)_P dT + \left(\frac{\partial H}{\partial P} \right)_T dP = C_P dT + \left(\frac{\partial H}{\partial P} \right)_T dP, \quad (11.19)$$

we obtain:

$$\Delta H = \int dH = \int C_P dT + \int \left(\frac{\partial H}{\partial P} \right)_T dP = 0, \quad (11.20)$$

or, in purely differential form:

$$dH = C_P dT + \left(\frac{\partial H}{\partial P} \right)_T dP = 0, \quad (11.21)$$

From eq. (11.21) we can define a new coefficient, called the *Joule–Thomson coefficient*, μ_{JT} , that measures the rate of change of temperature of a gas with respect to pressure in the Joule–Thomson process:

$$\mu_{\text{JT}} = \left(\frac{\partial T}{\partial P} \right)_H = -\frac{1}{C_P} \left(\frac{\partial H}{\partial T} \right)_P \quad (11.22)$$

The value of μ_{JT} depends on the type of gas, the temperature and pressure before expansion, and the heat capacity at constant pressure of the gas. The temperature at which μ_{JT} changes sign is called the “Joule–Thomson inversion temperature.” Since the pressure decreases during an expansion, ∂P is negative by definition, and the following possibilities are available for μ_{JT} :

| Gas temperature: | ∂P | μ_{JT} | ∂T | The gas will: |
|--|--------------|-------------------|--------------|---------------|
| <i>Below the inversion temperature</i> | – | + | – | cool |
| <i>Above the inversion temperature</i> | – | – | + | warm |

For example, helium has a very low Joule–Thomson inversion temperatures at standard pressure ($T = 45 \text{ K}$), and it warms when expanded at constant enthalpy at typical room temperatures. The only other gases that have standard inversion temperature lower than room temperature are hydrogen and neon. On the other hand, nitrogen and oxygen have high inversion temperatures ($T = 621 \text{ K}$ and $T = 764 \text{ K}$, respectively), and they both cool when expanded at room temperature. Therefore, it is possible to use the Joule–Thomson effect in refrigeration processes such as air conditioning.² As we already discussed in chapter 3, the temperature of an ideal gases stays constant in an adiabatic expansion, therefore its Joule–Thomson coefficient is always equal to zero.

²Nitrogen and oxygen are the two most abundant gases in the air. A sequence of Joule–Thomson expansions are also used for the industrial liquefaction of air.

11.3 Critical Phenomena

11.3.1 Compressibility factors

The compressibility factor is a correction coefficient that describes the deviation of a real gas from ideal gas behaviour. It is usually represented with the symbol z , and is calculated as:

$$z = \frac{\bar{V}}{\bar{V}_{\text{ideal}}} = \frac{P\bar{V}}{RT} \quad (11.23)$$

It is evident from eq. (11.23) that the compressibility factor is dependent on the pressure, and for an ideal gas $z = 1$ always. For a non-ideal gas at any given pressure, z can be higher or lower than one, separating the behavior of non-ideal gases into two possibilities. The dependence of the compressibility factor against pressure is represented for H_2 and CO_2 in Figure 11.5.




Figure 11.5: Non-Ideal Gases Behaviors.

The two types of possible behaviors are differentiated based on the compressibility factor at $P \rightarrow 0$. To analyze these situations we can use the vdW equation to calculate the compressibility factor as:

$$z = \frac{\bar{V}}{RT} \left(\frac{RT}{\bar{V} - b} - \frac{a}{\bar{V}^2} \right). \quad (11.24)$$

and then we can differentiate this equation at constant temperature with respect to changes in the pressure near $P = 0$, to obtain:

$$\left(\frac{\partial z}{\partial P}\right)_T \Big|_{P=0} = \frac{1}{RT} \left(b - \frac{a}{RT}\right). \quad (11.25)$$

which is then interpreted as follows:

- **Type I gases:** $b > \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} > 0$ *molecular size* dominates (H_2 -like behavior).
- **Type II gases:** $b < \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} < 0$ *attractive forces* dominates (CO_2 -like behavior).

The dependence of the compressibility factor as a function of temperature (Figure ??fig:Fig1Zb2)) results in different plots for each of the two types of behavior.




Figure 11.6: Temperature Dependence of the Compressibility Factor.

Both type I and type II non-ideal gases will approach the ideal gas behavior as $T \rightarrow \infty$, because $\frac{1}{RT} \rightarrow 0$ as $T \rightarrow \infty$. For type II gases, there are three interesting situations:

- At low T : $b < \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} < 0$, which is the behavior described above.
- At high T : $b > \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} > 0$, which is the same behavior of type I gases.
- At a very specific temperature, inversion will occur (i.e., at $T = 713\text{ K}$ for CO_2). This temperature is called the **Boyle temperature**, T_B , and is the temperature at which the attractive and repulsive forces balance out. It can be calculated from the vdW equation, since $b - \frac{a}{RT_B} = 0 \Rightarrow T_B = \frac{a}{bR}$. At the Boyle's temperature a type II gas shows ideal gas behavior over a large range of pressure.

11.3.2 Phase diagram of a non-ideal gas




Figure 11.7: The Pressure–Volume Diagram of a Non-Ideal Gas.

Let's now turn our attention to the PV phase diagram of a non-ideal gas, reported in Figure 11.7. We can start the analysis from an isotherm at a high temperature. Since every gas will behave as an ideal gas at those conditions, the corresponding isotherms will look similar to those of an ideal gas (T_5 and T_4 in Figure 11.7). Lowering the temperature, we start to see the deviation from ideality getting more prominent (T_3 in Figure 11.7) until we reach a particular temperature called the critical temperature, T_c .

Definition 11.2. Critical Temperature: The temperature above which no appearance of a second phase is observed, regardless of how high the pressure becomes.

At the critical temperature and below, the gas liquefies when the pressure is increased. For this reason, the liquefaction of a gas is called a *critical phenomenon*.

The critical temperature is the coordinate of a unique point, called the **critical point**, that can be visualized in the three-dimensional T, P, V diagram of each gas (Figure 11.8³).

³This diagram is taken from Wikipedia and distributed under CC-BY-SA license.




Figure 11.8: The three-dimensional diagram.

The critical point has coordinates T_c, P_c, \bar{V}_c . These critical coordinates can be determined from the vdW equation at T_c , as:

$$T_c = \frac{8a}{27Rb} \quad P_c = \frac{a}{27b^2} \quad \bar{V}_c = 3b, \quad (11.26)$$

These relations are used, in practice, to determine the vdW constants a, b from the experimentally measured critical isotherms.

The critical compressibility factor, z_c , is predicted from the vdW equation at:

$$z_c = \frac{P_c \bar{V}_c}{RT_c} = \left(\frac{a}{27b^2} \right) \left(\frac{3b}{R} \right) \left(\frac{27Rb}{8a} \right) = \frac{3}{8} = 0.375, \quad (11.27)$$

a value that is independent of the gas. Experimentally measured values of z_c for different non-ideal gases are in the range of 0.2–0.3. These values can be used to infer the accuracy of the vdW equation for each non-ideal gas. Since the experimental z_c is usually lower than the one calculated from the vdW equation, we can deduce that the vdW equation overestimates the critical molar volume.

Notice how slicing the $PT\bar{V}$ diagram at constant T results in the PV diagram that we reported in Figure 11.8. On the other hand, slicing the $PT\bar{V}$

diagram at constant P results in the PT diagram that we will examine in detail in the next chapter.

11.4 Fugacity

The chemical potential of a pure ideal gas can be calculated using eq. (9.21). Since we are not interested in mixture, we can drop the asterisk in μ^* , and rewrite eq. (9.21) as:

$$\mu_{\text{ideal}} = \mu^\ominus + RT \ln \frac{P}{P^\ominus}. \quad (11.28)$$

For a non-ideal gas, the pressure cannot be used in eq. (11.28) because each gas response to changes in pressure is not universal. We can, however, define a new variable to replace the pressure in eq. (11.28) and call it fugacity (f).

Definition 11.3. Fugacity: The effective pressure of a non-ideal gas that corresponds to the pressure of an ideal gas with the same temperature and chemical potential of the non-ideal one.

Eq. (11.28) then becomes:

$$\mu_{\text{non-ideal}} = \mu^\ominus + RT \ln \frac{f}{P^\ominus}. \quad (11.29)$$

Since the chemical potential of a gas μ is equal to the standard chemical potential μ^\ominus when $P = P^\ominus$, it is easy to use eq. (11.29) to demonstrate that:

$$\lim_{P \rightarrow 0} \frac{f}{P} = 1, \quad (11.30)$$

in other words, any non-ideal gas will approach the ideal gas behavior as $P \rightarrow 0$. This condition, in conjunction with the $T \rightarrow \infty$ behavior obtained in the previous section, results in the following statement:

The highest chances for any gas to behave ideally happen at high temperature and low pressure.

We can now return our attention to the definition of fugacity. Remembering that the chemical potential is the molar Gibbs free energy of a substance, we can write:

$$d\mu_{\text{ideal}} = \bar{V}_{\text{ideal}} dP, \quad (11.31)$$

and:

$$d\mu_{\text{non-ideal}} = \bar{V}_{\text{non-ideal}} dP, \quad (11.32)$$

Subtracting eq. (11.31) from eq. (11.32), we obtain:

$$d\mu_{\text{non-ideal}} - d\mu_{\text{ideal}} = (\bar{V}_{\text{non-ideal}} - \bar{V}_{\text{ideal}}) dP, \quad (11.33)$$

which we can then integrate between 0 and P :

$$\mu_{\text{non-ideal}} - \mu_{\text{ideal}} = \int_0^P (\bar{V}_{\text{non-ideal}} - \bar{V}_{\text{ideal}}) dP. \quad (11.34)$$

Using eqs. @ref(eq.dcpig) and @ref(eq.dcpnig) we can then replace the definition of chemical potentials, resulting into:

$$\ln f - \ln P = \frac{1}{RT} \int_0^P (\bar{V}_{\text{non-ideal}} - \bar{V}_{\text{ideal}}) dP, \quad (11.35)$$

which gives us a mathematical definition of the fugacity, as:

$$f = P \cdot \underbrace{\exp \left[\frac{1}{RT} \int_0^P (\bar{V}_{\text{non-ideal}} - \bar{V}_{\text{ideal}}) dP \right]}_{\text{fugacity coefficient, } \phi(T, P)}. \quad (11.36)$$

The exponential term in eq. (11.36) is complicated to write, but it can be interpreted as a coefficient—unique to each non-ideal gas—that can be measured experimentally. Such coefficients are dependent on pressure and temperature and are called the *fugacity coefficients*. Using letter ϕ to represent the fugacity coefficient, we can rewrite eq. (11.36) as:

$$f = \phi P, \quad (11.37)$$

which gives us a straightforward interpretation of the fugacity as an effective pressure. As such, the fugacity will have the same unit as the pressure, while the fugacity coefficients will be adimensional.

As we already saw in chapter ??ChemicalEquilibrium), the fugacity can be used to replace the pressure in the definition of the equilibrium constant for reactions that involve non-ideal gases. The new constant is usually called K_f , and is obtained from:

$$K_f = \prod_i f_{i,\text{eq}}^{\nu_i} = K_P \prod_i \phi_i^{\nu_i}. \quad (11.38)$$

Chapter 12

Phase Equilibrium

12.1 Phase Stability

We have already encountered the gas, liquid, and solid phases and already discussed some of their properties. These terms are intuitive since these are the three most common states of matter.¹ For this reason, we have previously used the terms without the necessity of formally defining their meaning. However, a formal definition of “phase” is necessary to discuss several concepts in this chapter and the following ones:

Definition 12.1. *Phase:* A region of the system with homogeneous chemical composition and physical state.

Let’s now use the total differential of the chemical potential and the definition of molar Gibbs free energy for one component:

$$\begin{aligned} d\mu &= \left(\frac{\partial\mu}{\partial T}\right)_P dT + \left(\frac{\partial\mu}{\partial P}\right)_T dP \\ d\mu &= -SdT + \bar{V}dP, \end{aligned} \tag{12.1}$$

¹Other states of matter—such as plasma—are possible, but they are not usually observed at the values of temperature and pressure that classical thermodynamics is usually applied to. Discussion of these extreme cases is beyond the scope of this textbook.

to write:

$$\left(\frac{\partial\mu}{\partial T}\right)_P = -S \quad \left(\frac{\partial\mu}{\partial P}\right)_T = \overline{V}. \quad (12.2)$$

We can use these definitions to study the dependence of the chemical potential with respect to changes in pressure and temperature. If we plot μ as a function of T using the first coefficient in eq. (12.3), we obtain the diagram in Figure 12.1. The diagram presents three curves, each corresponding to one of the three most common states of matter – solid, liquid, and gas. As we saw in several previous chapters, the entropy of a phase is almost constant with respect to temperature,² and therefore the three curves are essentially straight, with negative angular coefficients $-S$. This also explains why the solid phase has a basically flat line since, according to the third law, the entropy of a perfect solid is zero and close to zero if the solid is not perfect. The difference between the three lines' angular coefficients is explained by the fact that each of these states has a different value of entropy:

$$\left(\frac{\partial\mu_{\text{solid}}}{\partial T}\right)_P = -S_s \quad \left(\frac{\partial\mu_{\text{liquid}}}{\partial T}\right)_P = -S_l \quad \left(\frac{\partial\mu_{\text{gas}}}{\partial T}\right)_P = -S_g, \quad (12.3)$$

and since the entropy of a gas is always bigger than the entropy of a liquid, which in turn, is yet bigger than the entropy of a solid ($S_g \gg S_l > S_s$), we obtain three lines with different angular coefficients that intersect each other. At each temperature, the phase with the lowest chemical potential will be the most stable (see red segments in Figure 12.1). At each intersection between two lines, the two phases have the same chemical potential, representing the temperature at which they coexist. This temperature is the temperature at which the phase change happens. Recalling from general chemistry, at the junction between the solid and the liquid lines, the fusion (fus) process occurs, and the corresponding temperature is called the melting point T_m . At the junction between the liquid and the gas lines, the vaporization (vap) process happens, and the corresponding temperature is called the boiling point T_b . Depending on the substance and the pressure at which the process happens, the solid line might intersect the gas line before the liquid line. When that occurs, the liquid phase is never observed, and only the sublimation (subl) process happens at the sublimation point T_{subl} .

²Think, for example, at the integral $\int SdT$, for which we can assume S independent of temperature to obtain $S\Delta T$. In practice, the entropy increases slightly with the temperature. Therefore the curves in Figure 12.1 are slightly concave downwards (remember that they are obtained from values of $-S$, so if S increase with T , the curves bend downwards.)




Figure 12.1: Dependence of the Chemical Potentials of Solid, Liquid, and Gas Phases on Temperature at Constant Pressure.

The effects of pressure on this diagram can be studied using the second coefficient in eq. (12.3). For the majority of substances, $\bar{V}_g \gg \bar{V}_l > \bar{V}_s$, hence the curves will shift to lower values when the pressure is reduced, as in Figure 12.2. Notice also that since $\bar{V}_l \cong \bar{V}_s$, the shifts for both the solid and liquid lines is much smaller than the shift for the gas line. These shifts also translate to different values of the junctions, which means the phase changes will occur at different temperatures. Therefore both the melting point and the boiling point in general decrease when pressure is increased (and vice versa). Notice how the change for the melting point is always much smaller than the change for the boiling point. Water is a noticeable exception to these trends because $\bar{V}_{H_2O,l} < \bar{V}_{ice}$. This explains the experimental observation that increasing the pressure on ice causes the ice to melt. [Despite the effect being minimal, it is one of the contributing causes to the fact that we can skate on ice, but we can't on stone. If we increase our pressure on ice by reducing our footprints' surface area using thin skates, ice will slightly melt under our own weight, creating a thin liquid film on which we can skate because of the reduced friction.]

Considering the intersections between two lines, two phases are in equilibrium with each other at each of these points. Therefore their chemical potentials must be equal:

For two or more phases to be in equilibrium, their chemical potential must be equal:




Figure 12.2: Effect of Pressure on the Chemical Potential Diagram.

$$\mu_\alpha = \mu_\beta. \quad (12.4)$$

If we now change either the temperature or the pressure, the location of the intersection will be shifted (see again Figure 12.2 and the discussion above). For infinitesimal changes in variables, the new location will be:

$$\mu_\alpha + d\mu_\alpha = \mu_\beta + d\mu_\beta, \quad (12.5)$$

which using eq. (12.4), simply becomes:

$$d\mu_\alpha = d\mu_\beta. \quad (12.6)$$

Replacing the differential with the definition of chemical potential in eq. (12.1), we obtain:

$$\begin{aligned} -S_\alpha dT + \bar{V}_\alpha &= -S_\beta dT + \bar{V}_\beta \\ \underbrace{(S_\beta - S_\alpha)}_{\Delta S} dT &= \underbrace{(\bar{V}_\beta - \bar{V}_\alpha)}_{\Delta \bar{V}}, \end{aligned} \quad (12.7)$$

which can be rearranged into:

$$\frac{dP}{dT} = \frac{\Delta S}{\Delta V}. \quad (12.8)$$

This equation is known as the **Clapeyron equation**, and it is the mathematical relation at the basis of the pressure-temperature phase diagrams. Plotting the results of eq. (12.8) on a PT phase diagram for common substances results in three lines representing the equilibrium between two different phases. These diagrams are useful to study the relationship between the phases of a substance.

12.2 Gibbs Phase Rule

In chapter 1, we have already seen that the number of independent variables required to describe an ideal gas is two. This number was derived by counting the total number of variables ($3 : P, \bar{V}, T$), and reduce it by one because the ideal gas law constrains the value of one of them, once the other two are fixed. For a generic system potentially containing more than one chemical substance in several different phases, however, the number of independent variables can be different than two. For a system composed of c components (chemical substances) and p phases, the number of independent variables, f , is given by the Gibbs phase rule:

$$f = c - p + 2. \quad (12.9)$$

The Gibbs phase rule derives from the fact that different phases are in equilibrium with each other at some conditions, resulting in the reduction of the number of independent variables at those conditions. More rigorously, when two phases are in thermodynamic equilibrium, their chemical potentials are equal (see eq. (12.4)). For each equality, the number of independent variables—also called the number of *degrees of freedom*—is reduced by one. For example, the chemical potentials of the liquid and its vapor depend on both T and P . But when these phases are in equilibrium with each other, their chemical potentials must be equal. If either the pressure or the temperature is fixed, the other variable will be uniquely determined by the equality relation. In other terms, when a liquid is in equilibrium with its vapor at a given pressure, the temperature is determined by the fact that the chemical potentials of the two phases is the same, and is denoted as the boiling temperature T_b . Similarly, at a given temperature, the pressure

of the vapor is uniquely determined by the same equality relation and is denoted as the vapor pressure, P^* .

The Gibbs phase rule is obtained considering that the number of independent variables is given by the total number of variables minus the constraints. The total number of variables is given by temperature, pressure, plus all the variables required to describe each of the phases. The composition of each phase is determined by $(c - 1)$ variables.³ The number of constraints is determined by the number of possible equilibrium relations, which is $c(p - 1)$ since the chemical potential of each component must be equal in all phases. The number of degrees of freedom f is then given by $f = (c-1)p+2-c(p-1) = c - p + 2$, which is the Gibbs phase rule, as in eq. (12.9).

12.3 PT Phase Diagrams




Figure 12.3: The Pressure–Temperature Phase Diagram.

Let's now discuss the pressure–temperature diagram of a typical substance, as reported in Figure 12.3. Each of the lines reported in the diagram represents an equilibrium between two phases, and therefore it represents a

³For a 1-component system $c - 1 = 1 - 1 = 0$, and no additional variable is required to determine the composition of each phase. For a 2-component system, however, each phase will contain both components, hence $c - 1 = 2 - 1 = 1$ additional variable will be required to describe it—the mole fraction.

condition that reduces the number of degrees of freedom to one. The lines can be determined using the Clapeyron equation, eq. (12.8). The interpretation of each line is as follows:

12.3.1 Liquid \rightleftharpoons Gas equilibrium

For this equilibrium we can use Trouton's rule, eq. (7.7), and write:

$$\Delta_{\text{vap}}S = S_g - S_l \cong 88 \frac{\text{kJ}}{\text{mol}} > 0 \quad \text{always,} \quad (12.10)$$

where the entropy of vaporization is always positive, even for cases where the Trouton's rule is violated. The difference in molar volumes is easily obtained, since the volume of the gas is always much greater than the volume of the liquid:

$$\bar{V}_g - \bar{V}_l \cong \bar{V}_g = 22.4 \frac{\text{L}}{\text{mol}} > 0 \quad \text{always.} \quad (12.11)$$

Replacing these values in the Clapeyron equation, we obtain:

$$\frac{dP}{dT} = \frac{88}{22.4} \left(\frac{0.0831}{8.31} \right) = 0.004 \text{ bar} > 0 \quad \text{always,} \quad (12.12)$$

which is always positive, regardless of violations to the Trouton's rule. Notice how small this value is, meaning that the liquid–gas equilibrium curve is mostly flat as $T \rightarrow 0$.

12.3.2 Solid \rightleftharpoons Gas equilibrium

If we look at the signs of each quantity, this case is similar to the previous one:

$$\begin{aligned} \Delta_{\text{subl}}S &> 0 \quad \text{always} \\ \Delta_{\text{subl}}\bar{V} &> 0 \quad \text{always} \end{aligned} \quad (12.13)$$

$$\frac{dP}{dT} > 0 \quad \text{always.}$$

However, the Trouton's rule is not valid for the solid–gas equilibrium, and $\frac{dP}{dT}$ will be larger than for the previous case.

12.3.3 Solid \rightleftharpoons Liquid equilibrium

The final curve is for the solid-liquid equilibrium, for which we have:

$$\Delta_{\text{fus}}S = \frac{\Delta_{\text{fusion}}H}{T_m} > 0 \quad \text{always,} \quad (12.14)$$

since fusion is always an exothermic process, ($\Delta_{\text{fus}}H > 0$). On the other side:

$$\Delta_{\text{fusion}}\bar{V} = \bar{V}_l - \bar{V}_s > 0 \quad \text{generally.} \quad (12.15)$$

In other words, the difference of the molar volume of the liquid and that of the solid is positive for most substances, but it might be negative (for example for H₂O). As such:

$$\frac{dP}{dT} > 0 \quad \text{generally.} \quad (12.16)$$

For H₂O and a few other substances, $\frac{dP}{dT} < 0$, an anomalous behavior that has crucial consequences for the existence of life on earth. For this importance, it is also depicted in Figure 12.3 using a dashed green line.

Since the differences in molar volumes between the solid and the liquid phases are usually small (changes are generally of the order of 10⁻³ L), $\frac{dP}{dT}$ is always much larger than for the previous two cases. The resulting lines for the solid–liquid equilibria are still almost vertical, regardless of the signs of their angular coefficients.

12.3.4 The triple point and the critical point

The only point in the *PT* diagram where all the three phases coexist is called the triple point. The number of degrees of freedom at the triple point for every 1-component diagram is $f = 1 - 3 + 2 = 0$. The fact that the triple point has zero degrees of freedom means that its coordinates, T_{tp} , P_{tp} , \bar{V}_{tp} , are uniquely determined for each chemical substance. For this reason, the value of the triple point of water was fixed by definition—rather than measured—until 2019. This definition was necessary to establish the base unit of the thermodynamic temperature scale in the SI (the Kelvin).⁴

⁴For more information on the 2019 redefinition of the SI units, see this Wikipedia page.

In addition to the triple point where the solid, liquid, and gas phases meet, a triple point may involve more than one condensed phase. Triple points are common for substances with multiple solid phases (polymorphs), involving either two solid phases and a liquid one or three solid phases. Helium is a special case that presents a triple point involving two different fluid phases, called the lambda point. Since the number of degrees of freedom cannot be negative, the Gibbs phase rule for a 1-component diagram sets the limit to how many phases can coexist to just three. Therefore, quadruple points (or higher coexistence points) are not possible for pure substances, even for polymorphs.⁵

Another point with a fixed position in the PT diagram is the critical point, T_c, P_c, \bar{V}_c . We have already given the definition of the critical temperature in 11.2. This point represents the end of the liquid–gas equilibrium curve. This point is also semantically important to define different regions of the phase diagram, as in Figure 12.3. A gas whose pressure and temperature are below the critical point is called a *vapor*. A gas whose temperature and pressure are above the critical point is called a *supercritical fluid*. Finally, a liquid whose pressure is above the critical point is called a *compressible liquid*.⁶

12.4 The Clausius–Clapeyron Equation

Let's now take a closer look at the equilibrium between a condensed phase and the gas phase. For both the vaporization and sublimation processes, Clausius showed that the Clapeyron equation can be simplified by using:

$$\Delta_{\text{vap}} S = \frac{\Delta_{\text{vap}} H}{T} \quad \Delta \bar{V} = \bar{V}_{\text{g}} - \bar{V}_{\text{l}} \cong \bar{V}_{\text{g}}, \quad (12.17)$$

resulting in:

$$\frac{dP}{dT} = \frac{\Delta_{\text{vap}} S}{\Delta \bar{V}} \cong \frac{\Delta_{\text{vap}} H}{T \bar{V}_{\text{g}}}. \quad (12.18)$$

Using the ideal gas law to replace the molar volume of the gas, we obtain:

⁵Notice that quadruple points are possible for 2-component diagrams.

⁶Notice that the temperature of a liquid must be below the critical point, otherwise it is no longer a liquid but rather a supercritical fluid.

$$\frac{dP}{dT} = \frac{P\Delta_{\text{vap}}H}{RT^2}, \quad (12.19)$$

which can be rearranged as:

$$\frac{dP}{P} = \frac{\Delta_{\text{vap}}H}{R} \frac{dT}{T^2}. \quad (12.20)$$

Eq. (12.20) is known as the **Clausius–Clapeyron equation**, and it measures the dependence of the vapor pressure of a substance as a function of the temperature. The Clausius–Clapeyron equation can be integrated to obtain:

$$\begin{aligned} \int_{P_i}^{P_f} \frac{dP}{P} &= \frac{\Delta_{\text{vap}}H}{R} \int_{T_i}^{T_f} \frac{dT}{T^2} \\ \ln \frac{P_f}{P_i} &= -\frac{\Delta_{\text{vap}}H}{R} \left(\frac{1}{T_f} - \frac{1}{T_i} \right). \end{aligned} \quad (12.21)$$

The integrated Clausius–Clapeyron equation shows that the vapor pressure depends exponentially on the temperature. Thus, even a small change in the temperature will result in a significant change in the vapor pressure. In fact, we daily use the fact that the vapor pressure of water changes drastically when we increase its temperature for cooking most of our food. For example, at an external pressure of 1 bar, it rapidly grows from $P^* = 0.02$ bar to $P^* = 1$ bar when the temperature is increased from $T = 293$ K (around room temperature) to $T = 373$ K (boiling point). The integrated Clausius–Clapeyron equation is also often used to determine the enthalpy of vaporization from measurements of vapor pressure at different temperatures.

Chapter 13

Multi-Component Phase Diagrams

Chapter 14

Solutions

14.1 Activity

14.2 Colligative Properties

14.3 Binding Equilibria

Chapter 15

Chemical Kinetics

Chapter 16

Appendix

16.1 Thermodynamic Data of Inorganic Substances at 298 K

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| Ag(g) | 284.9 | 246 | 173 | 20.8 |
| Ag(s) | 0 | 0 | 42.6 | 25.4 |
| Ag ⁺ (aq) | 105.8 | 77.1 | 73.5 | |
| AgCN(s) | 146 | 156.9 | 107.2 | 66.7 |
| Ag ₂ CO ₃ (s) | -505.8 | -436.8 | 167.4 | 112.3 |
| AgNO ₃ (s) | -124.4 | -33.4 | 140.9 | 93.1 |
| Ag ₂ O(s) | -31.1 | -11.2 | 121.3 | 65.9 |
| Ag ₂ S(s) | -32.6 | -40.7 | 144 | 76.5 |
| AgBr(s) | -100.4 | -96.9 | 107.1 | 52.4 |
| AgCl(s) | -127.0 | -109.8 | 96.3 | 50.8 |
| AgF(s) | -204.6 | -187 | 84 | |
| AgI(s) | -61.8 | -66.2 | 115.5 | 56.8 |
| Al(g) | 330 | 289.4 | 164.6 | 21.4 |
| Al(s) | 0 | 0 | 28.3 | 24.2 |
| Al ₂ O ₃ (s) | -1675.7 | -1582.3 | 50.9 | 79.0 |
| AlF ₃ (s) | -1510.4 | -1431.1 | 66.5 | 75.1 |
| AlI ₃ (s) | -302.9 | | 195.9 | |
| AlBr ₃ (s) | -527.2 | | 180.2 | 100.6 |
| AlCl ₃ (s) | -704.5 | -628.11 | 112.3 | 91.1 |
| Al(OH) ₃ (s) | -1277 | | | |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-----------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| Al(OH)_4^- (aq) | -1490 | -1297 | 117 | |
| AlPO_4 (s) | -1733.8 | -1617.9 | 90.8 | 93.2 |
| Ar(g) | 0 | | 154.9 | 20.8 |
| B(s) | 0 | 0 | 5.9 | 11.1 |
| B(g) | 565 | 521.0 | 153.4 | 20.8 |
| BH(g) | 442.7 | 412.7 | 171.8 | 29.2 |
| BH_3 (g) | 89.2 | 93.3 | 188.2 | 36.0 |
| B_2S_3 (s) | -240.6 | | 100.0 | 111.7 |
| Ba(g) | 180 | 146 | 170.2 | |
| Ba(s) | 0 | 0 | 62.5 | 28.1 |
| BaCO_3 (s) | -1213.0 | -1134.4 | 112.1 | 86.0 |
| BaH_2 (s) | -177 | -138.2 | 63.0 | |
| BaBr_2 (s) | -757.3 | -736.8 | 146.0 | |
| BaCl_2 (s) | -855 | -806.7 | 123.7 | 75.1 |
| BaF_2 (s) | -1207.1 | -1156.8 | 96.4 | 71.2 |
| BaI_2 (s) | -602.1 | -597 | 167.0 | |
| BaO(s) | -548.0 | -520.3 | 72.1 | 47.3 |
| BaSO_4 (s) | -1473.2 | -1362.2 | 132.2 | 101.8 |
| Be(g) | 324 | 286.6 | 136.3 | 20.8 |
| Be(s) | 0 | 0 | 9.5 | 13.4 |
| BeBr_2 (s) | -353.5 | | 108 | 69.4 |
| BeCl_2 (s) | -490.4 | -445.6 | 75.8 | 62.4 |
| BeF_2 (s) | -1026.8 | -979.4 | 53.4 | 51.8 |
| BeI_2 (s) | -192.5 | | 121 | 71.1 |
| BeO(s) | -609.4 | -580.1 | 13.8 | 25.6 |
| Be(OH)_2 (s) | -902.5 | -815.0 | 45.5 | 62.1 |
| BeSO_4 (s) | -1205.2 | -1093.8 | 77.9 | 85.7 |
| Bi(g) | 207.1 | 168.2 | 187 | 20.8 |
| Bi(s) | 0 | 0 | 56.7 | 25.5 |
| Bi_2O_3 (s) | -573.9 | -493.7 | 151.5 | 113.5 |
| BiCl_3 (s) | -379.1 | -315.0 | 177.0 | 105.0 |
| Br^- (aq) | -121.4 | -104.0 | 82.6 | |
| Br(g) | 111.9 | 82.4 | 175 | 20.8 |
| Br_2 (g) | 30.9 | 3.1 | 245.5 | 36.0 |
| Br_2 (l) | 0 | 0 | 152.2 | 75.7 |
| BrCl(g) | 14.6 | -1 | 240.1 | 35.0 |
| BrF(g) | -93.8 | -109.2 | 229 | 33.0 |
| BrF_3 (g) | -1136 | 1119.4 | 254.4 | 66.6 |
| C(g) | 716.7 | 671.3 | 158.1 | 0.8 |
| C(s,diamond) | 1.9 | 2.9 | 2.4 | 6.1 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| C(s,graphite) | 0 | 0 | 5.7 | 8.5 |
| CB ₄ (g) | 83.9 | 67 | 358.1 | |
| CB ₄ (s) | 29.4 | 47.7 | 212.5 | |
| CCl ₂ F ₂ (g) | -477.4 | -439.4 | 300.8 | |
| CCl ₂ O(g) | -219.1 | -204.9 | 283.5 | |
| CCl ₄ (g) | -95.7 | -53.6 | 309.9 | |
| CCl ₄ (l) | -128.2 | -62.6 | 216.2 | |
| CF ₄ (g) | -933.6 | -888.3 | 261.6 | |
| CS ₂ (g) | 116.7 | 67.1 | 237.8 | 45.4 |
| CS ₂ (l) | 89 | 64.6 | 151.3 | 76.4 |
| CO(g) | -110.5 | -137.2 | 197.7 | 29.1 |
| CO ₂ (g) | -393.5 | -394.4 | 213.8 | 37.1 |
| Ca(g) | 177.8 | 144 | 154.9 | 20.8 |
| Ca(s) | 0 | 0 | 41.6 | 25.9 |
| Ca(OH) ₂ (s) | -985.2 | -897.5 | 83.4 | 87.5 |
| CaBr ₂ (s) | -682.8 | -663.6 | 130 | |
| CaCl ₂ (s) | -795.4 | -748.8 | 108.4 | 72.9 |
| CaCN(s) | -184.5 | | | |
| CaCO ₃ (s,arag.) | 207.8 | -1128.2 | 88 | 82.3 |
| CaCO ₃ (s,calc.) | 1207.6 | -1129.1 | 91.7 | 83.5 |
| CaF ₂ (s) | -1228.0 | -1175.6 | 68.5 | 67.0 |
| CaH ₂ (s) | -181.5 | -142.5 | 41.4 | 41.0 |
| CaI ₂ (s) | -533.5 | -528.9 | 142 | |
| CaO(s) | -634.9 | -603.3 | 38.1 | 42.0 |
| CaSO ₄ (s) | -1434.5 | -1322.0 | 106.5 | 99.7 |
| Cd(g) | 111.8 | | 167.7 | 20.8 |
| Cd(s) | 0 | 0 | 51.8 | 26.0 |
| CdBr ₂ (s) | -316.2 | -296.3 | 137.2 | 76.7 |
| CdCl ₂ (s) | -391.5 | -343.9 | 115.3 | 74.7 |
| CdCO ₃ (s) | -750.6 | -669.4 | 92.5 | |
| CdF ₂ (s) | -700.4 | -647.7 | 77.4 | |
| CdS(s) | -161.9 | -156.5 | 64.9 | |
| CdSO ₄ (s) | -933.3 | -822.7 | 123.0 | 99.6 |
| Cl ⁻ (aq) | -167.1 | -131.2 | 56.6 | |
| Cl(g) | 121.3 | 105.3 | 165.2 | 21.8 |
| Cl ₂ (g) | 0 | 0 | 223.1 | 33.9 |
| ClF(g) | -50.3 | -51.8 | 217.9 | 32.1 |
| ClF ₃ (g) | -163.2 | -123.0 | 281.6 | 63.9 |
| ClO ₂ (g) | 89.1 | 105 | 263.7 | 46.0 |
| Cl ₂ O(g) | 80.3 | 97.9 | 266.2 | 45.4 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| Co(g) | 424.7 | 380.3 | 179.5 | 23.0 |
| Co(s) | 0 | 0 | 30 | 24.8 |
| CoCl ₂ (s) | -312.5 | -269.8 | 109.2 | 78.5 |
| Cr(g) | 396.6 | 351.8 | 174.5 | 20.8 |
| Cr(s) | 0 | 0 | 23.8 | 23.4 |
| Cr ₂ O ₃ (s) | -1139.7 | -1058.1 | 81.2 | 118.7 |
| CrCl ₂ (s) | -395.4 | -356 | 115.3 | 71.2 |
| CrCl ₃ (s) | -556.5 | -486.1 | 123 | 91.8 |
| CrO ₂ (g) | -598 | | | |
| CrO ₃ (g) | -292.9 | | 266.2 | 56.0 |
| Cs(g) | 76.5 | 49.6 | 175.6 | 20.8 |
| Cs(s) | 0 | 0 | 85.2 | 32.2 |
| CsCl(s) | -443.0 | -414.5 | 101.2 | 52.5 |
| Cu(g) | 337.4 | 297.7 | 166.4 | 20.8 |
| Cu(s) | 0 | 0 | 33.2 | 24.2 |
| Cu ₂ O(s) | -168.6 | -146.0 | 93.1 | 63.6 |
| CuO(s) | -157.3 | -129.7 | 42.6 | |
| Cu ₂ S(s) | -79.5 | -86.2 | 120.9 | 76.3 |
| CuS(s) | -53.1 | -53.6 | 66.5 | 47.8 |
| CuSO ₄ (s) | -771.4 | -662.2 | 109.2 | |
| CuBr(s) | -104.6 | -100.8 | 96.1 | 54.7 |
| CuBr ₂ (s) | -141.8 | | | |
| CuCl(s) | -137.2 | -119.9 | 86.2 | 48.5 |
| CuCl ₂ (s) | -220.1 | -175.7 | 108.1 | 71.9 |
| CuCN(s) | 96.2 | 111.3 | 84.5 | |
| F ⁻ (aq) | -335.4 | -278.8 | -13.8 | |
| F(g) | 79.4 | 62.3 | 158.8 | 22.7 |
| F ₂ (g) | 0 | 0 | 202.8 | 32.3 |
| F ₂ O(g) | 24.5 | 41.8 | 247.5 | 43.3 |
| FO(g) | 109 | 105.3 | 216.4 | 32.0 |
| FB(g) | -122.2 | -149.8 | 200.5 | 58.6 |
| Fe(g) | 416.3 | 370.7 | 180.5 | 25.7 |
| Fe(s) | 0 | 0 | 27.3 | 25.1 |
| FeO(s) | -272.0 | -251.4 | 60.7 | |
| Fe ²⁺ (aq) | -89.1 | -78.9 | -137.7 | |
| Fe ₂ O ₃ (s) | -824.2 | -742.2 | 87.4 | 103.9 |
| Fe ³⁺ (aq) | -48.5 | -4.7 | -315.9 | |
| Fe ₃ O ₄ (s) | -1118.4 | -1015.4 | 146.4 | 143.4 |
| FeCO ₃ (s) | -740.6 | -666.7 | 92.9 | 82.1 |
| FeS ₂ (s) | -178.2 | -166.9 | 52.9 | 62.2 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| FeCl ₂ (s) | -341.8 | -302.3 | 118 | 75.7 |
| FeCl ₃ (s) | -399.5 | -334.0 | 142.3 | 96.7 |
| FeBr ₂ (s) | -249.8 | -238.1 | 140.6 | |
| FeBr ₃ (s) | -268.2 | | | |
| Fe ₃ C(s) | 25.1 | 20.1 | 104.6 | 105.9 |
| H(g) | 218.0 | 203.3 | 114.7 | 20.8 |
| H ⁺ (aq) | 0 | 0 | 0 | |
| H ₂ (g) | 0 | 0 | 130.7 | 28.8 |
| H ₂ O(g) | -241.8 | -228.6 | 188.8 | 33.6 |
| H ₂ O(l) | -285.8 | -237.1 | 70.0 | 75.3 |
| H ₂ O ₂ (g) | -136.3 | -105.6 | 232.7 | 43.1 |
| H ₂ O ₂ (l) | -187.8 | -120.4 | 109.6 | 89.1 |
| H ₂ S(g) | -20.6 | -33.4 | 205.8 | 34.2 |
| H ₂ Se(g) | 29.7 | 15.9 | 219 | 34.7 |
| H ₂ SO ₄ (aq) | -909.3 | -744.5 | 20.1 | |
| H ₂ SO ₄ (l) | -814.0 | -690.0 | 156.9 | 138.9 |
| H ₃ PO ₄ (l) | -1271.7 | -1123.6 | 150.8 | 145.0 |
| H ₃ PO ₄ (s) | -1284.4 | -1124.3 | 110.5 | 106.1 |
| HBr(aq) | -121.6 | -104.0 | 82.4 | |
| HBr(g) | -36.3 | -53.4 | 198.7 | 29.1 |
| HCl(aq) | -167.2 | -131.2 | 56.5 | |
| HCl(g) | -92.3 | -95.3 | 186.9 | 29.1 |
| HCN(g) | 135.1 | 124.7 | 201.8 | 35.9 |
| HCN(l) | 108.9 | 125 | 112.8 | 70.6 |
| HF(aq) | -332.6 | -278.8 | -13.8 | |
| HF(g) | -273.3 | -275.4 | 173.8 | |
| HI(aq) | -55.2 | -51.6 | 111.3 | |
| HI(g) | 26.5 | 1.7 | 206.6 | 29.2 |
| HNO ₂ (g) | -79.5 | -46.0 | 254.1 | |
| HNO ₃ (aq) | -207.4 | -111.3 | 146.4 | |
| HNO ₃ (g) | -133.9 | -73.5 | 266.9 | 54.1 |
| HNO ₃ (l) | -174.1 | -80.7 | 155.6 | 109.9 |
| He(g) | 0 | 0 | 126.2 | 20.8 |
| Hg(g) | 61.4 | 31.8 | 175 | |
| Hg(l) | 0 | 0 | 75.9 | 28.0 |
| Hg ₂ (g) | 108.8 | 68.2 | 288.1 | |
| HgO(s) | -90.8 | -58.5 | 70.3 | 44.1 |
| HgS(s,red) | -58.2 | -50.6 | 82.4 | 48.4 |
| Hg ₂ SO ₄ (s) | -743.1 | -625.8 | 200.7 | 132.0 |
| HgSO ₄ (s) | -707.5 | | | |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| Hg ₂ Cl ₂ (s) | -265.4 | -210.7 | 191.6 | 191.6 |
| HgCl ₂ (s) | -224.3 | -178.6 | 146.0 | 146.0 |
| Hg ₂ Br ₂ (s) | -206.9 | -181.1 | 218.0 | 218.0 |
| HgBr ₂ (s) | -170.7 | -153.1 | 172.0 | 172.0 |
| Hg ₂ I ₂ (s) | -121.3 | -111 | 233.5 | 233.5 |
| HgI ₂ (s) | -105.4 | -101.7 | 180.0 | 180.0 |
| I ⁻ (aq) | -56.8 | -51.6 | 106.5 | |
| I(g) | 106.8 | 70.2 | 180.8 | 20.8 |
| I ₂ (g) | 62.4 | 19.3 | 260.7 | 36.9 |
| I ₂ (s) | 0 | 0 | 116.1 | 54.4 |
| HIO ₃ (s) | -230.1 | | | |
| IBr(g) | 40.8 | 3.7 | 258.8 | 36.4 |
| ICl(g) | 17.8 | -5.5 | 247.6 | 35.6 |
| IF(g) | -95.7 | -118.5 | 236.2 | 33.4 |
| K(g) | 89.0 | 60.5 | 160.3 | 20.8 |
| K(s) | 0 | 0 | 64.7 | 29.6 |
| K ₂ CO ₃ (s) | -1151.0 | -1063.5 | 155.5 | 114.4 |
| K ₂ O(s) | -361.5 | -322.1 | 94.1 | |
| K ₂ O ₂ (s) | -494.1 | -425.1 | 102.1 | |
| K ₂ SO ₄ (s) | -1437.8 | -1321.4 | 175.6 | 131.5 |
| KBr(s) | -393.8 | -380.7 | 95.9 | 52.3 |
| KCl(s) | -436.5 | -408.5 | 82.6 | 51.3 |
| KF(s) | -567.3 | -537.8 | 66.6 | 49.0 |
| KI(s) | -327.9 | -324.9 | 106.3 | 52.9 |
| KClO ₃ (s) | -397.7 | -296.3 | 143.1 | 100.3 |
| KMnO ₄ (s) | -837.2 | -737.6 | 171.7 | 117.6 |
| KNO ₂ (s) | -369.8 | -306.6 | 152.1 | 107.4 |
| KNO ₃ (s) | -494.6 | -394.9 | 133.1 | 96.4 |
| KSCN(s) | -200.2 | -178.3 | 124.3 | 88.5 |
| Kr(g) | 0 | 0 | 164.1 | 20.8 |
| Li(g) | 159.3 | 126.6 | 138.8 | 20.8 |
| Li(s) | 0 | 0 | 29.1 | 24.9 |
| Li ⁺ (aq) | -278.5 | -293.3 | 12.4 | |
| Li ₂ O(s) | -597.9 | -561.2 | 37.6 | 54.1 |
| LiOH(s) | -487.5 | -441.5 | 42.8 | 49.6 |
| LiNO ₃ (s) | -483.1 | -381.1 | 90.0 | |
| LiBr(s) | -351.2 | -342 | 74.3 | |
| LiCl(s) | -408.6 | -384.4 | 59.3 | 48.0 |
| LiF(s) | -616 | -587.7 | 35.7 | 41.6 |
| LiI(s) | -270.4 | -270.3 | 86.8 | 51.0 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|--|-------------------------------|-------------------------------|-------------------------|-------------------|
| Mg(g) | 147.1 | 112.5 | 148.6 | 20.8 |
| Mg(s) | 0 | 0 | 32.7 | 24.9 |
| MgO(s) | -601.6 | -569.3 | 27.0 | 37.2 |
| Mg(OH) ₂ (s) | -924.5 | -833.5 | 63.2 | 77.0 |
| MgS(s) | -346.0 | -341.8 | 50.3 | 45.6 |
| MgSO ₄ (s) | -1284.9 | -1170.6 | 91.6 | 96.5 |
| MgBr ₂ (s) | -524.3 | -503.8 | 117.2 | |
| MgCl ₂ (s) | -641.3 | -591.8 | 89.6 | 71.4 |
| MgF ₂ (s) | -1124.2 | -1071.1 | 57.2 | 61.6 |
| Mn(g) | 280.7 | 238.5 | 173.7 | 20.8 |
| Mn(s) | 0 | 0 | 32 | 26.3 |
| MnO(s) | -385.2 | -362.9 | 59.7 | 45.4 |
| MnO ₂ (s) | -520.0 | -465.1 | 53.1 | 54.1 |
| MnO ₄ ⁻ (aq) | -541.4 | -447.2 | 191.2 | |
| MnBr ₂ (s) | -384.9 | | | |
| MnCl ₂ (s) | -481.3 | -440.5 | 118.2 | 72.9 |
| Mo(g) | 658.1 | 612.5 | 182 | 20.8 |
| Mo(s) | 0 | 0 | 28.7 | 24.1 |
| MoO ₂ (s) | -588.9 | -533.0 | 46.3 | 56.0 |
| MoO ₃ (s) | -745.1 | -668.0 | 77.7 | 75.0 |
| MoS ₂ (s) | -235.1 | -225.9 | 62.6 | 63.6 |
| MoS ₃ (s) | -364 | -354 | 119 | |
| N(g) | 472.7 | 455.5 | 153.3 | 20.8 |
| N ₂ (g) | 0 | 0 | 191.6 | 29.1 |
| NF ₃ (g) | -132.1 | -90.6 | 260.8 | 53.4 |
| NH ₃ (g) | -45.9 | -16.4 | 192.8 | 35.1 |
| NH ₄ ⁺ (aq) | -133.3 | -79.3 | 111.2 | |
| NH ₄ Cl(s) | -314.4 | -202.9 | 94.6 | 84.1 |
| NH ₄ NO ₃ (s) | -365.6 | -183.9 | 151.1 | 139.3 |
| NH ₄ OH(l) | -361.2 | -254.0 | 165.6 | 154.9 |
| (NH ₄) ₂ SO ₄ (s)-1180.9 | -901.7 | 220.1 | | 187.5 |
| N ₂ H ₄ (g) | 95.4 | 159.4 | 238.5 | |
| N ₂ H ₄ (l) | 50.6 | 149.3 | 121.2 | |
| NO ₂ (g) | 33.2 | 51.3 | 240.1 | 37.2 |
| N ₂ O(g) | 81.6 | 103.7 | 220 | 38.6 |
| NO(g) | 91.3 | 87.6 | 210.8 | |
| N ₂ O ₄ (g) | 11.1 | 99.8 | 304.4 | 79.2 |
| N ₂ O ₄ (l) | -19.5 | 97.5 | 209.2 | 142.7 |
| Na(g) | 107.5 | 77 | 153.7 | 20.8 |
| Na(s) | 0 | 0 | 51.3 | 28.2 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|-------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| Na ⁺ (aq) | -240.2 | -261.9 | 58.5 | |
| Na ₂ CO ₃ (s) | -1130.7 | -1044.4 | 135 | 112.3 |
| Na ₂ O(s) | -414.2 | -375.5 | 75.1 | 69.1 |
| Na ₂ O ₂ (s) | -510.9 | -447.7 | 95 | 89.2 |
| Na ₂ SO ₄ (s) | -1387.1 | -1270.2 | 149.6 | 128.2 |
| NaBr(aq) | -361.7 | -365.8 | 141.4 | |
| NaBr(g) | -143.1 | -177.1 | 241.2 | 36.3 |
| NaBr(s) | -361.1 | -349.0 | 86.8 | 51.4 |
| NaCl(aq) | -407.3 | -393.1 | 115.5 | |
| NaCl(s) | -411.2 | -384.1 | 72.1 | 50.5 |
| NaCN(s) | -87.5 | -76.4 | 115.6 | 70.4 |
| NaF(aq) | -572.8 | -540.7 | 45.2 | |
| NaF(s) | -576.6 | -546.3 | 51.1 | 46.9 |
| NaN ₃ (s) | 21.7 | 93.8 | 96.9 | 76.6 |
| NaNO ₃ (aq) | -447.5 | -373.2 | 205.4 | |
| NaNO ₃ (s) | -467.9 | -367.0 | 116.5 | 92.9 |
| NaO ₂ (s) | -260.2 | -218.4 | 115.9 | 72.1 |
| NaOH(s) | -425.8 | -379.7 | 64.4 | 59.5 |
| NaH(s) | -56.3 | -33.6 | 40 | 36.4 |
| Ne(g) | 0 | 0 | 146.3 | 20.8 |
| Ni(g) | 429.7 | 384.5 | 182.2 | 23.4 |
| Ni(s) | 0 | 0 | 29.9 | 26.1 |
| Ni ₂ O ₃ (s) | -489.5 | | | |
| Ni(OH) ₂ (s) | -529.7 | -447.2 | 88 | |
| NiBr ₂ (s) | -212.1 | | | |
| NiCl ₂ (s) | -305.3 | -259.0 | 97.7 | 71.7 |
| NiF ₂ (s) | -651.4 | -604.1 | 73.6 | 64.1 |
| O(g) | 249.2 | 231.7 | 161.1 | 21.9 |
| O ₂ (g) | 0 | 0 | 205.2 | 29.4 |
| O ₃ (g) | 142.7 | 163.2 | 238.9 | 39.2 |
| OH ⁻ (aq) | -230.0 | -157.2 | -10.9 | |
| Os(g) | 791 | 745 | 192.6 | 20.8 |
| Os(s) | 0 | 0 | 32.6 | 24.7 |
| OsO ₄ (g) | -337.2 | -292.8 | 293.8 | 74.1 |
| OsO ₄ (s) | -394.1 | -304.9 | 143.9 | |
| P(g,white) | 316.5 | 280.1 | 163.2 | 20.8 |
| P(s,black) | -39.3 | | | |
| P(s,red) | -17.6 | -12.5 | 22.8 | 21.2 |
| P(s,white) | 0 | 0 | 41.1 | 23.8 |
| P ₂ (g) | 144.0 | 103.5 | 218.1 | |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|--|-------------------------------|-------------------------------|-------------------------|-------------------|
| P ₄ (g) | 58.9 | 24.4 | 280.0 | |
| PCl ₃ (g) | -287.0 | -267.8 | 311.8 | 71.8 |
| PCl ₃ (l) | -319.7 | -272.3 | 217.1 | |
| PCl ₅ (g) | -374.9 | -305.0 | 364.6 | 112.8 |
| PH ₃ (g) | 5.4 | 13.5 | 210.2 | 37.1 |
| POCl ₃ (g) | -558.5 | -512.9 | 325.5 | |
| POCl ₃ (l) | -597.1 | -520.8 | 222.5 | |
| Pb(g) | 195.2 | 162.2 | 175.4 | 20.8 |
| Pb(s) | 0 | 0 | 64.8 | 26.8 |
| PbCl ₂ (s) | -359.4 | -314.1 | 136 | |
| PbCO ₃ (s) | -699.1 | -625.5 | 131 | 87.4 |
| PbO(s,litharge) | 219.0 | -188.9 | 66.5 | 45.8 |
| PbO(s,massic.) | 217.3 | -187.9 | 68.7 | 45.8 |
| PbO ₂ (s) | -277.4 | -217.3 | 68.6 | 64.6 |
| Pb(NO ₃) ₂ (aq) | -416.3 | -246.9 | 303.3 | |
| Pb(NO ₃) ₂ (s) | -451.9 | | | |
| PbS(s) | -100.4 | -98.7 | 91.2 | 49.5 |
| PbSO ₄ (s) | -920.0 | -813.0 | 148.5 | 103.2 |
| Rb(g) | 80.9 | 53.1 | 170.1 | 20.8 |
| Rb(s) | 0 | 0 | 76.8 | 31.1 |
| RbCl(s) | -435.4 | -407.8 | 95.9 | 52.4 |
| S(g,rhombic) | 277.2 | 236.7 | 167.8 | 23.7 |
| S(s,rhombic) | 0 | 0 | 32.1 | 22.6 |
| SO ₂ (g) | -296.8 | -300.1 | 248.2 | 39.9 |
| SO ₃ (g) | -395.7 | -371.1 | 256.8 | 50.7 |
| SO ₄ ²⁻ (aq) | -909.3 | -744.5 | 18.5 | |
| SOCl ₂ (g) | -212.5 | -198.3 | 309.8 | |
| Se(g,gray) | 227.1 | 187 | 176.7 | |
| Se(s,gray) | 0 | 0 | 42.4 | 25.4 |
| Si(g) | 450 | 405.5 | 168.0 | 22.3 |
| Si(s) | 0 | 0 | 18.8 | 20.0 |
| SiC(s,cubic) | -65.3 | -62.8 | 16.6 | 26.9 |
| SiC(s,hexag.) | -62.8 | -60.2 | 16.5 | 26.7 |
| SiCl ₄ (g) | -657.0 | -617.0 | 330.7 | |
| SiCl ₄ (l) | -687.0 | -619.8 | 239.7 | |
| SiH ₄ (g) | 34.3 | 56.9 | 204.6 | 42.8 |
| Sn(g,white) | 301 | 266.2 | 168.5 | 21.3 |
| Sn(s,gray) | -2.1 | 0.1 | 44.1 | 25.8 |
| Sn(s,white) | 0 | 0 | 51.2 | 27.0 |
| SnCl ₄ (g) | -471.5 | -432.2 | 365.8 | 98.3 |

| Substance: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|---------------------------------------|-------------------------------|-------------------------------|-------------------------|-------------------|
| SnCl ₄ (l) | -511.3 | -440.1 | 258.6 | 165.3 |
| SnO ₂ (s) | -557.6 | -515.8 | 49 | 52.6 |
| Ti(g) | 473 | 428.4 | 180.3 | 24.4 |
| Ti(s) | 0 | 0 | 30.7 | 25.1 |
| TiCl ₂ (s) | -513.8 | -464.4 | 87.4 | 69.8 |
| TiCl ₃ (s) | -720.9 | -653.5 | 139.7 | 97.2 |
| TiCl ₄ (g) | -763 | -726.3 | 353 | 95.4 |
| TiCl ₄ (l) | -804.2 | -737.2 | 252.3 | 145.2 |
| TiO ₂ (s) | -944.0 | -888.8 | 50.6 | 55.0 |
| U(g) | 533 | 488.4 | 199.8 | 23.7 |
| U(s) | 0 | 0 | 50.2 | 27.7 |
| UF ₄ (g) | -1598.7 | -1572.7 | 368 | 91.2 |
| UF ₄ (s) | -1914.2 | -1823.3 | 151.7 | 116.0 |
| UF ₆ (g) | -2147.4 | -2063.7 | 377.9 | 129.6 |
| UF ₆ (s) | -2197.0 | -2068.5 | 227.6 | 166.8 |
| UO ₂ (g) | -465.7 | -471.5 | 274.6 | 51.4 |
| UO ₂ (s) | -1085.0 | -1031.8 | 77.0 | 63.6 |
| V(g) | 514.2 | 754.4 | 182.3 | 26.0 |
| V(s) | 0 | 0 | 28.9 | 24.9 |
| V ₂ O ₅ (s) | -1550.6 | -1419.5 | 131.0 | 127.7 |
| VCl ₃ (s) | -580.7 | -511.2 | 131.0 | 93.2 |
| VCl ₄ (g) | -525.5 | -492.0 | 362.4 | 96.2 |
| VCl ₄ (l) | -569.4 | -503.7 | 255.0 | |
| Xe(g) | 0 | 0 | 169.7 | 20.8 |
| Zn(g) | 130.4 | 94.8 | 161.0 | 20.8 |
| Zn(s) | 0 | 0 | 41.6 | 25.4 |
| ZnBr ₂ (s) | -328.7 | -312.1 | 138.5 | |
| ZnCl ₂ (s) | -415.1 | -369.4 | 111.5 | 71.3 |
| ZnF ₂ (s) | -764.4 | -713.3 | 73.7 | 65.7 |
| ZnI ₂ (s) | -208.0 | -209.0 | 161.1 | |
| Zn(NO ₃) ₂ (s) | -483.7 | | | |
| ZnS(s, sphaler.) | 206.0 | -201.3 | 57.7 | 46.0 |
| ZnSO ₄ (s) | -982.8 | -871.5 | 110.5 | 99.2 |
| Zr(g) | 608.8 | 566.5 | 181.4 | 26.7 |
| Zr(s) | 0 | 0 | 39 | 25.4 |
| ZrCl ₂ (s) | -502.0 | -386 | 110 | |
| ZrCl ₄ (s) | -980.5 | -889.9 | 181.6 | 119.8 |

16.2 Thermodynamic Data of Organic Substances at 298 K

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|---|--------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| CHBr ₃ | Bromoform(g) | 25 | 16 | 331 | 71 |
| CHCl ₃ | Chloroform(l) | -134.1 | -73.7 | 201.7 | 114.2 |
| CHCl ₃ | Chloroform(g) | -102.7 | 6.0 | 295.7 | 65.7 |
| CH ₂ O ₂ | Formic acid(l) | -425 | -361.4 | 129 | 99 |
| CH ₂ O ₂ | Formic acid(g) | -378.7 | | | |
| CH ₃ | Methyl(g) | 145.7 | 47.9 | 194.2 | 38.7 |
| CH ₃ Br | Bromomethane(l) | -59.8 | | | |
| CH ₃ Br | Bromomethane(g) | -35.4 | -26.3 | 246.4 | 42.4 |
| CH ₃ Cl | Chloromethane(g) | -81.9 | -63 | 234.6 | 40.8 |
| CH ₃ F | Fluoromethane(g) | -234 | -210 | 222.9 | 37.5 |
| CH ₃ I | Iodomethane(l) | -13.6 | | 136.2 | 126 |
| CH ₃ I | Iodomethane(g) | 14.4 | 16 | 254.1 | 44.1 |
| CH ₃ NO ₂ | Nitromethane(l) | -112.6 | -14.4 | 171.8 | 106.6 |
| CH ₃ NO ₂ | Nitromethane(g) | -80.8 | -7 | 282.9 | 55.5 |
| CH ₄ | Methane(g) | -74.6 | -50.5 | 186.3 | 35.7 |
| CH ₄ O | Methanol(l) | -239.2 | -166.6 | 126.8 | 81.1 |
| CH ₄ O | Methanol(g) | -201 | -162.3 | 239.9 | 44.1 |
| CH ₅ N | Methylamine(l) | -47.3 | 35.7 | 150.2 | 102.1 |
| CH ₅ N | Methylamine(g) | -22.5 | 32.7 | 242.9 | 50.1 |
| C ₂ H ₂ | Ethyne (acetylene)(g) | 226.9 | 209 | 201 | 44 |
| C ₂ H ₄ | Ethene(g) | 52.5 | 68.4 | 219.3 | 42.9 |
| C ₂ H ₄ O ₂ | Acetic acid(l) | -484.3 | -389.9 | 159.8 | 123.3 |
| C ₂ H ₄ O ₂ | Acetic acid(g) | -432.2 | -374.2 | 283.5 | 63.4 |
| C ₂ H ₅ Br | Bromoethane(l) | -90.5 | -25.8 | 198.7 | 100.8 |
| C ₂ H ₅ Br | Bromoethane(g) | -61.9 | -23.9 | 286.7 | 64.5 |
| C ₂ H ₅ Cl | Chloroethane(l) | -136.8 | -59.3 | 190.8 | 104.3 |
| C ₂ H ₅ Cl | Chloroethane(g) | -112.1 | -60.4 | 276 | 62.8 |
| C ₂ H ₅ NO ₂ | Nitroethane(l) | -143.9 | | | 134.4 |
| C ₂ H ₅ NO ₂ | Nitroethane(g) | -103.8 | -5 | 320.5 | 79 |
| C ₂ H ₆ | Ethane(g) | -84 | -32 | 229.2 | 52.5 |
| C ₂ H ₆ O | Ethanol(l) | -277.6 | -174.8 | 160.7 | 112.3 |
| C ₂ H ₆ O | Ethanol(g) | -234.8 | -167.9 | 281.6 | 65.6 |
| C ₂ H ₆ O | Methoxymethane(l) | -203.3 | | | |
| C ₂ H ₆ O | Methoxymethane(g) | -184.1 | -112.6 | 266.4 | |
| C ₂ H ₇ N | Ethylamine(l) | -74.1 | | | 130 |
| C ₂ H ₇ N | Ethylamine(g) | -47.5 | 36.3 | 283.8 | 71.5 |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|--|---------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₃ H ₄ | Cyclopropene(g) | 277.1 | 286 | 244 | 53 |
| C ₃ H ₄ | Propyne(g) | 185 | 194 | 248 | 61 |
| C ₃ H ₆ | Cyclopropane(l) | 35.2 | | | |
| C ₃ H ₆ | Cyclopropane(g) | 53.3 | 104.5 | 237.5 | 55.6 |
| C ₃ H ₆ | Propene(g) | 20 | 62 | 267 | 64 |
| C ₃ H ₆ O | Acetone(l) | -248.4 | | 199.8 | 126.3 |
| C ₃ H ₆ O | Acetone(g) | -217.1 | -152.7 | 295.3 | 74.5 |
| C ₃ H ₆ O ₂ | Propanoic acid(l) | -510.7 | | 191 | 152.8 |
| C ₃ H ₆ O ₂ | Propanoic acid(g) | -455.7 | | | |
| C ₃ H ₈ | Propane(l) | -120.9 | | | |
| C ₃ H ₈ | Propane(g) | -103.8 | -23.4 | 270.3 | 73.6 |
| C ₃ H ₈ O | 1-Propanol(l) | -302.6 | | 193.6 | 143.9 |
| C ₃ H ₈ O | 1-Propanol(g) | -255.1 | | 322.6 | 85.6 |
| C ₃ H ₈ O | 2-Propanol(l) | -318.1 | | 181.1 | 156.5 |
| C ₃ H ₈ O | 2-Propanol(g) | -272.6 | | 309.2 | 89.3 |
| C ₃ H ₉ N | 1- Propanamine(g) | -72 | 40 | 324 | |
| C ₄ H ₆ | 1-Butyne(l) | 141.4 | | | |
| C ₄ H ₆ | 1-Butyne(g) | 165.2 | 202 | 291 | 81 |
| C ₄ H ₆ | 2-Butyne(l) | 119.1 | | | |
| C ₄ H ₆ | 2-Butyne(g) | 145.7 | 185 | 283 | 78 |
| C ₄ H ₆ | Cyclobutene(g) | 156.7 | 175 | 64 | 64 |
| C ₄ H ₈ | 2-Methyl-1- propene(g) | -17 | 58 | 294 | 89 |
| C ₄ H ₈ | 1-Butene(l) | -20.8 | | 227 | 118 |
| C ₄ H ₈ | 1-Butene(g) | 0.1 | 71 | 306 | 86 |
| C ₄ H ₈ | Cyclobutane(l) | 3.7 | | | |
| C ₄ H ₈ | Cyclobutane(g) | 27.7 | 110 | 265 | |
| C ₄ H ₈ O ₂ | Butanoic acid(l) | -533.8 | | 222.2 | 178.6 |
| C ₄ H ₈ O ₂ | Butanoic acid(g) | -475.9 | | | |
| C ₄ H ₁₀ | 2- Methylpropane(g) | -135 | -21 | 295 | 97 |
| C ₄ H ₁₀ | Butane(l) | -147.3 | | | 140.9 |
| C ₄ H ₁₀ | Butane(g) | -125.7 | -17 | 310 | 98 |
| C ₄ H ₁₀ O | 1-Butanol(l) | -327.3 | | 225.8 | 177.2 |
| C ₄ H ₁₀ O | 1-Butanol(g) | -274.9 | | | |
| C ₄ H ₁₀ O | 2-Butanol(l) | -342.6 | | 214.9 | 196.9 |
| C ₄ H ₁₀ O | 2-Butanol(g) | -292.8 | | 359.5 | 112.7 |
| C ₅ H ₈ | 1-Pentyne(g) | 144 | 210 | 330 | 105 |
| C ₅ H ₈ | 2-Pentyne(g) | 129 | 194 | 332 | 99 |
| C ₅ H ₈ | Cyclopentene(l) | 4.3 | | 201.2 | 122.4 |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|---|----------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₅ H ₈ | Cyclopentene(g) | 34 | 111 | 290 | 75 |
| C ₅ H ₁₀ | 1-Pentene(l) | -46.9 | | 262.6 | 154 |
| C ₅ H ₁₀ | 1-Pentene(g) | -21.1 | 79 | 346 | 110 |
| C ₅ H ₁₀ | 2-Methyl-1-butene(g) | -35.2 | 66 | 340 | 112 |
| C ₅ H ₁₀ | 2-Methyl-1-butene(l) | -61.1 | | 254 | 157.2 |
| C ₅ H ₁₀ | Cyclopentane(l) | -105.1 | | 204.5 | 128.8 |
| C ₅ H ₁₀ | Cyclopentane(g) | -76.4 | 39 | 293 | 83 |
| C ₅ H ₁₀ O ₂ | Pentanoic acid(l) | -559.4 | | 259.8 | 210.3 |
| C ₅ H ₁₀ O ₂ | Pentanoic acid(g) | -491.9 | | | |
| C ₅ H ₁₂ | 2,2-Dimethylpropane(g) | -166 | -15 | 306 | 122 |
| C ₅ H ₁₂ | 2-Methylbutane(g) | -155 | -15 | 344 | 119 |
| C ₅ H ₁₂ | Pentane(l) | -173.5 | | | 167.2 |
| C ₅ H ₁₂ | Pentane(g) | -146.9 | -8 | 349 | 120 |
| C ₅ H ₁₂ O | 1-Pentanol(l) | -351.6 | | | 208.1 |
| C ₅ H ₁₂ O | 1-Pentanol(g) | -294.6 | | | |
| C ₅ H ₁₂ O | 2-Pentanol(l) | -365.2 | | | |
| C ₅ H ₁₂ O | 2-Pentanol(g) | -311 | | | |
| C ₅ H ₁₂ O | 3-Pentanol(l) | -368.9 | | | 239.7 |
| C ₅ H ₁₂ O | 3-Pentanol(g) | -314.9 | | | |
| C ₅ H ₁₂ O | Methyl tert-butyl ether(l) | -313.6 | | 265.3 | 187.5 |
| C ₅ H ₁₂ O | Methyl tert-butyl ether(g) | -283.7 | | | |
| C ₆ H ₆ | Benzene(l) | 49.1 | 124.5 | 173.4 | 136 |
| C ₆ H ₆ | Benzene(g) | 82.9 | 129.7 | 269.2 | 82.4 |
| C ₆ H ₇ N | Aniline(l) | | | | 191.9 |
| C ₆ H ₇ N | Aniline(g) | 87.5 | -7 | 317.9 | 107.9 |
| C ₆ H ₁₀ | 1-Hexyne(g) | 124 | 219 | 369 | 128 |
| C ₆ H ₁₀ | Cyclohexene(l) | -28.5 | | 214.6 | 148.3 |
| C ₆ H ₁₀ | Cyclohexene(g) | -5 | 107 | 311 | 105 |
| C ₆ H ₁₂ | 1-Hexene(l) | -74.2 | | 295.2 | 183.3 |
| C ₆ H ₁₂ | 1-Hexene(g) | -43.5 | 87 | 385 | 132 |
| C ₆ H ₁₂ | 2-Methyl-1-pentene(g) | -59.4 | | | |
| C ₆ H ₁₂ | 2-Methyl-1-pentene(l) | -90 | | | |
| C ₆ H ₁₂ | Cyclohexane(l) | -156.4 | | | 154.9 |
| C ₆ H ₁₂ | Cyclohexane(g) | -123.4 | 32 | 298 | 106 |
| C ₆ H ₁₂ | Methylcyclopentane(g) | 106.2 | | | |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|---|------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₆ H ₁₂ | Methylcyclopentane(l) | 137.9 | | | |
| C ₆ H ₁₂ O ₂ | Hexanoic acid(l) | -583.8 | | | |
| C ₆ H ₁₂ O ₂ | Hexanoic acid(g) | -511.9 | | | |
| C ₆ H ₁₄ | 2,2-Dimethylbutane(g) | -185.9 | -10 | 358 | 142 |
| C ₆ H ₁₄ | 2,2-Dimethylbutane(l) | -213.8 | | 272.5 | 191.9 |
| C ₆ H ₁₄ | 2-Methylpentane(g) | -174.6 | -5 | 381 | 144 |
| C ₆ H ₁₄ | 2-Methylpentane(l) | -204.6 | | 290.6 | 193.7 |
| C ₆ H ₁₄ | 3-Methylpentane(g) | -171.9 | -2 | 380 | 143 |
| C ₆ H ₁₄ | 3-Methylpentane(l) | -202.4 | | 292.5 | 190.7 |
| C ₆ H ₁₄ | Hexane(l) | -198.7 | | | 195.6 |
| C ₆ H ₁₄ | Hexane(g) | -166.9 | -0.3 | 388 | 143 |
| C ₆ H ₁₄ O | 1-Hexanol(l) | -377.5 | | 287.4 | 240.4 |
| C ₆ H ₁₄ O | 1-Hexanol(g) | 315.9 | | | |
| C ₆ H ₁₄ O | 2-Hexanol(l) | -392 | | | |
| C ₆ H ₁₄ O | 2-Hexanol(g) | -333.5 | | | |
| C ₇ H ₆ O | Phenol(s) | -165.1 | | 144 | 127.4 |
| C ₇ H ₆ O | Phenol(g) | -96.4 | -33 | 316 | 104 |
| C ₇ H ₈ | Methylbenzene(l) | 12.0 | | 220 | 156 |
| C ₇ H ₈ | Methylbenzene(g) | 50.0 | 122 | 321 | 104 |
| C ₇ H ₁₄ | 1-Heptene(l) | -97.9 | | 327.6 | 211.8 |
| C ₇ H ₁₄ | 1-Heptene(g) | -62.3 | 96 | 424 | 15 |
| C ₇ H ₁₄ | Cycloheptane(l) | -156.6 | | | |
| C ₇ H ₁₄ | Cycloheptane(g) | -118.1 | | | |
| C ₇ H ₁₄ | Ethylicyclopentane(l) | -163.4 | | 279.9 | |
| C ₇ H ₁₄ | Ethylicyclopentane(g) | -126.9 | | | |
| C ₇ H ₁₄ | Methylcyclohexane(g) | -154.7 | | | |
| C ₇ H ₁₄ | Methylcyclohexane(l) | -190.1 | | | 184.8 |
| C ₇ H ₁₄ O ₂ | Heptanoic acid(l) | -610.2 | | | 265.4 |
| C ₇ H ₁₄ O ₂ | Heptanoic acid(g) | -536.2 | | | |
| C ₇ H ₁₆ | 2,2-Dimethylpentane(g) | -205.7 | | | |
| C ₇ H ₁₆ | 2,2-Dimethylpentane(l) | -238.3 | | 300.3 | 221.1 |
| C ₇ H ₁₆ | 2-Methylhexane(g) | -194.5 | | | |
| C ₇ H ₁₆ | 2-Methylhexane(l) | -229.5 | | 323.3 | 222.9 |
| C ₇ H ₁₆ | 3-Methylhexane(g) | -191.3 | | | |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|---|--------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₇ H ₁₆ | 3-Methylhexane(l) | -226.4 | | | |
| C ₇ H ₁₆ | Heptane(l) | -224.2 | | 224.7 | |
| C ₇ H ₁₆ | Heptane(g) | -187.6 | 8 | 428 | 166 |
| C ₇ H ₁₆ O | 1-Heptanol(l) | -403.3 | | | 272.1 |
| C ₇ H ₁₆ O | 1-Heptanol(g) | -336.5 | | | |
| C ₈ H ₁₀ | Ethylbenzene(l) | -12.3 | | | 183.2 |
| C ₈ H ₁₀ | Ethylbenzene(g) | 29.9 | 131 | 361 | 128 |
| C ₈ H ₁₆ | 1-Octene(l) | -124.5 | | | 241 |
| C ₈ H ₁₆ | 1-Octene(g) | -81.3 | 104 | 463 | 178 |
| C ₈ H ₁₆ | Cyclooctane(l) | -167.7 | | | |
| C ₈ H ₁₆ | Cyclooctane(g) | -124.4 | | | |
| C ₈ H ₁₆ | Ethylcyclohexane(l) | -212.1 | | 280.9 | 211.8 |
| C ₈ H ₁₆ | Ethylcyclohexane(g) | -171.5 | | | |
| C ₈ H ₁₆ O ₂ | Octanoic acid(l) | -636 | | | 297.9 |
| C ₈ H ₁₆ O ₂ | Octanoic acid(g) | -554.3 | | | |
| C ₈ H ₁₈ | 2-Methylheptane(g) | -215.3 | | | |
| C ₈ H ₁₈ | 2-Methylheptane(l) | -255 | | 356.4 | 252 |
| C ₈ H ₁₈ | 3-Methylheptane(g) | -212.5 | | | |
| C ₈ H ₁₈ | 3-Methylheptane(l) | -252.3 | | 362.6 | 250.2 |
| C ₈ H ₁₈ | Octane(l) | -250.1 | | | 254.6 |
| C ₈ H ₁₈ | Octane(g) | -208.5 | 16 | 467 | 189 |
| C ₈ H ₁₈ O | 1-Octanol(l) | -426.5 | | | 305.2 |
| C ₈ H ₁₈ O | 1-Octanol(g) | -355.6 | | | |
| C ₈ H ₁₉ | 2,2-Dimethylhexane(g) | -224.5 | | | |
| C ₈ H ₁₉ | 2,2-Dimethylhexane(l) | -261.9 | | | |
| C ₉ H ₁₈ | Propylcyclohexane(g)-192 | | | 420 | 242 |
| C ₉ H ₁₂ | Propylbenzene(g) | 8 | 137 | 401 | 154 |
| C ₉ H ₁₆ | 1-Nonyne(l) | 16.3 | | | |
| C ₉ H ₁₆ | 1-Nonyne(g) | 62.3 | | | |
| C ₉ H ₁₈ O ₂ | Nonanoic acid(l) | -659.7 | | | 362.4 |
| C ₉ H ₁₈ O ₂ | Nonanoic acid(g) | -577.3 | | | |
| C ₉ H ₂₀ | 2,2-Dimethylheptane(g) | -246 | | | |
| C ₉ H ₂₀ | 2,2-Dimethylheptane(l) | -288.1 | | | |
| C ₉ H ₂₀ | Nonane(l) | -274.7 | | | 284.4 |
| C ₉ H ₂₀ | Nonane(g) | -228.2 | 25 | 506 | 212 |
| C ₉ H ₂₀ O | 1-Nonanol(l) | -453.4 | | | |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|--|------------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₉ H ₂₀ O | 1-Nonanol(g) | -376.5 | | | |
| C ₁₀ H ₈ | Naphthalene(g) | 151 | 224 | 336 | |
| C ₁₀ H ₁₄ | Butylbenzene(l) | -63.2 | | 321.2 | 243.4 |
| C ₁₀ H ₁₄ | Butylbenzene(g) | -11.8 | | | |
| C ₁₀ H ₂₀ | 1-Decene(l) | -173.8 | | 425 | 300.8 |
| C ₁₀ H ₂₀ | 1-Decene(g) | -123.3 | | | 301 |
| C ₁₀ H ₂₀ | Butylcyclohexane(l) | -263.1 | | 345 | 271 |
| C ₁₀ H ₂₀ | Butylcyclohexane(g) | -213.7 | | | |
| C ₁₀ H ₂₀ O ₂ | Decanoic acid(s) | -713.7 | | | |
| C ₁₀ H ₂₀ O ₂ | Decanoic acid(l) | -684.3 | | | |
| C ₁₀ H ₂₀ O ₂ | Decanoic acid(g) | -594.9 | | | |
| C ₁₀ H ₂₂ | 2-Methylnonane(g) | -260.2 | | | |
| C ₁₀ H ₂₂ | 2-Methylnonane(l) | -309.8 | | 420.1 | 313.3 |
| C ₁₀ H ₂₂ | Decane(l) | -300.9 | | | 314.4 |
| C ₁₀ H ₂₂ | Decane(g) | -249.5 | 33 | 545 | 235 |
| C ₁₀ H ₂₂ O | 1-Decanol(l) | -478.1 | | | 370.6 |
| C ₁₀ H ₂₂ O | 1-Decanol(g) | -396.6 | | | |
| C ₁₁ H ₁₀ | 1-Methylnaphthalene(l) | 56.3 | | 254.8 | 224.4 |
| C ₁₁ H ₁₀ | 2-Methylnaphthalene(s) | 44.9 | | 220 | 196 |
| C ₁₁ H ₁₀ | 2-Methylnaphthalene(g) | 106.7 | | | |
| C ₁₁ H ₂₂ | 1-Undecene(g) | | | | 344.9 |
| C ₁₁ H ₂₄ | Undecane(l) | -327.2 | | | 344.9 |
| C ₁₁ H ₂₄ | Undecane(g) | -270.8 | 42 | 584 | 257 |
| C ₁₁ H ₂₄ O | 1-Undecanol(l) | -504.8 | | | |
| C ₁₂ H ₂₄ | 1-Dodecene(l) | -226.2 | | 484.8 | 360.7 |
| C ₁₂ H ₂₄ | 1-Dodecene(g) | -165.4 | | | |
| C ₁₂ H ₂₄ O ₂ | Dodecanoic acid(s) | -774.6 | | | 404.3 |
| C ₁₂ H ₂₄ O ₂ | Dodecanoic acid(l) | -737.9 | | | |
| C ₁₂ H ₂₄ O ₂ | Dodecanoic acid(g) | 642 | | | |
| C ₁₂ H ₂₆ | Dodecane(l) | -350.9 | | | 375.8 |
| C ₁₂ H ₂₆ | Dodecane(g) | -289.4 | 50 | 623 | 280 |
| C ₁₂ H ₂₆ O | 1-Dodecanol(l) | -528.5 | | | 438.1 |
| C ₁₂ H ₂₆ O | 1-Dodecanol(g) | -436.6 | | | |
| C ₁₄ H ₁₀ | Anthracene(g) | 231 | | | |
| C ₁₄ H ₁₀ | Phenanthrene(g) | 207 | | | |
| C ₁₅ H ₃₀ | Decylcyclopentane(l) | -367.3 | | | |
| C ₁₆ H ₂₆ | Decylbenzene(l) | -218.3 | | | |

| Formula: | Name: | $\Delta_f H^\ominus$ [kJ/mol] | $\Delta_f G^\ominus$ [kJ/mol] | S^\ominus [J/(mol K)] | C_P [J/(mol K)] |
|--|----------------------|----------------------------------|----------------------------------|----------------------------|----------------------|
| C ₁₆ H ₂₆ | Decylbenzene(g) | -138.6 | | | |
| C ₁₆ H ₃₂ | 1-Hexadecene(l) | -328.7 | | 587.9 | 488.9 |
| C ₁₆ H ₃₂ | 1-Hexadecene(g) | -248.4 | | | |
| C ₁₆ H ₃₂ O ₂ | Hexadecanoic acid(s) | -891.5 | | 452.4 | 460.7 |
| C ₁₆ H ₃₂ O ₂ | Hexadecanoic acid(l) | -838.1 | | | |
| C ₁₆ H ₃₂ O ₂ | Hexadecanoic acid(g) | -737.1 | | | |
| C ₁₆ H ₃₄ | N-hexadecane(l) | -456.1 | | | 501.6 |
| C ₁₆ H ₃₄ | N-hexadecane(g) | -374.8 | | | |
| C ₁₈ H ₁₂ | Chrysene(s) | 145.3 | | | |
| C ₁₈ H ₁₂ | Chrysene(g) | 269.8 | | | |