
The Live Textbook of Physical Chemistry

Volume 1: Classical Thermodynamics and Chemical Kinetics



Roberto Peverati

$P^{\varepsilon}V^{\varepsilon} = R_a T_i$
research

The Live Textbook of Physical Chemistry 1

Roberto Peverati

11 November 2026

Table of contents

Preface **1**
Author's Note to the August 2024 Edition 1
How to use this book 2
A note on units 3

1. Introduction to Thermodynamics **5**
1.1. Calculus for Physical Chemistry: Slicing and Gluing 5
1.1.1. Differentiation: Infinite Slicing 6
1.1.2. Integration: Gluing Together Differentials 7
1.1.3. Calculus for Thermodynamics 9
1.2. Thermodynamic Systems 11
1.3. Thermodynamic Variables 14
1.3.1. State and Path Variables 17
1.4. Chapter Review 18
1.4.1. Study Questions 18

2. Zeroth Law of Thermodynamics **22**
2.1. What is Thermodynamics? 22
2.2. The Zeroth Law of Thermodynamics 23
2.3. Calculation of Heat 24
2.3.1. Processes at constant volume (isochoric) 24
2.3.2. Processes at constant pressure (isobaric) 25
2.4. Calculation of Work 26
2.4.1. $|W_{\max}|$ and $|W_{\min}|$ in processes at constant temperature (isothermal) 28
2.5. Chapter Review 32
2.5.1. Study Questions 32

3. First Law of Thermodynamics **36**
3.1. Calculation of Internal Energy Changes 36
3.1.1. Internal energy in isothermal processes 37
3.1.2. Internal energy in adiabatic processes 38
3.1.3. Internal energy in isochoric processes 38
3.1.4. Internal energy in isobaric processes 39
3.2. The First Law of Thermodynamics 40
3.3. Reversible and Irreversible processes 40

3.4. Chapter Review 43
3.4.1. Study Questions 43

4. Thermochemistry **47**
4.1. Reaction Enthalpies 47
4.2. Standard Enthalpies of Formation 49
4.3. Hess's Law 50
4.4. Calculations of Enthalpies of Reaction at $T \neq 298$ K 51
4.5. Chapter Review 53
4.5.1. Study Questions 53

5. Thermodynamic Cycles **56**
5.1. Carnot Cycle 57
5.1.1. Stage 1: isothermal expansion $A \to B$ 58
5.1.2. Stage 2: adiabatic expansion $B \to C$ 59
5.1.3. Stage 3: isothermal compression $C \to D$ 60
5.1.4. Stage 4: adiabatic compression $D \to A$ 61
5.2. Energy, Heat, and Work in the Carnot Cycle 61
5.3. Efficiency of a Carnot Cycle 64
5.4. Chapter Review 65
5.4.1. Study Questions 65

6. Entropy and the Second Law of Thermodynamics **69**
6.1. Entropy 69
6.2. Irreversible Cycles 71
6.3. The Second Law of Thermodynamics 72
6.4. Boltzmann Entropy 74
6.4.1. Counting microstates 75
6.4.2. The Boltzmann equation 75
6.4.3. Why "disorder" can be misleading 76
6.5. Chapter Review 77
6.5.1. Study Questions 77

7. Calculation of Entropy and the Third Law of Thermodynamics **80**
7.1. Calculation of ΔS^{sys} 80
7.1.1. Entropy in isothermal processes 81
7.1.2. Entropy in adiabatic processes 82
7.1.3. Entropy in isochoric processes 82
7.1.4. Entropy in isobaric processes 83
7.2. Calculation of ΔS^{surr} 83
7.3. Clausius Theorem 85
7.4. The Third Law of Thermodynamics 86
7.5. Chapter Review 88
7.5.1. Study Questions 88

8. Thermodynamic Potentials **91**
8.1. Fundamental Equation of Thermodynamics 91
8.2. Thermodynamic Potentials 92
8.3. Gibbs and Helmholtz Energies 97
8.4. Maxwell Relations 99
8.5. Chapter Review 103
8.5.1. Study Questions 103

9. Gibbs Energy **107**
9.1. Gibbs Equation 107
9.2. Temperature Dependence of ΔG 109
9.3. Pressure Dependence of ΔG 111
9.4. Composition Dependence of ΔG 112
9.5. Chapter Review 114
9.5.1. Study Questions 114

10. Chemical Equilibrium **118**
10.1. Reaction Quotient and Equilibrium Constant 118
10.2. Temperature Dependence of K_{eq} 121
10.3. Pressure and Composition Dependence of K_{eq} 122
10.4. Chapter Review 125
10.4.1. Study Questions 125

11. Ideal and Non-Ideal Gases **129**
11.1. The Ideal Gas Equation 129
11.1.1. Boyle's Law 130
11.1.2. Charles's and Gay-Lussac's Laws 130
11.1.3. Avogadro's Law 132
11.1.4. The ideal gas Law 132
11.2. Behaviors of Non-Ideal Gases 133
11.2.1. The van der Waals equation 134
11.2.2. Joule–Thomson effect 135
11.3. Critical Phenomena 137
11.3.1. Compressibility factors 137
11.3.2. Phase diagram of a non-ideal gas 140
11.4. Fugacity 141
11.5. Chapter Review 144
11.5.1. Study Questions 144

12. Phase Equilibrium **147**
12.1. Phase Stability 147
12.2. Gibbs Phase Rule 151
12.3. PT Phase Diagrams 152
12.3.1. Liquid $\rightleftarrows$ Gas equilibrium 153
12.3.2. Solid $\rightleftarrows$ Gas equilibrium 154
12.3.3. Solid $\rightleftarrows$ Liquid equilibrium 154

12.3.4. The triple point and the critical point 155
12.4. The Clausius–Clapeyron Equation 156
12.5. Chapter Review 157
12.5.1. Study Questions 157


13. Multi-Component Phase Diagrams and Solutions 160
13.1. Describing a Two-Component System 160
13.2. Ideal Solutions and Raoult's Law 161
13.2.1. One volatile component 162
13.2.2. Two volatile components 163
13.2.3. Tx_{B} phase diagrams and fractional distillation . . . 165
13.3. Phase Diagrams of Non-Ideal Solutions 167
13.4. Activity 170
13.5. Colligative Properties 172
13.5.1. Vapor pressure lowering 173
13.5.2. Boiling point elevation and melting point depression 174
13.5.3. Osmotic pressure 176
13.6. Chapter Review 177
13.6.1. Study Questions 177

14. Chemical Kinetics 181
14.1. Differential and integrated rate laws 181
14.1.1. Zeroth-order reaction 182
14.1.2. First-order reaction 183
14.1.3. Second-order reaction 185
14.1.4. Third- and higher-order reactions 187
14.2. Complex Rate Laws 188
14.2.1. Consecutive reactions 188
14.2.2. Competitive reactions 191
14.2.3. Opposed reactions 192
14.3. Experimental Methods for Determination of Reaction Orders 194
14.3.1. Initial rates method 195
14.3.2. Isolation method 196
14.4. Temperature Dependence of the Rate Coefficients 197
14.5. Chapter Review 199
14.5.1. Study Questions 199

Appendices 203

A. Appendix 203
A.1. Thermodynamic Data of Inorganic Substances at 298 K . . 203
A.2. Thermodynamic Data of Organic Substances at 298 K . . . 207

Preface



This textbook is the official textbook for the Physical Chemistry 1 Course (CHM 3001) at Florida Institute of Technology.

The instructor for this course and author of this textbook is Dr. Roberto Peverati.

Contacts: rpeverati@fit.edu, Office: OPS 333, (321) 674-7735

Chemistry Program, Department of Chemistry and Chemical Engineering, Florida Institute of Technology, Melbourne, FL.

Author's Note to the August 2024 Edition

2024 marks the fifth year of existence for "The Live Textbook of Physical Chemistry." Faithful to my initial intent, the textbook has evolved substantially from its humble beginnings, and it continues to evolve to this day. Five years is a long time in education, and much has happened during this period, including a pandemic that forced everyone to online teaching and learning, and the rise of generative AI in many fields, including education and Academia. I have big plans for the next phase of the book's evolution, but due to time constraints and the ever-increasing demands of academic

duties, I had to postpone them for now. As such, the structure of the textbook has largely remained unchanged. If and when I will have time to restructure my entire courses, as well as the textbooks that go with them, I will present a true "Second Edition" of "The Live Textbook," but this is not it yet.

What I did have time to do, however, was to bring "The Live Textbook" up to the standards of a true academic textbook. Since its inception, I was well aware that there was a glaring omission: exercises. This summer, I finally had the opportunity to add new review sections at the end of every chapter, each containing practice problems and study questions. These new sections are designed to help readers verify their understanding of each chapter's content. More importantly, they are intended for my students to test their knowledge before exams. For this reason, they follow the same style as the questions I have used in my exams over the past five years. In fact, several of these questions and exercises are taken directly from previous exams. I can't promise that the same questions will be in future exams, but familiarizing with them will give a student the edge over students that decide to ignore them.

Finally, I am not pretending to have been unaware of the emergence of AI, generative models, and their impact on education, so I've tried to put them to a good use. In the past five years, I specifically used ChatGPT and Claude to rewrite some sections of this textbook, and I have made it clear when that was the case. These tools were especially valuable this summer for the new exercises and questions sections, where I abundantly used them to help supplement my existing materials with newly generated ones. I made sure the AI didn't hallucinate and to fix it when it did, so hopefully, everything is consistent. I must confess that I would not have met the deadline for the beginning of the semester without this new technology. Hopefully, this serves as a good example of how AI can be incorporated into the classroom.

Additionally, in the summer of 2026, I have reworked all of the pictures in the textbook to add alt-text descriptions. This is important for accessibility and it is (hopefully) compliant with the new Government directives on online accessibility for education.

As usual, if you spot any mistakes, I encourage you to reach out to me at the contacts listed above.

How to use this book

If you are a student in my course, please read this book carefully, since everything that will be in your exams is explained here! Since this book

is specifically tailored for the CHM 3001 course at Florida Tech, there are no superfluous parts. In other words, everything in it might be subject to question in the quizzes and the final exam.

> Definitions and exercises are numbered (e.g., Definition 1.1, Exercise 4.1) and are set apart from the rest of the text. Notes and examples are highlighted in this format (indented, and following a grey vertical bar). Please study the definitions carefully since they are fundamental concepts that will be used several times in the remainder of the text, and they will be subject to quizzes and exams. Exercises are essential for cementing the concepts, and you should attempt to execute them first without looking at the solution. Even if you were able to solve an exercise on your own, always read the solution after, since it might contain additional explanations expanding the main concepts in the text.

Navigating the book should be straightforward. On each page, there is a useful sidebar on the left that gives you an overview of all chapters, with a few important tools at its top. Arrows to move between chapters are at the bottom of each page. If you are old-school and prefer a pdf, you can download a printout by clicking on the corresponding icon at the top of the sidebar. If you are *really* old-school and prefer a printed book, the best solution is to download the pdf and print it yourself. It is a LaTeX book, and I can promise you it will look good on paper. However, I cannot provide physical copies to each student. In the sidebar, you will find a useful search box that is capable of searching the entire book. The most adventurous will find there a link to the raw GitHub source code. Feel free to head to the GitHub repository of this book and fork it.

For my students, each chapter of this book represents one week of work in the classroom and at home. The sidebar on the left will reflect your syllabus, as well as the main structure of the class on Canvas. The book is a live document, which means it will be updated throughout the semester with new material. While you are not required to check it every day, you might want to review each week's chapter before the lecture on Friday.

A note on units

In general, we will use SI units or some of their multiples throughout the textbook, lectures, and exercises. For example, temperatures will be measured in kelvin (K), energetic terms will be measured in either joules (J) or kilojoules (kJ), while volumes will be measured in cubic meters, or more often in liters (L), where $1\,\mathrm{L} = 10^{-3}\,\mathrm{m}^3$. An important exception is made

for pressures, which will be measured in bars (bar). This exception is not completely unjustified, since bar is still an (unconventional) multiple of the SI unit of pressure, pascal (Pa), where $1\,\text{bar} = 10^5\,\text{Pa}$. This choice is made to retain a reasonable similarity with the unit atmosphere (atm) which is extensively used in several other chemistry textbooks ($1\,\text{atm} = 1.013\,\text{bar}$) and in previous physical chemistry courses.

We will generally also try to avoid conversion between units, except for some trivial conversion between degrees Celsius (°C) and Kelvin, with the conversion factor being an addition of 273.15 K. Other unconventional conversions might happen in some of the exercises, with the conversion factors always reported within the exercise itself. Additionally, we will avoid unnecessary conversion between the average atmospheric pressure and bars by setting $P_{\text{atm}} = 1\,\text{bar}$, rather than $P_{\text{atm}} = 1\,\text{atm} = 1.013\,\text{bar}$, an approximation that is mostly inconsequential, at least at the scale of the problems that we treat here.

This live open textbook is distributed under the CC BY-NC-SA 4.0 License and it was funded by the Florida Tech Open Educational Resources Grant Program: A Collaboration of the Teaching Council, eEducation, and the Evans Library. Third-party images keep their own licenses, as credited in their captions or footnotes. The scripts used to build the book are available under the MIT License.

1. Introduction to Thermodynamics

1.1. Calculus for Physical Chemistry: Slicing and Gluing

Calculus is a powerful mathematical tool that helps us understand and analyze change. At its core, calculus involves two main procedures: differentiation and integration. These concepts are fundamental to the study of thermodynamics, as they enable us to examine how physical systems change. Undergraduate students often find calculus intimidating due to its rigorous presentation in mathematical courses. However, a strong mathematical foundation, while beneficial, is not always mandatory to study thermodynamics effectively.

If you are a student who lacks confidence in mathematics, I encourage you not to be deterred by the presence of calculus in this physical chemistry textbook. If you break this initial wall of fear for calculus, you might find this textbook quite rewarding. After all, we will finally explain where all those unmemorable formulas that you've been presented in introductory general chemistry courses are coming from. To facilitate your task, we will present in this chapter a simplified view of calculus. The starting point will be a basic question: how do we measure things in science? To answer this question, we will use calculus to measure the length of an object. At a first glance, this approach might seem pedantic. Why do we need to use calculus, with all of its mathematical complications, when we can just grab a ruler and stack it against our object to measure its length? However, we need to remind ourselves that our ultimate goal is physical chemistry, and calculus is the language of this field. By focusing on the straightforward task of measuring a simple length, we aim to make calculus more accessible and less daunting.[1] From this simple starting point, we will expand our horizon to introduce the central topic of this textbook: Thermodynamics. Our main focus will be on the relationship between chemistry and thermodynamics, but since this is an advanced undergraduate textbook, we will need to do

[1] I apologize in advance to the mathematicians that will read this book and cringe at the several unexplained approximations I have made. I am fully aware of the dangers of not introducing these concepts rigorously, but some compromises have to be made…

that from a rigorous perspective. If we want to see it in simple terms, we either deal with the approach of not explaining where things are coming from that is abundantly used in freshman chemistry courses, or we make the effort of learning a bit of calculus so we can use it to understand the world.

1.1.1. Differentiation: Infinite Slicing

Differentiation can be thought of as "slicing an object into infinitely thin pieces" to understand how it changes at a specific point. Imagine you have a long stick and you want to measure how its length changes along a specific direction. To do this, you would cut the stick into infinitely thin slices. Each slice is so thin that its change in length is practically infinitesimal. By examining each of these tiny slices and how they change, you can understand the rate at which the stick's length changes at any given point. This process of infinite slicing is called differentiation, and it is the most powerful tool to understand things that change, that is, most of the things we are interested in science.

How so? Let's look at a simple example. If we start from a stick of length L, we can infinitely slice it into infinitesimally small pieces of length dL. These incredibly tiny pieces are called **differentials** of the original quantity, in this particular case, the length of our stick. The beauty of these differentials, dL, is that they don't really depend on how long our object initially was: they will always be *infinitesimally small*. Imagine, for example, that you start with an object whose length is 1 m. After you slice it an infinite amount of times, each differential could be pictured as a length of $0.000[...]0001\,\mathrm{m}$, where we have replaced an infinite amount of zeros with the notation [...]. If we start instead with a second object whose length is 1 km, we end up with differentials that are just as infinitesimally small. This picture with infinitely many zeros is only a way to visualize the idea: a differential is smaller than any number that we could write down, no matter how many zeros we use.

Now, through some mathematical magic, these strange numbers with an infinite amount of zeros, are essentially the closest thing you can get to 0, without practically being 0. For this reason, they can be used much more effectively than something that purely doesn't exist.[2] The key word here is *essentially*, because the differentials are as close to zero as we want, but they still contain some fundamental information related to the original objects. In the first place, they still have the dimension (and the units) of the original quantity: dL is an infinitesimal *length*, measured in meters, and it cannot be compared with, say, an infinitesimal time. Additionally,

[2] Yes, we are purposely skipping a lot of stuff here, see the note above.

the differentials will also contain information on the rate of change (the "slope") of the length in the original objects. The question that remains is: How are we going to access this apparently hidden information? In other words, how are we going to reconstruct the length of the original object from the differentials? The answer is surprisingly simple: By comparing different differentials to each other. More specifically, despite their zeroness, we are allowed to calculate the ratio between differentials, such as $\frac{dL}{dx}$. In this specific case, we are calculating the ratio between the differential of the length of our stick, and the position, x, along an axis that is oriented the same way as our stick.[3] This special ratio is called the *derivative*, and it is fundamental to compare one differential to another. In simple terms, the derivative tells us how one quantity (the one at the top) changes, when we purposely change another (the one at the bottom). Going back to our simple example, the derivative $\frac{dL}{dx}$ tells us how the length of our stick changes when we change the position on the axis. For this case, the derivative is a simple number $\frac{dL}{dx} = 1$, but more complicated cases are possible. So, how can we use this information to measure the length of our stick? A second calculus procedure, integration, comes to our rescue.

1.1.2. Integration: Gluing Together Differentials

Integration is the procedure that glues infinitely tiny slices back together to reconstruct the initial object. In simple terms, if you start with the infinitely thin slices of length that you cut earlier, you can add them all up to find the total length of the stick. Integration takes all these infinitesimally small pieces and combines them into a whole, helping you determine the accumulated total from the infinitesimal changes. Obviously this procedure is very complicated, and it involves gluing (summing over) an infinite amount of infinitesimally small things. If you can't wrap your head around this, that's OK, this concept puzzled humanity for thousands of years. The ancient Greeks were very concerned by this, but they failed to find a solution.[4] It took two 17th century geniuses, Isaac Newton and Gottfried Wilhelm Leibniz, to figure out how to do so.

The solution came by first defining the mathematical operation that "undoes" the slicing:

$$L = \int dL. \tag{1.1}$$

This operation is called an integral, and is represented by the symbol $\int$. The integral is the inverse of d, as it reconstructs the original object by

[3] The axis doesn't have to have the same orientation of the stick, but it is easier if we do so, in the first place.

[4] Look up Zeno's paradoxes for an interesting account of the situation at Greece's times.

gluing together an infinite amount of infinitesimally small differentials. This operation is, in practice, just a sanity check for the differentiation procedure introduced in the previous section. What eq. 1.1 is telling us, is nothing other than: if you start from an object, L, and apply a certain operation to it (d), then there has to be another operation ($\int$) that undoes what the first operation did. This inverse procedure becomes really useful when we want to measure things in the real world. How so? Because we can compare differentials of an unknown quantity to differentials of known ones, and then use the latter to reconstruct the former. In our simple example, we can use the derivative, $\frac{dL}{dx} = 1$, to compare the length of the object (unknown) to the position along our axis (known, because we can manipulate it). This is the mathematical counterpart of taking an object with unknown length, and comparing it to the length of a standard stick (a meter, a kilometer, a mile, …). The formula that describes this operation is:

$$L = \int dL = \int_i^f 1dx = x_f - x_i = \Delta x, \tag{1.2}$$

where the length (L) of the original object is reconstructed by fixing the initial piece at position x_i on the x axis, the final piece at position x_f, and then by gluing together the differentials dx in between these points, using the integral procedure. Switching from dL to dx has the noticeable advantage of going from something that we initially don't know anything about (the length of the stick) to something that we can manipulate as much as we want, because we specifically built it for this task (the position along the axis, x). This concept, of course, is not limited to length. If we differentiate an area, or a volume, or a pressure, or a temperature using eq. 1.1, we obtain the corresponding differentials. By comparing these differentials to specifically built ones that we are able to manipulate to our will, we can reconstruct the original quantity via integration, using eq. 1.2. Every differential will retain the *dimension* of the original quantity (dT still retains the dimension of a temperature, a.k.a. it *is* a temperature, despite the fact that it has a value of essentially zero). In addition, every differential will retain *hidden* information about the initial object, which we can reconstruct by comparing to something we know, and then by applying integration to the latter. Notice that it is the operation in eq. 1.2 that turns the infinitesimal pieces back into a finite, measurable quantity, by comparing an unknown differential to a known one. This is effectively the "measuring" procedure, written in mathematical terms.

When we wrote eq. 1.2, we glanced over the fact that $\int_i^f 1dx = x_f - x_i$. Where did that come from? And most importantly, how are we going to manage more complicated cases? At this point, you'll have to go fetch a mathematics textbook, as you need to know how to perform some of those integrals. For all intents and purposes, we can use those formulas as recipes

that mathematicians have written in the past. Granted, we are well aware of the fact that if we want to understand where the formulas are coming from, it is possible to do so with a little effort.[5] Mathematicians have clear rules on how to compute many of these objects, and one of such rules tells us that $\int_i^f dx = x_f - x_i$. Other common integration rules that we'll need in this course are, for example: $\int_i^f x^n\, dx = \frac{x^{n+1}}{n+1}\Big|_i^f = \frac{1}{n+1}\left(x_f^{n+1} - x_i^{n+1}\right)$ for $n \neq -1$, and $\int_i^f x^{-1} dx = \ln|x_f| - \ln|x_i| = \ln\left|\frac{x_f}{x_i}\right|$.

This is indeed a good point to go fetch that old math textbook and refresh some of the simplest integration rules, as well as some of the simplest differentiation ones. Not that we will use all of them, but we might indeed use a few ones.

1.1.3. Calculus for Thermodynamics

Now comes the interesting question: How are we going to practically perform these two important operations of differentiation and integration in thermodynamics? Well, imagine we need to study the behavior of a machine that prints out a number on a display. The first thing we need to do if we want to study this machine is to find something that makes the number change. Let's represent this something with a knob. We can then turn the knob voluntarily one way or another, and register how the number changes on the display. This is how you apply calculus in thermodynamics (and in most science, for that matter). Our machine might be the length of an object L, while our knob might be the position along an axis x. We can voluntarily change the position on the axis, and observe how the length changes on the display. Does that sound familiar? Can we use eq. 1.2 to do so? I believe so…

Now, obviously the example of length and position is the simplest we could imagine, and doesn't really pertain to physical chemistry. A more relevant example is that of a gas, whose pressure changes when we change the temperature at constant volume. In this case, the pressure, P, is the machine, and the temperature, T, is the knob. To understand the machine, we will need to know the derivative $\frac{dP}{dT}$. In many cases the derivative between our machine and our knob(s) might not be as simple as 1. In some of such cases, the derivative might be a different number, while in others it might be as complicated as a function itself. Some of the machines we will encounter might have more than just one knob, each with their own specific derivative, and each as complicated as it might be. In all cases, however, our analysis follows the same procedure: First, we identify all the knobs that affect the

[5] Yes, this is to a degree analogous to the plug and chug approach of general chemistry that we are trying to avoid here. However, we'll let this one pass, otherwise we risk presenting a mathematics textbook, rather than a physical chemistry one.

machine. Second, we use calculus to voluntarily change the position of the knobs and to register how the machine behaves. In mathematical terms, this procedure is to define and study the total differential:

$$d\mathcal{M} = \left(\frac{\partial \mathcal{M}}{\partial a}\right) da + \left(\frac{\partial \mathcal{M}}{\partial b}\right) db + \left(\frac{\partial \mathcal{M}}{\partial c}\right) dc + \cdots, \tag{1.3}$$

where $\mathcal{M}$ is our machine, $d\mathcal{M}$ is its total differential, $\{a, b, c, \cdots\}$ are the variables that affect the machine's behavior (i.e. the knobs), and $\frac{\partial \mathcal{M}}{\partial a}$ represents a partial derivative of the machine $\mathcal{M}$ with respect to the variable a obtained by keeping all other variables constant. Notice that the number of variables is left unidentified, as it is our goal to identify all of the variables that a machine depends on, and there are as many as necessary.




Figure 1.1.: A machine $\mathcal{M}$ with three knobs, a, b, and c. Turning each knob by an infinitesimal amount (da, db, dc) changes the number on the display. The total change, $d\mathcal{M}$, is the sum of the three contributions in eq. 1.3, each obtained by multiplying how sensitive the machine is to that knob (the partial derivative) by how much we turned it.

The final piece of the puzzle we need to apply calculus to thermodynamics is to know whether or not we can apply these two procedures to any quantity that enters the picture. The answer to this question, unfortunately, is a resounding no. Differentiation and integration can be applied to many variables that are "well-behaved." Such variables are called **state variables** in thermodynamics. Unfortunately though, there are also a few variables that are not well-behaved at all. These are called **path variables** in thermodynamics. It turns out that some of the quantities that thermodynamics is mostly concerned about, such as heat and work, belong to this "ill-behaved" category. Before we delve deeper into state and path variables, however, we

need to define what variables are in thermodynamics. And before we can do that, we need to take a whole step back and define what thermodynamics is concerned about, that is the thermodynamic system.

1.2. Thermodynamic Systems

A thermodynamic system—or just simply a system—is a portion of space with defined boundaries that separate it from its surroundings (see also the title picture of this book). The surroundings may include other thermodynamic systems or physical systems that are not thermodynamic systems. A boundary may be a real physical barrier or a purely notional one. Defining a system this way is itself a deliberate simplification that is common in science. This procedure is often jokingly referred to as the "spherical cow" analogy,[6] where a complex real-world object (a cow) is treated as a simple sphere to make the math tractable. Typical examples of systems are reported in Figure 1.2 below.




Figure 1.2.: Examples of Thermodynamic Systems and Their Boundaries. The Liquid in a Flask and the Gas in a Balloon Have Physical Boundaries, while the Boundaries of a Cloud and of a Flame (Dashed Red Lines) Are Defined by a Condition that We Choose.

In the first case, a liquid is contained in a typical Erlenmeyer flask. The boundaries of the system are the glass walls of the flask (and the surface of the liquid, which separates it from the air above). The second system is represented by the gas contained in a balloon. The boundary is a physical barrier also in this case, being the plastic of the balloon. The third case is that of a thundercloud. The boundary is not a well-defined physical barrier, but rather some condition of pressure and chemical composition at the interface between the cloud and the atmosphere. Finally, the fourth case is the case of an open flame. In this case, the boundary is again non-physical,

[6] The "spherical cow" analogy is sometimes quoted in its extended, joking form as "a spherical cow in a vacuum." See Wikipedia's article on the spherical cow and the article *Higher multipoles of the cow*, American Journal of Physics 94, 264 (2026).

and possibly even harder to define than for a cloud. For example, we can choose to define the flame based on some temperature threshold, color criterion, or even some chemical one. Despite the lack of physical boundaries, the cloud and the flame—as portions of space containing matter—can be defined as a thermodynamic system.

A system can exchange exclusively mass, exclusively energy, or both mass and energy with its surroundings. Depending on the boundaries' ability to transfer these quantities, a system is defined as open, closed, or isolated. An open system exchanges both mass and energy. A closed system exchanges only energy, but not mass. Finally, an isolated system exchanges neither mass nor energy.

When a system exchanges mass or energy with its surroundings, some of its parameters (variables) change. For example, if a system loses mass to the surroundings, the number of molecules (or moles) in the system will decrease. Similarly, if a system absorbs some energy, one or more of its variables (such as its temperature) increase. Mass and energy can flow into the system or out of the system. Let's consider mass exchange only. If some molecules of a substance leave the system, and then the same amount of molecules flow back into the system, the system will not be modified. We can count, for example, 100 molecules leaving a system and assign them the value of –100 in an outgoing process, and then observe the same 100 molecules going back into the system and assign them a value of +100. Regardless of the number of molecules present in the system in the first place, the overall balance will be –100 (from the outgoing process) +100 (from the ingoing process) = 0, which brings the system to its initial situation (mass has not changed). However, from a mathematical standpoint, we could have equally assigned the label +100 to the outgoing process and –100 to the ingoing one, and the overall total would have stayed the same: +100–100 = 0. Which of the two labels is best? For this case, it seems natural to define a mass going out of the system as negative (the system is losing it), and a mass going into the system as positive (the system is gaining it), but is it as straightforward for energy?

Type of System	**Mass**	**Energy** (either heat or work)
Open	Y	Y
Closed	N	Y
Isolated	N	N

Here is another example. Let's consider a system that is composed of your body. When you exercise, you lose mass in the form of water (sweat) and CO_2 (from respiration). This mass loss can be easily measured by stepping on a scale before and after exercise. The number you observe on the scale will go down.

Hence you have lost weight. After exercise, you will reintegrate the lost mass by drinking and eating. If you have reinstated the same amount you have lost, your weight will be the same as before the exercise (no weight loss). Nevertheless, which label do you attach to the amounts that you have lost and gained? Let's say that you are running a 5 km race without drinking or eating, and you measure your weight dropping 2 kg after the race. After the race, you drink 1.5 kg of water and eat a 500 g energy bar. Overall you did not lose any weight, and it would seem reasonable to label the 2 kg that you've lost as negative (–2) and the 1.5 kg of water that you drank and the 500 g bar that you ate as positive (+1.5 +0.5 = +2). But is it the only way? After all, you didn't gain nor lose any weight, so why not calling the 2 kg due to exercise +2 and the 2 that you've ingested as –2? It might seem silly, but mathematically it would not make any difference, the total would still be zero. Now, let's consider energy instead of mass. To run the 5 km race, you have spent 500 kcal, which then you reintegrate precisely by eating the energy bar. Which sign would you put in front of the kilocalories that you "burned" during the race? In principle, you've lost them, so if you want to be consistent, you should use a negative sign. But if you think about it, you've put quite an effort to "lose" those kilocalories, so it might not feel bad to assign them a positive sign instead. After all, it's perfectly OK to say, "I've done a 500 kcal run today", while it might sound quite awkward to say, "I've done a –500 kcal run today." Our previous exercise with mass demonstrates that it doesn't really matter which sign you put in front of the quantities. As long as you are consistent throughout the process, the signs will cancel out. If you've done a +500 kcal run, you've eaten a bar for –500 kcal, resulting in a total zero loss/gain. Alternatively, if you've done a –500 kcal run, you would have eaten a +500 kcal bar, for a total of again zero loss/gain.

These simple examples demonstrate that the sign that we assign to quantities that flow through a boundary is arbitrary (i.e., we can define it any way we want, as long as we are always consistent with ourselves). There is no best way to assign those signs. If you ask two different people, you might obtain two different answers. But we are scientists, and we must make sure to be rigorous. For this reason, chemists have established a convention for the signs that we will follow throughout this course. If we are consistent in following the convention, we are guaranteed to never make any mistake with the signs.

Definition 1.1. *The chemistry convention of the sign is system-centric:*[7]

- *If something (energy or mass) goes **into** the system it has a **positive** sign (the system is gaining)*
- *If something (energy or mass) goes **out of** the system it has a **negative** sign (the system is losing)*

If you want a trick to remember the convention, use the weight loss/gain during the exercise example above. You are the system, if you lose weight, the kilograms will be negative (–2 kg), while if you gain weight, they will be positive (+2 kg). Similarly, if you eat an energy bar, you are the system, and you will have increased your energy by +500 kcal (positive). In contrast, if you burned energy during exercise, you are the system, and you will have lost energy, hence –500 kcal (negative). If the system is a balloon filled with gas, and the balloon is losing mass, you are the balloon, and you are losing weight; hence the mass will be negative. If the balloon is absorbing heat (likely increasing its temperature and increasing its volume), you are the system, and you are gaining heat; hence heat will be positive.

1.3. Thermodynamic Variables

The system is defined and studied using parameters that are called variables. These variables are quantities that we can measure, such as pressure and temperature. However, don't be surprised if, on some occasions, you encounter variables that are a little harder to measure directly, such as entropy. If we know the values of all the "relevant variables" of a system, we know the state of the system. The relationships between all possible variables and the state of the system are called "state functions". Imagine state functions as the "machines" that we described in the previous section. The relevant variables are called natural variables, and you should imagine them as the "knobs" of the machines that we want to study. When we need to study a specific aspect of the system, then we need to know the total differential of the state function that is relevant for that aspect.

What are the "relevant variables" of a system? The answer to this question depends on the system, and it is not always straightforward. The simplest

[7] Notice that physicists use a different sign convention when it comes to thermodynamics. To eliminate confusion, I will not describe the physics convention here, but if you are reading thermodynamics on a physics textbook, or if you are browsing the web and stumble on thermodynamics formula (e.g., on Wikipedia), please be advised that some quantity, such as work, might have a different sign than the one that is used in this textbook. Obviously, the science will not change, but you need to be *always* consistent, so if you decide that you want to use the physics convention, make sure to *always* use the physics convention. In this course, on the other hand, we will *always* use the chemistry one, as defined here.

case is the case of an ideal gas, for which the natural variables are those that enter the ideal gas law and the corresponding equation:

$$PV = nRT \tag{1.4}$$

Therefore, the natural variables for an ideal gas are the pressure P, the volume V, the number of moles n, and the temperature T, with R being the ideal gas constant. Recalling from the general chemistry courses, R is a universal dimensional constant which has the value of $R = 8.31\,\mathrm{J\,mol^{-1}\,K^{-1}}$ in SI units. We will use the ideal gas equation and its variables as an example to discuss variables and functions in this chapter. We will analyze more complicated cases in the next chapters. Variables can be classified according to numerous criteria, each with its advantages and disadvantages. A typical classification is:

- **Physical variables** (P, V, T in the ideal gas law): independent of the chemical composition of the system.
- **Chemical variables** (n in the ideal gas law): dependent on the chemical composition of the system.

Alternatively, another useful classification is:

- **Intensive variables** (P, T in the ideal gas law): independent of the physical size (extension) of the system.
- **Extensive variables** (V, n in the ideal gas law): dependent on the physical size (extension) of the system.

When we deal with thermodynamic systems, it is more convenient to work with intensive variables. Luckily, it is relatively easy to convert extensive variables into intensive ones by just taking the ratio between the two of them. For an ideal gas, by taking the ratio between V and n, we obtain the intensive variable called molar volume:

$$\overline{V} = \frac{V}{n}. \tag{1.5}$$

We can then recast eq. 1.4 as:

$$P\overline{V} = RT, \tag{1.6}$$

which is the preferred equation that we will use for the remainder of this course. The ideal gas equation connects the 3 variables pressure, molar volume, and temperature, reducing the number of independent variables to just 2. In other words, once 2 of the 3 variables are known, the other one can be easily obtained using these simple relations:

$$P(T, \overline{V}) = \frac{RT}{\overline{V}}, \tag{1.7}$$

$$\overline{V}(T, P) = \frac{RT}{P}, \tag{1.8}$$

$$T(P, \overline{V}) = \frac{P\overline{V}}{R}. \tag{1.9}$$

These equations define three state functions, each one expressed in terms of two independent natural variables. For example, eq. 1.7 defines the state function called "pressure", expressed as a function of temperature and molar volume. Similarly, eq. 1.8 defines the "molar volume" as a function of temperature and pressure, and eq. 1.9 defines the "temperature" as a function of pressure and molar volume. As we mentioned above, when we know the natural variables that define a state function, we can express the function using its total differential, for example for the pressure $P(T, \overline{V})$, using the definition of total differential in eq. 1.3, we get:

$$dP = \left(\frac{\partial P}{\partial T}\right) dT + \left(\frac{\partial P}{\partial \overline{V}}\right) d\overline{V} \tag{1.10}$$

Recalling Schwarz's theorem, the mixed partial second derivatives that can be obtained from eq. 1.10 are the same:

$$\frac{\partial^2 P}{\partial T \partial \overline{V}} = \frac{\partial}{\partial \overline{V}} \frac{\partial P}{\partial T} = \frac{\partial}{\partial T} \frac{\partial P}{\partial \overline{V}} = \frac{\partial^2 P}{\partial \overline{V} \partial T} \tag{1.11}$$

Which can be easily verified considering that:

$$\frac{\partial}{\partial \overline{V}} \frac{\partial P}{\partial T} = \frac{\partial}{\partial \overline{V}} \left(\frac{R}{\overline{V}}\right) = -\frac{R}{\overline{V}^2} \tag{1.12}$$

and

$$\frac{\partial}{\partial T} \frac{\partial P}{\partial \overline{V}} = \frac{\partial}{\partial T} \left(\frac{-RT}{\overline{V}^2}\right) = -\frac{R}{\overline{V}^2} \tag{1.13}$$

While for the ideal gas law, all the variables are "well-behaved" and always satisfy Schwarz's theorem, we will encounter some variables for which Schwarz's theorem does not hold.

1.3.1. State and Path Variables

Mathematically, if Schwarz's theorem is violated (i.e., if the mixed second derivatives are not equal), then the corresponding function cannot be integrated. These ill-behaved variables are called **path variables** (or path functions) because they depend on the path, rather than the state of the system. In contrast to these ill-behaved variables, well-behaved variables that can be used to define the state of the system are called **state variables** (or state functions).

Since path functions violate Schwarz's theorem, their differential cannot be defined exactly, therefore eq. 1.2 does not exist. The most typical examples of path functions that we will encounter in the next chapters are heat (Q) and work (W). For these functions, we can attempt to infinitely slice the initial variable by using the same calculus procedure introduced in section 1.1.1 and defined in eq. 1.1. The resulting infinitely small pieces, however, are different than regular "exact" differentials, and are called **inexact differentials**. To differentiate between exact and inexact differentials, we use the letter d for the former, and the letter for the latter. It is important to remember that inexact differentials are defined using eq. 1.1, but the procedure in eq. 1.2 does not exist for them. Summarizing for a case that we will use often in thermodynamics, we can define the following quantity for heat (Q):

$$Q = \int Q. \tag{1.14}$$

However, we cannot use the familiar formula given by eq. 1.2 to calculate it:

$$\int_i^f Q \neq Q_f - Q_i, \tag{1.15}$$

as the left hand side of this equation is not defined.[8] Work also behaves similarly.

> We will return to exact and inexact differentials when we discuss heat and work, but for this chapter, it is crucial to notice the difference between a state function and a path function. A typical example to understand the difference between state and path function is to consider the distance between two geographical locations. Let's, for example, consider the distance between New York City and Los Angeles. If we fly straight from one city

[8] Technically, the integral itself does exist, but it takes different values when calculated along different paths, so it is not unique.

to the other, there are roughly 4,000 km between them. This "air distance" depends exclusively on the geographical location of the two cities. It stays constant regardless of the method of transportation that I have access to travel between them. Since the cities' positions depend uniquely on their latitudes and longitudes, the "air distance" is a state function, i.e., it is uniquely defined from a simple relationship between measurable variables. However, the "air distance" is not the distance that I will practically have to drive when I go from NYC to LA. Such "travel distance" depends on the method of transportation that I decide to take (airplane vs. car vs. train vs. boat vs. …). It will depend on a plentiful amount of other factors such as the choice of the road to be traveled (if going by car), the atmospheric conditions (if flying), and so on. A typical "travel distance" by car is, for example, about 4,500 km, which is about 12% more than the "air distance." Indeed, we could even design a very inefficient road trip that avoids all highways and will result in a "travel distance" of 8,000 km or even more (200% of the "air distance"). The "travel distance" is a clear example of a path function because it depends on the specific path that I decide to travel to go from NYC to LA. See Figure 1.3.



Figure 1.3.: State Functions vs. Path Functions.

1.4. Chapter Review

1.4.1. Study Questions

1. What is a differential, such as dL?

a. The derivative of L with respect to position.
b. A small but finite change in L, such as 1 mm.

c. An infinitesimally small piece of L that keeps the dimension of a length.
d. The total length L of the object.
e. A pure number with no dimension.

---

2. What does integration do, in the language of this chapter?

a. It glues together infinitely many infinitesimal pieces to reconstruct the whole quantity.
b. It slices a quantity into infinitesimal pieces.
c. It calculates the slope of a function at a point.
d. It converts a quantity from one unit to another.
e. It removes the dimension from a quantity.

---

3. Which of the following does an isolated system exchange with its surroundings?

a. Mass only.
b. Energy only.
c. Both mass and energy.
d. Neither mass nor energy.
e. Heat, but not work.

---

4. According to the chemistry sign convention, what is the sign of the heat released by a system to its surroundings?

a. Positive, since heat is energy.
b. Negative, since the system is losing energy.
c. Zero, since energy is conserved.
d. Positive if the process is fast, negative if it is slow.
e. It depends on the temperature of the surroundings.

---

5. Which of the following is an intensive variable?

a. Volume.
b. Number of moles.

c. Mass.
d. Temperature.
e. Total energy.

---

6. What is the total differential of the pressure of an ideal gas, $P(T, \overline{V})$?

a. $dP = \frac{dT}{d\overline{V}}$.
b. $dP = PdT + Pd\overline{V}$.
c. $dP = \frac{\partial P}{\partial T} + \frac{\partial P}{\partial \overline{V}}$.
d. $dP = \left(\frac{\partial T}{\partial P}\right) dT + \left(\frac{\partial \overline{V}}{\partial P}\right) d\overline{V}$.
e. $dP = \left(\frac{\partial P}{\partial T}\right) dT + \left(\frac{\partial P}{\partial \overline{V}}\right) d\overline{V}$.

---

7. What does Schwarz's theorem state for a state function?

a. The mixed second partial derivatives are equal, regardless of the order of differentiation.
b. The first derivatives are always zero.
c. The function cannot be integrated.
d. The function depends on the path.
e. The second derivatives are always positive.

---

8. Which of the following is a path function?

a. Pressure.
b. Temperature.
c. Work.
d. Molar volume.
e. Internal energy.

---

9. What does the symbol indicate, as in Q?

a. An exact differential.
b. An inexact differential, whose integral depends on the path.
c. A partial derivative.

d. A state function.
e. A very large change.

---

10. In the example of the trip from New York to Los Angeles, why is the air distance a state function?

a. Because it depends on the means of transportation.
b. Because it changes with the weather.
c. Because it depends only on the positions of the two cities, not on the route.
d. Because it is always longer than the travel distance.
e. Because it is measured in kilometers.

Answers

1.c, 2.a, 3.d, 4.b, 5.d, 6.e, 7.a, 8.c, 9.b, 10.c

2. Zeroth Law of Thermodynamics

In chapter 1, we introduced the tools that we need to study thermodynamics: a bit of calculus, the definition of a system, and the distinction between state and path functions. In this chapter, we will define the two ways in which a system can exchange energy with its surroundings, heat and work, and we will learn how to calculate them. Before we do that, however, we need a solid definition of temperature, which comes from the zeroth law of thermodynamics.

2.1. What is Thermodynamics?

Thermodynamics is the branch of science that deals with heat and work, and their relation to energy. These are the two ways in which energy can be transferred between a system and its surroundings:

- **Work** is exchanged when the system changes one of its external, macroscopic parameters against a force. The typical example in chemistry is a gas that changes its volume by pushing a piston against an external pressure.
- **Heat** is exchanged because of a temperature difference between the system and its surroundings, without any change in the external parameters. Heat flows through the random collisions between the molecules at the boundary, from the hotter side to the colder one.

As we saw in chapter 1, heat and work are not "well-behaved" quantities because they are path functions. While it might be simple to measure the amount of heat and/or work experimentally, these measured quantities cannot be used to define the state of a system. Since heat and work are path functions, their values depend directly on the methods used to transfer them (their paths). Understanding and quantifying these energy transfers is the reason why thermodynamics was developed in the first place. The origins of thermodynamics date back to the eighteenth and nineteenth centuries, when steam engines started to be used to convert heat into work for technological applications. These early scientists needed a mathematical tool to understand how heat and work were related to each other, and how

they were related to the other variables that they were able to measure, such as temperature and volume.

Before we even discuss the definition of energy and how it relates to heat and work, it is crucial to introduce the essential concept of temperature. Temperature is an intuitive concept that has a surprisingly complex definition at the microscopic level.[1] However, for all our purposes, it is not essential to have a microscopic definition of temperature, as long as we have the guarantee that this quantity can be measured unambiguously. In other words, we only need a mathematical definition of temperature that agrees with the physical existence of thermometers.

2.2. The Zeroth Law of Thermodynamics

We all know from experience that if we put a hot object in contact with a cold one, after some time they reach the same temperature, and heat stops flowing between them. When this happens, we say that the two objects are in *thermal equilibrium*. The zeroth law of thermodynamics states that if two thermodynamic systems are each in thermal equilibrium with a third one, then they are in thermal equilibrium with each other. The law might appear trivial and possibly redundant, but it is exactly what makes thermometers possible: the thermometer is the third system, and if it reads the same temperature when in contact with two different objects, we can conclude that the two objects are in thermal equilibrium with each other, even if they have never touched. For this reason, the zeroth law is a fundamental requirement for the mathematical formulation of thermodynamics, and it needs to be stated. The zeroth law can be summarized by the following simple mathematical relation:

Definition 2.1. *Zeroth Law of Thermodynamics:* If $T_A = T_B$, and $T_B = T_C$, then $T_A = T_C$.

Notice that when we state the zeroth law, it appears intuitive. However, this is not necessarily the case. Let's, for example, consider a pot of boiling water at $P = 1$ bar. Its temperature, T_{H_2O}, is about 373 K. Let's now submerge in this water a coin made of wood and another coin made of metal. After some sufficient time, the wood coin will be in thermal equilibrium with the water, and its temperature $T_W = T_{H_2O}$. Similarly, the metal coin will also be in thermal equilibrium with the water, hence $T_M = T_{H_2O}$. According to the zeroth law, the temperature of the wood coin and that of the metal coin are precisely the same $T_W = T_M = 373$ K, even if they are

[1] In fact, we will not even give a rigorous microscopic definition of temperature within this textbook.

not in direct contact with each other. Now here's the catch: since wood and metal transmit heat in different manners, if I take the coins out of the water and put them immediately in your hands, one of them will feel just warm, but the other will burn you. If you had to guess the temperature of the two coins without a thermometer, and without knowing that they were immersed in boiling water, would you suppose that they have the same temperature? Probably not.

2.3. Calculation of Heat

Heat (Q) is a property that gets transferred between substances. Similarly to work, the amount of heat that flows through a boundary can be measured, but its mathematical treatment is complicated because *heat is a path function*. As you probably recall from general chemistry, the ability of a substance to absorb heat is given by a coefficient called the heat capacity, which is measured in SI in $\frac{\text{J}}{\text{mol K}}$. However, since heat is a path function, these coefficients are not unique, and we have different ones depending on how the heat transfer happens.

2.3.1. Processes at constant volume (isochoric)

The heat capacity at constant volume measures the ability of a substance to absorb heat at constant volume. Recalling from general chemistry, the molar heat capacity at constant volume has the following formal definition:

> The molar heat capacity at constant volume is the amount of heat required to increase the temperature of 1 mol of a substance by 1 K at constant volume.

This is a procedural definition that defines how we can measure C_V in practice. While this procedure is useful in laboratory settings and in introductory chemistry courses, we need to go beyond it to understand its origin and its meaning. Have you ever wondered why you need to increase the temperature by 1 K? What if you want to increase it by 2? Or 1/2, or 1/1000? Also, the definition is highly imprecise, as there certainly has to be a difference when we increase the temperature of a substance from 1 K to 2 K, to when we increase it from 1001 K to 1002 K. Those situations certainly cannot lead to the same results. How are we going to circumvent this poor definition? We need to apply calculus to remove those arbitrary units and arbitrary increments (remember that differentials are all the same size, and unitless):

$$C_V = \frac{Q_V}{ndT} \Rightarrow Q_V = nC_V dT. \tag{2.1}$$

This new differential definition of C_V is independent of the unit we use to measure it, and does not require a procedural definition. Given a known value of C_V, the amount of heat that gets transferred can be easily calculated by measuring the changes in temperature, after integration of eq. 2.1:

$$Q_V = nC_V dT \rightarrow \int Q_V = n\int_{T_i}^{T_f} C_V dT \rightarrow Q_V = nC_V \int_{T_i}^{T_f} dT, \tag{2.2}$$

which, assuming C_V independent of temperature, simply becomes:

$$Q_V \cong nC_V \Delta T. \tag{2.3}$$

2.3.2. Processes at constant pressure (isobaric)

Similarly to the previous case, the heat capacity at constant pressure measures the ability of a substance to absorb heat at constant pressure. Recalling again from general chemistry:

> The molar heat capacity at constant pressure is the amount of heat required to increase the temperature of 1 mol of a substance by 1 K at constant pressure.

And once again, applying calculus to obtain a differential definition of C_P, we get:

$$C_P = \frac{Q_P}{ndT} \Rightarrow Q_P = nC_P dT \rightarrow \int Q_P = n\int_{T_i}^{T_f} C_P dT, \tag{2.4}$$

which results in the simple formula:

$$Q_P \cong nC_P \Delta T. \tag{2.5}$$

2.4. Calculation of Work

In thermodynamics, work (W) is the ability of a system to transfer energy by exerting a force on its surroundings. Work can be measured simply by evaluating its effects, such as displacing a massive object by some amount of space. The mathematical treatment of work, however, is complicated because *work is a path function*. In the following sections, we will analyze how work is calculated in some prototypical situations commonly encountered in the thermodynamical treatment of systems.




Figure 2.1.: Isothermal Expansion of an Ideal Gas Against a Constant External Pressure.

Let's consider the situation in Figure 2.1, where a special beaker with a piston that is free to move is filled with an ideal gas. The beaker sits on a desk, so the piston is not subject to any external forces other than the external pressure, P_{ext}, and the internal pressure of the gas, P.[2] The piston is initially compressed to a position that is not in equilibrium (i). After the process, the piston reaches a final equilibrium position (f). How do we calculate the work (W) performed by the system?

From basic physics, we recall that the infinitesimal amount of work associated with an object moving in space is given by the force acting on the object (F) multiplied by the infinitesimal amount it gets displaced (dh):

$$W = -F dh, \tag{2.6}$$

where the negative sign comes from the chemistry sign convention, Definition 1.1, since the work in Figure 2.1 is *performed* by the system (expansion). Which force should we use? When the gas expands, the work it

[2] For this simple thought experiment, we will ignore any external force that is not significant. In other words, we will not consider the friction of the piston on the beaker walls or any other foreign influence.

performs is the energy needed to push back the surroundings, so the relevant force is the one that the surroundings exert on the piston. Relying upon another definition from physics, the pressure is the ratio between the force (F) and the area (A) that such force acts upon, so the force exerted by the surroundings is related to the external pressure, P_{ext}, by:

$$P_{\text{ext}} = F/A. \tag{2.7}$$

Obtaining F from eq. 2.7 and replacing it in eq. 2.6, we obtain:

$$W = -P_{\text{ext}} \underbrace{Adh}_{dV}, \tag{2.8}$$

and considering that Adh (area times infinitesimal height) is the definition of an infinitesimal volume dV, we obtain:

$$W = -P_{\text{ext}} dV. \tag{2.9}$$

The external pressure is not necessarily the same as the pressure of the gas, P. In a fast expansion, the gas inside the beaker can be at a much higher pressure than the surroundings. However, if the expansion happens slowly enough that the piston is always balanced, $P_{\text{ext}} = P$ at every moment, and the work can be written using the pressure of the gas:

$$W = -PdV \qquad (\text{when } P_{\text{ext}} = P). \tag{2.10}$$

If we want to calculate the amount of work performed by a system, W, from eq. 2.9, we need to recall that W is an inexact differential. As such, we cannot integrate it from initial to final as for the (exact) differential of a state function, because:

$$\int_i^f W \neq W_f - W_i, \tag{2.11}$$

but rather:

$$\int_{\text{path}} W = W, \tag{2.12}$$

where the integration is performed along the *path*. Using eq. 2.12, we can integrate eq. 2.9 as:

$$\int W = W = -\int_i^f P_{\text{ext}} dV, \tag{2.13}$$

where the integral on the left-hand side is taken along the path,[3] while the integral on the right-hand side can be taken between the initial and final states, since V is a state function. How do we solve the integral in eq. 2.13? It turns out that there are many different ways to solve this integral (perhaps not surprisingly, since the left-hand side depends on the path), which we will explore in the next section.

2.4.1. $|W_{\text{max}}|$ and $|W_{\text{min}}|$ in processes at constant temperature (isothermal)

At constant temperature, the piston in Figure 2.1 moves along the isotherm in figure 2.2, obtained for 1 mol of an ideal gas at $T = 298$ K.




Figure 2.2.: Isotherm of 1 mol of an ideal gas at 298 K, with the initial (i) and final (f) states of an expansion.

An expansion of the gas will happen between P_i and P_f. If the expansion happens in a one-step fast process, for example against external atmospheric pressure, then we can consider such final pressure constant (for example $P_f = P_{\text{ext}} = 1$ bar), and solve the integral as:

$$W_{\text{1-step}} = -\int_i^f P_{\text{ext}} dV = -P_{\text{ext}} \int_i^f dV = -P_{\text{ext}}(V_f - V_i). \tag{2.14}$$

[3] from here on we will replace the notation $\int_{\text{path}}$ with the more convenient $\int$ and we will keep in mind that the integral of an inexact differential must be taken along the path.

Notice how the work is negative, since during an expansion the work is performed by the system (recall the chemistry sign convention). The absolute value of the work[4] represents the red area in figure 2.3:




Figure 2.3.: Work for a one-step expansion against a constant external pressure: the red rectangle under the final pressure.

$$|W_{\text{1-step}}| = P_{\text{ext}}(V_f - V_i) \tag{2.15}$$

If the process happens in two steps by pausing at an intermediate position (1) until equilibrium is reached, then we should calculate the work by dividing it into two separate processes, A and B, and solve each one as we did in the previous case. The first process is an expansion between P_i and P_1, with P_1 constant. The absolute value of the work, W_A, is represented by the blue area in figure 2.4:

$$|W_A| = P_1(V_1 - V_i) \tag{2.16}$$

The second process is an expansion between P_1 and P_f, with $P_f = P_{\text{ext}}$ constant. The absolute value of the work for this second process is represented by the green area in figure 2.5:

$$|W_B| = P_f(V_f - V_1) \tag{2.17}$$

The total absolute value of the work for the 2-step process is given by the sum of the two areas, as in figure 2.6:

[4] we use the absolute value to avoid confusions due to the fact that the expansion work is negative according to Definition 1.1.




Figure 2.4.: Work for the first step of a two-step expansion: the blue rectangle under the intermediate pressure.




Figure 2.5.: Work for the second step of a two-step expansion: the green rectangle under the final pressure.




Figure 2.6.: Total work for the two-step expansion: the sum of the blue and green rectangles.

$$|W_{2\text{-step}}| = |W_A| + |W_B| = P_1(V_1 - V_i) + P_f(V_f - V_1). \tag{2.18}$$

As can be easily verified by comparing the shaded areas in the plots, $|W_{2\text{-step}}| > |W_{1\text{-step}}|$.

We can easily extend this procedure to consider processes that happen in 3, 4, 5, ..., n steps. What is the limit of this procedure? In other words, what happens when $n \to \infty$? A simple answer is given by figure 2.7, which clearly demonstrates that the maximum value of the area underneath the curve $|W_{\max}|$ is achieved in an ∞-step process. In this limit, each step is infinitesimally small, the external pressure is always equal to the pressure of the gas, and we can use eq. 2.10 to calculate the work as:

$$|W_{\infty\text{-step}}| = |W_{\max}| = \sum_{n}^{\infty} P_n(V_n - V_{n-1}) = \int_i^f P dV. \tag{2.19}$$

The integral on the right hand side of eq. 2.19 can be solved for an ideal gas by calculating the pressure using the ideal gas law $P = \frac{nRT}{V}$, and solving the integral since n, R, and T are constant:

$$|W_{\max}| = nRT \int_i^f \frac{dV}{V} = nRT \ln \frac{V_f}{V_i}. \tag{2.20}$$

This example demonstrates why work is a path function. If we perform a fast 1-step expansion, the system will perform an amount of work that is much smaller than the amount of work it can perform if the expansion between the same points happens slowly in an ∞-step process.




Figure 2.7.: Maximum work for the isothermal expansion: the whole area under the isotherm, which is the limit of an expansion performed in more and more steps (6 steps in orange, 30 steps in green, ∞ steps in gray).

The same considerations that we made up to this point for expansion processes apply in reverse to compression ones. The only difference is that the work associated with compressions will have a positive sign since it must be performed onto the system. As such, the amount of work for a transformation that happens in a finite number of steps will be an upper bound to the minimum amount of work required to compress the system.[5] $|W_{\min}|$ for compressions is calculated as the area underneath the PV curve, exactly as $|W_{\max}|$ for expansions in eq. 2.19.

2.5. Chapter Review

2.5.1. Study Questions

1. What does the zeroth law of thermodynamics state?

a. If two systems are each in thermal equilibrium with a third one, then they are in thermal equilibrium with each other.
b. The energy of the universe is conserved.
c. The entropy of the universe increases.
d. Heat always flows from hot to cold objects.
e. The entropy of a perfect crystal is zero at 0 K.

[5] In contrast to a lower bound for expansion processes.

2. A wooden coin and a metal coin are left for a long time in boiling water. What can we say about their temperatures?

a. The metal coin is hotter, because it burns when touched.
b. The wooden coin is hotter, because wood is an insulator.
c. We cannot say anything without a thermometer.
d. They have the same temperature, even if they feel different to the touch.
e. Their temperatures depend on their masses.

---

3. What is the differential definition of the molar heat capacity at constant volume?

a. $C_V = \frac{Q_V}{\Delta T}$.
b. $C_V = \frac{Q_V}{n\,dT}$.
c. $C_V = n\,Q_V\,dT$.
d. $C_V = \frac{dT}{Q_V}$.
e. $C_V = \frac{Q_P}{n\,dT}$.

---

4. How is the heat exchanged at constant pressure calculated, assuming C_P independent of temperature?

a. $Q_P = nC_V\Delta T$.
b. $Q_P = P\Delta V$.
c. $Q_P = nRT\ln\frac{V_f}{V_i}$.
d. $Q_P = 0$.
e. $Q_P = nC_P\Delta T$.

---

5. Why is the work of an expansion negative in the chemistry sign convention?

a. Because the volume decreases.
b. Because the pressure is negative.
c. Because the work is performed by the system, which loses energy.
d. Because the temperature decreases.
e. Because work is a path function.

---

6. What is the work for a one-step expansion against a constant external pressure?

a. $W = -P_{\text{ext}}(V_f - V_i)$.
b. $W = P_{\text{ext}}(V_f - V_i)$.
c. $W = -nRT \ln \frac{V_f}{V_i}$.
d. $W = 0$.
e. $W = nC_V \Delta T$.

---

7. A gas expands isothermally between the same initial and final states in one step, in two steps, or in infinitely many steps. In which case is the absolute value of the work the largest?

a. One step.
b. Two steps.
c. It is the same in all cases.
d. Infinitely many steps.
e. It depends on the gas.

---

8. What is the absolute value of the maximum work for the isothermal expansion of an ideal gas?

a. $|W_{\text{max}}| = P_{\text{ext}} \Delta V$.
b. $|W_{\text{max}}| = nRT \ln \frac{V_f}{V_i}$.
c. $|W_{\text{max}}| = nR\Delta T$.
d. $|W_{\text{max}}| = nC_V \Delta T$.
e. $|W_{\text{max}}| = nRT \frac{V_f}{V_i}$.

---

9. What do the one-step, two-step, and infinitely-many-step expansions demonstrate?

a. That work is a state function.
b. That the temperature changes during an isothermal process.
c. That heat and work are the same thing.
d. That the ideal gas law is not valid.
e. That work depends on how the process is carried out between the same initial and final states.

---

10. How must a compression be performed to require the minimum amount of work?

a. As fast as possible, in one step.
b. In two steps.
c. Infinitely slowly, in infinitely many steps.
d. At constant volume.
e. Against zero external pressure.

Answers

1.a, 2.d, 3.b, 4.e, 5.c, 6.a, 7.d, 8.b, 9.e, 10.c

3. First Law of Thermodynamics

In chapter 2, we learned how to calculate heat and work, and we saw that both of them are path functions: their values depend on how a process is carried out. In this chapter, we will connect heat and work to a state function, the internal energy, and we will see how this connection becomes one of the most fundamental laws of nature, the first law of thermodynamics. Along the way, we will introduce a second state function, the enthalpy, which will be the protagonist of the next chapter.

3.1. Calculation of Internal Energy Changes

Energy is a property of a system that can be either transferred or converted. The internal energy (U) of a system is a thermodynamic state function defined as:

Definition 3.1. *Internal Energy:* The energy contained within the system, excluding kinetic energy and potential energy of motion and position of the system as a whole.

In the absence of chemical transformations, heat and work are the only two forms of energy that thermodynamics is concerned with. Keeping in mind Definition 1.1, which gives the convention for the signs of heat and work, the change in internal energy of a system can be written as:

$$\Delta U = Q + W, \tag{3.1}$$

which we can write in differential form by considering that the internal energy is a state function, as:

$$dU = Q + W, \tag{3.2}$$

which, for processes where the pressure of the system equals the external pressure (as in the slow processes that we discussed in section 2.4, and in processes at constant pressure, where the system is in mechanical equilibrium with the atmosphere), using eq. 2.10 becomes:

$$dU = Q - PdV. \tag{3.3}$$

3.1.1. Internal energy in isothermal processes

To study the behavior of the internal energy in a process at constant temperature ($dT = 0$), James Prescott Joule (1818–1889) created the apparatus depicted in Figure 3.1.




Figure 3.1.: The Joule Expansion Experiment.

The left side of the Joule apparatus's inner chamber is filled with an ideal gas, while a vacuum is created in the right chamber. Both chambers are immersed in a water bath, whose temperature is monitored with a thermometer: if the gas absorbed or released any heat during the experiment, the temperature of the water would change. When the valve between the chambers is opened, the gas expands into the empty chamber and equilibrates. The work associated with the transformation is:

$$W = -P_{\text{ext}} dV = 0, \tag{3.4}$$

since the gas expands into a vacuum, there is nothing for it to push against, and $P_{\text{ext}} = 0$. Thus, any change in internal energy must be due to heat, which can be detected by monitoring the temperature at the beginning, T_i, and at the end of the experiment, T_f. Joule observed that, for a gas behaving ideally, the temperature does not change, $T_i = T_f$. Since the temperature doesn't change, no heat is exchanged, and therefore the internal energy stays constant:

$$dU = Q = 0. \tag{3.5}$$

> Notice that Joule's conclusion is valid only for an ideal gas. If we expand a real gas, we do notice a change in temperature associated with the expansion. A typical example of this behavior is when you use a pressurized spray bottle and release its content for an extended time in the air. The container will typically get colder. We will discuss this behavior in chapter 11 when we will study non-ideal gases.

From this simple experiment, we can conclude that the internal energy of an ideal gas depends only on its temperature.

3.1.2. Internal energy in adiabatic processes

An adiabatic process is defined as a process that happens without the exchange of heat. As such, $Q = 0$, and the work associated with an adiabatic process is equal to the change in internal energy:

$$dU = W = -PdV, \tag{3.6}$$

which can then be calculated using the formulas that we derived in section 2.4. Notice that the work is still a path function: in general, its value depends on the path. However, *along adiabatic paths*, the work is fixed by the change of a state function, so all adiabatic paths connecting the same two states require the same amount of work. Notice also that isothermal and adiabatic are two very different processes. While an adiabatic process happens without the exchange of heat across the system's boundaries, this does not mean that the system's temperature does not change. Isothermal processes are usually associated with a heat transfer across the boundaries to maintain the temperature of the system constant. For adiabatic processes, it is quite the opposite since they are usually associated with a change in temperature.

3.1.3. Internal energy in isochoric processes

An isochoric process is a process in which the volume does not change. Therefore, $W = 0$, and $dU = Q_V$, which using eq. 2.1, becomes:

$$dU = Q_V = nC_V dT. \tag{3.7}$$

Since no work is performed at these conditions, the heat exchanged is equal to the change of a state function, ΔU. Once again, heat is still a path function in general, but *along constant-volume paths* its value is fixed by the initial and final states only. Eq. 3.7 also gives a mathematical justification of the concept of heat capacity at constant volume. C_V can now be interpreted as the partial derivative (a coefficient) of a state function (the internal energy):

$$C_V = \left(\frac{\partial U}{\partial T}\right)_{V,n=1}, \tag{3.8}$$

where we have replaced the total derivative d with a partial one ∂, and we have specified that the differentiation happens at constant volume and number of moles. Eq. 3.8 brings a rigorous definition of heat capacity at constant volume for 1 mol of substance:

Definition 3.2. *The heat capacity of a substance, C_V, represents its ability to absorb **energy** at constant **volume**.*

3.1.4. Internal energy in isobaric processes

In an isobaric process, the pressure does not change, hence $dP = 0$. Unfortunately, eq. 3.2 for this case does not simplify further, as happened in the two previous cases. However, in section 2.3.2, we have introduced the useful concept of heat capacity at constant P. C_P was used in an isobaric process in the same manner as C_V was used in the isochoric case. That is, as a coefficient to measure the amount of heat absorbed at constant pressure. Eq. 3.8 gave a mathematical definition of C_V as the partial derivative of a state function (the internal energy). But if heat capacities are coefficients, and coefficients are partial derivatives of state functions, how do we explain C_P? In order to do so, we can introduce a new state function, called the enthalpy (H), as:

$$H = U + PV, \tag{3.9}$$

and its differential, calculated as:

$$dH = dU + d(PV) = dU + PdV + \overbrace{VdP}^{0}, \tag{3.10}$$

which can be rearranged as:

$$dU = dH - PdV. \tag{3.11}$$

Replacing eq. 3.11 into eq. 3.3:

$$dH - PdV = Q_P - PdV, \tag{3.12}$$

which simplifies to:

$$dH = Q_P = nC_P dT. \tag{3.13}$$

Eq. 3.13 establishes that the heat exchanged at constant pressure is equal to a new state function called the enthalpy, defined by eq. 3.9. It also establishes a mathematical justification of the concept of heat capacity at constant pressure. Similarly to C_V, C_P can now be interpreted as the partial derivative (a coefficient) of the new state function (the enthalpy):

$$C_P = \left(\frac{\partial H}{\partial T}\right)_{P,n=1}, \tag{3.14}$$

Eq. 3.14 brings also a rigorous definition of heat capacity at constant pressure for 1 mol of substance:

Definition 3.3. *The heat capacity of a substance, C_P, represents its ability to absorb* ***enthalpy*** *at constant* ***pressure****.*

3.2. The First Law of Thermodynamics

We finally come to a working definition of the first law. If we take an isolated system—i.e., a system that exchanges neither energy nor mass with its surroundings—its internal energy is conserved. If the internal energy is conserved, $dU = 0$. Therefore, for an isolated system:

$$Q = -W, \tag{3.15}$$

and heat and work can be easily calculated using any of the appropriate formulas introduced in either section 2.4 or section 2.3.

The first law is a conservation law. It is intuitive since it comes directly from Lavoisier's principle of "nothing is lost, nothing is created, everything is transformed." Considering that the only system that is truly isolated is the universe, we can condense the first law in one simple sentence:

Definition 3.4. *First Law of Thermodynamics:* The energy of the universe is conserved.

3.3. Reversible and Irreversible processes

Let's now consider the cycle in Figure 3.2. The process in this case starts from state 1 (system at P_1V_1), expands to state 2 (system at P_2V_2), and compresses back to state 1 (system back to P_1V_1).




Figure 3.2.: Expansion/Compression Cycle of an Ideal Gas.

Since the process starts and finishes at the same state, the value of the internal energy at the end of the process will be the same as its value at the beginning, regardless of the path:[1]

$$\oint dU = 0, \tag{3.16}$$

where the symbol $\oint$ indicates an integral around a cycle. Considering the work associated with the cycle, however, the situation is radically different because it depends on the path that the system is taking, and in general

$$\oint_{\text{path}} W \neq 0. \tag{3.17}$$

For instance, if we perform the expansion in one step, the work associated with it will be (using eq. 2.14):[2]

$$W_{\text{1-step}}^{\text{expansion}} = -P_2(\underbrace{V_2 - V_1}_{>0}) < 0, \tag{3.18}$$

[1] recall that the internal energy is a state function, so its value depends exclusively on the conditions at the beginning and at the end. In a cycle, we're going back to the same point, so the conditions at the beginning and at the end are equal by definition.
[2] notice that the work for the expansion is negative, as it should be.

and if we also perform the compression in 1-step:[3]

$$W_{\text{1-step}}^{\text{compression}} = -P_1(\underbrace{V_1 - V_2}_{<0}) > 0. \tag{3.19}$$

With a little bit of math, it is easy to prove that the total work for the entire cycle is:

$$\begin{aligned} W_{\text{1-step}}^{\text{cycle}} &= W_{\text{1-step}}^{\text{expansion}} + W_{\text{1-step}}^{\text{compression}} \\ &= -P_2(V_2 - V_1) - P_1(V_1 - V_2) \\ &= -P_2(V_2 - V_1) + P_1(V_2 - V_1) \\ &= (\underbrace{V_2 - V_1}_{>0})(\underbrace{P_1 - P_2}_{>0}) > 0, \end{aligned} \tag{3.20}$$

or, in other words, the surroundings have to put more work into the compression than they get back from the expansion. Since the gas returns to its initial state, $\oint dU = 0$, and this extra work must leave the system as heat. The energy is not destroyed, but part of the work has been degraded into heat.

> In practice, if we want to manually perform this cycle by pushing on the piston by hand, we will notice that it requires more energy to push down than the amount it gives back when we release it, and it moves back up.

In contrast, if both the expansion and the compression happen in a slow ∞-step manner, the work associated with them will be W_{max} and W_{min}, respectively, which are calculated using eq. 2.20. The total work related to the cycle will be in this case:

$$\begin{aligned} W_{\infty\text{-step}}^{\text{cycle}} &= W_{\text{max}}^{\text{expansion}} + W_{\text{min}}^{\text{compression}} \\ &= -nRT \ln \frac{V_f}{V_i} - nRT \ln \frac{V_i}{V_f} \\ &= -nRT \underbrace{\left(\ln \frac{V_f}{V_i} - \ln \frac{V_f}{V_i} \right)}_{=0} = 0, \end{aligned} \tag{3.21}$$

which means that, in this case, the work obtained from the expansion is exactly the work needed for the compression, and no work is degraded into heat.

[3] notice that the work for the compression is positive, as it should be.

> In practice, if we were able to perform this cycle manually by pushing the piston down by hand, we would notice that it requires the same amount of energy to push down as the amount it gives back when it moves up.

This process can happen both ways without losses, and is called *reversible*:

Definition 3.5. *Reversible process:* A process whose direction can be inverted at any moment by an infinitesimally small change in the conditions of the surroundings (for example, an infinitesimally small increase of the external pressure), so that the system goes back through exactly the same states.[4]

A few important considerations can be made by analyzing Definition 3.5:

1. **A reversible process is infinitely slow.** It happens in an infinite number of infinitesimal steps, and at each step the system is in equilibrium with its surroundings (for example, $P = P_{\text{ext}}$ at every moment).
2. **A reversible process is the most efficient one.** A reversible expansion gives the maximum work, W_{max}, and a reversible compression requires the minimum work, W_{min}. Running a reversible process forward and then backward leaves no trace, neither in the system nor in the surroundings.
3. **All real processes are irreversible.** Reversible processes are idealizations, like the ideal gas. We can approach them by carrying out a process very slowly, but never reach them. Despite this, they are extremely useful, since they set the limits that real processes can only approach.

3.4. Chapter Review

3.4.1. Study Questions

1. What is the internal energy of a system?

a. The kinetic energy of the system as a whole.
b. The energy contained within the system, excluding the kinetic and potential energy of the system as a whole.
c. The heat stored in the system.
d. The work that the system can perform.

[4] Adapted from: Sears, F.W. and Salinger, G.L. (1986), Thermodynamics, Kinetic Theory, and Statistical Thermodynamics, 3rd edition (Addison-Wesley).

e. The potential energy of the system in a gravitational field.

---

2. What is the first law of thermodynamics in differential form for a closed system?

a. $dU = Q + W$.
b. $dU = Q - W$.
c. $dU = TdS$.
d. $dU = 0$ always.
e. $dU = PdV$.

---

3. What did Joule conclude from the expansion of an ideal gas into a vacuum?

a. The gas cools down during the expansion.
b. The gas performs work on the surroundings.
c. Heat flows into the gas.
d. The internal energy of an ideal gas depends only on its temperature.
e. The internal energy of an ideal gas depends on its volume.

---

4. What characterizes an adiabatic process?

a. The temperature is constant.
b. The volume is constant.
c. The pressure is constant.
d. The internal energy is constant.
e. No heat is exchanged, so $dU = W$.

---

5. How does the internal energy change in an isochoric process?

a. $dU = -PdV$.
b. $dU = 0$.
c. $dU = nC_V dT$.
d. $dU = nC_P dT$.
e. $dU = W$.

---

6. How can the heat capacity at constant volume be written as a derivative of a state function?

a. $C_V = \left(\frac{\partial U}{\partial T}\right)_V$ (for 1 mol).
b. $C_V = \left(\frac{\partial H}{\partial T}\right)_P$ (for 1 mol).
c. $C_V = \left(\frac{\partial U}{\partial V}\right)_T$.
d. $C_V = \left(\frac{\partial T}{\partial U}\right)_V$.
e. $C_V = \left(\frac{\partial P}{\partial T}\right)_V$.

---

7. What is the definition of enthalpy?

a. $H = U - PV$.
b. $H = U + TS$.
c. $H = Q + W$.
d. $H = U + PV$.
e. $H = U - TS$.

---

8. To which quantity is the heat exchanged at constant pressure equal?

a. The change in internal energy, ΔU.
b. The change in enthalpy, ΔH.
c. The work, W.
d. Zero.
e. The change in temperature, ΔT.

---

9. An ideal gas is expanded in one step and then compressed back in one step. What is the total work of this cycle?

a. Zero, since the gas returns to its initial state.
b. Negative, since net work is performed by the gas.
c. It is equal to the change in internal energy.
d. It cannot be calculated.
e. Positive, since more work is spent compressing the gas than is obtained from the expansion.

---

10. What is the total work of an expansion–compression cycle of an ideal gas performed reversibly, in infinitely many steps, at constant temperature?

a. Positive.
b. Negative.
c. Zero.
d. Infinite.
e. Equal to nRT.

Answers

1.b, 2.a, 3.d, 4.e, 5.c, 6.a, 7.d, 8.b, 9.e, 10.c

4. Thermochemistry

In chapter 3, we have discussed thermodynamical changes in energy in the absence of chemical reactions. When a chemical reaction takes place, some bonds break and some new ones form. Breaking a bond always requires energy, while forming a bond always releases energy. The balance between the energy spent to break the bonds of the reactants and the energy released when the bonds of the products form determines whether the reaction, overall, absorbs or releases energy.[1] For a proper thermodynamic treatment of the system, this extra energy must be included in the net balance.

4.1. Reaction Enthalpies

In this chapter, we will consider the heat associated with chemical reactions. Since most chemical reactions happen at constant atmospheric pressure (isobaric conditions) in the lab, we can use eq. 3.13 to replace the inexact differential of the heat with the exact differential of the state function called enthalpy. The advantage of this transformation is that it allows us to study the heat associated with chemical reactions at constant pressure independently of their path. If we call the molecules at the beginning of the reaction "reactants" and the molecules at the end of the reaction "products," the heat associated with the reaction (rxn) is defined as:

$$\Delta_{\text{rxn}} H = H_{\text{products}} - H_{\text{reactants}} \, . \tag{4.1}$$

For example, if we take a simple reaction of the form:

$$\text{A} + \text{B} \rightarrow \text{C} + \text{D},$$

the heat at constant pressure is equal to the enthalpy of reaction, which is calculated as:

[1] A common misconception is that energy is "stored" in chemical bonds and released when they break. It is the opposite: a bond is a more stable (lower-energy) arrangement than the separated atoms, so breaking it always costs energy. Fuels release energy when they burn because the bonds that form in the products (for example, in CO_2 and H_2O) are, overall, stronger than the ones broken in the reactants.

$$Q_P = \Delta_{\text{rxn}}H = \underbrace{(H_{\text{C}} + H_{\text{D}})}_{\text{products}} - \underbrace{(H_{\text{A}} + H_{\text{B}})}_{\text{reactants}}. \tag{4.2}$$

Using the chemistry sign convention, Definition 1.1, reactions are classified in terms of the sign of their reaction enthalpies as follows:

Definition 4.1.

- $\Delta_{\text{rxn}}H > 0 \Rightarrow$ *Endothermic reaction* (heat is gained by the system).
- $\Delta_{\text{rxn}}H < 0 \Rightarrow$ *Exothermic reaction* (heat is lost by the system).

If we expand the sample reaction to account for its stoichiometry:

$$a\text{A} + b\text{B} \rightarrow c\text{C} + d\text{D}\ ,$$

where a, b, c, d are the stoichiometric coefficients of species $\text{A}, \text{B}, \text{C}, \text{D}$. Eq. 4.2 can be rewritten as:

$$Q_P = \Delta_{\text{rxn}}H = \underbrace{(cH_{\text{C}} + dH_{\text{D}})}_{\text{products}} - \underbrace{(aH_{\text{A}} + bH_{\text{B}})}_{\text{reactants}}, \tag{4.3}$$

while for the most general case we can write it:

$$\Delta_{\text{rxn}}H = \sum_i \nu_i H_i, \tag{4.4}$$

where ν_i is the stoichiometric coefficient of species i with its own sign. The signs of the stoichiometric coefficients are defined according to eq. 4.3 as:

Definition 4.2. *Signs of the stoichiometric coefficients:*

- ν_i is **positive** if i is a **product**.
- ν_i is **negative** if i is a **reactant**.

4.2. Standard Enthalpies of Formation

In principle, we could use eq. 4.3 to calculate the reaction enthalpy associated with any reaction. However, to do so, the absolute enthalpies H_i of reactants and products would be required. Unfortunately, absolute enthalpies are not known—and theoretically unknowable, since this would require an absolute zero for the enthalpy scale, which does not exist.[2] To prevent this problem, enthalpies relative to a defined reference state must be used. This reference state is defined as the constituent elements in their standard state, and the enthalpies of 1 mol of substance in this reference state are called **standard enthalpies of formation**.

Definition 4.3. The *standard enthalpy of formation* of compound i, $\Delta_\mathrm{f}H_i^\ominus$, is the change of enthalpy during the formation of 1 mol of i from its constituent elements, with all substances in their standard states.

The standard pressure is defined at $P^\ominus = 100$ kPa $= 1$ bar.[3] Strictly speaking, there is no standard temperature, but standard enthalpies of formation are usually reported at room temperature, $T = 298.15$ K. Standard states are indicated with the symbol $\ominus$ and they are defined for elements as the form in which such element is most stable at standard pressure (for example, for hydrogen, carbon, and oxygen the standard states are $\mathrm{H}_{2(g)}$, $\mathrm{C}_{(s,\text{graphite})}$, and $\mathrm{O}_{2(g)}$, respectively).[4]

For example, the standard enthalpies of formation of some common compounds at $T = 298.15$ K are calculated from the following reactions:

$$\begin{aligned}
\mathrm{C}_{(s,\text{graphite})} + \mathrm{O}_{2(g)} &\rightarrow \mathrm{CO}_{2(g)} & \Delta_\mathrm{f}H^\ominus_{\mathrm{CO}_{2(g)}} &= -394 \text{ kJ/mol} \\
\mathrm{C}_{(s,\text{graphite})} + 2\mathrm{H}_{2(g)} &\rightarrow \mathrm{CH}_{4(g)} & \Delta_\mathrm{f}H^\ominus_{\mathrm{CH}_{4(g)}} &= -75 \text{ kJ/mol} \\
\mathrm{H}_{2(g)} + \frac{1}{2}\mathrm{O}_{2(g)} &\rightarrow \mathrm{H_2O}_{(l)} & \Delta_\mathrm{f}H^\ominus_{\mathrm{H_2O}_{(l)}} &= -286 \text{ kJ/mol}
\end{aligned} \tag{4.5}$$

A comprehensive list of standard enthalpies of formation of inorganic and organic compounds is also reported in Appendix A.

[2] An example of a known absolute zero for a scale is the zero of the temperature scale, a temperature that can be approached only as a limit from above. No such thing exists for the enthalpy.

[3] prior to 1982 the value of $P^\ominus = 1.0$atm was used. The two values of $P^\ominus$ are within 1% of each other, since 1 atm = 101.325 kPa.

[4] There are some exceptions, such as phosphorus, for which the most stable form at 1 bar is black phosphorus, but white phosphorus is chosen as the standard reference state for zero enthalpy of formation. For the purposes of this course, however, we can safely ignore them.

4.3. Hess's Law

The calculation of a standard reaction enthalpy can be performed using the following cycle:

$$\begin{array}{ccc} \text{reactants} & \xrightarrow{\Delta_{\text{rxn}}H^{\ominus}} & \text{products} \\ -\Delta_{\text{f}}H^{\ominus}_{\text{reactants}} \downarrow & & \uparrow \Delta_{\text{f}}H^{\ominus}_{\text{products}} \\ \multicolumn{3}{c}{\text{"elements in their standard reference state"}} \end{array} \tag{4.6}$$

This process is summarized by the simple formula:

$$\Delta_{\text{rxn}}H^{\ominus} = \Delta_{\text{f}}H^{\ominus}_{\text{products}} - \Delta_{\text{f}}H^{\ominus}_{\text{reactants}}. \tag{4.7}$$

Notice how there is a negative sign in front of the enthalpy of formation of the reactants because they are normally defined for the reactions that go from the elements to the reactants and not vice-versa. To close the cycle in eq. 4.6, however, we should go from the reactants to the elements, and therefore we must invert the sign in front of the formation enthalpies of the reactants. Eq. 4.7 can be generalized using the same technique used to derive eq. 4.4, resulting in:

$$\Delta_{\text{rxn}}H^{\ominus} = \sum_i \nu_i \Delta_{\text{f}}H^{\ominus}_i, \tag{4.8}$$

which is a mathematical expression of the law that is known as **Hess's Law**. Hess's law is valid at constant pressure because, at those conditions, the heat of reaction—a path function—is equal to the enthalpy of reaction—a state function. Therefore, the enthalpy of a reaction depends exclusively on the initial and final state, and it can be obtained via the pathway that passes through the elements in their standard state (the formation pathway).

Exercise 4.1. Calculate the standard enthalpy of combustion at 298 K of 1 mol of methane, using the data in eq. 4.5.

Solution: The reaction that is under consideration is:

$$\text{CH}_{4(g)} + 2\text{O}_{2(g)} \rightarrow \text{CO}_{2(g)} + 2\text{H}_2\text{O}_{(l)} \qquad \Delta_{\text{rxn}}H^{\ominus} = ?$$

Using Hess's Law, eq. 4.8, the enthalpy of combustion of methane is:

$$\Delta_{\text{rxn}}H^{\ominus} = \Delta_{\text{f}}H^{\ominus}_{\text{CO}_{2(g)}} + 2\Delta_{\text{f}}H^{\ominus}_{\text{H}_2O_{(l)}} - \Delta_{\text{f}}H^{\ominus}_{\text{CH}_{4(g)}} - 2\underbrace{\Delta_{\text{f}}H^{\ominus}_{\text{O}_{2(g)}}}_{=0}$$

whose values are reported in eq. 4.5. Notice that the formation enthalpy of $O_{2(g)}$ is zero, since it is an element in its standard state. The final result is:

$$\Delta_{\text{rxn}}H^{\ominus} = \overbrace{-394}^{\Delta_{\text{f}}H^{\ominus}_{\text{CO}_{2(g)}}} + 2\overbrace{(-286)}^{\Delta_{\text{f}}H^{\ominus}_{\text{H}_2O_{(l)}}} - \overbrace{(-75)}^{\Delta_{\text{f}}H^{\ominus}_{\text{CH}_{4(g)}}} = -891 \text{ kJ/mol}.$$

where the negative sign indicates that the reaction is exothermic (see definition 4.1), as we should expect. The cycle that we used to solve this exercise can be summarized as:

$$\begin{array}{ccc} \text{CH}_{4(g)} + 2\text{O}_{2(g)} & \xrightarrow{\Delta_{\text{rxn}}H^{\ominus}} & \text{CO}_{2(g)} + 2\text{H}_2\text{O}_{(l)} \\ {\scriptstyle -\Delta_{\text{f}}H^{\ominus}_{\text{CH}_{4(g)},\text{O}_{2(g)}}}\searrow & & \nearrow{\scriptstyle \Delta_{\text{f}}H^{\ominus}_{\text{CO}_{2(g)},\text{H}_2\text{O}_{(l)}}} \\ & \text{H}_{2(g)}, \text{C}_{(s,\text{graphite})}, \text{O}_{2(g)} & \end{array}$$

Notice that at standard pressure and $T = 298$ K water is in liquid form. However, when we burn methane, the heat associated with the exothermic reaction immediately vaporizes the water. Substances in different states of matter have different formation enthalpies, and $\Delta_{\text{f}}H^{\ominus}_{\text{H}_2O_{(g)}} = -242$ kJ/mol. The difference between the formation enthalpies of the same substance in different states represents the latent heat that separates them. For example, for water:

$$\begin{aligned} \Delta_{\text{vap}}H^{\ominus}_{\text{H}_2O} &= \Delta_{\text{f}}H^{\ominus}_{\text{H}_2O_{(g)}} - \Delta_{\text{f}}H^{\ominus}_{\text{H}_2O_{(l)}} \\ &= (-242) - (-286) = +44 \text{ kJ/mol} \end{aligned}$$

which is the latent heat of vaporization for water, $\Delta_{\text{vap}}H^{\ominus}_{\text{H}_2O}$. The latent heat is positive to indicate that the system absorbs energy in going from the liquid to the gaseous state (and it will release energy when going the opposite direction from gas to liquid).

4.4. Calculations of Enthalpies of Reaction at $T \neq 298$ K

Standard enthalpies of formation are usually reported at room temperature ($T = 298$ K), but enthalpies of formation at any temperature T' can be calculated from the values at 298 K using eq. 2.4 and eq. 3.13:

$$dH = C_P dT \rightarrow \int_{H^{\ominus}_{T=298}}^{H_{T'}} dH = \int_{T=298}^{T'} C_P dT$$

$$H^{\ominus}_{T'} - H^{\ominus}_{T=298} = \int_{T=298}^{T'} C_P dT \tag{4.9}$$

$$H^{\ominus}_{T'} = H^{\ominus}_{T=298} + \int_{T=298}^{T'} C_P dT,$$

which, in conjunction with Hess's Law, eq. 4.8, results in:

$$\Delta_{\text{rxn}} H^{\ominus}_{T'} = \Delta_{\text{rxn}} H^{\ominus}_{T=298} + \int_{T=298}^{T'} \Delta C_P dT, \tag{4.10}$$

with $\Delta C_P = \sum_i \nu_i C_{P,i}$.

Exercise 4.2. Calculate $\Delta_{\text{rxn}} H$ of the following reaction at 398 K, knowing that $\Delta_{\text{rxn}} H^{\ominus}$ at 298 K is -283.0 kJ/mol, and the following C_P values: $CO_{(g)}$ = 29 J/(mol K), $O_{2(g)}$ = 30 J/(mol K), $CO_{2(g)}$ = 38 J/(mol K):

$$CO_{(g)} + \frac{1}{2} O_{2(g)} \rightarrow CO_{2(g)},$$

Solution: Using eq. 4.10 we obtain:

$$\Delta_{\text{rxn}} H^{398} = \overbrace{-283.0}^{\Delta_{\text{rxn}} H^{\ominus}} + \int_{298}^{398} (\overbrace{38}^{C_P^{CO_2}} - \overbrace{29}^{C_P^{CO}} - \frac{1}{2} \overbrace{30}^{C_P^{O_2}}) \times 10^{-3} dT,$$

which, assuming that the heat capacities do not depend on the temperature, becomes:

$$\begin{aligned} \Delta_{\text{rxn}} H^{398} &= -283.0 + \left(38 - 29 - \frac{1}{2} 30\right) \times 10^{-3} (398 - 298) \\ &= -283.6 \text{ kJ/mol}. \end{aligned}$$

As we notice from this result, a difference in temperature of 100 K translates into a change in $\Delta_{\text{rxn}} H^{\ominus}$ of this reaction of only 0.6 kJ/mol. This is a trend that is often observed, and values of $\Delta_{\text{rxn}} H$ are very weakly dependent on changes in temperature for most chemical reactions. This numerical result can also be compared with the amount that is experimentally measured for $\Delta_{\text{rxn}} H^{398}$ of this reaction, which is –283.67 kJ/mol. This comparison strongly supports the assumption that we used to solve the integral in eq. 4.10, confirming that the heat capacities are mostly independent of temperature.

4.5. Chapter Review

4.5.1. Study Questions

1. What characterizes an endothermic reaction?

a. $\Delta_{\text{rxn}}H < 0$, and heat is released by the system.
b. $\Delta_{\text{rxn}}H = 0$.
c. $\Delta_{\text{rxn}}H > 0$, and heat is gained by the system.
d. The reaction is always spontaneous.
e. The reaction happens at constant volume.

---

2. What is the sign convention for the stoichiometric coefficients ν_i?

a. Positive for products and negative for reactants.
b. Positive for reactants and negative for products.
c. Always positive.
d. Positive for gases and negative for liquids.
e. Positive for elements and negative for compounds.

---

3. What is the standard enthalpy of formation of a compound?

a. The enthalpy of the compound at 0 K.
b. The enthalpy change when 1 mol of the compound is decomposed into atoms.
c. The heat released when the compound burns in oxygen.
d. The absolute enthalpy of the compound at 298 K.
e. The enthalpy change when 1 mol of the compound is formed from its elements, with all substances in their standard states.

---

4. What is the standard pressure used in thermodynamic tables?

a. 0 bar.
b. 1 bar.
c. 1 atm exactly.
d. 10 bar.

e. It depends on the substance.

---

5. What is the standard enthalpy of formation of $O_{2(g)}$?

a. -286 kJ/mol.
b. -394 kJ/mol.
c. $+498$ kJ/mol.
d. 0 kJ/mol, since it is an element in its standard state.
e. It cannot be measured.

---

6. Which formula expresses Hess's law?

a. $\Delta_{\mathrm{rxn}} H^{\ominus} = \sum_i \nu_i \Delta_{\mathrm{f}} H_i^{\ominus}$.
b. $\Delta_{\mathrm{rxn}} H^{\ominus} = \sum_i \Delta_{\mathrm{f}} H_i^{\ominus}$.
c. $\Delta_{\mathrm{rxn}} H^{\ominus} = \prod_i \nu_i \Delta_{\mathrm{f}} H_i^{\ominus}$.
d. $\Delta_{\mathrm{rxn}} H^{\ominus} = Q_V$.
e. $\Delta_{\mathrm{rxn}} H^{\ominus} = \sum_i \nu_i S_i^{\ominus}$.

---

7. Why can Hess's law be used to calculate reaction enthalpies?

a. Because all reactions are exothermic.
b. Because heat is a state function.
c. Because the enthalpy is a state function, so its change does not depend on the path.
d. Because all reactions happen at standard conditions.
e. Because enthalpies of formation are always negative.

---

8. What does the difference between the enthalpies of formation of $H_2O_{(g)}$ and $H_2O_{(l)}$ represent?

a. The enthalpy of formation of water.
b. The heat capacity of water.
c. The enthalpy of combustion of hydrogen.
d. Zero, since they are the same substance.
e. The enthalpy (latent heat) of vaporization of water.

---

9. How can a reaction enthalpy at a temperature T' be calculated from its value at 298 K?

a. $\Delta_{\text{rxn}}H_{T'} = \Delta_{\text{rxn}}H_{298} \cdot \frac{T'}{298}$.
b. $\Delta_{\text{rxn}}H_{T'} = \Delta_{\text{rxn}}H_{298} + \int_{298}^{T'} \Delta C_P \, dT$.
c. $\Delta_{\text{rxn}}H_{T'} = \Delta_{\text{rxn}}H_{298}$ always.
d. $\Delta_{\text{rxn}}H_{T'} = \Delta_{\text{rxn}}H_{298} - T'\Delta S$.
e. $\Delta_{\text{rxn}}H_{T'} = \int_{298}^{T'} C_P \, dT$.

---

10. What did the calculation for the oxidation of CO at 398 K show about the temperature dependence of reaction enthalpies?

a. Reaction enthalpies double every 100 K.
b. Reaction enthalpies change sign above 298 K.
c. Reaction enthalpies cannot be calculated above 298 K.
d. Reaction enthalpies usually depend only weakly on temperature.
e. Reaction enthalpies are zero at high temperature.

Answers

1.c, 2.a, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

5. Thermodynamic Cycles

The first law of thermodynamics places no restrictions on the conversion of energy from one form to another. For example, let's consider once again the Joule experiment (Figure 3.1). If we design a cycle that goes from the gas on the left chamber only to the gas equilibrated in both chambers and backward, as in Figure 5.1, there are no restrictions imposed on this hypothetical cycle by the first law.




Figure 5.1.: Closing the Cycle in The Joule Expansion Experiment.

As we saw in section 3.1.1, states 1 and 2 have exactly the same energy at constant temperature. Restricting the analysis to the information contained in the first law, the ideal gas could hypothetically go from state 1 (all gas in the left chamber) to state 2 (gas in both chambers), as well as spontaneously close the cycle back from state 2 to state 1, without external intervention. While the transformation from $1 \rightarrow 2$ is intuitively spontaneous (it's the same transformation that we considered in section 3.1.1), the backward transformation from $2 \rightarrow 1$ is clearly not as intuitive. In this case, the gas should spontaneously compress back to the left side, leaving a vacuum on the right chamber, without interventions from the outside. This transformation is clearly never observed. A gas just does not spontaneously

concentrate on one side of a room, leaving a vacuum on the other side. In fact, when we need to create a vacuum, a lot of energy must be spent. Suppose we use exclusively information contained in the first law. In this case, there is nothing that might suggest a system's preference to perform the transformation $1 \to 2$, while preventing the $2 \to 1$ from happening spontaneously. Both states have the same energy, and

$$\oint dU = 0. \tag{5.1}$$

James Joule himself was indeed convinced that this must be the case and that we don't observe the backward transformation in practice only because we cannot build ideal machines.[1] Another scientist of that era was not convinced. William Thomson, the 1st Baron Kelvin (1824–1907), was unsure about this idea, and invested substantial resources to try to prove Joule wrong.[2]

The key to resolving the controversy, in favor of Kelvin, came from an unexpected source: the theoretical work of the French military engineer Nicolas Léonard Sadi Carnot (1796–1832), published years before Joule and Kelvin started working on this problem, and largely forgotten until Kelvin and Rudolf Clausius built on it in the late 1840s and 1850s.[3] At that time, the importance of steam engines was growing for industrial applications, but a theoretical perspective was lacking. Carnot was convinced that a scientific understanding of heat engines was necessary to improve their efficiency.

5.1. Carnot Cycle

The main contribution of Carnot to thermodynamics is his abstraction of the steam engine's essential features into a more general and idealized heat engine. The definition of Carnot's idealized cycle is as follows:

Definition 5.1. A *Carnot cycle* is an idealized process composed of two isothermal and two adiabatic transformations. Each transformation is either an expansion or a compression of an *ideal gas*. All transformations are assumed to be *reversible*, and no energy is lost to mechanical friction.

[1] Either because we don't really have ideal gases, or because we are unable to construct mechanical devices without loss, or in general because of other experimental factors.

[2] Interestingly enough, both Joule and Lord Kelvin are now recognized as key figures in the development of thermodynamics and science in general. So much so, that the energy unit and the temperature unit in the SI system are named after them.

[3] Carnot's lone book, the *Réflexions sur la Puissance Motrice du Feu* ("Reflections on the Motive Power of Fire") was published in France in 1824, the same year Kelvin was born and just 6 years after Joule's birth.

A Carnot cycle connects two "heat reservoirs" at temperatures T_h (hot) and T_l (low), respectively. The reservoirs have a large thermal capacity so that their temperatures are unaffected by the cycle. The system is composed exclusively of the ideal gas, which is the only substance that changes temperature throughout the cycle. If we report the four transformations of a Carnot cycle on a PV diagram, we obtain the following plot:




Figure 5.2.: PV-Diagram of a Carnot Cycle (computed for 1 mol of a monatomic ideal gas between $T_h = 600$ K and $T_l = 300$ K).

5.1.1. Stage 1: isothermal expansion $A \to B$




Figure 5.3.: Stage 1 of a Carnot cycle: isothermal expansion. The cylinder is in contact with the hot reservoir, from which the gas absorbs the heat $|Q_h|$.

Starting the analysis of the cycle from point A in Figure 5.2, (figure 5.3)(https://en.wikipedia.org/wiki/Carnot_cycle), and have been generated and distributed by Author BlyumJ under CC-BY-SA license.]

the first transformation we encounter is an isothermal expansion at T_h. Since the transformation is isothermal:

$$\Delta U_1 = \overset{<0}{\widetilde{W_1}} + \overset{>0}{\widetilde{Q_1}} = 0 \Rightarrow Q_1 = -W_1, \tag{5.2}$$

and heat and work can be calculated for this stage using eq. 2.20:

$$\begin{aligned} Q_1 = |Q_h| &= nRT_h \overbrace{\ln \frac{V_B}{V_A}}^{>0 \text{ since } V_B > V_A} > 0, \\ W_1 &= -Q_1 = -nRT_h \ln \frac{V_B}{V_A} < 0, \end{aligned} \tag{5.3}$$

where we denoted $|Q_h|$ the absolute value of the heat that gets **into** the system from the hot reservoir.

5.1.2. Stage 2: adiabatic expansion $B \to C$




Figure 5.4.: Stage 2 of a Carnot cycle: adiabatic expansion. The cylinder is insulated, no heat is exchanged, and the gas cools down while it keeps expanding.

The second transformation is an adiabatic expansion between T_h and T_l. Since we are at adiabatic conditions:

$$Q_2 = 0 \Rightarrow \Delta U_2 = W_2, \tag{5.4}$$

and the negative energy (expansion work) can be calculated using:

$$\Delta U_2 = W_2 = n \underbrace{\int_{T_h}^{T_l} C_V dT}_{<0 \text{ since } T_l<T_h} < 0. \tag{5.5}$$

5.1.3. Stage 3: isothermal compression $C \to D$




Figure 5.5.: Stage 3 of a Carnot cycle: isothermal compression. The cylinder is in contact with the cold reservoir, to which the gas releases the heat $|Q_l|$.

The third transformation is an isothermal compression at T_l. The formulas are the same as those used for stage 1, but they will result in heat and work with reversed signs (since this is a compression):

$$\Delta U_3 = \overset{>0}{\widetilde{W_3}} + \overset{<0}{\widetilde{Q_3}} = 0 \Rightarrow Q_3 = -W_3, \tag{5.6}$$

and:

$$\begin{aligned} Q_3 &= -|Q_l| = nRT_l \overbrace{\ln \frac{V_D}{V_C}}^{<0 \text{ since } V_D<V_C} < 0, \\ W_3 &= -Q_3 = -nRT_l \ln \frac{V_D}{V_C} > 0, \end{aligned} \tag{5.7}$$

where $|Q_l|$ is the absolute value of the heat that gets **out of** the system to the cold reservoir ($Q_3 = -|Q_l|$ being the heat entering the system).




Figure 5.6.: Stage 4 of a Carnot cycle: adiabatic compression. The cylinder is insulated again, and the compression warms the gas back to its initial temperature.

5.1.4. Stage 4: adiabatic compression $D \to A$

The fourth and final transformation is an adiabatic compression that restores the system to point A, bringing it from T_l to T_h. Similarly to stage 2:

$$Q_4 = 0 \Rightarrow \Delta U_4 = W_4, \tag{5.8}$$

since we are at adiabatic conditions. The energy associated with this process is now positive (compression work), and can be calculated using:

$$\Delta U_4 = W_4 = n \underbrace{\int_{T_l}^{T_h} C_V dT}_{>0 \text{ since } T_\mathrm{h} > T_\mathrm{l}} > 0. \tag{5.9}$$

Notice how $\Delta U_4 = -\Delta U_2$ because $\int_x^y = -\int_y^x$.

5.2. Energy, Heat, and Work in the Carnot Cycle

Summarizing the results of the previous sections, the total amount of energy for a Carnot cycle is:

$$\begin{aligned}\Delta U_{\mathrm{TOT}} &= \Delta U_1 + \Delta U_2 + \Delta U_3 + \Delta U_4 \\ &= 0 + n\int_{T_h}^{T_l} C_V dT + 0 + n\int_{T_l}^{T_h} C_V dT \\ &= n\int_{T_h}^{T_l} C_V dT - n\int_{T_h}^{T_l} C_V dT = 0\end{aligned} \tag{5.10}$$

which is zero, as it must be for any cycle, since $\oint dU = 0$. Notice how the result comes about: the two isothermal stages do not change the energy of an ideal gas, while the energy lost by the gas in the adiabatic expansion (from T_h to T_l) is exactly regained in the adiabatic compression (from T_l back to T_h). The amounts of work and heat, however, are not zero, since Q and W are path functions. Adding up the work of the four stages, the two adiabatic terms cancel out for the same reason, and we obtain:

$$\begin{aligned}W_{TOT} &= W_1 + W_2 + W_3 + W_4 \\ &= -nRT_h \ln\frac{V_B}{V_A} + n\int_{T_h}^{T_l} C_V dT - nRT_l \ln\frac{V_D}{V_C} + n\int_{T_l}^{T_h} C_V dT \\ &= -nRT_h \ln\frac{V_B}{V_A} - nRT_l \ln\frac{V_D}{V_C},\end{aligned} \tag{5.11}$$

The two volume ratios are not independent. Since the two adiabats connect the same two temperatures, it can be shown that $V_C/V_D = V_B/V_A$.[4] Therefore, $\ln\frac{V_D}{V_C} = -\ln\frac{V_B}{V_A}$, and eq. 5.11 reduces to:

$$W_{TOT} = -nR\,(T_h - T_l)\ln\frac{V_B}{V_A} < 0, \tag{5.12}$$

which is negative, because $T_h > T_l$ and $V_B > V_A$. Negative work means that the work is done by the system. In other words, the system is performing PV-work by transferring heat from a hot reservoir to a cold one via a Carnot cycle. On the other hand, for the heat:

[4] This relation follows from the equation of an adiabatic transformation of an ideal gas, which we do not derive in this book. We will take it as given.

$$\begin{aligned} Q_{\text{TOT}} &= Q_1 + Q_2 + Q_3 + Q_4 \\ &= |Q_h| + 0 - |Q_l| + 0 \\ &= nRT_h \ln \frac{V_B}{V_A} + nRT_l \ln \frac{V_D}{V_C} \\ &= nR\left(T_h - T_l\right) \ln \frac{V_B}{V_A} = -W_{TOT}, \end{aligned} \tag{5.13}$$

which is exactly what we should expect from the first law: since $\Delta U_{\text{TOT}} = 0$, all the net heat absorbed by the gas in a cycle must leave it as work. Since the heat is exchanged only in the two isothermal stages, this can be written as:

$$W_{TOT} = -(Q_1 + Q_3), \tag{5.14}$$

and, replacing Q_1 and Q_3 with the absolute values of the heats drawn from the hot and cold reservoirs, $|Q_h|$, and $|Q_l|$ respectively:

$$|W_{TOT}| = |Q_h| - |Q_l|\,, \tag{5.15}$$

or, in other words, more heat is extracted from the hot reservoir than it is put into the cold one. The difference between the absolute value of these amounts of heat gives the total work of the cycle. This process is depicted in Figure 5.7.




Figure 5.7.: Carnot Cycle Diagram.

Exercise 5.1. Up to this point, we have discussed Carnot cycles working in the hot $\rightarrow$ cold direction ($A \rightarrow B \rightarrow C \rightarrow D \rightarrow A$), since this is the

primary mode of operation of heat engines that produce work. However, a heat engine could also—in principle—work in the reversed cold → hot direction ($A \to D \to C \to B \to A$). Write the equations for heat, work, and energy of each stage of a Carnot cycle going the opposite direction than the one discussed in section 5.1 and section 5.2.

Solution: When the heat engine works in reverse order, the formulas remain the same, but all the signs in front of Q, W, and U will be reversed. In this case, the total work would get **into** the system, and heat would be transferred from the cold reservoir to the hot one. Figure 5.7 would be modified as in figure 5.8.




Figure 5.8.: A Carnot cycle run in reverse works as a refrigerator: the work $|W_{TOT}|$ is used to move the heat $|Q_l|$ from the cold reservoir to the hot one.

This reversed mode of operation is the basic principle behind refrigerators and air conditioning.

5.3. Efficiency of a Carnot Cycle

The efficiency (ε) of a cycle is defined as the ratio between the absolute value of the work extracted from the cycle ($|W_{TOT}|$) and the heat that gets into the system ($|Q_h|$):

$$\varepsilon = \frac{|W_{TOT}|}{|Q_h|} = \frac{-W_{TOT}}{Q_1} \tag{5.16}$$

where the minus sign in front of the work is necessary because the efficiency is defined as a positive number. Replacing eq. 5.14 into eq. 5.16, we obtain:

$$\varepsilon = \frac{Q_3 + Q_1}{Q_1} = 1 + \frac{Q_3}{Q_1}. \tag{5.17}$$

If we go back to eq. 5.16 and we replace eq. 5.12 for W_{TOT} and eq. 5.3 for Q_1, we obtain:

$$\varepsilon = \frac{nR\,(T_h - T_l)\ln V_B/V_A}{nRT_h \ln V_B/V_A} = \frac{T_h - T_l}{T_h} = 1 - \frac{T_l}{T_h} < 1, \tag{5.18}$$

which proves that the efficiency of a Carnot cycle is strictly smaller than 1.[5] In other words, no cycle can convert 100% of the heat into work it extracts from a hot reservoir. This finding had remarkable consequences on the entire thermodynamics field and set the foundation for the introduction of entropy. We will use eq. 5.16 and eq. 5.18 for this purpose in the next chapter, but we conclude the discussion on Carnot cycles by returning to Lord Kelvin. In 1851 he used this finding to formulate his statement "It is impossible for a self-acting machine, unaided by any external agency, to convey heat from one body to another at a higher temperature. It is impossible, by means of inanimate material agency, to derive mechanical effect from any portion of matter by cooling it below the temperature of the coldest of the surrounding objects."[6] This statement conclusively disproved Joule's original theories and demonstrated that there is some fundamental principle to govern the flow of heat beyond the first law of thermodynamics.

5.4. Chapter Review

5.4.1. Study Questions

1. What does the first law of thermodynamics say about a gas that spontaneously compresses back into one side of the Joule apparatus?

a. It forbids it, since energy would not be conserved.
b. It requires work to be done on the gas.
c. It requires heat to flow out of the gas.
d. Nothing: the process would conserve energy, so the first law does not forbid it.
e. It shows that the process is spontaneous.

[5] Eq. 5.18 can be equal to 1 only if $T_l = 0$ K or $T_h = \infty$, two conditions that are both equally impossible.

[6] Thomson W. Transactions of the Royal Society of Edinburgh. 1851 XX 261–268, 289–298..

---

2. What transformations make up a Carnot cycle?

a. Two isochoric and two isobaric transformations.
b. Two isothermal and two adiabatic reversible transformations.
c. Four isothermal transformations.
d. Four adiabatic transformations.
e. One isothermal, one adiabatic, one isochoric, and one isobaric transformation.

---

3. What happens during the isothermal expansion at T_h in a Carnot cycle?

a. $\Delta U = 0$, heat is absorbed from the hot reservoir, and the same amount of energy leaves as work.
b. No heat is exchanged.
c. The temperature drops from T_h to T_l.
d. Heat is released to the cold reservoir.
e. Work is done on the gas.

---

4. What happens during the adiabatic expansion in a Carnot cycle?

a. Heat is absorbed from the hot reservoir.
b. The internal energy stays constant.
c. Heat is released to the cold reservoir.
d. The volume decreases.
e. No heat is exchanged, the gas performs work, and its temperature drops from T_h to T_l.

---

5. What is the total change in internal energy for a complete Carnot cycle?

a. $nR(T_h - T_l) \ln \frac{V_B}{V_A}$.
b. $nC_V(T_h - T_l)$.
c. Zero, since the internal energy is a state function.
d. Equal to the total work.

e. Equal to the heat absorbed from the hot reservoir.

---

6. What is the total work of a Carnot cycle?

a. $W_{TOT} = nR(T_h - T_l) \ln \frac{V_B}{V_A}$.
b. $W_{TOT} = -nR(T_h - T_l) \ln \frac{V_B}{V_A}$.
c. $W_{TOT} = 0$.
d. $W_{TOT} = nRT_h \ln \frac{V_B}{V_A}$.
e. $W_{TOT} = nC_V(T_h - T_l)$.

---

7. How is the efficiency of a heat engine defined?

a. $\varepsilon = \frac{|Q_h|}{|W_{TOT}|}$.
b. $\varepsilon = \frac{|Q_l|}{|Q_h|}$.
c. $\varepsilon = \frac{|W_{TOT}|}{|Q_l|}$.
d. $\varepsilon = \frac{|W_{TOT}|}{|Q_h|}$.
e. $\varepsilon = \frac{T_h}{T_l}$.

---

8. What is the efficiency of a Carnot cycle in terms of the reservoir temperatures?

a. $\varepsilon = 1 - \frac{T_l}{T_h}$.
b. $\varepsilon = 1 - \frac{T_h}{T_l}$.
c. $\varepsilon = \frac{T_h}{T_l}$.
d. $\varepsilon = \frac{T_h - T_l}{T_l}$.
e. $\varepsilon = 1$.

---

9. Why is the efficiency of a Carnot cycle always smaller than 1?

a. Because of friction in the engine.
b. Because the gas is not ideal.
c. Because heat is a state function.

d. Because the cycle is irreversible.
e. Because it would be 1 only if $T_l = 0$ K or $T_h = \infty$, which are impossible.

---

10. What happens when a Carnot cycle is run in reverse?

a. It produces more work than the forward cycle.
b. It reaches 100% efficiency.
c. Work is put into the system, and heat is moved from the cold reservoir to the hot one, as in a refrigerator.
d. Heat flows from the hot reservoir to the cold one without work.
e. It violates the first law.

Answers

1.d, 2.b, 3.a, 4.e, 5.c, 6.b, 7.d, 8.a, 9.e, 10.c

6. Entropy and the Second Law of Thermodynamics

In chapter 5, we used heat engines to understand why some processes are spontaneous while others are not, and we found that no engine can convert all the heat it absorbs into work. Carnot's findings did not just inspire Lord Kelvin on this subject, but they also motivated Rudolf Clausius (1822–1888) to introduce a new state function, the *entropy*. In this chapter, we will follow Clausius' reasoning to define the entropy, we will use it to write the second law of thermodynamics, and we will then look at the same quantity from the microscopic point of view of Boltzmann, to understand what entropy really measures.

6.1. Entropy

Let's return to the efficiency of a Carnot cycle, and bring together the two expressions that we found in eq. 5.17 and eq. 5.18:

$$\varepsilon = 1 + \frac{Q_3}{Q_1} = 1 - \frac{T_l}{T_h}. \tag{6.1}$$

Subtracting 1 from both sides, we obtain $\frac{Q_3}{Q_1} = -\frac{T_l}{T_h}$. We can then multiply both sides by $\frac{Q_1}{T_l}$, which separates the quantities related to the cold reservoir from the ones related to the hot reservoir:

$$\frac{Q_3}{T_l} = -\frac{Q_1}{T_h}, \tag{6.2}$$

or, moving everything to the left-hand side:

$$\frac{Q_3}{T_l} + \frac{Q_1}{T_h} = 0. \tag{6.3}$$

The left-hand side of eq. 6.3 is a sum of two terms, one for each isothermal stage of the Carnot cycle. Each term is the heat exchanged during that

stage, divided by the temperature at which it is exchanged. Since, according to Definition 5.1, each transformation in a Carnot cycle is reversible, these are heats exchanged at reversible conditions, Q_{REV}. The two adiabatic stages do not contribute, since no heat is exchanged during them.

Is this result special to the Carnot cycle? Not really. Any reversible cycle in a PV diagram can be approximated by a sequence of small Carnot cycles, drawn next to each other like tiles, so that their outer edges follow the shape of the cycle in a zig-zag of isotherms and adiabats. Inside the cycle, each isotherm and each adiabat is traveled twice, once in each direction, by two neighboring Carnot cycles, so their contributions cancel out. Only the outer zig-zag contour remains. If we apply eq. 6.3 to each small cycle and add everything up, we obtain:

$$\sum_i \frac{Q_{\mathrm{REV},i}}{T_i} = 0, \tag{6.4}$$

where the summation runs over all the isothermal stages around the contour. If we make the small cycles smaller and smaller, the zig-zag contour approaches any smooth reversible cycle, and, following the same calculus procedure that we introduced in chapter 1, the sum becomes an integral around the cycle:

$$\oint \frac{Q_{\mathrm{REV}}}{T} = 0. \tag{6.5}$$

Eq. 6.5 is a remarkable result. The heat, Q, is a path function, and its integral around a cycle is in general *not* zero. However, if we take the heat exchanged reversibly and divide it by the temperature, we obtain a quantity whose integral around *any* reversible cycle is zero. As we saw for the energy in eq. 3.16, this is precisely the property that defines a state function: when we go back to the starting point, we always find the same value. Clausius realized this in 1865, and he decided to call the new state function *entropy*, and to indicate it with the letter S:

Definition 6.1. *Entropy:* The state function S whose infinitesimal change is equal to the heat exchanged at reversible conditions, divided by the temperature at which it is exchanged:

$$dS = \frac{Q_{\mathrm{REV}}}{T}. \tag{6.6}$$

For a transformation between an initial and a final state, the change in entropy is obtained by integration along any reversible path that connects the two states:

$$\Delta S = S_f - S_i = \int_i^f \frac{Q_{\text{REV}}}{T}. \tag{6.7}$$

A few important considerations can be made by analyzing Definition 6.1:

1. **Dividing by T turns a path function into a state function.** In chapter 1, we introduced inexact differentials, such as Q, which cannot be integrated as differences between final and initial values. Eq. 6.6 tells us that, for reversible processes, dividing Q_{REV} by the temperature turns it into the exact differential of a state function, dS. Mathematicians call $1/T$ an *integrating factor*.
2. **Only the reversible heat works.** The heat exchanged along an irreversible path is different, and dividing it by T does *not* give dS. To calculate the entropy change of an irreversible process, we must find a reversible path between the same initial and final states and calculate ΔS along that path. Since the entropy is a state function, the result is valid for the irreversible process as well.
3. **The same heat matters more at low temperature.** The entropy change produced by a given amount of heat is larger when the heat is exchanged at a low temperature than at a high temperature. Intuitively, giving 1 kJ of heat to a cold object changes it more than giving the same 1 kJ to a hot one.
4. **The units of entropy are energy divided by temperature**, J/K in SI. The entropy is an extensive property, and its molar version, $\overline{S}$, is measured in $\mathrm{J\,mol^{-1}\,K^{-1}}$.
5. **Only changes in entropy are defined, for now.** Eq. 6.7 gives us differences in entropy, but not absolute values. We will see in chapter 7 that the third law of thermodynamics fixes the zero of the entropy scale.

6.2. Irreversible Cycles

Up to this point, we have discussed *reversible* cycles only. What happens when the cycle is irreversible? In chapter 5, we saw that the efficiency of a Carnot cycle, eq. 5.18, is the maximum efficiency that any cycle working between two temperatures can reach. Any real (irreversible) cycle loses some energy along the way, for example to friction, and its efficiency is always smaller than the Carnot one. Therefore, eq. 6.1 does not hold anymore for an *irreversible* cycle, and it must be replaced by an inequality:

$$\overbrace{1 + \frac{Q_3^{\text{IRR}}}{Q_1^{\text{IRR}}}}^{\varepsilon_{\text{IRR}}} < \overbrace{1 - \frac{T_l}{T_h}}^{\varepsilon_{\text{REV}}}. \tag{6.8}$$

Following exactly the same steps used in section 6.1 (subtracting 1 from both sides and multiplying by $\frac{Q_1^{\mathrm{IRR}}}{T_l}$, which is positive, so the direction of the inequality does not change), we obtain:

$$\frac{Q_3^{\mathrm{IRR}}}{Q_1^{\mathrm{IRR}}} < -\frac{T_l}{T_h} \longrightarrow \frac{Q_3^{\mathrm{IRR}}}{T_l} + \frac{Q_1^{\mathrm{IRR}}}{T_h} < 0 \longrightarrow \sum_i \frac{Q_{\mathrm{IRR},i}}{T_i} < 0, \tag{6.9}$$

which, using the same calculus procedure as before, becomes:

$$\oint \frac{Q_{\mathrm{IRR}}}{T} < 0. \tag{6.10}$$

Putting eq. 6.5 and eq. 6.10 together, we obtain:

$$\oint \frac{Q}{T} \leq 0, \tag{6.11}$$

where the equal sign holds for reversible cycles exclusively, while the inequality sign holds for irreversible ones. Eq. 6.11 is known as the **Clausius inequality**. In words, it tells us that around an irreversible cycle, the system always gives away more "heat divided by temperature" than it absorbs. This is the mathematical version of the fact that some of the energy that goes through a real engine is always wasted.

6.3. The Second Law of Thermodynamics

We are now ready to use the Clausius inequality to understand spontaneity. Let's consider an isolated system that undergoes an irreversible transformation from state 1 to state 2, and then let's bring it back from state 2 to state 1 along a reversible path, as in Figure 6.1.

This cycle is similar to the one in Figure 5.1 for the Joule expansion experiment: the gas expands spontaneously into the vacuum ($1 \to 2$), but it never goes back on its own ($2 \to 1$). To bring it back, we must compress it from the outside.[1] Since the cycle contains an irreversible step, it is irreversible overall, and the Clausius inequality, eq. 6.11, gives:

[1] Strictly speaking, during the reversible compression the system cannot be isolated, since a reversible return to state 1 requires exchanging heat and work with the surroundings. This does not affect our argument: we use the reversible path only as a tool to calculate the entropy change between states 1 and 2, and since the entropy is a state function, the result does not depend on how we actually bring the system back. This is therefore a plausibility argument rather than a rigorous proof, but it leads to the correct result.




Figure 6.1.: Spontaneous and Non-Spontaneous Transformations in a Cycle.

$$\int_1^2 \frac{Q_{\text{IRR}}}{T} + \int_2^1 \frac{Q_{\text{REV}}}{T} < 0. \tag{6.12}$$

The second integral is taken along a reversible path, so, according to eq. 6.7, it is the entropy change from state 2 to state 1, which is $-\Delta S$, where $\Delta S = S_2 - S_1$ is the entropy change of the forward process. Moving it to the right-hand side, we obtain:

$$\underbrace{\int_1^2 \frac{Q_{\text{REV}}}{T}}_{\Delta S} > \underbrace{\int_1^2 \frac{Q_{\text{IRR}}}{T}}_{=0}, \tag{6.13}$$

where the right-hand side is zero because the system is isolated during the forward process, and therefore $Q_{\text{IRR}} = 0$. Eq. 6.13 simply becomes:

$$\Delta S > 0. \tag{6.14}$$

A few important considerations can be made by analyzing eq. 6.14:

1. **In an isolated system, spontaneous processes increase the entropy.** Every irreversible process that happens on its own in an

isolated system has $\Delta S > 0$. Spontaneous processes are always irreversible, since reversible processes are idealizations that require infinitely slow, controlled changes.

2. **The entropy changes even if no heat is exchanged.** In the Joule expansion, $Q = 0$, and yet $\Delta S > 0$. This is not a contradiction: the entropy change must be calculated along a reversible path between the same states, and along that path heat *is* exchanged. We will calculate this value in chapter 7.
3. **The reverse process would decrease the entropy**, and it never happens on its own in an isolated system. This is why the gas never goes back to one side of the box.

Since the only system that is truly isolated is the universe, we can write a concise statement for a new fundamental law of thermodynamics:

Definition 6.2. *Second Law of Thermodynamics:* For any spontaneous process, the entropy of the universe increases.

6.4. Boltzmann Entropy

Up to this point, we have treated entropy as a macroscopic quantity, defined through heat and temperature. This definition is powerful, but it does not tell us what entropy *is* at the level of molecules, which is where chemistry happens. The microscopic meaning of entropy was found by Ludwig Eduard Boltzmann (1844–1906), who connected it to the number of ways in which the molecules of a system can be arranged.

To understand Boltzmann's idea, we need to distinguish between two ways of describing a system:

- A **macrostate** is described by the macroscopic variables that we can measure, such as pressure, volume, and temperature.
- A **microstate** is a complete specification of where every single molecule is and how it moves.[2]

Many different microstates correspond to the same macrostate, since we can swap molecules around without changing the pressure or the temperature. The number of microstates that correspond to a given macrostate is called its **multiplicity**, and is indicated with Ω.

[2] Positions and velocities are continuous quantities, so to count microstates we have to divide space into small cells, and only ask which cell each molecule is in. Quantum mechanics, which we will study in P-Chem 2, makes this counting exact, since the energy levels of molecules are discrete.

6.4.1. Counting microstates

Let's see how this works with a simple example. Consider a box divided into two halves, left and right, containing just four molecules, which we label a, b, c, and d. Each molecule can be in either half, and we consider as a macrostate the number of molecules in the left half. The microstates are all the possible ways of assigning each molecule to one of the two halves:

Table 6.1.: Microstates of four molecules in a box divided into two halves.

Molecules on the left	Microstates (molecules on the left)	Ω
4	$abcd$	1
3	abc, abd, acd, bcd	4
2	ab, ac, ad, bc, bd, cd	6
1	a, b, c, d	4
0	none	1

There are $2^4 = 16$ microstates in total. If the molecules move around randomly, each microstate is equally likely, and the probability of each macrostate is proportional to its multiplicity. A few important considerations can be made by analyzing table 6.1:

1. **The evenly distributed macrostate is the most probable.** Two molecules on each side has $\Omega = 6$, which corresponds to a probability of 6/16, almost 40%.
2. **The macrostate with all molecules on one side is the least probable.** It has $\Omega = 1$, so its probability is only 1/16.
3. **The effect becomes overwhelming for many molecules.** With N molecules, the probability of finding all of them on the left is $1/2^N$. For $N = 100$ molecules, this is about 10^{-30}. For a mole of gas, with $N \approx 6 \times 10^{23}$, it is so small that it will never be observed. This is why the gas in the Joule experiment never goes back to one side of the box: not because it is forbidden, but because it is overwhelmingly improbable.

6.4.2. The Boltzmann equation

Boltzmann connected the multiplicity to the thermodynamic entropy through the formula that became famous as the **Boltzmann equation**:

$$S = k_B \ln \Omega, \tag{6.15}$$

where k_B is the Boltzmann constant, $k_B = R/N_A = 1.380649 \times 10^{-23}$ J/K, with R being the ideal gas constant and N_A Avogadro's constant. The Boltzmann constant is the ideal gas constant "per molecule", and it is the conversion factor between the microscopic counting of Ω and the macroscopic entropy measured in J/K.

Why the logarithm? If we put together two independent systems, the number of microstates of the combined system is the *product* of the two multiplicities, $\Omega = \Omega_1 \Omega_2$, since every microstate of the first can be combined with every microstate of the second. However, the entropy is extensive, so the entropy of the combined system must be the *sum* of the two entropies. The logarithm is the function that turns products into sums: $k_B \ln(\Omega_1 \Omega_2) = k_B \ln \Omega_1 + k_B \ln \Omega_2$.

Let's now check that Boltzmann's entropy agrees with Clausius' one, using the expansion of an ideal gas into twice its initial volume. Each molecule now has twice as many positions available, so, for each microstate of the initial state, there are 2^N microstates of the final state, where N is the number of molecules. Using eq. 6.15:

$$\Delta S = k_B \ln \Omega_f - k_B \ln \Omega_i = k_B \ln \frac{\Omega_f}{\Omega_i} = k_B \ln 2^N = N k_B \ln 2 = nR \ln 2, \tag{6.16}$$

where in the last step we used $N k_B = n N_A \frac{R}{N_A} = nR$. In chapter 7, we will calculate the same entropy change from Clausius' definition, obtaining $\Delta S = nR \ln \frac{V_f}{V_i}$, which for $V_f = 2V_i$ is exactly the same result. The two definitions of entropy describe the same quantity.

6.4.3. Why "disorder" can be misleading

Entropy is often described as a measure of "disorder." This description is not completely wrong, but it can be misleading. A more accurate description is that the entropy measures the *number of microscopic arrangements* compatible with what we observe macroscopically. For example, when ice melts, the entropy increases because the water molecules in the liquid can move around and take many more positions and orientations than in the rigid crystal. Calling the liquid "more disordered" is a shortcut for "has many more microstates," and it is the number of microstates that we should keep in mind.

The shortcut becomes a misconception when we apply it to everyday objects. A messy room does not have a higher thermodynamic entropy than a tidy one. The thermodynamic entropy counts the arrangements of about 10^{23} molecules, and the arrangement of a few dozen books and socks does not contribute to it in any measurable way. Moreover, a messy room and a tidy room are each just *one* specific arrangement of the objects. If we really want to count arrangements of objects, we need many identical copies of the same room.[3]

6.5. Chapter Review

6.5.1. Study Questions

1. Which quantity has a sum (or integral) equal to zero around any reversible cycle?

a. The heat, Q_{REV}.
b. The heat divided by the temperature, $\frac{Q_{\text{REV}}}{T}$.
c. The work, W.
d. The temperature, T.
e. The heat multiplied by the temperature, $Q_{\text{REV}}T$.

---

2. Which formula defines the entropy according to Clausius?

a. $dS = \frac{Q_{\text{REV}}}{T}$.
b. $dS = \frac{Q_{\text{IRR}}}{T}$.
c. $dS = Q_{\text{REV}}\, T$.
d. $S = \frac{T}{Q}$.
e. $dS = \frac{W}{T}$.

---

3. How can we calculate the entropy change of an irreversible process?

a. By integrating the irreversible heat divided by the temperature.
b. It cannot be calculated.

[3] A better version of the analogy is that of a hotel with many identical rooms containing the same objects. The collection of all the unmade rooms in the morning has a higher entropy than the collection of the same rooms after the housekeepers have arranged all the objects in every room in exactly the same way.

c. By using the work instead of the heat.
d. By calculating it along a reversible path between the same initial and final states.
e. By assuming it is always zero.

---

4. What are the units of entropy in the SI?

a. J.
b. K/J.
c. $\mathrm{J} \cdot \mathrm{K}$.
d. J/mol.
e. J/K.

---

5. What is the Clausius inequality?

a. $\oint \frac{Q}{T} \geq 0$.
b. $\oint \frac{Q}{T} = 0$ always.
c. $\oint \frac{Q}{T} \leq 0$.
d. $\oint Q \leq 0$.
e. $\oint dS > 0$.

---

6. How does the efficiency of an irreversible cycle compare with that of a Carnot cycle between the same temperatures?

a. It is smaller.
b. It is larger.
c. It is the same.
d. It is always zero.
e. It can be larger than 1.

---

7. What does the second law of thermodynamics state?

a. The energy of the universe is conserved.
b. The entropy of the universe is constant.
c. The entropy of a system always increases.
d. For any spontaneous process, the entropy of the universe increases.

e. Heat can be completely converted into work.

---

8. A gas expands into a vacuum inside an insulated container (the Joule expansion). What are the heat exchanged and the entropy change of the gas?

a. $Q > 0$ and $\Delta S > 0$.
b. $Q = 0$ and $\Delta S > 0$.
c. $Q = 0$ and $\Delta S = 0$.
d. $Q < 0$ and $\Delta S < 0$.
e. $Q = 0$ and $\Delta S < 0$.

---

9. Which formula is the Boltzmann equation for the entropy?

a. $S = k_B \Omega$.
b. $S = R \ln T$.
c. $S = \frac{\Omega}{k_B}$.
d. $S = k_B T$.
e. $S = k_B \ln \Omega$.

---

10. Four molecules move randomly in a box divided into two halves. Which macrostate is the most probable?

a. All four molecules on the left.
b. Three molecules on the left and one on the right.
c. Two molecules on each side.
d. All four molecules on the right.
e. All macrostates are equally probable.

Answers

1.b, 2.a, 3.d, 4.e, 5.c, 6.a, 7.d, 8.b, 9.e, 10.c

7. Calculation of Entropy and the Third Law of Thermodynamics

In chapter 6, we defined the entropy as a state function, and we found that the entropy of the universe increases in every spontaneous process. A definition, however, is not very useful until we know how to calculate it. In this chapter, we will learn how to calculate the entropy changes of the most common transformations: heating and cooling, expansions and compressions, and phase changes. We will then see how to account for the surroundings, and we will introduce the third law of thermodynamics, which fixes the zero of the entropy scale and allows us to tabulate absolute entropies.

The Second Law can be used to infer the spontaneity of a process, as long as the entropy of the universe is considered. To do so, we need to remind ourselves that the universe can be divided into a system and its surroundings (environment). When we calculate the entropy of the universe as an indicator of the spontaneity of a process, we need to *always* consider changes in entropy in *both* the system (sys) and its surroundings (surr):

$$\Delta S^{\text{universe}} = \Delta S^{\text{sys}} + \Delta S^{\text{surr}}, \tag{7.1}$$

or, in differential form:

$$dS^{\text{universe}} = dS^{\text{sys}} + dS^{\text{surr}}. \tag{7.2}$$

7.1. Calculation of ΔS^{sys}

In general ΔS^{sys} can be calculated from its definition, definition 6.1, integrated along a reversible path, eq. 6.7. In practice, it is always convenient to keep in mind that entropy is a state function, and as such it does not depend on the path. For this reason, we can break every transformation into elementary steps, and calculate the entropy on any path that goes from the initial state to the final state, such as, for example:

$$\begin{array}{ccc} P_i, T_i & \xrightarrow{\Delta_{\mathrm{TOT}} S^{\mathrm{sys}}} & P_f, T_f \\ {\scriptstyle \Delta_1 S^{\mathrm{sys}}} \searrow & & \nearrow {\scriptstyle \Delta_2 S^{\mathrm{sys}}} \\ & P_i, T_f & \end{array} \tag{7.3}$$

$$\Delta_{\mathrm{TOT}} S^{\mathrm{sys}} = \Delta_1 S^{\mathrm{sys}} + \Delta_2 S^{\mathrm{sys}},$$

with $\Delta_1 S^{\mathrm{sys}}$ calculated at constant P, and $\Delta_2 S^{\mathrm{sys}}$ at constant T. The most important elementary steps from which we can calculate the entropy resemble the prototypical processes for which we calculated the energy in section 3.1.

7.1.1. Entropy in isothermal processes

- For an ideal gas at constant temperature $\Delta U = 0$, and $Q_{\mathrm{REV}} = -W_{\mathrm{REV}}$. Using the formula for W_{REV} in eq. 2.19 (or its analogue for P), we obtain:

$$\Delta S^{\mathrm{sys}} = \int_i^f \frac{Q_{\mathrm{REV}}}{T} = \frac{-W_{\mathrm{REV}}}{T} = \frac{nRT \ln \frac{V_f}{V_i}}{T} = nR \ln \frac{V_f}{V_i}, \tag{7.4}$$

  or, similarly:

$$\Delta S^{\mathrm{sys}} = nR \ln \frac{P_i}{P_f}. \tag{7.5}$$

- A phase change is a particular case of an isothermal process that does not follow the formulas introduced above since an ideal gas never liquefies. The entropy associated with a phase change at constant pressure can be calculated from its definition, remembering that $Q_{\mathrm{REV}} = \Delta H$. For example for vaporizations:

$$\Delta_{\mathrm{vap}} S = \frac{\Delta_{\mathrm{vap}} H}{T_B}, \tag{7.6}$$

with $\Delta_{\mathrm{vap}} H$ being the enthalpy of vaporization of a substance, and T_B its boiling temperature.

It is experimentally observed that the entropies of vaporization of many liquids have almost the same value of:

$$\Delta_{\mathrm{vap}} S \approx 10.5R, \tag{7.7}$$

which corresponds in SI to the range of about 85–88 J/(mol K). This simple rule is named **Trouton's rule**, after the Irish physicist who discovered it, Frederick Thomas Trouton (1863–1922).

Exercise 7.1. Calculate the standard entropy of vaporization of water knowing $\Delta_{\text{vap}}H^{\ominus}_{\text{H}_2\text{O}} = 44$ kJ/mol, as calculated in Exercise 4.1.

Solution: Using eq. 7.6—and knowing that at standard conditions of $P^{\ominus} = 1$ bar the boiling temperature of water is 373 K—we calculate:

$$\Delta_{\text{vap}}S^{\ominus}_{\text{H}_2\text{O}} = \frac{44 \times 10^3 \text{J/mol}}{373 \text{ K}} = 118 \text{ J mol}^{-1} \text{ K}^{-1}. \tag{7.8}$$

The entropy of vaporization of water is far from Trouton's rule range of 85–88 J/(mol K) because of the hydrogen bond interactions between its molecules. Other similar exceptions are ethanol, formic acid, and hydrogen fluoride.

7.1.2. Entropy in adiabatic processes

Since adiabatic processes happen without the exchange of heat, $Q = 0$, it would be tempting to think that $\Delta S^{\text{sys}} = 0$ for every one of them. A transformation at constant entropy (isentropic) is always, in fact, a reversible adiabatic process. However, the opposite case is not always true, and an irreversible adiabatic transformation is usually associated with a change in entropy. To explain this fact, we need to recall that the definition of entropy includes the heat exchanged at reversible conditions only. Therefore, for irreversible adiabatic processes $\Delta S^{\text{sys}} \neq 0$. The calculation of the entropy change for an irreversible adiabatic transformation requires a substantial effort, and we will not cover it at this stage. The situation for adiabatic processes can be summarized as follows:

$$\begin{aligned} &\text{reversible:} && \frac{Q_{\text{REV}}}{T} = 0 \longrightarrow \Delta S^{\text{sys}} = 0 \quad \text{(isentropic)}, \\ &\text{irreversible:} && \frac{Q_{\text{IRR}}}{T} = 0 \longrightarrow \Delta S^{\text{sys}} \neq 0. \end{aligned} \tag{7.9}$$

7.1.3. Entropy in isochoric processes

We can calculate the heat exchanged in a process that happens at constant volume, Q_V, using eq. 2.2. Since the heat exchanged at those conditions equals the energy (eq. 3.7), and the energy is a state function, we can use Q_V

regardless of the path (reversible or irreversible). The entropy associated with the process will then be:

$$\Delta S^{\text{sys}} = \int_i^f \frac{Q_{\text{REV}}}{T} = \int_i^f nC_V \frac{dT}{T}, \tag{7.10}$$

which, assuming C_V independent of temperature and solving the integral on the right-hand side, becomes:

$$\Delta S^{\text{sys}} \approx nC_V \ln \frac{T_f}{T_i}. \tag{7.11}$$

7.1.4. Entropy in isobaric processes

Similarly to the constant volume case, we can calculate the heat exchanged in a process that happens at constant pressure, Q_P, using eq. 2.4. Again, similarly to the previous case, Q_P equals a state function (the enthalpy), and we can use it regardless of the path to calculate the entropy as:

$$\Delta S^{\text{sys}} = \int_i^f \frac{Q_{\text{REV}}}{T} = \int_i^f nC_P \frac{dT}{T}, \tag{7.12}$$

which, assuming C_P independent of temperature and solving the integral on the right-hand side, becomes:

$$\Delta S^{\text{sys}} \approx nC_P \ln \frac{T_f}{T_i}. \tag{7.13}$$

7.2. Calculation of ΔS^{surr}

While the entropy of the system can be broken down into simple cases and calculated using the formulas introduced above, the entropy of the surroundings does not require such a complicated treatment, and it can always be calculated as:

$$\Delta S^{\text{surr}} = \frac{Q_{\text{surr}}}{T_{\text{surr}}} = \frac{-Q_{\text{sys}}}{T_{\text{surr}}}, \tag{7.14}$$

or, in differential form:

$$dS^{\text{surr}} = \frac{Q_{\text{surr}}}{T_{\text{surr}}} = \frac{-Q_{\text{sys}}}{T_{\text{surr}}}, \tag{7.15}$$

where the substitution $Q_{\text{surr}} = -Q_{\text{sys}}$ can be performed regardless of whether the transformation is reversible or not. In other words, the surroundings always absorb heat reversibly. To justify this statement, we need to restrict the analysis of the interaction between the system and the surroundings to just the vicinity of the system itself. Outside of a generally restricted region, the rest of the universe is so vast that it remains untouched by anything happening inside the system.[1] To facilitate our comprehension, we might consider a system composed of a beaker on a workbench. We can then consider the room that the beaker is in as the immediate surroundings. To all effects, the beaker+room combination behaves as a system isolated from the rest of the universe. The room is obviously much larger than the beaker itself, and therefore every energy production that happens in the system will have minimal effect on the parameters of the room. For example, an exothermic chemical reaction occurring in the beaker will not affect the overall temperature of the room substantially. When we study our reaction, T_{surr} will be constant, and the transfer of heat from the reaction to the surroundings will happen at reversible conditions.

Exercise 7.2. Calculate the changes in entropy of the universe for the process of 1 mol of supercooled water, freezing at –10°C, knowing the following data: $\Delta_{\text{fus}}H = 6$ kJ/mol, $C_P^{\text{H}_2\text{O}_{(l)}} = 76\ \text{J mol}^{-1}\,\text{K}^{-1}$, $C_P^{\text{H}_2\text{O}_{(s)}} = 38\ \text{J mol}^{-1}\,\text{K}^{-1}$, and assuming both C_P to be independent of temperature.

Solution: ΔS^{sys} for the process under consideration can be calculated using the following cycle:

$$\begin{array}{lcll} \text{H}_2\text{O}_{(l)} & \xrightarrow{\Delta S_{\text{sys}}} & \text{H}_2\text{O}_{(s)} & T = 263\ \text{K} \\ \Delta S_1 \downarrow & & \uparrow \Delta S_3 & \\ \text{H}_2\text{O}_{(l)} & \xrightarrow{\Delta S_2} & \text{H}_2\text{O}_{(s)} & T = 273\ \text{K} \end{array} \tag{7.16}$$

$$\Delta S^{\text{sys}} = \Delta S_1 + \Delta S_2 + \Delta S_3$$

ΔS_1 and ΔS_3 are the isobaric heating and cooling processes of liquid and solid water, respectively, and can be calculated by filling the given data into

[1] Even if we think of the most energetic event that we could imagine happening here on earth—such as the explosion of an atomic bomb or the hit of a meteorite from outer space—such an event will not modify the average temperature of the universe by the slightest degree.

eq. 7.12. ΔS_2 is a phase change (isothermal process) and can be calculated translating eq. 7.6 to the freezing transformation. Overall:

$$\begin{aligned}\Delta S^{\text{sys}} &= \int_{263}^{273} \frac{C_P^{\text{H}_2\text{O}_{(l)}}}{T} dT + \frac{-\Delta_{\text{fus}} H}{273} + \int_{273}^{263} \frac{C_P^{\text{H}_2\text{O}_{(s)}}}{T} dT \\ &= 76 \ln \frac{273}{263} - \frac{6 \times 10^3}{273} + 38 \ln \frac{263}{273} = -20.6 \text{ J/K}.\end{aligned} \tag{7.17}$$

Don't be confused by the fact that ΔS^{sys} is negative. This is ***not*** the entropy of the universe! Hence it tells ***nothing*** about spontaneity! We can now calculate ΔS^{surr} from Q_{sys}, noting that we can calculate the enthalpy around the same cycle in eq. 7.16. To do that, we already have $\Delta_{\text{fus}} H$ from the given data, and we can calculate ΔH_1 and ΔH_3 using eq. 2.4.

$$\begin{aligned}Q^{\text{sys}} = \Delta H &= \int_{263}^{273} C_P^{\text{H}_2\text{O}_{(l)}} dT + (-\Delta_{\text{fus}} H) + \int_{273}^{263} C_P^{\text{H}_2\text{O}_{(s)}} dT \\ &= 76 \times 10^{-3}(273 - 263) - 6 + 38 \times 10^{-3}(263 - 273) \\ &= -5.6 \text{ kJ}.\end{aligned} \tag{7.18}$$

$$\Delta S^{\text{surr}} = \frac{-Q_{\text{sys}}}{T} = \frac{5.6 \times 10^3}{263} = +21.3 \text{ J/K}.$$

Bringing eq. 7.16 and eq. 7.18 results together, we obtain:

$$\Delta S^{\text{universe}} = \Delta S^{\text{sys}} + \Delta S^{\text{surr}} = -20.6 + 21.3 = +0.7 \text{ J/K}. \tag{7.19}$$

Since the entropy changes in the universe are positive, the process is spontaneous, as expected.

7.3. Clausius Theorem

By replacing eq. 7.15 into eq. 7.2 we can write the differential change in the entropy of the system as:

$$dS^{\text{sys}} = dS^{\text{universe}} - dS^{\text{surr}} = dS^{\text{universe}} + \frac{Q_{\text{sys}}}{T}. \tag{7.20}$$

According to the second law, for any spontaneous process $dS^{\text{universe}} \geq 0$, and therefore, replacing it into eq. 7.20:

$$dS^{\text{sys}} \geq \frac{Q_{\text{sys}}}{T}, \tag{7.21}$$

which is the mathematical expression of the so-called **Clausius theorem**. Eq. 7.21 distinguishes between three conditions:

$$\begin{aligned} dS^{\text{sys}} &> \frac{Q_{\text{sys}}}{T} && \text{spontaneous, irreversible transformation} \\ dS^{\text{sys}} &= \frac{Q_{\text{sys}}}{T} && \text{reversible transformation} \\ dS^{\text{sys}} &< \frac{Q_{\text{sys}}}{T} && \text{non-spontaneous, irreversible transformation.} \end{aligned} \tag{7.22}$$

Clausius theorem provides a useful criterion to infer the spontaneity of a process, especially in cases where it's hard to calculate $\Delta S^{\text{universe}}$. Eq. 7.21 requires knowledge of quantities that are dependent on the system exclusively, such as the difference in entropy, the amount of heat that crosses the boundaries, and the temperature at which the process happens.[2] If a process produces more entropy than the amount of heat that crosses the boundaries divided by the absolute temperature, it will be spontaneous. Vice versa, if the entropy produced is smaller than the amount of heat crossing the boundaries divided by the absolute temperature, the process will be non-spontaneous. The equality holds for systems in equilibrium with their surroundings, or for reversible processes since they happen through a series of equilibrium states. Measuring or calculating these quantities might not always be the simplest of calculations. We will return to the Clausius theorem in the next chapter when we seek more convenient indicators of spontaneity.

7.4. The Third Law of Thermodynamics

In chapter 4, we have discussed how to calculate reaction enthalpies for any reaction, given the formation enthalpies of reactants and products. In this section, we will try to do the same for reaction entropies. In this case,

[2] In cases where the temperature of the system changes throughout the process, T is just the (constant) temperature of its immediate surroundings, T_{surr}, as explained in section 7.2.

however, our task is simplified by a fundamental law of thermodynamics, introduced by Walther Hermann Nernst (1864–1941) in 1906.[3] The statement that was initially known as Nernst's Theorem is now officially recognized as the third fundamental law of thermodynamics, and it has the following definition:

Definition 7.1. *Third Law of Thermodynamics:* The entropy of a perfectly ordered, pure, crystalline substance is zero at $T = 0$ K.

This law sets an unambiguous zero of the entropy scale, similar to what happens with absolute zero in the temperature scale. The absolute value of the entropy of every substance can then be calculated in reference to this unambiguous zero. As such, absolute entropies are always positive. This is in stark contrast to what happened for the enthalpy. An unambiguous zero of the enthalpy scale is lacking, and standard formation enthalpies (which might be negative) must be agreed upon to calculate relative differences.

In simpler terms, given a substance i, we are not able to measure absolute values of its enthalpy H_i (and we must resort to known enthalpy differences, such as $\Delta_\mathrm{f}H^\ominus$). At the same time, for entropy, we can measure S_i thanks to the third law, and we usually report them as $S_i^\ominus$. A comprehensive list of standard entropies of inorganic and organic compounds is reported in Appendix A. Reaction entropies can be calculated from the tabulated standard entropies as differences between products and reactants, using:

$$\Delta_\mathrm{rxn}S^\ominus = \sum_i \nu_i S_i^\ominus, \tag{7.23}$$

with ν_i being the usual stoichiometric coefficients with their signs given in Definition 4.2.

The careful wording in the definition of the third law (definition 7.1) allows for the fact that some crystals might form with defects (i.e., not as a perfectly ordered crystal). In this case, a residual entropy will be present even at $T = 0$ K. However, this residual entropy can be removed, at least in theory, by forcing the substance into a perfectly ordered crystal.[4]

An interesting corollary to the third law states that it is impossible to find a procedure that reduces the temperature of a substance to $T = 0$ K in a finite number of steps.

[3] Walther Nernst was awarded the 1920 Nobel Prize in Chemistry for his work in thermochemistry.

[4] A procedure that—in practice—might be extremely difficult to achieve.

7.5. Chapter Review

7.5.1. Study Questions

1. How is the entropy change of the universe calculated?

a. $\Delta S^{\text{universe}} = \Delta S^{\text{sys}} + \Delta S^{\text{surr}}$.
b. $\Delta S^{\text{universe}} = \Delta S^{\text{sys}} - \Delta S^{\text{surr}}$.
c. $\Delta S^{\text{universe}} = \Delta S^{\text{sys}}$.
d. $\Delta S^{\text{universe}} = \Delta S^{\text{sys}} \cdot \Delta S^{\text{surr}}$.
e. $\Delta S^{\text{universe}} = 0$ always.

---

2. What is the entropy change of an ideal gas in an isothermal expansion?

a. $\Delta S = 0$.
b. $\Delta S = nC_V \ln \frac{T_f}{T_i}$.
c. $\Delta S = nR \ln \frac{V_f}{V_i}$.
d. $\Delta S = nR(V_f - V_i)$.
e. $\Delta S = \frac{W}{T}$.

---

3. How is the entropy of vaporization of a liquid calculated at its boiling point?

a. $\Delta_{\text{vap}} S = \Delta_{\text{vap}} H \cdot T_B$.
b. $\Delta_{\text{vap}} S = nR \ln T_B$.
c. $\Delta_{\text{vap}} S = 0$.
d. $\Delta_{\text{vap}} S = \Delta_{\text{vap}} H - T_B$.
e. $\Delta_{\text{vap}} S = \frac{\Delta_{\text{vap}} H}{T_B}$.

---

4. Why does water deviate from Trouton's rule?

a. Because it boils at 100 °C.
b. Because of the hydrogen bonds between its molecules.
c. Because its molar mass is small.
d. Because it is an ideal liquid.
e. Because its enthalpy of vaporization is negative.

---

5. What is the entropy change of the system in a reversible adiabatic process?

a. Always positive.
b. Always negative.
c. Equal to $\frac{Q}{T}$ with $Q > 0$.
d. Zero, since the process is isentropic.
e. Infinite.

---

6. What is the entropy change for heating a substance at constant pressure, with C_P independent of temperature?

a. $\Delta S \approx nC_P \ln \frac{T_f}{T_i}$.
b. $\Delta S \approx nC_P(T_f - T_i)$.
c. $\Delta S \approx nR \ln \frac{T_f}{T_i}$.
d. $\Delta S \approx \frac{nC_P}{T_f - T_i}$.
e. $\Delta S = 0$.

---

7. How is the entropy change of the surroundings calculated?

a. $\Delta S^{\text{surr}} = \frac{Q_{\text{sys}}}{T_{\text{sys}}}$.
b. $\Delta S^{\text{surr}} = -\Delta S^{\text{sys}}$.
c. $\Delta S^{\text{surr}} = \frac{-Q_{\text{sys}}}{T_{\text{surr}}}$.
d. $\Delta S^{\text{surr}} = 0$.
e. $\Delta S^{\text{surr}} = nR \ln \frac{V_f}{V_i}$.

---

8. Supercooled water freezes spontaneously at –10 °C, even though the entropy of the water decreases. How is this possible?

a. The entropy of the universe decreases, which is allowed for freezing.
b. The second law does not apply to phase changes.
c. The process is reversible.
d. The entropy of the water actually increases.

e. The heat released to the surroundings increases their entropy by more than the water loses.

---

9. What does the Clausius theorem state?

a. $dS^{\text{sys}} = \frac{Q}{T}$ always.
b. $dS^{\text{sys}} \geq \frac{Q}{T}$, with the equality for reversible processes.
c. $dS^{\text{sys}} \leq \frac{Q}{T}$ for spontaneous processes.
d. $dS^{\text{sys}} = 0$ for all processes.
e. $dS^{\text{universe}} < 0$ for spontaneous processes.

---

10. What does the third law of thermodynamics make possible for the entropy that is not possible for the enthalpy?

a. Calculating changes at constant pressure.
b. Measuring it with a calorimeter.
c. Using it for chemical reactions.
d. Tabulating absolute values, since it fixes the zero of the entropy scale.
e. Making it independent of temperature.

Answers

1.a, 2.c, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

8. Thermodynamic Potentials

In chapter 6 and chapter 7, we learned that the entropy of the universe tells us whether a process is spontaneous. This criterion is general, but it is not very practical: to use it, we always need to calculate what happens to the surroundings, in addition to what happens to the system. Chemists would much rather have a criterion that depends only on the system, and that works at the conditions that we can easily control in a lab, such as constant temperature and constant pressure. In this chapter, we will build such criteria. We will start by combining the first and second laws into a single equation, and we will then use a simple mathematical trick to define new state functions, called *thermodynamic potentials*, each tailored to a specific set of experimental conditions. One of them, the Gibbs energy, will be the protagonist of the rest of this book.

8.1. Fundamental Equation of Thermodynamics

Let's summarize some of the results from the first and second law of thermodynamics that we have seen so far. For reversible processes in closed systems, the first law gives us the change in internal energy, and the definition of entropy gives us the reversible heat:

$$\begin{aligned} \text{From } 1^{\text{st}} \text{ Law:} \qquad & dU = Q_{\text{REV}} - PdV \\ \text{From The Definition of Entropy:} \qquad & dS = \frac{Q_{\text{REV}}}{T} \rightarrow Q_{\text{REV}} = TdS \\ \\ \Rightarrow \quad & dU = TdS - PdV. \end{aligned} \tag{8.1}$$

Eq. 8.1 is called the **fundamental equation of thermodynamics** since it combines the first and the second laws. Even though we started the derivation above by restricting to reversible transformations only, if we look carefully at eq. 8.1, we notice that it exclusively involves state functions (U, T, S, P, and V). Since state functions do not care about the path, the relation between their changes must be the same for any path,

and it applies to both reversible and irreversible processes. The fundamental equation, however, remains constrained to closed systems. This fact restricts its utility for chemistry, since when a chemical reaction happens, the amounts of the chemical species change.

At the end of the 19th century, Josiah Willard Gibbs (1839–1903) proposed an important addition to the fundamental equation to account for changes in composition. Gibbs was able to do so by introducing a new quantity that he called the chemical potential:

Definition 8.1. The *chemical potential* is the amount of energy absorbed or released due to a change of the particle number of a given chemical species.

The chemical potential of species i is usually abbreviated as μ_i, and it enters the fundamental equation of thermodynamics as:

$$dU = TdS - PdV + \sum_i \mu_i dn_i, \tag{8.2}$$

where dn_i is the differential change in the number of moles of substance i, and the summation extends over all chemical species in the system. In words, μ_i tells us by how much the energy of the system changes when we add a tiny amount of species i, while keeping everything else fixed. As we will see in the next chapters, it measures the "escaping tendency" of a species: matter spontaneously moves from where its chemical potential is high to where it is low, just like heat moves from high to low temperature.

According to the fundamental equation, the internal energy of a system is a function of the three variables entropy, S, volume, V, and the numbers of moles $\{n_i\}$.[1] To emphasize this connection, we can use the notation $U(S, V, \{n_i\})$, and we call S, V, and $\{n_i\}$ the **natural variables** of the energy. Using the language of chapter 1, the natural variables are the "knobs" that control the "machine" U: if we know how to turn them, we know everything about how U changes.

8.2. Thermodynamic Potentials

The natural variables of the internal energy have a practical problem. While the volume and the number of moles are easy to control, nobody has ever built an "entropy-meter," and we have no knob to set the entropy of a system in the lab. The knobs that we *can* easily turn are the temperature

[1] In the case of the numbers of moles we include them in curly brackets to indicate that there might be more than one, depending on how many species are present.




Figure 8.1.: The internal energy as a machine. Its natural variables, the knobs that control it, are the entropy S, the volume V, and the numbers of moles $\{n_i\}$, as in eq. 8.2.

(with a thermostat or a water bath) and the pressure (by leaving the beaker open to the atmosphere). We would like, therefore, to define new state functions whose natural variables include T and P instead of S and V.

There is a simple trick to do this, called a **Legendre transformation**. Look at eq. 8.2: the variables appear in pairs, multiplied together, as T and S in TdS, and $-P$ and V in $-PdV$. These pairs are called *conjugate variables*. In each pair, one variable is intensive (T and $-P$), the other one is extensive (S and V), and their product has the units of an energy.[2] Now, let's subtract the product TS from U and take the differential. Using the product rule, $d(TS) = TdS + SdT$, and therefore:

$$d(U - TS) = \underbrace{TdS - PdV + \sum_i \mu_i dn_i}_{dU} - TdS - SdT = -SdT - PdV + \sum_i \mu_i dn_i. \tag{8.3}$$

The term TdS has disappeared, and it has been replaced by $-SdT$. The new function, $U - TS$, has T as a natural variable instead of S: we have swapped a knob that we cannot turn for one that we can. This is all there is to a Legendre transformation: to replace a natural variable with its conjugate partner, we subtract the product of the two from the original function. In the language of our machines, a Legendre transformation swaps one knob for its partner, as summarized in figure 8.2. The new functions obtained this way are called **thermodynamic potentials**.[3]

[2] The intensive variable can be thought of as a thermodynamic "force," and the extensive one as the corresponding "displacement," similarly to how a force times a displacement gives a work in classical mechanics.

[3] Even if we introduced both concepts in the same chapter, it is important to never confuse the *thermodynamic potentials*—which are energy functions such as H, A,




Figure 8.2.: The Legendre transformations as knob swaps. Starting from the internal energy, whose knobs are S, V, and $\{n_i\}$, we obtain the enthalpy by swapping the volume knob for the pressure knob, the Helmholtz energy by swapping the entropy knob for the temperature knob, and the Gibbs energy by swapping both. The knob of each variable has the same color in all the figures of this chapter.




Figure 8.3.: The enthalpy as a machine. Compared with the internal energy, the volume knob has been replaced by the pressure knob: its natural variables are S, P, and $\{n_i\}$.

We have already used this trick, without saying it, when we defined the enthalpy in section 3.1.4. If we take the internal energy and subtract the product of the conjugate variables $-P$ and V, we obtain $U - (-P)V = U + PV = H$, as in eq. 3.9. Taking the differential of this definition, we obtain:

$$dH = dU + VdP + PdV, \tag{8.4}$$

and using the fundamental equation, eq. 8.2, to replace dU, we obtain:

$$\begin{aligned} dH &= TdS - PdV + \sum_i \mu_i dn_i + VdP + PdV \\ &= TdS + VdP + \sum_i \mu_i dn_i, \end{aligned} \tag{8.5}$$

which is the fundamental equation for enthalpy. The natural variables of the enthalpy are S, P, and $\{n_i\}$. The Legendre transformation has allowed us to go from $U(S, V, \{n_i\})$ to $H(S, P, \{n_i\})$ by replacing the dependence on the extensive variable, V, with an intensive one, P.




Figure 8.4.: The Helmholtz energy as a machine. Compared with the internal energy, the entropy knob has been replaced by the temperature knob: its natural variables are T, V, and $\{n_i\}$.

The function that we have obtained in eq. 8.3, where we replaced the entropy with the temperature, is called the Helmholtz energy, A:

$$A = U - TS, \tag{8.6}$$

and its fundamental equation is:

---

and G—with the *chemical potential*—which describes how the energy changes with the composition.

$$\begin{aligned} dA &= dU - SdT - TdS = TdS - PdV + \sum_i \mu_i dn_i - SdT - TdS \\ &= -SdT - PdV + \sum_i \mu_i dn_i. \end{aligned} \tag{8.7}$$

The Helmholtz energy is named after Hermann Ludwig Ferdinand von Helmholtz (1821–1894), and its natural variables are temperature, volume, and the number of moles.




Figure 8.5.: The Gibbs energy as a machine. Both the entropy and the volume knobs have been replaced, by temperature and pressure: its natural variables are T, P, and $\{n_i\}$, the knobs that we control when we run a reaction in an open beaker.

Finally, we can perform both Legendre transformations at once, to replace both the entropy and the volume with their intensive partners. In that case, we define a new function called the Gibbs energy, G, as:

$$G = U - TS + PV = H - TS, \tag{8.8}$$

which, taking again the differential and using eq. 8.2 becomes:

$$\begin{aligned} dG &= dU - SdT - TdS + VdP + PdV = dH - SdT - TdS \\ &= TdS - PdV + \sum_i \mu_i dn_i - SdT - TdS + VdP + PdV \\ &= VdP - SdT + \sum_i \mu_i dn_i. \end{aligned} \tag{8.9}$$

The Gibbs energy is named after Willard Gibbs himself, and its natural variables are temperature, pressure, and number of moles: exactly the knobs that we control when we run a reaction in an open beaker.

A summary of the four thermodynamic potentials is given in the following table.

Name	Symbol	Fundamental Equation	Natural Variables
Energy	U	$dU = TdS - PdV + \sum_i \mu_i dn_i$	$S, V, \{n_i\}$
Enthalpy	H	$dH = TdS + VdP + \sum_i \mu_i dn_i$	$S, P, \{n_i\}$
Helmholtz Energy	A	$dA = -SdT - PdV + \sum_i \mu_i dn_i$	$T, V, \{n_i\}$
Gibbs Energy	G	$dG = VdP - SdT + \sum_i \mu_i dn_i$	$T, P, \{n_i\}$

A few important considerations can be made by analyzing this table:

1. **Each potential is suited to different conditions.** We should use the potential whose natural variables are the ones that we keep constant in our experiment. The internal energy is natural for an isolated, rigid container. The enthalpy is natural for heat exchanged at constant pressure, as we saw in chapter 4. The Helmholtz energy is natural for processes at constant temperature and volume, such as reactions in a sealed rigid vessel. The Gibbs energy is natural for processes at constant temperature and pressure, which is the case for most chemical reactions in the lab and for all the processes in living organisms.
2. **No information is lost.** A Legendre transformation does not throw away anything: the four potentials contain exactly the same information, written in terms of different variables.
3. **The thermodynamic potentials are the analog of the potential energy in classical mechanics.** A ball rolls downhill, and it stops at the bottom, where its potential energy is at a minimum. As we will show in the next section, a system at constant T and V evolves spontaneously towards the minimum of A, and a system at constant T and P evolves towards the minimum of G.[4]

8.3. Gibbs and Helmholtz Energies

The Legendre transformation procedure translates all information contained in the original function to the new one. Therefore, $H(S, P, \{n_i\})$, $A(T, V, \{n_i\})$, and $G(T, P, \{n_i\})$ all contain the same information that is in $U(S, V, \{n_i\})$. However, the new functions depend on different natural variables, and they are useful at different conditions. For example, when we want to study chemical changes, we are interested in studying the term $\sum_i \mu_i dn_i$ that appears in each thermodynamic potential. To do so, we need to isolate the chemical term by keeping all other natural variables constant. For example, changes in the chemical term will correspond to changes in the internal energy at constant S and constant V:

[4] For the mathematically inclined, an entertaining method to summarize the same thermodynamic potentials is the thermodynamic square.

$$dU(S,V,\{n_i\}) = \sum_i \mu_i dn_i \quad \text{if} \quad dS = dV = 0. \tag{8.10}$$

Similarly:

$$\begin{aligned} dH(S,P,\{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if} \quad dS = dP = 0, \\ dA(T,V,\{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if} \quad dT = dV = 0, \\ dG(T,P,\{n_i\}) &= \sum_i \mu_i dn_i \quad \text{if} \quad dT = dP = 0. \end{aligned} \tag{8.11}$$

The latter two cases are particularly interesting, since most of chemistry happens at constant temperature and either constant volume,[5] or constant pressure.[6] Neither of them requires the entropy to be constant, which we could not control anyway. We will now show that A and G also give us what we were looking for at the beginning of this chapter: criteria for spontaneity that depend only on the system. The starting point is the Clausius theorem, eq. 7.21, which contains the second law written in terms of the system only:

$$dS^{\text{sys}} \geq \frac{Q}{T_{\text{surr}}} \quad \longrightarrow \quad TdS \geq Q, \tag{8.12}$$

where in the second step we multiplied both sides by T, the temperature of the system and of its surroundings, which we keep constant. We can now consider two cases, side by side: constant V (left), where no work is done and the heat is $Q_V = dU$, and constant P (right), where the heat is $Q_P = dH$:

constant V :	constant P :
$TdS \geq dU$	$TdS \geq dH$
$TdS - dU \geq 0$	$TdS - dH \geq 0$

(8.13)

On the other hand, at constant temperature, $SdT = 0$, and the differentials of the definitions of A and G, eq. 8.6 and eq. 8.8, simplify to:

[5] For example, several industrial processes in sealed reactors.
[6] For example, most processes in a chemistry lab.

$$\begin{aligned} &\text{constant } T, V: && \text{constant } T, P: \\ &(dA)_{T,V} = dU - TdS && (dG)_{T,P} = dH - TdS \\ &dU = (dA)_{T,V} + TdS && dH = (dG)_{T,P} + TdS \end{aligned} \tag{8.14}$$

Replacing dU and dH from the last line of eq. 8.14 into eq. 8.13, the terms TdS cancel out, and we obtain:

$$\begin{aligned} &TdS - (dA)_{T,V} - TdS \geq 0 && TdS - (dG)_{T,P} - TdS \geq 0 \\ &(dA)_{T,V} \leq 0 && (dG)_{T,P} \leq 0. \end{aligned} \tag{8.15}$$

These are the conditions on dA and dG for inferring the spontaneity of a process. Notice how they contain only properties of the system: the entropy change of the surroundings is hidden inside them, through the heat that the system exchanges. They can be summarized as follows:

Definition 8.2.

- During a spontaneous process at constant *temperature* and *volume*, the *Helmholtz energy* will decrease ($dA < 0$), until it reaches a stationary point at which the system will be at equilibrium ($dA = 0$).
- During a spontaneous process at constant *temperature* and *pressure*, the *Gibbs energy* will decrease ($dG < 0$), until it reaches a stationary point at which the system will be at equilibrium ($dG = 0$).

8.4. Maxwell Relations

Let's consider the fundamental equations for the thermodynamic potentials that we have derived in section 8.2:




Figure 8.6.: Behavior of Helmholtz (red) and Gibbs (blue) Energies for Spontaneous Processes at Constant T, V (left) and Constant T, P (right).

$$\begin{aligned} dU(S,V,\{n_i\}) &= \;\; TdS - PdV + \sum_i \mu_i dn_i \\ dH(S,P,\{n_i\}) &= \;\; TdS + VdP + \sum_i \mu_i dn_i \\ dA(T,V,\{n_i\}) &= -SdT - PdV + \sum_i \mu_i dn_i \\ dG(T,P,\{n_i\}) &= -SdT + VdP + \sum_i \mu_i dn_i \; . \end{aligned} \tag{8.16}$$

Since we know the natural variables of each potential, we can also write the same differentials using the general formula for the total differential, eq. 1.3. Each coefficient in front of dS, dV, dT, dP, or dn_i is a partial derivative of the potential:

$$
\begin{aligned}
dU &= \underbrace{\left(\frac{\partial U}{\partial S}\right)_{V,\{n_i\}}}_{T} dS + \underbrace{\left(\frac{\partial U}{\partial V}\right)_{S,\{n_i\}}}_{-P} dV + \sum_i \underbrace{\left(\frac{\partial U}{\partial n_i}\right)_{S,V,\{n_{j\neq i}\}}}_{\mu_i} dn_i \\
dH &= \underbrace{\left(\frac{\partial H}{\partial S}\right)_{P,\{n_i\}}}_{T} dS + \underbrace{\left(\frac{\partial H}{\partial P}\right)_{S,\{n_i\}}}_{V} dP + \sum_i \underbrace{\left(\frac{\partial H}{\partial n_i}\right)_{S,P,\{n_{j\neq i}\}}}_{\mu_i} dn_i \\
dA &= \underbrace{\left(\frac{\partial A}{\partial T}\right)_{V,\{n_i\}}}_{-S} dT + \underbrace{\left(\frac{\partial A}{\partial V}\right)_{T,\{n_i\}}}_{-P} dV + \sum_i \underbrace{\left(\frac{\partial A}{\partial n_i}\right)_{T,V,\{n_{j\neq i}\}}}_{\mu_i} dn_i \\
dG &= \underbrace{\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}}}_{-S} dT + \underbrace{\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}}}_{V} dP + \sum_i \underbrace{\left(\frac{\partial G}{\partial n_i}\right)_{T,P,\{n_{j\neq i}\}}}_{\mu_i} dn_i \ ,
\end{aligned}
\tag{8.17}
$$

Comparing eq. 8.16 and eq. 8.17 term by term, we can read off what each partial derivative is equal to. For example, the coefficient of dS in dU is T in the first equation and $\left(\frac{\partial U}{\partial S}\right)_{V,\{n_i\}}$ in the second one, so these two quantities must be equal. In this way, we obtain the following new definitions:

$$
\begin{aligned}
T &= \left(\frac{\partial U}{\partial S}\right)_{V,\{n_i\}} = \left(\frac{\partial H}{\partial S}\right)_{P,\{n_i\}} \\
-P &= \left(\frac{\partial U}{\partial V}\right)_{S,\{n_i\}} = \left(\frac{\partial A}{\partial V}\right)_{T,\{n_i\}} \\
V &= \left(\frac{\partial H}{\partial P}\right)_{S,\{n_i\}} = \left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} \\
-S &= \left(\frac{\partial A}{\partial T}\right)_{V,\{n_i\}} = \left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}}
\end{aligned}
\tag{8.18}
$$

and:

$$
\begin{aligned}
\mu_i &= \left(\frac{\partial U}{\partial n_i}\right)_{S,V,\{n_{j\neq i}\}} = \left(\frac{\partial H}{\partial n_i}\right)_{S,P,\{n_{j\neq i}\}} \\
&= \left(\frac{\partial A}{\partial n_i}\right)_{T,V,\{n_{j\neq i}\}} = \left(\frac{\partial G}{\partial n_i}\right)_{T,P,\{n_{j\neq i}\}} \ .
\end{aligned}
$$

Since T, P, V, and S are now defined as first partial derivatives of a thermodynamic potential, we can take a second partial derivative with respect to the other natural variable. As we saw in chapter 1, Schwarz's theorem guarantees that, for a state function, the order in which we take the two

derivatives does not matter. Therefore, the two mixed second derivatives of each potential must be equal, which gives the following relations:

$$\begin{aligned}
\frac{\partial^2 U}{\partial S \partial V} &= +\left(\frac{\partial T}{\partial V}\right)_{S,n_i} = -\left(\frac{\partial P}{\partial S}\right)_{V,n_i} \\
\frac{\partial^2 H}{\partial S \partial P} &= +\left(\frac{\partial T}{\partial P}\right)_{S,n_i} = +\left(\frac{\partial V}{\partial S}\right)_{P,n_i} \\
-\frac{\partial^2 A}{\partial T \partial V} &= +\left(\frac{\partial S}{\partial V}\right)_{T,n_i} = +\left(\frac{\partial P}{\partial T}\right)_{V,n_i} \\
\frac{\partial^2 G}{\partial T \partial P} &= -\left(\frac{\partial S}{\partial P}\right)_{T,n_i} = +\left(\frac{\partial V}{\partial T}\right)_{P,n_i}
\end{aligned} \tag{8.19}$$

The relations in eq. 8.19 are called **Maxwell relations**,[7] and are useful in experimental settings to relate quantities that are hard to measure with others that are more intuitive. Their real power is that they let us calculate how the entropy changes with pressure or volume, which we cannot measure directly, from how P, V, and T are related, which we can measure easily.

Let's see an example. The third Maxwell relation tells us that $\left(\frac{\partial S}{\partial V}\right)_T = \left(\frac{\partial P}{\partial T}\right)_V$. For an ideal gas, $P = \frac{nRT}{V}$, and the right-hand side is easy to calculate: $\left(\frac{\partial P}{\partial T}\right)_V = \frac{nR}{V}$. Therefore, $dS = \frac{nR}{V} dV$ at constant temperature, and integrating between V_i and V_f:

$$\Delta S = nR \ln \frac{V_f}{V_i} \qquad \text{(constant } T\text{)}, \tag{8.20}$$

which is exactly the result that we obtained in eq. 7.4, using the heat exchanged along a reversible path. With the Maxwell relation, we obtained it without ever thinking about heat, starting only from the ideal gas law.

Exercise 8.1. Derive the last Maxwell relation in eq. 8.19.

Solution: We can start our derivation from the definitions of V and S as partial derivatives of G:

$$V = \left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} \qquad \text{and:} \qquad -S = \left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}},$$

and then take a second partial derivative of each quantity with respect to the second variable:

[7] Maxwell relations should not be confused with the Maxwell equations of electromagnetism.

$$\left(\frac{\partial V}{\partial T}\right)_{P,\{n_i\}} = \frac{\partial}{\partial T}\left[\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}}\right]_{P,\{n_i\}}$$

$$-\left(\frac{\partial S}{\partial P}\right)_{T,\{n_i\}} = \frac{\partial}{\partial P}\left[\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}}\right]_{T,\{n_i\}} .$$

These two derivatives are mixed partial second derivatives of G with respect to T and P, and therefore, according to Schwarz's theorem, they are equal to each other:

$$\frac{\partial}{\partial T}\left[\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}}\right]_{P,\{n_i\}} = \frac{\partial}{\partial P}\left[\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}}\right]_{T,\{n_i\}} ,$$

hence:

$$\left(\frac{\partial V}{\partial T}\right)_{P,\{n_i\}} = -\left(\frac{\partial S}{\partial P}\right)_{T,\{n_i\}} ,$$

which is the last of Maxwell relations, as defined in eq. 8.19. This relation is particularly useful because it connects the quantity $\left(\frac{\partial S}{\partial P}\right)_{T,\{n_i\}}$—which is impossible to measure in a lab—with the quantity $\left(\frac{\partial V}{\partial T}\right)_{P,\{n_i\}}$—which is easier to measure from an experiment that determines isobaric volumetric thermal expansion coefficients.

8.5. Chapter Review

8.5.1. Study Questions

1. What is the fundamental equation of thermodynamics for a closed system?

a. $dU = TdS + PdV$.
b. $dU = Q - PdV$ only for reversible processes.
c. $dU = TdS - PdV$.
d. $dU = SdT - VdP$.
e. $dU = TdS - VdP$.

---

2. Why does the fundamental equation apply to irreversible processes too, even if it was derived for reversible ones?

a. Because it contains only state functions.
b. Because irreversible processes do not exist.
c. Because heat is a state function.
d. Because it contains the entropy.
e. Because it is an approximation.

---

3. What is the chemical potential?

a. The energy stored in chemical bonds.
b. The potential energy of a molecule.
c. The pressure of a chemical species.
d. The energy needed to break a molecule into atoms.
e. The amount of energy absorbed or released due to a change in the number of particles of a chemical species.

---

4. What are the natural variables of the internal energy?

a. T, P, $\{n_i\}$.
b. S, V, $\{n_i\}$.
c. T, V, $\{n_i\}$.
d. S, P, $\{n_i\}$.
e. U, V, T.

---

5. What does a Legendre transformation do?

a. It adds heat to the system.
b. It removes all information from the original function.
c. It converts a path function into a state function.
d. It defines a new function by subtracting a product of conjugate variables, replacing one natural variable with its conjugate.
e. It changes the units of the energy.

---

6. What are the natural variables of the Gibbs energy?

a. T, P, $\{n_i\}$.
b. S, V, $\{n_i\}$.
c. T, V, $\{n_i\}$.
d. S, P, $\{n_i\}$.
e. G, H, S.

---

7. What is the fundamental equation for the Helmholtz energy?

a. $dA = TdS - PdV + \sum_i \mu_i dn_i$.
b. $dA = -SdT + VdP + \sum_i \mu_i dn_i$.
c. $dA = -SdT - PdV + \sum_i \mu_i dn_i$.
d. $dA = TdS + VdP + \sum_i \mu_i dn_i$.
e. $dA = SdT + PdV$.

---

8. What is the condition for a spontaneous process at constant temperature and pressure?

a. $dA < 0$.
b. $dS = 0$.
c. $dH > 0$.
d. $dG > 0$.
e. $dG < 0$, until $dG = 0$ at equilibrium.

---

9. From which mathematical property do the Maxwell relations follow?

a. The first law of thermodynamics.
b. The equality of the mixed second derivatives of a state function (Schwarz's theorem).
c. The ideal gas law.
d. The definition of the chemical potential.
e. The Clausius inequality.

---

10. Why is the Maxwell relation $\left(\frac{\partial V}{\partial T}\right)_P = -\left(\frac{\partial S}{\partial P}\right)_T$ useful?

a. Because it shows that the entropy is constant.
b. Because it defines the temperature.
c. Because it is valid only for ideal gases.
d. Because it relates a quantity that is hard to measure (how S changes with P) to one that is easy to measure (thermal expansion).
e. Because it gives the value of the Gibbs energy.

Answers

1.c, 2.a, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

9. Gibbs Energy

In chapter 8, we found that, at constant temperature and pressure, a process is spontaneous if it decreases the Gibbs energy of the system. In this chapter, we will concentrate on chemical processes that happen at these conditions.[1] We will learn how to calculate the Gibbs energy of a reaction from tabulated data, and how the Gibbs energy changes with temperature, pressure, and composition. These three dependencies will be the foundations of the next chapters on chemical equilibrium, phase equilibrium, and solutions.

9.1. Gibbs Equation

Recalling from chapter 8, the definition of G is:

$$G = U - TS + PV = H - TS, \tag{9.1}$$

which, taking the differential at constant T and P, becomes:

$$dG = dH \overbrace{- SdT}^{=0} - TdS = dH - TdS. \tag{9.2}$$

Integrating eq. 9.2 between the initial and final states of a process results in:

$$\begin{gathered} \int_i^f dG = \int_i^f dH - T \int_i^f dS \\ \Delta G = \Delta H - T\Delta S \end{gathered} \tag{9.3}$$

which is the famous **Gibbs equation** for ΔG. Using Definition 8.2, we can use ΔG to infer the spontaneity of a chemical process that happens at constant T and P using $\Delta G \leq 0$. If we set ourselves at standard conditions,

[1] The majority of chemical reactions in a lab happen at those conditions, and all biological functions happen at those conditions as well.

we can calculate the standard Gibbs energy of reaction, $\Delta_{\text{rxn}}G^{\ominus}$, for any reaction as:

$$\begin{aligned}\Delta_{\text{rxn}}G^{\ominus} &= \Delta_{\text{rxn}}H^{\ominus} - T\Delta_{\text{rxn}}S^{\ominus} \\ &= \sum_i \nu_i \Delta_{\text{f}}H_i^{\ominus} - T\sum_i \nu_i S_i^{\ominus},\end{aligned} \tag{9.4}$$

where $\Delta_{\text{f}}H_i^{\ominus}$ are the standard enthalpies of formation, $S_i^{\ominus}$ are the standard entropies, and ν_i are the stoichiometric coefficients for every species i involved in the reaction. All these quantities are commonly available, and we have already discussed their usage in chapter 4 and chapter 7, respectively.[2]

The following four options are possible for $\Delta G^{\ominus}$ of a chemical reaction:

$\Delta G^{\ominus}$		$\Delta H^{\ominus}$	$\Delta S^{\ominus}$	Spontaneous?
$-$	*if*	$-$	$+$	*Always*
$+$	*if*	$+$	$-$	*Never*
$-/+$	*if*	$-$	$-$	*Depends on T:* spontaneous at low T
$+/-$	*if*	$+$	$+$	*Depends on T:* spontaneous at high T

Or, in other words:

- Exothermic reactions that increase the entropy are always spontaneous.
- Endothermic reactions that reduce the entropy are always non-spontaneous.
- For the other two cases, the spontaneity of the reaction depends on the temperature:
  - Exothermic reactions that reduce the entropy are spontaneous at low T.
  - Endothermic reactions that increase the entropy are spontaneous at high T.

[2] It is not uncommon to see values of $\Delta_{\text{f}}G^{\ominus}$ tabulated alongside $\Delta_{\text{f}}H^{\ominus}$ and $S_i^{\ominus}$, which simplifies even further the calculation. In fact, a comprehensive list of standard Gibbs energy of formation of inorganic and organic compounds is reported in the appendix of this book (Appendix A). For cases where $\Delta_{\text{f}}G^{\ominus}$ are not reported, they can always be calculated from their constituents.

A simple criterion to estimate the sign of the entropy change of a reaction is to count the moles of *gas* among the reactants and the products. Gases have much larger entropies than liquids and solids, since their molecules can occupy a much larger volume. Therefore, if the reaction produces more moles of gas than it consumes, it will most likely increase the entropy. Vice versa, if the number of moles of gas decreases, the entropy will most likely decrease. For example, the combustion of methane, $CH_{4(g)} + 2O_{2(g)} \rightarrow CO_{2(g)} + 2H_2O_{(l)}$, goes from 3 moles of gas to 1, and its entropy change is indeed negative. This criterion is only a rule of thumb: when the number of moles of gas does not change, we need the tabulated entropies to decide.

As we saw in section 8.2, the natural variables of the Gibbs energy are the temperature, T, the pressure, P, and chemical composition, as the number of moles $\{n_i\}$. The Gibbs energy can therefore be expressed using the total differential as (see also the last formula in eq. 8.17):

$$dG(T,P,\{n_i\}) = \underbrace{\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}}}_{\text{temperature dependence}} dT + \underbrace{\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}}}_{\text{pressure dependence}} dP + \sum_i \underbrace{\left(\frac{\partial G}{\partial n_i}\right)_{T,P,\{n_{j\neq i}\}}}_{\text{composition dependence}} dn_i. \tag{9.5}$$

If we know the behavior of G as we vary each of the three natural variables independently of the other two, we can reconstruct the total differential dG. Each of these terms represents a coefficient in eq. 9.5, which are given in eq. 8.18.

9.2. Temperature Dependence of ΔG

$$\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}} = -S$$

Let's analyze the first coefficient that gives the dependence of the Gibbs energy on temperature. Since this coefficient is equal to $-S$ and the entropy is always positive, G must decrease when T increases at constant P and $\{n_i\}$, and vice versa.

If we replace this coefficient for $-S$ in the Gibbs equation, eq. 9.3, we obtain:

$$\Delta G = \Delta H + T\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}}, \tag{9.6}$$

and since eq. 9.6 includes both ΔG and its partial derivative with respect to temperature $\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}}$ we need to rearrange it to include the temperature derivative only. To do so, we can start by evaluating the partial derivative of $\left(\frac{\Delta G}{T}\right)$ using the product rule:

$$\left[\frac{\partial\left(\frac{\Delta G}{T}\right)}{\partial T}\right]_{P,\{n_i\}} = \frac{1}{T}\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}} - \frac{1}{T^2}\Delta G, \tag{9.7}$$

which, replacing ΔG from eq. 9.6 into eq. 9.7, becomes:

$$\begin{aligned}\left[\frac{\partial\left(\frac{\Delta G}{T}\right)}{\partial T}\right]_{P,\{n_i\}} &= \frac{1}{T}\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}} - \frac{1}{T^2}\left[\Delta H + T\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}}\right] \\ &= \frac{1}{T}\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}} - \frac{\Delta H}{T^2} - \frac{1}{T}\left(\frac{\partial \Delta G}{\partial T}\right)_{P,\{n_i\}},\end{aligned} \tag{9.8}$$

which simplifies to:

$$\left[\frac{\partial\left(\frac{\Delta G}{T}\right)}{\partial T}\right]_{P,\{n_i\}} = -\frac{\Delta H}{T^2}. \tag{9.9}$$

Eq. 9.9 is known as the **Gibbs–Helmholtz equation**, and is useful in its integrated form to calculate the Gibbs energy for a chemical reaction at any temperature T by knowing just the standard Gibbs energy of formation and the standard enthalpy of formation for the individual species, which are usually reported at $T = 298$ K. The integration is performed as follows:

$$\begin{aligned}\int_{T_i=298\text{ K}}^{T_f=T} \frac{\partial\left(\frac{\Delta_{\text{rxn}} G}{T}\right)}{\partial T} &= -\int_{T_i=298\text{ K}}^{T_f=T} \frac{\Delta_{\text{rxn}} H}{T^2} \\ \frac{\Delta_{\text{rxn}} G^{\ominus}(T)}{T} &= \frac{\Delta_{\text{rxn}} G^{\ominus}}{298\text{ K}} + \Delta_{\text{rxn}} H^{\ominus}\left(\frac{1}{T} - \frac{1}{298\text{ K}}\right),\end{aligned} \tag{9.10}$$

giving the integrated Gibbs–Helmholtz equation:

$$\frac{\Delta_{\text{rxn}} G^{\ominus}(T)}{T} = \frac{\sum_i \nu_i \Delta_{\text{f}} G_i^{\ominus}}{298\text{ K}} + \sum_i \nu_i \Delta_{\text{f}} H_i^{\ominus}\left(\frac{1}{T} - \frac{1}{298\text{ K}}\right) \tag{9.11}$$

9.3. Pressure Dependence of ΔG

$$\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = V$$

We can now turn our attention to the second coefficient that gives how the Gibbs energy changes when the pressure changes. To do this, we put the system at constant T and $\{n_i\}$, and then we consider infinitesimal variations of G. From eq. 8.9:

$$dG = VdP - SdT + \sum_i \mu_i dn_i \quad \xrightarrow{\text{constant } T,\{n_i\}} \quad dG = VdP, \tag{9.12}$$

which is the differential equation that we were looking for. To study changes of G for macroscopic changes in P, we can integrate eq. 9.12 between initial and final pressures, and considering an ideal gas, we obtain:

$$\begin{aligned} \int_i^f dG &= \int_i^f VdP \\ \Delta G &= nRT \int_i^f \frac{dP}{P} = nRT \ln \frac{P_f}{P_i}. \end{aligned} \tag{9.13}$$

If we take $P_i = P^\ominus = 1\,\text{bar}$, we can rewrite eq. 9.13 as:

$$G = G^\ominus + nRT \ln \frac{P_f}{P^\ominus}, \tag{9.14}$$

which is useful to convert standard Gibbs energies of formation to pressures different from standard pressure, using:

$$\Delta_\text{f} G = \Delta_\text{f} G^\ominus + nRT \ln \frac{P_f}{\underbrace{P^\ominus}_{=1\text{ bar}}} = \Delta_\text{f} G^\ominus + nRT \ln P_f \tag{9.15}$$

For liquids and solids, V is essentially independent of P (liquids and solids are incompressible), and eq. 9.12 can be integrated as:

$$\Delta G = \int_i^f VdP = V \int_i^f dP = V\Delta P. \tag{9.16}$$

The plots in Figure 9.1 show the remarkable difference in the behaviors of $\Delta_\text{f} G$ for a gas and for a liquid, as obtained from eq. 9.13 and eq. 9.16.




Figure 9.1.: Pressure Dependence of the Gibbs Energy of Formation of Liquid and Gaseous Ethanol at T = 310 K. The Curves Cross at the Vapor Pressure of Liquid Ethanol at this Temperature, which is 0.15 bar.

9.4. Composition Dependence of ΔG

$$\left(\frac{\partial G}{\partial n_i}\right)_{T,P} = \mu_i$$

The third and final coefficient gives the chemical potential as the dependence of G on the chemical composition at constant T and P. To understand what the chemical potential means, let's consider a pure substance, and let's imagine building a sample of it by adding small amounts, dn, one after the other, at constant T and P. Each small amount that we add is identical to what is already in the sample. Therefore, each of them changes the Gibbs energy by the same amount, $dG = \mu^* dn$, where μ^* indicates the chemical potential of the pure substance. In other words, μ^* is an intensive property: it depends on T and P, but not on how much substance we have. Since the Gibbs energy is extensive, when there is no substance there is also no Gibbs energy. We can then integrate from an empty sample ($n = 0$, $G = 0$) to a sample with n moles and Gibbs energy G:

$$\int_0^G dG = \int_0^n \mu^* dn, \tag{9.17}$$

and since μ^* does not depend on the number of moles, we can take it out of the integral:

$$\int_0^G dG = \mu^* \int_0^n dn \quad \rightarrow \quad G = \mu^* n \quad \rightarrow \quad \mu^* = \frac{G}{n}, \tag{9.18}$$

which gives a straightforward interpretation of the chemical potential of a pure substance as the molar Gibbs energy.

We can start from eq. 9.14 and write for a pure substance that is brought from $P_i = P^{\ominus}$ to $P_f = P$ at constant T:

$$G - G^{\ominus} = nRT \ln \frac{P}{P^{\ominus}}, \tag{9.19}$$

dividing both sides by n, we obtain:

$$\frac{G}{n} - \frac{G^{\ominus}}{n} = RT \ln \frac{P}{P^{\ominus}}, \tag{9.20}$$

which, for a pure substance at $P^{\ominus} = 1$ bar, becomes:

$$\mu^* - \mu^{\ominus} = RT \ln P. \tag{9.21}$$

Notice that, while we use the pressure of the gas inside the logarithm in eq. 9.21, the quantity is formally divided by the standard pressure $P^{\ominus} = 1$ bar, and therefore it is a dimensionless quantity, as it should be. For simplicity of notation, however, we will omit the division by $P^{\ominus}$ in the remainder of this textbook, especially wherever it does not create confusion. Let's now consider a mixture of ideal gases, and let's try to find out whether the chemical potential of a pure gas inside the mixture, μ_i^{mixture}, is the same as its chemical potential outside the mixture, μ^*. To do so, we can use eq. 9.21 and replace the pressure P with the partial pressure P_i:

$$\mu_i^{\text{mixture}} = \mu_i^{\ominus} + RT \ln P_i, \tag{9.22}$$

where the partial pressure P_i can be obtained from the simple relation that is known as **Dalton's Law**:

$$P_i = y_i P, \tag{9.23}$$

with y_i being the concentration of gas i measured as a mole fraction in the gas phase $y_i = \frac{n_i}{n_{\text{TOT}}} < 1$. Replacing eq. 9.23 into eq. 9.22, we obtain:

$$\begin{aligned}\mu_i^{\text{mixture}} &= \mu_i^{\ominus} + RT\ln(y_i P) \\ &= \underbrace{\mu_i^{\ominus} + RT\ln P}_{\mu_i^*} + RT\ln y_i,\end{aligned} \tag{9.24}$$

which then reduces to the following equation:

$$\mu_i^{\text{mixture}} = \mu_i^* + RT\ln y_i. \tag{9.25}$$

Analyzing eq. 9.25, we can immediately see that, since $y_i < 1$:

$$\mu_i^{\text{mixture}} < \mu_i^*, \tag{9.26}$$

or, in other words, the chemical potential of a substance in the mixture is always lower than the chemical potential of the pure substance. If we consider a process where we start from two separate pure ideal gases and finish with a mixture of the two, we can calculate the change in Gibbs energy due to the mixing process with:

$$\Delta_{\text{mixing}}G = \sum n_i \left(\mu_i^{\text{mixture}} - \mu_i^*\right) < 0, \tag{9.27}$$

or, in other words, the process is spontaneous under all circumstances, and pure ideal gases will always mix.

9.5. Chapter Review

9.5.1. Study Questions

1. Which equation gives the Gibbs energy change of a process at constant T and P?

a. $\Delta G = \Delta H + T\Delta S$.
b. $\Delta G = \Delta H - T\Delta S$.
c. $\Delta G = \Delta U - T\Delta S$.
d. $\Delta G = T\Delta S - \Delta H$.
e. $\Delta G = \Delta H \cdot \Delta S$.

---

2. An exothermic reaction decreases the entropy of the system. When is it spontaneous?

a. Always.
b. Never.
c. Only at high temperature.
d. Only at low temperature.
e. Only at high pressure.

---

3. An endothermic reaction increases the entropy of the system. When is it spontaneous?

a. Only at high temperature.
b. Only at low temperature.
c. Always.
d. Never.
e. Only at low pressure.

---

4. Since $\left(\frac{\partial G}{\partial T}\right)_{P,\{n_i\}} = -S$, how does the Gibbs energy of a substance change when the temperature increases?

a. It increases, since the entropy is positive.
b. It stays constant.
c. It increases linearly with the volume.
d. It oscillates.
e. It decreases, since the entropy is positive.

---

5. What is the Gibbs–Helmholtz equation?

a. $\left(\frac{\partial G}{\partial P}\right)_T = V$.
b. $\Delta G = \Delta H - T\Delta S$.
c. $\left[\frac{\partial(\Delta G/T)}{\partial T}\right]_P = -\frac{\Delta H}{T^2}$.
d. $\left[\frac{\partial(\Delta G/T)}{\partial T}\right]_P = \frac{\Delta S}{T^2}$.
e. $\Delta G = -RT \ln K$.

---

6. What is the pressure dependence coefficient of the Gibbs energy?

a. $\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = -V.$
b. $\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = V.$
c. $\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = -S.$
d. $\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = H.$
e. $\left(\frac{\partial G}{\partial P}\right)_{T,\{n_i\}} = 0.$

---

7. How does the Gibbs energy of an ideal gas depend on the pressure at constant temperature?

a. $G = G^{\ominus} - nRT \ln \frac{P}{P^{\ominus}}$.
b. $G = G^{\ominus} + nRT \frac{P}{P^{\ominus}}$.
c. $G = G^{\ominus} + V\Delta P$.
d. $G = G^{\ominus} + nRT \ln \frac{P}{P^{\ominus}}$.
e. G does not depend on P.

---

8. Why does the Gibbs energy of a liquid change much less with pressure than that of a gas?

a. Because the molar volume of a liquid is small and almost independent of pressure.
b. Because liquids have zero entropy.
c. Because liquids are always at standard pressure.
d. Because the Gibbs energy of a liquid is zero.
e. Because liquids do not have a chemical potential.

---

9. What is the chemical potential of a pure substance?

a. Its enthalpy.
b. Its entropy per mole.
c. Its pressure divided by RT.
d. Zero at standard conditions.
e. Its molar Gibbs energy, $\mu^* = G/n$.

---

10. Two pure ideal gases are allowed to mix at constant T and P. What is the sign of $\Delta_{\text{mixing}}G$?

a. Positive, so the gases do not mix.
b. Zero, since ideal gases do not interact.
c. Negative, so the gases always mix spontaneously.
d. It depends on the gases.
e. It depends on the temperature.

Answers

1.b, 2.d, 3.a, 4.e, 5.c, 6.b, 7.d, 8.a, 9.e, 10.c

10. Chemical Equilibrium

In chapter 9, we learned that the Gibbs energy decreases during a spontaneous process at constant temperature and pressure, and we found how it depends on the composition of a mixture. In this chapter, we will apply these results to chemical reactions. Most reactions do not go all the way to products: they stop at a mixture of reactants and products, the chemical equilibrium. We will see that the composition of this mixture is set by the minimum of the Gibbs energy, which leads us to the equilibrium constant that you know from general chemistry. We will then study how the equilibrium constant changes with temperature and pressure, which gives a mathematical form to Le Chatelier's principle.

10.1. Reaction Quotient and Equilibrium Constant

Let's consider a prototypical reaction at constant T, P:

$$a\mathrm{A} + b\mathrm{B} \rightarrow c\mathrm{C} + d\mathrm{D} \tag{10.1}$$

The Gibbs energy of the reaction is defined as:

$$\Delta_{\mathrm{rxn}} G = G_{\mathrm{products}} - G_{\mathrm{reactants}} = G^{\mathrm{C}} + G^{\mathrm{D}} - G^{\mathrm{A}} - G^{\mathrm{B}}, \tag{10.2}$$

and replacing the absolute Gibbs energies with the chemical potentials μ_i, we obtain:

$$\Delta_{\mathrm{rxn}} G = c\mu_{\mathrm{C}} + d\mu_{\mathrm{D}} - a\mu_{\mathrm{A}} - b\mu_{\mathrm{B}}. \tag{10.3}$$

Assuming the reaction is happening in the gas phase, we can then use eq. 9.22 to replace the chemical potentials with their value in the reaction mixture, as:

$$\begin{aligned}\Delta_{\text{rxn}}G &= c(\mu_{\text{C}}^{\ominus} + RT\ln P_{\text{C}}) + d(\mu_{\text{D}}^{\ominus} + RT\ln P_{\text{D}}) + \\ &\quad - a(\mu_{\text{A}}^{\ominus} + RT\ln P_{\text{A}}) - b(\mu_{\text{B}}^{\ominus} + RT\ln P_{\text{B}}) \\ &= \underbrace{c\mu_{\text{C}}^{\ominus} + d\mu_{\text{D}}^{\ominus} - a\mu_{\text{A}}^{\ominus} - b\mu_{\text{B}}^{\ominus}}_{\Delta_{\text{rxn}}G^{\ominus}} + RT\ln\frac{P_{\text{C}}^{c}\cdot P_{\text{D}}^{d}}{P_{\text{A}}^{a}\cdot P_{\text{B}}^{b}}.\end{aligned} \tag{10.4}$$

We can define a new quantity called the *reaction quotient* as a function of the partial pressures of each substance:[1]

$$Q_P = \frac{P_{\text{C}}^{c}\cdot P_{\text{D}}^{d}}{P_{\text{A}}^{a}\cdot P_{\text{B}}^{b}}, \tag{10.5}$$

and we can then simply rewrite eq. 10.4 using eq. 10.5 as:

$$\Delta_{\text{rxn}}G = \Delta_{\text{rxn}}G^{\ominus} + RT\ln Q_P. \tag{10.6}$$

This equation tells us that the sign of $\Delta_{\text{rxn}}G$ is influenced by the reaction quotient Q_P. For a spontaneous reaction at the beginning, the partial pressures of the reactants are much higher than the partial pressures of the products, therefore $Q_P \ll 1$ and $\Delta_{\text{rxn}}G < 0$, as we expect. As the reaction proceeds, the partial pressures of the products will increase, while the partial pressures of the reactants will decrease. Consequently, both Q_P and $\Delta_{\text{rxn}}G$ will increase. The reaction will completely stop when $\Delta_{\text{rxn}}G = 0$, which is the chemical equilibrium point. At the reaction equilibrium:

$$\Delta_{\text{rxn}}G = 0 = \Delta_{\text{rxn}}G^{\ominus} + RT\ln K_P, \tag{10.7}$$

where we have defined a new quantity called **equilibrium constant**, as the value the reaction quotient assumes when the reaction reaches equilibrium, and we have denoted it with the symbol K_P.[2] From eq. 10.7 we can derive the following fundamental equation on the standard Gibbs energy of reaction:

$$\Delta_{\text{rxn}}G^{\ominus} = -RT\ln K_P. \tag{10.8}$$

To extend the concept of K_P beyond the four species in the prototypical reaction eq. 10.1, we can use the product of a series symbol $\left(\prod_i\right)$, and write:

[1] Notice that since we used eq. 9.21 to derive the reaction quotient, the partial pressures inside it are always dimensionless since they are divided by $P^{\ominus}$.

[2] The subscript P refers to the fact that the equilibrium constant is measured in terms of partial pressures.

$$K_P = \prod_i P_{i,\text{eq}}^{\nu_i}, \tag{10.9}$$

where $P_{i,\text{eq}}$ are the partial pressures of each species at equilibrium. Eq. 10.9 is in principle valid for ideal gases only. However, reactions involving ideal gases are pretty rare. As such, we can further extend the concept of equilibrium constant and write:

$$K_{\text{eq}} = \prod_i a_{i,\text{eq}}^{\nu_i}, \tag{10.10}$$

where we have replaced the partial pressure at equilibrium, $P_{i,\text{eq}}$, with a new concept introduced initially by Gilbert Newton Lewis (1875–1946),[3] that he termed **activity**, and represented by the letter a. The activity is a dimensionless "effective concentration" that tells us how much each species contributes to the equilibrium. Its expression depends on the state of the species:

- **Ideal gases:** the activity is the partial pressure divided by the standard pressure, $a_i = P_i/P^{\ominus}$, as in eq. 10.9.
- **Non-ideal gases:** the pressure is replaced by an "effective pressure," the fugacity, $a_i = f_i/P^{\ominus}$, which we will introduce in chapter 11.
- **Pure liquids and solids:** the activity is simply $a_i = 1$. This is why pure solids and liquids do not appear in the equilibrium constants that you wrote in general chemistry.
- **Solutions:** for dilute solutions, the activity is approximately equal to a measured concentration, such as the mole fraction, or the molar concentration divided by the standard one, $[i]/[i]^{\ominus}$ with $[i]^{\ominus} = 1$ mol/L. For concentrated solutions, a correction factor is needed. We will derive the activity of solutions in chapter 13.

For now, it is interesting to use the activity to write the definition of the following two constants:

$$K_y = \prod_i \left(y_{i,\text{eq}}\right)^{\nu_i} \qquad\qquad K_C = \prod_i \left([i]_{\text{eq}}/[i]^{\ominus}\right)^{\nu_i}, \tag{10.11}$$

which can then be related with K_P for a mixture of ideal gases using:

$$P_i = y_i P \qquad\qquad P_i = \frac{n_i}{V} RT = [i]RT, \tag{10.12}$$

which then results in:

[3] Gilbert Lewis is the same scientist who invented the concept of Lewis Structures.

$$K_P = K_y \cdot \left(\frac{P}{P^\ominus}\right)^{\Delta\nu} \qquad K_P = K_C \left(\frac{[i]^\ominus RT}{P^\ominus}\right)^{\Delta\nu}, \tag{10.13}$$

with $\Delta\nu = \sum_i \nu_i$.

Using the general equilibrium constant, K_{eq}, we can also rewrite the fundamental equation on $\Delta_{\text{rxn}}G^\ominus$ that we derived in eq. 10.8 to be applicable at most conditions, as:

$$\Delta_{\text{rxn}}G^\ominus = -RT \ln K_{\text{eq}}, \tag{10.14}$$

and since $\Delta_{\text{rxn}}G^\ominus$ depends on T, P and $\{n_i\}$, it is useful to explore how K_{eq} depends on those variables as well.

10.2. Temperature Dependence of K_{eq}

To study the temperature dependence of K_{eq} we can use eq. 10.14 for the general equilibrium constant and write:

$$\ln K_{\text{eq}} = -\frac{\Delta G^\ominus}{RT}, \tag{10.15}$$

which we can then differentiate with respect to temperature at constant $P, \{n_i\}$ on both sides:

$$\left(\frac{\partial \ln K_{\text{eq}}}{\partial T}\right)_{P,\{n_i\}} = -\frac{1}{R}\left[\frac{\partial\left(\frac{\Delta G^\ominus}{T}\right)}{\partial T}\right]_{P,\{n_i\}}, \tag{10.16}$$

and, using the Gibbs–Helmholtz equation (eq. 9.9) to simplify the right-hand side, becomes:

$$\left(\frac{\partial \ln K_{\text{eq}}}{\partial T}\right)_{P,\{n_i\}} = -\frac{1}{R}\left(-\frac{\Delta H^\ominus}{T^2}\right) = \frac{\Delta H^\ominus}{RT^2}, \tag{10.17}$$

which gives the dependence of $\ln K_{\text{eq}}$ on T that we were looking for. Eq. 10.17 is also called **van 't Hoff equation**,[4] and it is the mathematical expression of Le Chatelier's principle. The simplest interpretation is as follows:

[4] named after Jacobus Henricus "Henry" van 't Hoff Jr. (1852–1911).

- For an exothermic reaction ($\Delta H^{\ominus} < 0$): K_{eq} will decrease as the temperature increases.
- For an endothermic reaction ($\Delta H^{\ominus} > 0$): K_{eq} will increase as the temperature increases.

If we integrate the van 't Hoff equation between two arbitrary points at constant P, and assuming constant $\Delta H^{\ominus}$, we obtain the following:

$$\int_1^2 d \ln K_{\text{eq}} = \frac{\Delta H^{\ominus}}{R} \int_1^2 \frac{dT}{T^2}, \tag{10.18}$$

which leads to the linear equation:

$$\ln K_{\text{eq}}(2) = \ln K_{\text{eq}}(1) - \frac{\Delta H^{\ominus}}{R} \left(\frac{1}{T_2} - \frac{1}{T_1} \right), \tag{10.19}$$

which is the equation that produces the so-called **van 't Hoff plots**, from which $\Delta H^{\ominus}$ can be experimentally determined:




Figure 10.1.: Van 't Hoff Plots for an Endothermic (Left, Blue) and an Exothermic (Right, Red) Reaction at Constant P.

10.3. Pressure and Composition Dependence of K_{eq}

While K_P is independent of both total pressure and number of moles for an ideal gas, the same is not necessarily true for the other equilibrium constants.

$$\left(\frac{\partial K_P}{\partial P}\right)_{T,\{n_i\}} = 0 \qquad \left(\frac{\partial K_P}{\partial n_i}\right)_{T,P} = 0. \tag{10.20}$$

For example, it is easy to look at eq. 10.13 and determine that K_y usually depends on P.[5] Using Dalton's Law, eq. 9.23, we can also notice that the equilibrium partial pressures of the reactants and products in a gas-phase reaction can be expressed in terms of their equilibrium mole fractions y_i and the total pressure P. As such, we can use K_y to demonstrate that the equilibrium mole fractions will change when P changes,[6] as it is demonstrated by the following exercise.

Exercise 10.1. Calculate the mole fraction change for the dissociation of $Cl_{2(g)}$ when the pressure is increased from $P^\ominus$ to $P_f = 2.5$ bar at constant $T = 2\,298$ K, knowing that $\Delta_f G^\ominus_{Cl_{(g)}} = 105.3$ kJ/mol and $\Delta_f H^\ominus_{Cl_{(g)}} = 121.3$ kJ/mol, and remembering that both of these values are tabulated at $T = 298$ K.

Solution: Let's consider the reaction:

$$Cl_{2(g)} \rightleftarrows 2Cl_{(g)}$$

We can divide the exercise into two parts. In the first one, we will deal with calculating the equilibrium constant at $T = 2\,298$ K from the data at $T = 298$ K. In the second one, we will calculate the change in mole fraction when the pressure is increased from $P^\ominus = 1$ bar to $P_f = 2.5$ bar.

- Let's begin the first part by calculating $\Delta_{rxn} G^\ominus$ and $\Delta_{rxn} H^\ominus$ from:

$$\Delta_{rxn} G^\ominus = 2\Delta_f G^\ominus_{Cl_{(g)}} - \Delta_f G^\ominus_{Cl_{2(g)}}$$
$$\Delta_{rxn} H^\ominus = 2\Delta_f H^\ominus_{Cl_{(g)}} - \Delta_f H^\ominus_{Cl_{2(g)}},$$

  and since $Cl_{2(g)}$ is an element in its most stable form at $T = 298$ K, its standard enthalpy and Gibbs energy of formation are $\Delta_f H^\ominus_{Cl_{2(g)}} = \Delta_f G^\ominus_{Cl_{2(g)}} = 0$. Therefore:[7]

$$\Delta_{rxn} G^\ominus = 2 \cdot 105.3 - 0 = 210.6 \text{ kJ/mol}$$
$$\Delta_{rxn} H^\ominus = 2 \cdot 121.3 - 0 = 242.6 \text{ kJ/mol}.$$

[5] K_y becomes independent of P in the particular case where $\Delta\nu = 0$, i.e., for reactions where the total number of moles of reactants is the same as the total number of moles of the products.

[6] Keep in mind that K_P will *not* change.

[7] Notice how a positive $\Delta_{rxn} G^\ominus$ indicates that the dissociation of $Cl_{2(g)}$ is non-spontaneous at $T = 298$ K and $P = 1$ bar. As such, we should expect a very small value for K_P.

Using eq. 10.8 to calculate $K_P(P^\ominus, 298\text{ K})$, we obtain:[8]

$$\ln[K_P(P^\ominus, 298\text{ K})] = \frac{-\Delta_{\text{rxn}}G^\ominus}{RT} = \frac{-210.6 \times 10^3}{8.31 \cdot 298} = -85.0.$$

We can now use the integrated van 't Hoff equation, eq. 10.19, to calculate K_P at $T = 2\,298$ K:

$$\ln[K_P(P^\ominus,2\,298\text{ K})] = \ln[K_P(P^\ominus, 298\text{ K})] + \\ - \frac{\Delta_{\text{rxn}}H^\ominus}{R}\left(\frac{1}{2\,298} - \frac{1}{298}\right),$$

which becomes:

$$\ln[K_P(P^\ominus,2\,298\text{ K})] = -85.0 + \\ - \frac{242.6 \times 10^3}{8.31}\left(\frac{1}{2\,298} - \frac{1}{298}\right) = 0.262\,,$$

which corresponds to:

$$K_P(P^\ominus, 2\,298\text{ K}) = \exp(0.262) = 1.30.$$

- Let's now move to the second part of the exercise, where we increase the pressure from 1 bar to 2.5 bar at constant $T = 2\,298$ K. We start by writing the definition of K_P and K_y:

$$K_P = \frac{P^2_{\text{Cl}_{(g)}}}{P_{\text{Cl}_{2(g)}}} \qquad\qquad K_y = \frac{y^2_{\text{Cl}_{(g)}}}{y_{\text{Cl}_{2(g)}}},$$

and using eq. 10.13:

$$\Delta\nu = 2 - 1 = 1$$
$$K_P = K_y \cdot \frac{P}{P^\ominus} \quad \longrightarrow K_y = K_P\left(\frac{P}{P^\ominus}\right)^{-1},$$

we can calculate the initial K_y at $P_i = P^\ominus$, using:

$$K_y(P^\ominus, 2\,298\text{ K}) = 1.30 = \frac{1.30}{1}.$$

and calculate the initial concentration of $\text{Cl}_{2(g)}$ and $\text{Cl}_{(g)}$ at $P^\ominus$, recalling that $y_{\text{Cl}_{2(g)}} = 1 - y_{\text{Cl}_{(g)}}$:

$$K_y(P_i, 2\,298\text{ K}) = \frac{\left(y^i_{\text{Cl}_{(g)}}\right)^2}{1 - y^i_{\text{Cl}_{(g)}}} = 1.30.$$

[8] The result corresponds to $K_P = 1.2 \times 10^{-37}$, an incredibly minuscule number, as we should expect given the data of $\Delta_{\text{rxn}}G^\ominus$.

Solving the quadratic equation, we obtain one negative answer—which is unphysical—,[9] and:

$$y^i_{\mathrm{Cl}_{(g)}} = 0.662 \quad \longrightarrow y^i_{\mathrm{Cl}_{2(g)}} = 1 - 0.662 = 0.338.$$

At the end of the process, $P_f = 2.5$ bar, and we obtain:

$$K_y(P_f, 2\,298\ \mathrm{K}) = 0.520 = K_P \frac{P^\ominus}{P_f} = \frac{1.30}{2.5},$$

and, using the same technique used before to solve the quadratic equation:

$$K_y(P_f, 2\,298\ \mathrm{K}) = \frac{\left(y^f_{\mathrm{Cl}_{(g)}}\right)^2}{1 - y^f_{\mathrm{Cl}_{(g)}}} = 0.520,$$

gives:

$$y^f_{\mathrm{Cl}_{(g)}} = 0.507 \quad \longrightarrow y^f_{\mathrm{Cl}_{2(g)}} = 1 - 0.507 = 0.493.$$

To summarize, when we increase the pressure from 1 bar to 2.5 bar at $T = 2\,298$ K, the equilibrium constant in terms of the mole fraction decreases from $K_y(P^\ominus, 2\,298\ \mathrm{K}) = 1.30$ to $K_y(P_f = 2.5\ \mathrm{bar}, 2\,298\ \mathrm{K}) = 0.520$. This reduction is causing a shift of the equilibrium towards the reactants, with the concentration of $\mathrm{Cl}_{2(g)}$ increasing from $y^i_{\mathrm{Cl}_{2(g)}} = 0.338$ to $y^f_{\mathrm{Cl}_{2(g)}} = 0.493$ and the concentration of $\mathrm{Cl}_{(g)}$ decreasing from $y^i_{\mathrm{Cl}_{(g)}} = 0.662$ to $y^f_{\mathrm{Cl}_{(g)}} = 0.507$.

The dependence of K_{eq} on P highlighted above is another mathematical expression of Le Chatelier's principle, on this occasion, for changes in pressure. The interpretation for a reaction happening in the gas phase is as follows:

- If the total pressure increases, the equilibrium will shift towards the side of the chemical equation that contains the smallest total number of moles of gas (the equilibrium in exercise 10.1 shifts toward the reactant).

10.4. Chapter Review

10.4.1. Study Questions

1. How is the Gibbs energy of a reaction related to the reaction quotient?

[9] Concentration cannot be negative.

a. $\Delta_{\text{rxn}}G = \Delta_{\text{rxn}}G^{\ominus} + RT\ln Q$.
b. $\Delta_{\text{rxn}}G = \Delta_{\text{rxn}}G^{\ominus} - RT\ln Q$.
c. $\Delta_{\text{rxn}}G = RTQ$.
d. $\Delta_{\text{rxn}}G = \Delta_{\text{rxn}}G^{\ominus}Q$.
e. $\Delta_{\text{rxn}}G = -RT\ln K$.

---

2. What is true at chemical equilibrium?

a. $\Delta_{\text{rxn}}G^{\ominus} = 0$.
b. $Q = 1$.
c. $\Delta_{\text{rxn}}G = 0$, and the reaction quotient equals the equilibrium constant.
d. The reaction stops because the reactants are used up.
e. $K = 0$.

---

3. How is the standard Gibbs energy of reaction related to the equilibrium constant?

a. $\Delta_{\text{rxn}}G^{\ominus} = RT\ln K_{\text{eq}}$.
b. $\Delta_{\text{rxn}}G^{\ominus} = K_{\text{eq}}/RT$.
c. $\Delta_{\text{rxn}}G^{\ominus} = RTK_{\text{eq}}$.
d. $\Delta_{\text{rxn}}G^{\ominus} = 0$ at equilibrium.
e. $\Delta_{\text{rxn}}G^{\ominus} = -RT\ln K_{\text{eq}}$.

---

4. The dissociation of $\text{Cl}_{2(g)}$ has a large positive $\Delta_{\text{rxn}}G^{\ominus}$ at 298 K. What does this tell us about its equilibrium constant?

a. It is very large.
b. It is very small.
c. It is equal to 1.
d. It is negative.
e. It cannot be defined.

---

5. What is the activity of a pure liquid or solid?

a. Its mole fraction.
b. Its molar concentration.

c. Its vapor pressure.
d. 1.
e. 0.

---

6. How are K_P and K_y related for a reaction between ideal gases?

a. $K_P = K_y \left(\frac{P}{P^\circ}\right)^{\Delta\nu}$.
b. $K_P = K_y$ always.
c. $K_P = K_y \left(\frac{P^\circ}{P}\right)^{\Delta\nu}$.
d. $K_P = K_y RT$.
e. $K_P = K_y^{\Delta\nu}$.

---

7. What is the van 't Hoff equation?

a. $\left(\frac{\partial \ln K_{\text{eq}}}{\partial T}\right)_P = -\frac{\Delta H^\circ}{RT^2}$.
b. $\left(\frac{\partial \ln K_{\text{eq}}}{\partial T}\right)_P = \frac{\Delta S^\circ}{R}$.
c. $\left(\frac{\partial \ln K_{\text{eq}}}{\partial T}\right)_P = \frac{\Delta H^\circ}{RT^2}$.
d. $\left(\frac{\partial K_{\text{eq}}}{\partial P}\right)_T = 0$.
e. $\ln K_{\text{eq}} = -\frac{\Delta G^\circ}{R}$.

---

8. How does the equilibrium constant of an exothermic reaction change when the temperature increases?

a. It increases.
b. It stays constant.
c. It becomes negative.
d. It first increases, then decreases.
e. It decreases.

---

9. In a van 't Hoff plot of $\ln K$ versus $1/T$, what is the slope of the line?

a. $\frac{\Delta H^{\ominus}}{R}$.
b. $-\frac{\Delta H^{\ominus}}{R}$.
c. $\frac{\Delta S^{\ominus}}{R}$.
d. $-\Delta G^{\ominus}$.
e. RT.

---

10. What happens when the total pressure of a gas-phase reaction at equilibrium is increased, if the number of moles of gas changes in the reaction?

a. K_P increases, and the equilibrium shifts towards the products.
b. K_P decreases, and the equilibrium shifts towards the reactants.
c. Nothing changes.
d. K_P does not change, but the equilibrium shifts towards the side with fewer moles of gas.
e. The equilibrium shifts towards the side with more moles of gas.

Answers

1.a, 2.c, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

11. Ideal and Non-Ideal Gases

Up to this point, we have used the ideal gas as our main example, and in chapter 10 we wrote equilibrium constants in terms of the partial pressures of ideal gases. Real gases, however, are not ideal: their molecules occupy some space, and they attract each other. In this chapter, we will first look back at how the ideal gas law was discovered, and then we will study what happens when its assumptions break down. We will see that non-ideal behavior is responsible for some very useful phenomena, such as the cooling of a gas when it expands and the liquefaction of gases, and we will introduce the fugacity, a quantity that allows us to keep using our thermodynamic formulas for non-ideal gases.

11.1. The Ideal Gas Equation

The concept of an ideal gas is a theoretical construct that allows for straightforward treatment and interpretation of gases' behavior. As such, the ideal gas is a simplified *model* that we use to understand nature, and it does not correspond to any real system. In typical "spherical cow" spirit, the ideal gas model strips away many real-world complications so we can focus on the core relationships between pressure, volume, temperature, and amount of gas. The following two assumptions define the ideal gas model:

Definition 11.1.

- The particles that compose an ideal gas do not occupy any volume.
- The particles that compose an ideal gas do not interact with each other.

Because of its simplicity, the ideal gas model has been the historical foundation of thermodynamics and of science in general. The first studies of the ideal gas behavior date back to the seventeenth century, and the scientists that performed them are among the founders of modern science.

11.1.1. Boyle's Law

In 1662 Robert Boyle (1627–1691) found that the pressure and the volume of an ideal gas are inversely related at constant temperature. Boyle's Law has the following mathematical description:

$$P \propto \frac{1}{V} \quad \text{at const. } T, \tag{11.1}$$

or, in other terms:

$$PV = k_1 \quad \text{at const. } T, \tag{11.2}$$

which results in the familiar PV plots of Figure 11.1. As we already discussed in chapter 2, each of the curves in Figure 11.1 is obtained at constant temperature, and it is therefore called *"isotherm."*




Figure 11.1.: PV-Diagram of 1 mol of an Ideal Gas.

11.1.2. Charles's and Gay-Lussac's Laws

It took scientists more than a century to expand Boyle's work and study the relationship between volume and temperature. In 1787 Jacques Alexandre César Charles (1746–1823) wrote the relationship known as Charles's Law:

$$V \propto T \quad \text{at const. } P, \tag{11.3}$$

or, in other terms:

$$V = k_2 T \quad \text{at const. } P, \tag{11.4}$$

which results in the plots of Figure 11.2. Each of the curves is obtained at constant pressure, and it is termed *"isobar."*




Figure 11.2.: VT-Diagram of 1 mol of an Ideal Gas.

The interesting thing about isobars is that each line seems to converge to a specific point along the temperature line when we extrapolate them to $V \to 0$. This led to the introduction of the absolute temperature scale, suggesting that the temperature will never get smaller than $-273.15°\text{C}$.

It took an additional 21 years to write a formal relationship between pressure and temperature. The following relationships were proposed by Joseph Louis Gay-Lussac (1778–1850) in 1808:

$$P \propto T \quad \text{at const. } V, \tag{11.5}$$

or, in other terms:

$$P = k_3 T \quad \text{at const. } V, \tag{11.6}$$

which results in the plots of Figure 11.3. Each of the curves is obtained at constant volume, and it is termed *"isochor."*




Figure 11.3.: PT-Diagram of 1 mol of an Ideal Gas.

11.1.3. Avogadro's Law

Three years later, in 1811, Amedeo Avogadro (1776–1856) discovered a seemingly unrelated principle by studying the composition of matter. His Avogadro's Law encodes the relationship between the number of moles in an ideal gas and its volume as:

$$V \propto n \quad \text{at const. } P, T, \tag{11.7}$$

or in other terms:

$$V = k_4 n \quad \text{at const. } P, T, \tag{11.8}$$

which results in the straight lines of Figure 11.4.

11.1.4. The ideal gas Law

Despite all of the ingredients being available for more than 20 years, it's only in 1834 that Benoît Paul Émile Clapeyron (1799–1864) was finally able to combine them into what is now known as the **ideal gas Law**. Using the same formulas obtained above, we can write:

$$PV = \underbrace{k_3 T}_{\text{from Gay-Lussac's}} \cdot \underbrace{k_4 n}_{\text{from Avogadro's}}, \tag{11.9}$$




Figure 11.4.: Vn-Diagram of an Ideal Gas at Constant Pressure (1 bar).

which by renaming the product of the two constants k_3 and k_4 as R, becomes:

$$PV = nRT \tag{11.10}$$

The value of the constant R can be determined experimentally by measuring the volume that 1 mol of an ideal gas occupies at a constant temperature (e.g., at $T = 0°\text{C}$) and a constant pressure (e.g., atmospheric pressure $P = 1$ atm). At those conditions, the volume is measured at 22.4 L, resulting in the following value of R:

$$R = \frac{VP}{nT} = \frac{22.4 \cdot 1}{1 \cdot 273} = 0.082 \ \frac{\text{L atm}}{\text{mol K}}, \tag{11.11}$$

which a simple conversion to SI units transforms into:

$$R = 8.31 \ \frac{\text{J}}{\text{mol K}}. \tag{11.12}$$

11.2. Behaviors of Non-Ideal Gases

Non-ideal gases (sometimes also referred to as "real gases"), do not behave as ideal gases because at least one of the assumptions in definition 11.1 is violated. What characterizes non-ideal gases is that there is no unique equation that we can use to describe their behavior. For this reason, we have a plethora of several experimental models, none of which is superior to the other. The van der Waals (vdW) equation is the only model that

we will analyze in detail because of its simple interpretation. However, it is far from universal, and for several non-ideal gases, it is severely inaccurate. Other popular non-ideal gas equations are the Clausius equation, the virial equation, the Redlich–Kwong equation and several others.[1]

11.2.1. The van der Waals equation

One of the simplest empirical equations that describe non-ideal gases was obtained in 1873 by Johannes Diderik van der Waals (1837–1923). The vdW equation includes two empirical parameters (a and b) with different values for different non-ideal gases. Each of the parameters corresponds to a correction for the breaking of one of the two conditions that define the ideal gas behavior (definition 11.1). The vdW equation is obtained from the ideal gas equation performing the following simple substitutions:

$$\begin{aligned} P &\rightarrow \left(P + \frac{a}{\overline{V}^2}\right) \\ \overline{V} &\rightarrow \left(\overline{V} - b\right), \end{aligned} \tag{11.13}$$

which results in:

$$\begin{aligned} P\overline{V} = RT \;\rightarrow\; \left(P + \frac{a}{\overline{V}^2}\right)\left(\overline{V} - b\right) &= RT \\ P = \frac{RT}{\overline{V} - b} - \frac{a}{\overline{V}^2}&. \end{aligned} \tag{11.14}$$

The parameter a accounts for the presence of intermolecular interactions, while the parameter b accounts for the non-negligible volume of the gas molecules. Despite the parameters having simple interpretations, their values for each gas must be determined experimentally. Values for these parameters for some significant non-ideal gases are reported below:

	$a\left[\frac{\mathrm{L}^2\mathrm{bar}}{\mathrm{mol}^2}\right]$	$b\left[\frac{\mathrm{L}}{\mathrm{mol}}\right]$
Ammonia	4.225	0.0371
Argon	1.355	0.03201
Carbon dioxide	3.640	0.04267
Carbon monoxide	1.505	0.03985
Chlorine	6.579	0.05622
Freon	10.78	0.0998

[1] For more information on empirical equations for non-ideal gases see Wikipedia's article on real gases.

	$a\left[\frac{\mathrm{L}^2\mathrm{bar}}{\mathrm{mol}^2}\right]$	$b\left[\frac{\mathrm{L}}{\mathrm{mol}}\right]$
Helium	0.0346	0.0238
Hydrogen	0.2476	0.02661
Mercury	8.200	0.01696
Methane	2.283	0.04278
Neon	0.2135	0.01709
Nitrogen	1.370	0.0387
Oxygen	1.382	0.03186
Radon	6.601	0.06239
Xenon	4.250	0.05105

11.2.2. Joule–Thomson effect




Figure 11.5.: The Joule–Thomson Experiment.

We have already met William Thomson, also known as Lord Kelvin, and his seminal work on the second law of thermodynamics. In conjunction with that work, Thomson is famous for developing a sensitive method for measuring the temperature changes related to the expansion of a gas. These experiments improved on the earlier work by James Joule, and Lord Kelvin's improved instrument depicted in Figure 11.5 is named the Joule–Thomson apparatus. The apparatus is composed of two chambers, each with its own mobile piston. The chambers are connected via a valve or a porous plug. The entire equipment is also thermally isolated from the surroundings. This instrument is a more sensitive version of the Joule expansion apparatus that we already described in chapter 3 (compare with Figure 3.1).

Thomson realized that a gas flowing through an obstruction experiences a drop in pressure. If the entire apparatus is insulated, it will not exchange heat with its surroundings ($Q = 0$), and each transformation will happen at adiabatic conditions. Let's consider an initial condition with 1 mol of gas in the left chamber, occupying a volume V_l, and a completely closed right

chamber, for which $V_r^i = 0$. After the process completes, the volume of the left chamber will reduce to $V_l^f = 0$, while the volume of the right chamber will be V_r. Using the first law of thermodynamics, we can write:

$$\Delta U = U_r - U_l = \underbrace{Q}_{=0} + W = W_l + W_r, \tag{11.15}$$

with:

$$\begin{aligned} W_l &= -\int_{V_l}^{0} P_l dV = P_l V_l \\ W_r &= -\int_{0}^{V_r} P_r dV = -P_r V_r. \end{aligned} \tag{11.16}$$

Replacing eq. 11.16 into eq. 11.15, results in:

$$\begin{aligned} U_r - U_l &= P_l V_l - P_r V_r \\ \underbrace{U_r + P_r V_r}_{H_r} &= \underbrace{U_l + P_l V_l}_{H_l}, \end{aligned} \tag{11.17}$$

which, replacing the definition of enthalpy $H = U + PV$, we obtain:

$$\begin{aligned} H_r &= H_l \\ \Delta H &= 0, \end{aligned} \tag{11.18}$$

or, in other words, the process is **isenthalpic**. Using the total differential of H:

$$dH = \left(\frac{\partial H}{\partial T}\right)_P dT + \left(\frac{\partial H}{\partial P}\right)_T dP = C_P dT + \left(\frac{\partial H}{\partial P}\right)_T dP, \tag{11.19}$$

we obtain:

$$\Delta H = \int dH = \int C_P dT + \int \left(\frac{\partial H}{\partial P}\right)_T dP = 0, \tag{11.20}$$

or, in purely differential form:

$$dH = C_P dT + \left(\frac{\partial H}{\partial P}\right)_T dP = 0. \tag{11.21}$$

From eq. 11.21 we can define a new coefficient, called the *Joule–Thomson coefficient*, μ_{JT}, that measures the rate of change of temperature of a gas with respect to pressure in the Joule–Thomson process:

$$\mu_{\mathrm{JT}} = \left(\frac{\partial T}{\partial P}\right)_H = -\frac{1}{C_P}\left(\frac{\partial H}{\partial P}\right)_T . \tag{11.22}$$

The value of μ_{JT} depends on the type of gas, the temperature and pressure before expansion, and the heat capacity at constant pressure of the gas. The temperature at which μ_{JT} changes sign is called the "Joule–Thomson inversion temperature." Since the pressure decreases during an expansion, ∂P is negative by definition, and the following possibilities are available for μ_{JT}:

Gas temperature:	∂P	μ_{JT}	∂T	The gas will:
Below the inversion temperature	–	+	–	cool
Above the inversion temperature	–	–	+	warm

For example, helium has a very low Joule–Thomson inversion temperature at standard pressure ($T = 45$ K), and it warms when expanded at constant enthalpy at typical room temperatures. The only other gases that have standard inversion temperature lower than room temperature are hydrogen and neon. On the other hand, nitrogen and oxygen have high inversion temperatures ($T = 621$ K and $T = 764$ K, respectively), and they both cool when expanded at room temperature. Therefore, it is possible to use the Joule–Thomson effect in refrigeration processes such as air conditioning.[2] As we already discussed in chapter 3, the temperature of an ideal gas stays constant in an adiabatic expansion, therefore its Joule–Thomson coefficient is always equal to zero.

11.3. Critical Phenomena

11.3.1. Compressibility factors

The compressibility factor is a correction coefficient that describes the deviation of a real gas from ideal gas behavior. It is usually represented with the symbol z, and is calculated as:

[2] Nitrogen and oxygen are the two most abundant gases in the air. A sequence of Joule–Thomson expansions is also used for the industrial liquefaction of air.

$$z = \frac{\overline{V}}{\overline{V}_{\text{ideal}}} = \frac{P\overline{V}}{RT}. \tag{11.23}$$

It is evident from eq. 11.23 that the compressibility factor is dependent on the pressure, and for an ideal gas $z = 1$ always. For a non-ideal gas at any given pressure, z can be higher or lower than one, separating the behavior of non-ideal gases into two possibilities. The dependence of the compressibility factor against pressure is represented for H_2 and CO_2 in Figure 11.6.




Figure 11.6.: Compressibility Factor of Hydrogen (Type I) and Carbon Dioxide (Type II) at 350 K, Computed with the van der Waals Equation.

The two types of possible behaviors are differentiated based on the compressibility factor at $P \to 0$. To analyze these situations we can use the vdW equation to calculate the compressibility factor as:

$$z = \frac{\overline{V}}{RT}\left(\frac{RT}{\overline{V} - b} - \frac{a}{\overline{V}^2}\right), \tag{11.24}$$

which can be simplified as $z = \frac{\overline{V}}{\overline{V}-b} - \frac{a}{RT\overline{V}}$. We are interested in what happens at low pressure, where the molar volume is very large compared to b. In this case, we can use the approximation $\frac{\overline{V}}{\overline{V}-b} = \frac{1}{1-b/\overline{V}} \approx 1 + \frac{b}{\overline{V}}$, which gives:

$$z \approx 1 + \frac{1}{\overline{V}}\left(b - \frac{a}{RT}\right) \approx 1 + \frac{P}{RT}\left(b - \frac{a}{RT}\right), \tag{11.25}$$

where in the last step we used the ideal gas law, $\frac{1}{V} \approx \frac{P}{RT}$, which is a good approximation at low pressure. Eq. 11.25 is a straight line in P, and its slope gives the behavior of the compressibility factor near $P = 0$:

$$\left(\frac{\partial z}{\partial P}\right)_T\Bigg|_{P=0} = \frac{1}{RT}\left(b - \frac{a}{RT}\right), \tag{11.26}$$

which is then interpreted as follows:

- **Type I gases**: $b > \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} > 0$ *molecular size* dominates (H_2−like behavior).
- **Type II gases**: $b < \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} < 0$ *attractive forces* dominate (CO_2−like behavior).

The dependence of the compressibility factor as a function of temperature (Figure 11.7) results in different plots for each of the two types of behavior.




Figure 11.7.: Temperature Dependence of the Compressibility Factor, Computed with the van der Waals Equation. The van der Waals Boyle temperature of CO_2 (about 1030 K) is higher than the experimental value of 713 K, since the van der Waals equation is only an approximate model.

Both type I and type II non-ideal gases will approach the ideal gas behavior as $T \to \infty$, because $\frac{1}{RT} \to 0$ as $T \to \infty$. For type II gases, there are three interesting situations:

- At low T: $b < \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} < 0$, which is the behavior described above.
- At high T: $b > \frac{a}{RT} \Rightarrow \frac{\partial z}{\partial P} > 0$, which is the same behavior of type I gases.

- At a very specific temperature, inversion will occur (i.e., at $T = 713$ K for CO_2). This temperature is called the **Boyle temperature**, T_B, and is the temperature at which the attractive and repulsive forces balance out. It can be calculated from the vdW equation, since $b - \frac{a}{RT_B} = 0 \Rightarrow T_B = \frac{a}{bR}$. At the Boyle temperature a type II gas shows ideal gas behavior over a large range of pressure.

11.3.2. Phase diagram of a non-ideal gas




Figure 11.8.: The Pressure–Volume Diagram of a Non-Ideal Gas, Computed with the van der Waals Equation in Reduced Units (P/P_c and $\overline{V}/\overline{V}_c$). Below the Critical Temperature, the Flat Segments Inside the Green Region Mark the Coexistence of Liquid and Vapor.

Let's now turn our attention to the PV phase diagram of a non-ideal gas, reported in Figure 11.8. We can start the analysis from an isotherm at a high temperature. Since every gas will behave as an ideal gas at those conditions, the corresponding isotherms will look similar to those of an ideal gas (T_5 and T_4 in Figure 11.8). Lowering the temperature, we start to see the deviation from ideality getting more prominent (T_3 in Figure 11.8) until we reach a particular temperature called the critical temperature, T_c.

Definition 11.2. *Critical Temperature:* The temperature above which no appearance of a second phase is observed, regardless of how high the pressure becomes.

At the critical temperature and below, the gas liquefies when the pressure is increased. For this reason, the liquefaction of a gas is called a *critical phenomenon*.

The critical temperature is the coordinate of a unique point, called the **critical point**, that can be visualized in the three-dimensional T, P, V diagram of each gas (a surface whose slices at constant temperature are the isotherms of Figure 11.8).

The critical point has coordinates $\{T_c, P_c, \overline{V}_c\}$. These critical coordinates can be determined from the vdW equation at T_c, as:

$$T_c = \frac{8a}{27Rb} \qquad P_c = \frac{a}{27b^2} \qquad \overline{V}_c = 3b. \tag{11.27}$$

These relations are used, in practice, to determine the vdW constants a, b from the experimentally measured critical isotherms.

The critical compressibility factor, z_c, is predicted from the vdW equation at:

$$z_c = \frac{P_c \overline{V}_c}{RT_c} = \left(\frac{a}{27b^2}\right)\left(\frac{3b}{R}\right)\left(\frac{27Rb}{8a}\right) = \frac{3}{8} = 0.375, \tag{11.28}$$

a value that is independent of the gas. Experimentally measured values of z_c for different non-ideal gases are in the range of 0.2–0.3. These values can be used to infer the accuracy of the vdW equation for each non-ideal gas. Since the experimental z_c is usually lower than the one calculated from the vdW equation, we can deduce that the vdW equation overestimates the critical molar volume.

Notice how slicing the $PT\overline{V}$ diagram at constant T results in the PV diagram that we reported in Figure 11.8. On the other hand, slicing the $PT\overline{V}$ diagram at constant $\overline{V}$ results in a PT diagram, similar to the one that we will examine in detail in the next chapter.

11.4. Fugacity

The chemical potential of a pure ideal gas can be calculated using eq. 9.21. Since we are not interested in a mixture, we can drop the asterisk in μ^*, and rewrite eq. 9.21 as:

$$\mu_{\text{ideal}} = \mu^{\ominus} + RT \ln \frac{P}{P^{\ominus}}. \tag{11.29}$$

For a non-ideal gas, the pressure cannot be used in eq. 11.29 because the response of each gas to changes in pressure is not universal. We can, however, define a new variable to replace the pressure in eq. 11.29 and call it fugacity (f).

Definition 11.3. *Fugacity:* The effective pressure of a non-ideal gas that corresponds to the pressure of an ideal gas with the same temperature and chemical potential of the non-ideal one.

Eq. 11.29 then becomes:

$$\mu_{\text{non-ideal}} = \mu^{\ominus} + RT \ln \frac{f}{P^{\ominus}}. \tag{11.30}$$

To complete the definition of the fugacity, we need to decide how it relates to the pressure. At very low pressure, the molecules of any gas are so far apart that their volume and their interactions become negligible, and every gas behaves ideally. In this limit, the chemical potential of the non-ideal gas, eq. 11.30, must become equal to that of the ideal gas, eq. 11.29, which is possible only if the fugacity becomes equal to the pressure:

$$\lim_{P \to 0} \frac{f}{P} = 1, \tag{11.31}$$

in other words, the fugacity is defined so that any non-ideal gas approaches the ideal gas behavior as $P \to 0$. This condition, in conjunction with the $T \to \infty$ behavior obtained in the previous section, results in the following statement:

> The highest chances for any gas to behave ideally happen at high temperature and low pressure.

We can now return our attention to the definition of fugacity. Remembering that the chemical potential is the molar Gibbs energy of a substance, we can write:

$$d\mu_{\text{ideal}} = \overline{V}_{\text{ideal}} dP, \tag{11.32}$$

and:

$$d\mu_{\text{non-ideal}} = \overline{V}_{\text{non-ideal}} dP. \tag{11.33}$$

Subtracting eq. 11.32 from eq. 11.33, we obtain:

$$d\mu_{\text{non-ideal}} - d\mu_{\text{ideal}} = \left(\overline{V}_{\text{non-ideal}} - \overline{V}_{\text{ideal}}\right) dP, \tag{11.34}$$

which we can then integrate between 0 and P:

$$\mu_{\text{non-ideal}} - \mu_{\text{ideal}} = \int_0^P \left(\overline{V}_{\text{non-ideal}} - \overline{V}_{\text{ideal}}\right) dP. \tag{11.35}$$

Using eq. 11.29 and eq. 11.30 we can then replace the definition of chemical potentials, resulting in:

$$\ln f - \ln P = \frac{1}{RT} \int_0^P \left(\overline{V}_{\text{non-ideal}} - \overline{V}_{\text{ideal}}\right) dP, \tag{11.36}$$

which gives us a mathematical definition of the fugacity, as:

$$f = P \cdot \underbrace{\exp\left[\frac{1}{RT} \int_0^P \left(\overline{V}_{\text{non-ideal}} - \overline{V}_{\text{ideal}}\right) dP\right]}_{\text{fugacity coefficient, } \phi(T,P)}. \tag{11.37}$$

The exponential term in eq. 11.37 is complicated to write, but it can be interpreted as a coefficient—unique to each non-ideal gas—that can be measured experimentally. Such coefficients are dependent on pressure and temperature and are called the *fugacity coefficients*. Using letter ϕ to represent the fugacity coefficient, we can rewrite eq. 11.37 as:

$$f = \phi P, \tag{11.38}$$

which gives us a straightforward interpretation of the fugacity as an effective pressure. As such, the fugacity will have the same unit as the pressure, while the fugacity coefficients will be dimensionless.

As we already saw in chapter 10, the fugacity can be used to replace the pressure in the definition of the equilibrium constant for reactions that involve non-ideal gases. The new constant is usually called K_f, and is obtained from:

$$K_f = \prod_i f_{i,\text{eq}}^{\nu_i} = K_P \prod_i \phi_i^{\nu_i}. \tag{11.39}$$

11.5. Chapter Review

11.5.1. Study Questions

1. Which two assumptions define the ideal gas model?

a. The particles are spheres, and they move slowly.
b. The particles have the same mass, and they collide elastically.
c. The particles do not occupy any volume, and they do not interact with each other.
d. The particles are at rest, and they attract each other.
e. The gas is at low temperature and high pressure.

---

2. How did Charles's isobars lead to the idea of an absolute temperature scale?

a. When extrapolated to zero volume, all isobars meet at the same temperature, $-273.15\ ^\circ\mathrm{C}$.
b. They show that the volume is constant.
c. They are horizontal lines.
d. They meet at $0\ ^\circ\mathrm{C}$.
e. They show that the pressure can be negative.

---

3. What does the parameter a in the van der Waals equation account for?

a. The volume of the gas molecules.
b. The temperature of the gas.
c. The number of moles.
d. The molar mass of the gas.
e. The attractive interactions between the gas molecules.

---

4. What quantity stays constant in a Joule–Thomson expansion?

a. The temperature.
b. The enthalpy.
c. The pressure.

d. The volume.
e. The internal energy.

---

5. When does a gas cool down in a Joule–Thomson expansion?

a. Always.
b. Never.
c. Only if it is an ideal gas.
d. When its temperature is below its inversion temperature ($\mu_{\mathrm{JT}} > 0$).
e. When its temperature is above its inversion temperature.

---

6. What is the compressibility factor of an ideal gas?

a. $z = 1$ at all conditions.
b. $z = 0$.
c. $z > 1$ at high pressure.
d. $z < 1$ at low temperature.
e. $z = 3/8$.

---

7. How is the Boyle temperature obtained from the van der Waals parameters?

a. $T_{\mathrm{B}} = \frac{8a}{27Rb}$.
b. $T_{\mathrm{B}} = \frac{bR}{a}$.
c. $T_{\mathrm{B}} = \frac{a}{bR}$.
d. $T_{\mathrm{B}} = \frac{a}{27b^2}$.
e. $T_{\mathrm{B}} = 3b$.

---

8. What is the critical temperature of a gas?

a. The temperature at which the gas freezes.
b. The temperature at which the gas behaves ideally.
c. The boiling temperature at 1 bar.
d. The temperature at which the compressibility factor is zero.
e. The temperature above which the gas cannot be liquefied, no matter how high the pressure.

---

9. The van der Waals equation predicts a critical compressibility factor $z_c = 3/8 = 0.375$, while experiments give 0.2–0.3. What does this tell us?

a. That the experiments are wrong.
b. That the van der Waals equation is only an approximate model.
c. That all gases are ideal at the critical point.
d. That the van der Waals equation is exact.
e. That the critical point does not exist.

---

10. What is the value of the fugacity coefficient, $\phi = f/P$, of any gas as $P \to 0$?

a. 0.
b. Infinity.
c. 3/8.
d. 1.
e. It depends on the gas.

Answers

1.c, 2.a, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

12. Phase Equilibrium

In chapter 11, we saw that a non-ideal gas can be liquefied, and that the liquid and the gas can coexist under certain conditions. In chapter 9, we introduced the chemical potential, the molar Gibbs energy of a substance, and we learned how it changes with temperature and pressure. In this chapter, we will put these two ideas together to understand when a pure substance is solid, liquid, or gas, and what happens at the boundaries between these phases. We will build the phase diagrams that chemists use every day, and we will derive the equations that tell us how melting and boiling points change with pressure.

12.1. Phase Stability

We have already encountered the gas, liquid, and solid phases and already discussed some of their properties. These terms are intuitive since these are the three most common states of matter.[1] For this reason, we have previously used the terms without the necessity of formally defining their meaning. However, a formal definition of "phase" is necessary to discuss several concepts in this chapter and the following ones:

Definition 12.1. *Phase:* A region of the system with homogeneous chemical composition and physical state.

Let's now use the total differential of the chemical potential and the definition of molar Gibbs energy for one component:

$$\begin{aligned} d\mu &= \left(\frac{\partial \mu}{\partial T}\right)_P dT + \left(\frac{\partial \mu}{\partial P}\right)_T dP \\ d\mu &= -S dT + \overline{V} dP, \end{aligned} \tag{12.1}$$

to write:

[1] Other states of matter—such as plasma—are possible, but they are not usually observed at the values of temperature and pressure that classical thermodynamics is usually applied to. Discussion of these extreme cases is beyond the scope of this textbook.

$$\left(\frac{\partial \mu}{\partial T}\right)_P = -S \qquad \left(\frac{\partial \mu}{\partial P}\right)_T = \overline{V}. \tag{12.2}$$

We can use these definitions to study the dependence of the chemical potential with respect to changes in pressure and temperature. If we plot μ as a function of T using the first coefficient in eq. 12.2, we obtain the diagram in Figure 12.1. The diagram presents three curves, each corresponding to one of the three most common states of matter – solid, liquid, and gas. As we saw in several previous chapters, the entropy of a phase is almost constant with respect to temperature,[2] and therefore the three curves are essentially straight, with negative slopes equal to $-S$. Since the solid has the smallest entropy of the three phases, its line is the least steep.[3] The difference between the slopes of the three lines is explained by the fact that each of these states has a different value of entropy:

$$\left(\frac{\partial \mu_{\text{solid}}}{\partial T}\right)_P = -S_{\text{s}} \qquad \left(\frac{\partial \mu_{\text{liquid}}}{\partial T}\right)_P = -S_{\text{l}} \qquad \left(\frac{\partial \mu_{\text{gas}}}{\partial T}\right)_P = -S_{\text{g}}, \tag{12.3}$$

and since the entropy of a gas is always bigger than the entropy of a liquid, which in turn, is yet bigger than the entropy of a solid ($S_{\text{g}} \gg S_{\text{l}} > S_{\text{s}}$), we obtain three lines with different slopes that intersect each other, as in Figure 12.1. A few important considerations can be made by analyzing this diagram:

1. **The most stable phase has the lowest chemical potential.** At each temperature, the phase whose line is the lowest is the stable one (red segments in Figure 12.1). Just as a ball rolls downhill, matter moves spontaneously towards the phase with the lowest chemical potential, since this lowers the Gibbs energy at constant T and P.
2. **Phase changes happen where two lines cross.** At each intersection, the two phases have the same chemical potential, and they coexist. At the crossing between the solid and the liquid lines, the fusion (fus) process occurs, at the melting point T_{m}. At the crossing between the liquid and the gas lines, the vaporization (vap) process occurs, at the boiling point T_{b}.

[2] Think, for example, of the integral $\int S dT$, for which we can assume S independent of temperature to obtain $S\Delta T$. In practice, the entropy increases slightly with the temperature. Therefore the curves in Figure 12.1 are slightly concave downwards (remember that they are obtained from values of $-S$, so if S increases with T, the curves bend downwards.)

[3] The solid line would become perfectly flat only as $T \to 0$, where, according to the third law, the entropy of a perfect crystal goes to zero. At any temperature at which a substance melts, the entropy of the solid is positive, and its line slopes downward.

3. **Heating favors the phases with higher entropy.** Since the gas line is the steepest, the gas always wins at high enough temperature, while the solid always wins at low enough temperature.
4. **The liquid can be skipped.** Depending on the substance and on the pressure, the solid line might intersect the gas line before the liquid line. When that occurs, the liquid phase is never observed, and the solid turns directly into gas, at the sublimation (subl) point T_{subl}.




Figure 12.1.: Dependence of the Chemical Potentials of Solid, Liquid, and Gas Phases on Temperature at Constant Pressure.

The effects of pressure on this diagram can be studied using the second coefficient in eq. 12.2. For the majority of substances, $\overline{V}_{\text{g}} \gg \overline{V}_{\text{l}} > \overline{V}_{\text{s}}$, hence the curves will shift to lower values when the pressure is reduced, as in Figure 12.2. Notice also that since $\overline{V}_{\text{l}} \cong \overline{V}_{\text{s}}$, the shifts for both the solid and liquid lines are much smaller than the shift for the gas line. These shifts also translate to different values of the junctions, which means the phase changes will occur at different temperatures. Therefore both the melting point and the boiling point in general increase when pressure is increased (and vice versa). Notice how the change for the melting point is always much smaller than the change for the boiling point. Water is a noticeable exception to this trend because $\overline{V}_{\text{H}_2\text{O,l}} < \overline{V}_{\text{ice}}$. This explains the experimental observation that increasing the pressure on ice lowers its melting point.[4]

Considering the intersections between two lines, two phases are in equilibrium with each other at each of these points. For two or more phases to be in equilibrium, their chemical potentials must be equal:

[4] You might have heard that this is why we can skate on ice. The effect is real, but far too small to explain skating: the pressure under the blade of a skate lowers the melting point of ice by less than one degree, while we can skate on ice at –20 °C. Ice is slippery mostly because of a very thin, liquid-like layer that is always present on its surface, and because of the heat produced by friction.




Figure 12.2.: Effect of Pressure on the Chemical Potential Diagram.

$$\mu_\alpha = \mu_\beta. \tag{12.4}$$

If we now change either the temperature or the pressure, the location of the intersection will be shifted (see again Figure 12.2 and the discussion above). For infinitesimal changes in variables, the new location will be:

$$\mu_\alpha + d\mu_\alpha = \mu_\beta + d\mu_\beta, \tag{12.5}$$

which using eq. 12.4, simply becomes:

$$d\mu_\alpha = d\mu_\beta. \tag{12.6}$$

Replacing the differential with the definition of chemical potential in eq. 12.1, we obtain:

$$\begin{aligned} -S_\alpha dT + \overline{V}_\alpha dP &= -S_\beta dT + \overline{V}_\beta dP \\ \underbrace{(S_\beta - S_\alpha)}_{\Delta S} dT &= \underbrace{(\overline{V}_\beta - \overline{V}_\alpha)}_{\Delta \overline{V}} dP, \end{aligned} \tag{12.7}$$

which can be rearranged into:

$$\frac{dP}{dT} = \frac{\Delta S}{\Delta \overline{V}}. \tag{12.8}$$

This equation is known as the **Clapeyron equation**, and it is the mathematical relation at the basis of the pressure-temperature phase diagrams.

Plotting the results of eq. 12.8 on a PT phase diagram for common substances results in three lines representing the equilibrium between two different phases. A few important considerations can be made by analyzing eq. 12.8:

1. **The slope of a phase boundary is the ratio between two differences.** It depends only on how much the entropy and the molar volume change when we go from one phase to the other.
2. **The sign of the slope is decided by the volume change.** Going from a lower-temperature phase to a higher-temperature one, the entropy always increases ($\Delta S > 0$). Therefore, the line slopes up if the volume increases ($\Delta \overline{V} > 0$), and down if it decreases.
3. **Small volume changes give steep lines.** When the two phases have almost the same molar volume, as for a solid and a liquid, $\Delta \overline{V}$ is small, and the line is almost vertical. When one of the phases is a gas, $\Delta \overline{V}$ is large, and the line is much flatter.

12.2. Gibbs Phase Rule

In chapter 1, we have already seen that the number of independent variables required to describe an ideal gas is two. This number was derived by counting the total number of variables ($3 : P, \overline{V}, T$), and reducing it by one because the ideal gas law constrains the value of one of them, once the other two are fixed. For a generic system potentially containing more than one chemical substance in several different phases, however, the number of independent variables can be different than two. For a system composed of c components (chemical substances) and p phases, the number of independent variables, f, is given by the Gibbs phase rule:

$$f = c - p + 2. \tag{12.9}$$

The Gibbs phase rule derives from the fact that different phases are in equilibrium with each other at some conditions, resulting in the reduction of the number of independent variables at those conditions. More rigorously, when two phases are in thermodynamic equilibrium, their chemical potentials are equal (see eq. 12.4). For each equality, the number of independent variables—also called the number of *degrees of freedom*—is reduced by one. For example, the chemical potentials of the liquid and its vapor depend on both T and P. But when these phases are in equilibrium with each other, their chemical potentials must be equal. If either the pressure or the temperature is fixed, the other variable will be uniquely determined by the equality relation. In other terms, when a liquid is in equilibrium with its vapor at a given pressure, the temperature is determined by the fact that

the chemical potentials of the two phases are the same, and is denoted as the boiling temperature T_b. Similarly, at a given temperature, the pressure of the vapor is uniquely determined by the same equality relation and is denoted as the vapor pressure, P^*.

The Gibbs phase rule is obtained considering that the number of independent variables is given by the total number of variables minus the constraints. The total number of variables is given by temperature, pressure, plus all the variables required to describe each of the phases. The composition of each phase is determined by $(c-1)$ variables.[5] The number of constraints is determined by the number of possible equilibrium relations, which is $c(p-1)$ since the chemical potential of each component must be equal in all phases. The number of degrees of freedom f is then given by $f = (c-1)p + 2 - c(p-1) = c - p + 2$, which is the Gibbs phase rule, as in eq. 12.9.

A few important considerations can be made by analyzing eq. 12.9 for a pure substance ($c = 1$, so $f = 3 - p$):

1. **One phase, $f = 2$.** We can change both T and P independently, and the substance stays in the same phase. In a PT diagram, single phases are *areas*.
2. **Two phases, $f = 1$.** If we choose the temperature, the pressure at which the two phases coexist is fixed, and vice versa. Two-phase equilibria are *lines*.
3. **Three phases, $f = 0$.** Nothing can be chosen: three phases can coexist only at a single temperature and pressure. Three-phase equilibria are *points*.

12.3. PT Phase Diagrams

Let's now discuss the pressure–temperature diagram of a typical substance, as reported in Figure 12.3. Each of the lines reported in the diagram represents an equilibrium between two phases, and therefore it represents a condition that reduces the number of degrees of freedom to one. The lines can be determined using the Clapeyron equation, eq. 12.8. The interpretation of each line is as follows:

[5] For a 1-component system $c - 1 = 1 - 1 = 0$, and no additional variable is required to determine the composition of each phase. For a 2-component system, however, each phase will contain both components, hence $c - 1 = 2 - 1 = 1$ additional variable will be required to describe it–the mole fraction.




Figure 12.3.: The Pressure–Temperature Phase Diagram of Carbon Dioxide, Computed with the Clausius–Clapeyron Equation (the Pressure Axis Is Logarithmic). The Dashed Green Line Shows, for Comparison, an Anomalous Solid–Liquid Line with a Negative Slope, as for Water.

12.3.1. Liquid $\rightleftarrows$ Gas equilibrium

For this equilibrium we can use Trouton's rule, eq. 7.7, and write:

$$\Delta_{\text{vap}}S = S_{\text{g}} - S_{\text{l}} \cong 88 \frac{\text{J}}{\text{mol K}} > 0 \quad \text{always,} \tag{12.10}$$

where the entropy of vaporization is always positive, even for cases where the Trouton's rule is violated. The difference in molar volumes is easily obtained, since the volume of the gas is always much greater than the volume of the liquid:

$$\overline{V}_{\text{g}} - \overline{V}_{\text{l}} \cong \overline{V}_{\text{g}} = 22.4 \frac{\text{L}}{\text{mol}} > 0 \quad \text{always.} \tag{12.11}$$

Replacing these values in the Clapeyron equation, we obtain:

$$\frac{dP}{dT} = \frac{88}{22.4}\left(\frac{0.0831}{8.31}\right) = 0.04 \text{ bar/K} > 0 \quad \text{always,} \tag{12.12}$$

which is always positive, regardless of violations to Trouton's rule. Notice how small this value is: the liquid–gas line in Figure 12.3 is much flatter than the solid–liquid one.

12.3.2. Solid ⇄ Gas equilibrium

If we look at the signs of each quantity, this case is similar to the previous one:

$$\begin{aligned} \Delta_{\text{subl}} S &> 0 \quad \text{always} \\ \Delta_{\text{subl}} \overline{V} &> 0 \quad \text{always} \end{aligned} \tag{12.13}$$

$$\frac{dP}{dT} > 0 \quad \text{always.}$$

However, the entropy of sublimation is larger than the entropy of vaporization, since going from solid to gas is equivalent to melting and then vaporizing ($\Delta_{\text{subl}} S = \Delta_{\text{fus}} S + \Delta_{\text{vap}} S$). Near the triple point, where the two lines meet, the solid–gas line is therefore steeper than the liquid–gas one.

12.3.3. Solid ⇄ Liquid equilibrium

The final curve is for the solid-liquid equilibrium, for which we have:

$$\Delta_{\text{fus}} S = \frac{\Delta_{\text{fus}} H}{T_{\text{m}}} > 0 \quad \text{always,} \tag{12.14}$$

since fusion is always an endothermic process, ($\Delta_{\text{fus}} H > 0$). On the other side:

$$\Delta_{\text{fus}} \overline{V} = \overline{V}_{\text{l}} - \overline{V}_{\text{s}} > 0 \quad \text{generally.}$$

In other words, the difference of the molar volume of the liquid and that of the solid is positive for most substances, but it might be negative (for example for H_2O). As such:

$$\frac{dP}{dT} > 0 \quad \text{generally.} \tag{12.15}$$

For H_2O and a few other substances, $\frac{dP}{dT} < 0$, an anomalous behavior that has crucial consequences for the existence of life on earth.[6] Because of its

[6] As is well explained by Wikipedia's article on the properties of water: "The unusual density curve and lower density of ice than of water is vital to life—if water were most dense at the freezing point, then in winter the very cold water at the surface of lakes and other water bodies would sink, lakes could freeze from the bottom up, and all life in them would be killed. Furthermore, given that water is a good thermal insulator (due to its heat capacity), some frozen lakes might not completely thaw in summer. The layer of ice that floats on top insulates the water below. Water at about 4 °C (39 °F) also sinks to the bottom, thus keeping the temperature of the water at the bottom constant."

importance, this behavior is also depicted in Figure 12.3 using a dashed green line.

Since the differences in molar volumes between the solid and the liquid phases are usually small (changes are generally of the order of 10^{-3} L), $\frac{dP}{dT}$ is always much larger than for the previous two cases. The resulting lines for the solid–liquid equilibria are therefore almost vertical, regardless of the signs of their slopes.

12.3.4. The triple point and the critical point

The only point in the PT diagram where all the three phases coexist is called the triple point. The number of degrees of freedom at the triple point for every 1-component diagram is $f = 1 - 3 + 2 = 0$. The fact that the triple point has zero degrees of freedom means that its coordinates, $\{T_{\text{tp}}, P_{\text{tp}}, \overline{V}_{\text{tp}}\}$, are uniquely determined for each chemical substance. For this reason, the value of the triple point of water was fixed by definition—rather than measured—until 2019. This definition was necessary to establish the base unit of the thermodynamic temperature scale in the SI (the kelvin).[7]

In addition to the triple point where the solid, liquid, and gas phases meet, a triple point may involve more than one condensed phase. Triple points are common for substances with multiple solid phases (polymorphs), involving either two solid phases and a liquid one or three solid phases. Helium is a special case that presents a triple point involving two different fluid phases, called the lambda point. Since the number of degrees of freedom cannot be negative, the Gibbs phase rule for a 1-component diagram sets the limit to how many phases can coexist to just three. Therefore, quadruple points (or higher coexistence points) are not possible for pure substances, even for polymorphs.[8]

Another point with a fixed position in the PT diagram is the critical point, $\{T_{\text{c}}, P_{\text{c}}, \overline{V}_{\text{c}}\}$. We have already given the definition of the critical temperature in definition 11.2. This point represents the end of the liquid–gas equilibrium curve. This point is also semantically important to define different regions of the phase diagram, as in Figure 12.3. A gas whose temperature is below the critical temperature is called a *vapor*, since it can be liquefied by compression. A gas whose temperature and pressure are above the critical ones is called a *supercritical fluid*. Finally, a liquid whose pressure is above the critical point is called a *compressible liquid*.[9]

[7] For more information on the 2019 redefinition of the SI units, see Wikipedia's article on the 2019 redefinition of the SI base units.

[8] Notice that quadruple points are possible for 2-component diagrams.

[9] Notice that the temperature of a liquid must be below the critical point, otherwise it is no longer a liquid but rather a supercritical fluid.

12.4. The Clausius–Clapeyron Equation

Let's now take a closer look at the equilibrium between a condensed phase and the gas phase. For both the vaporization and sublimation processes, Clausius showed that the Clapeyron equation can be simplified by using:

$$\Delta_{\text{vap}}S = \frac{\Delta_{\text{vap}}H}{T} \qquad \Delta\overline{V} = \overline{V}_{\text{g}} - \overline{V}_{\text{l}} \cong \overline{V}_{\text{g}}, \tag{12.16}$$

resulting in:

$$\frac{dP}{dT} = \frac{\Delta_{\text{vap}}S}{\Delta\overline{V}} \cong \frac{\Delta_{\text{vap}}H}{T\overline{V}_{\text{g}}}. \tag{12.17}$$

Using the ideal gas law to replace the molar volume of the gas, we obtain:

$$\frac{dP}{dT} = \frac{P\Delta_{\text{vap}}H}{RT^2}, \tag{12.18}$$

which can be rearranged as:

$$\frac{dP}{P} = \frac{\Delta_{\text{vap}}H}{R}\frac{dT}{T^2}. \tag{12.19}$$

Eq. 12.19 is known as the **Clausius–Clapeyron equation**, and it measures the dependence of the vapor pressure of a substance as a function of the temperature. The Clausius–Clapeyron equation can be integrated to obtain:

$$\begin{aligned} \int_{P_i}^{P_f}\frac{dP}{P} &= \frac{\Delta_{\text{vap}}H}{R}\int_{T_i}^{T_f}\frac{dT}{T^2} \\ \ln\frac{P_f}{P_i} &= -\frac{\Delta_{\text{vap}}H}{R}\left(\frac{1}{T_f} - \frac{1}{T_i}\right). \end{aligned} \tag{12.20}$$

The integrated Clausius–Clapeyron equation shows that the vapor pressure depends exponentially on the temperature. Thus, even a small change in the temperature will result in a significant change in the vapor pressure. In fact, we daily use the fact that the vapor pressure of water changes drastically when we increase its temperature for cooking most of our food. For example, at an external pressure of 1 bar, it rapidly grows from $P^* = 0.02$ bar to $P^* = 1$ bar when the temperature is increased from $T = 293$ K (around room temperature) to $T = 373$ K (boiling point). The integrated Clausius–Clapeyron equation is also often used to determine the

enthalpy of vaporization from measurements of vapor pressure at different temperatures.

12.5. Chapter Review

12.5.1. Study Questions

1. What is a phase?

a. A region of the system at constant temperature.
b. A region of the system with homogeneous chemical composition and physical state.
c. Any pure substance.
d. A region of the system with constant volume.
e. A mixture of solid and liquid.

---

2. In a plot of the chemical potential versus temperature, which phase has the steepest (most negative) slope, and why?

a. The solid, because it is the densest.
b. The liquid, because it can flow.
c. All phases have the same slope.
d. The gas, because it has the highest entropy.
e. The solid, because it has the highest entropy.

---

3. At a given temperature and pressure, which phase of a substance is the most stable?

a. The one with the lowest chemical potential.
b. The one with the highest chemical potential.
c. The one with the lowest entropy.
d. The one with the largest volume.
e. Always the liquid.

---

4. What condition must be satisfied for two phases to be in equilibrium?

a. Their entropies must be equal.
b. Their volumes must be equal.
c. Their enthalpies must be equal.
d. Their densities must be equal.
e. Their chemical potentials must be equal.

---

5. What is the Clapeyron equation?

a. $\frac{dP}{dT} = \frac{\Delta V}{\Delta S}$.
b. $\frac{dP}{dT} = \Delta S\, \Delta \overline{V}$.
c. $\frac{dP}{dT} = \frac{\Delta S}{\Delta \overline{V}}$.
d. $\frac{dP}{dT} = \frac{\Delta G}{\Delta \overline{V}}$.
e. $\frac{dP}{dT} = \frac{R}{\Delta \overline{V}}$.

---

6. Why does the solid–liquid line of water have a negative slope in the PT phase diagram?

a. Because ice has a higher entropy than liquid water.
b. Because the molar volume of ice is larger than that of liquid water.
c. Because water has hydrogen bonds.
d. Because the enthalpy of fusion of water is negative.
e. Because water boils at 100 °C.

---

7. What is the Gibbs phase rule?

a. $f = c + p + 2$.
b. $f = c - p$.
c. $f = p - c + 2$.
d. $f = c - p + 2$.
e. $f = 2 - p$.

---

8. How many degrees of freedom are there at the triple point of a pure substance?

a. 0.
b. 1.

c. 2.
d. 3.
e. It depends on the substance.

---

9. What does the critical point represent in a PT phase diagram?

a. The point where solid, liquid, and gas coexist.
b. The end of the solid–liquid line.
c. The normal boiling point.
d. The point where the solid sublimates.
e. The end of the liquid–gas equilibrium line.

---

10. According to the integrated Clausius–Clapeyron equation, how does the vapor pressure of a liquid depend on the temperature?

a. It decreases linearly.
b. It is independent of temperature.
c. It increases exponentially.
d. It increases linearly.
e. It is proportional to $1/T$.

Answers

1.b, 2.d, 3.a, 4.e, 5.c, 6.b, 7.d, 8.a, 9.e, 10.c

13. Multi-Component Phase Diagrams and Solutions

In chapter 12, we studied what happens when a single substance is split between two or more phases, and we used the chemical potential to understand when, for example, a liquid boils or a solid melts. Most of the chemistry we do in the lab, however, does not involve pure substances, but mixtures: we dissolve salts in water, we mix solvents, we bubble gases through liquids. In this chapter, we will extend the ideas of the previous chapter to systems that contain two or more chemical species. As we will see, the presence of a second component opens up a whole new set of phenomena that are extremely useful in practice, from the separation of liquids by distillation to the reason why we spread salt on icy roads in winter.

Systems that include two or more chemical species in the same phase are usually called *solutions*. The species present in the largest amount is usually called the *solvent*, and the others are called *solutes*. Solutions are possible for all three states of matter:

Type:	Solvent	Solute	Examples:
Solid solutions	Solid	Solid	Alloys: brass, bronze
	Solid	Liquid	Dental amalgam
	Solid	Gas	Hydrogen stored in palladium
Liquid solutions	Liquid	Solid	Saltwater, bleach
	Liquid	Liquid	Alcoholic beverages, vinegar
	Liquid	Gas	Carbonated drinks
Gaseous solutions	Gas	Solid	Smoke, smog
	Gas	Liquid	Aerosols and perfumes
	Gas	Gas	Air

13.1. Describing a Two-Component System

Let's start by counting how many variables we need to describe a solution of two components (a *binary* solution). Recalling the Gibbs phase rule from chapter 12, the number of degrees of freedom for $c = 2$ components is:

$$f = 2 - p + 2 = 4 - p. \tag{13.1}$$

A few important considerations can be made by analyzing eq. 13.1:

1. **One phase needs three variables.** When the solution is in a single phase (e.g., a liquid), we need $4 - 1 = 3$ variables to describe it. These are usually the temperature, T, the pressure, P, and the composition. For two components, the composition is given by a single mole fraction, since the other one is obtained from $x_\mathrm{A} + x_\mathrm{B} = 1$. We will use x_i for the mole fractions in the liquid phase and y_i for those in the gas phase.
2. **Three variables would require a 3D plot.** To represent all states of a single-phase binary system, we would need a three-dimensional T, P, x diagram. Since 3D plots are hard to draw and to read, we will always keep one of the variables constant: either the temperature (obtaining a Px diagram) or the pressure (obtaining a Tx diagram).
3. **Two phases leave two variables.** When a liquid and its vapor coexist, $f = 4{-}2 = 2$. If we also fix the temperature, only one variable remains free. In other words, at a given temperature, once we choose the composition of the liquid, the pressure and the composition of the vapor are fixed by nature. This is what makes the diagrams in this chapter so useful: they tell us exactly what vapor will form above a given liquid.

13.2. Ideal Solutions and Raoult's Law

In chapter 11, we simplified the treatment of gases by introducing the ideal gas, a model where molecules do not interact with each other. For liquids, this assumption is simply impossible, since the interactions between molecules are what keeps a liquid together in the first place. We need, therefore, a different kind of simplification:

Definition 13.1. *Ideal solution:* A solution where the interactions between molecules of different species (A–B) are, on average, the same as the interactions between molecules of the same species (A–A and B–B).

In an ideal solution, a molecule of A does not "notice" whether its neighbors are molecules of A or B. This has two immediate consequences: mixing the two liquids releases or absorbs no heat ($\Delta_\mathrm{mix} H = 0$), and the volume of the mixture is the sum of the volumes of the two liquids ($\Delta_\mathrm{mix} V = 0$). The only thing that changes upon mixing is the number of ways in which we can arrange the molecules, which increases. As we saw in chapter 6, this means that the entropy increases, and that mixing in an ideal solution is a spontaneous process driven entirely by entropy. Mixtures of chemically similar molecules, such as benzene and toluene, or hexane and heptane, behave as ideal solutions to a very good approximation. We will also assume

that the vapor above the solution behaves as a mixture of ideal gases, which is reasonable at the low pressures that we usually deal with.

What is the vapor pressure of an ideal solution? Let's think about a molecule of A at the surface of the liquid. Its tendency to escape into the gas phase depends on how strongly it is held by its neighbors. In an ideal solution, the neighbors hold it exactly as strongly as in the pure liquid, so each molecule of A at the surface escapes as easily as it would from pure A. However, only a fraction x_A of the molecules at the surface are molecules of A. It is then reasonable to expect that the partial pressure of A above the solution is the vapor pressure of pure A, reduced by this fraction. This plausibility argument is confirmed experimentally, and it was formulated by François-Marie Raoult (1830–1901) in what is known as **Raoult's law**:

$$P_i = x_i P_i^*, \tag{13.2}$$

where P_i is the partial pressure of component i above the solution, x_i is its mole fraction in the liquid, and P_i^* is the vapor pressure of pure i at the same temperature. Raoult's law can also be used as an alternative definition of an ideal solution: a solution is ideal if all of its components follow eq. 13.2 at all compositions.

13.2.1. One volatile component

Let's first consider a solution where only one of the two components, A, is volatile. This is the case, for example, of a solution of sugar in water, since sugar has no measurable vapor pressure. In this case, the pressure above the solution is entirely due to A, and Raoult's law describes a straight line in the Px_B diagram, going from P_A^* for pure A ($x_\mathrm{B} = 0$) to zero for pure B ($x_\mathrm{B} = 1$), as in Figure 13.1.

A few important considerations can be made by analyzing Figure 13.1:

1. **The line separates two regions.** Above the line, the pressure is higher than the vapor pressure of the solution, and only the liquid is stable. Below the line, the pressure is lower, the liquid evaporates, and only the vapor is stable. Each region has $f = 3$ degrees of freedom, but only two of them are visible in the diagram, since the temperature is kept constant.
2. **Along the line, liquid and vapor coexist.** Raoult's law acts as an additional constraint for the points on the line, which have only two degrees of freedom. Since the temperature is fixed, choosing the composition of the liquid determines the pressure, and vice versa.




Figure 13.1.: The Pressure–Composition Phase Diagram of a Solution of Toluene (A) with a Nonvolatile Solute (B) at 25 °C.

3. **Adding a nonvolatile solute lowers the vapor pressure.** Moving from left to right along the line, the vapor pressure decreases. This is the first example of a *colligative property*, which we will discuss in detail at the end of this chapter.

13.2.2. Two volatile components

When both components are volatile, each of them follows Raoult's law, and both contribute to the vapor. Since we are treating the vapor as a mixture of ideal gases, the total pressure is simply the sum of the two partial pressures, according to Dalton's law, eq. 9.23:

$$P_{\mathrm{TOT}} = P_{\mathrm{A}} + P_{\mathrm{B}} = x_{\mathrm{A}} P_{\mathrm{A}}^* + x_{\mathrm{B}} P_{\mathrm{B}}^* = P_{\mathrm{A}}^* + x_{\mathrm{B}} \left(P_{\mathrm{B}}^* - P_{\mathrm{A}}^* \right), \tag{13.3}$$

where in the last step we used $x_{\mathrm{A}} = 1 - x_{\mathrm{B}}$. Eq. 13.3 is the equation of a straight line that goes from P_{A}^* to P_{B}^*, as reported in red in Figure 13.2. The partial pressures of each of the two components are also reported, using black dotted lines.

Exercise 13.1. Calculate the mole fraction in the vapor phase of a liquid solution composed of 67% of toluene (A) and 33% of benzene (B) (in moles), given the vapor pressures of the pure substances: $P_{\mathrm{A}}^* = 0.03$ bar, and $P_{\mathrm{B}}^* = 0.10$ bar.

Solution: The data available for the system are summarized as follows:

$$\begin{aligned} x_{\mathrm{A}} &= 0.67 & x_{\mathrm{B}} &= 0.33 \\ P_{\mathrm{A}}^* &= 0.03 \text{ bar} & P_{\mathrm{B}}^* &= 0.10 \text{ bar} \\ & & P_{\mathrm{TOT}} &= ? \\ y_{\mathrm{A}} &= ? & y_{\mathrm{B}} &= ? \end{aligned} \tag{13.4}$$




Figure 13.2.: The Pressure–Composition Phase Diagram of an Ideal Solution of toluene (A) and benzene (B) at 25 °C, Computed with Raoult's Law.

The partial pressures and the total pressure of the vapors can be calculated combining Raoult's and Dalton's laws:

$$\begin{aligned} P_A &= x_A P_A^* = 0.67 \cdot 0.03 = 0.020 \text{ bar} \\ P_B &= x_B P_B^* = 0.33 \cdot 0.10 = 0.033 \text{ bar} \\ P_{TOT} &= P_A + P_B = 0.053 \text{ bar}. \end{aligned} \tag{13.5}$$

Since each partial pressure is proportional to the number of moles of that component in the vapor, we can calculate the mole fractions in the vapor phase as:

$$\begin{aligned} y_A &= \frac{P_A}{P_{TOT}} \qquad y_B = \frac{P_B}{P_{TOT}} \\ y_A &= \frac{0.020}{0.053} = 0.38 \qquad y_B = \frac{0.033}{0.053} = 0.62. \end{aligned} \tag{13.6}$$

Notice how the vapor is much richer in benzene ($y_B = 0.62$) than the liquid ($x_B = 0.33$). Benzene has the higher vapor pressure (it is more *volatile*), so its molecules escape more easily into the gas phase.

The result of Exercise 13.1 is completely general: *the vapor above an ideal solution is always richer in the more volatile component than the liquid it comes from.* Since the compositions of the liquid and of the vapor are different, we can report both of them in the same diagram, as in Figure 13.3. The line that gives the composition of the liquid, x_B, is called the *liquidus line* (or bubble point line), while the line that gives the composition of the vapor, y_B, is called the *dew point line*.

The liquidus and dew point lines enclose a new region of the diagram, where the liquid and the vapor coexist. Let's follow the arrow in Figure 13.3 to understand how to read this diagram:




Figure 13.3.: The Pressure–Composition Phase Diagram of an Ideal Solution of toluene (A) and benzene (B) at 25 °C, with Both the Liquidus and the Dew Point Lines.

1. **We start from a liquid** with composition x_B^i at high pressure (point i). Here only the liquid is stable.
2. **We lower the pressure** at constant temperature and composition, moving straight down, until we hit the liquidus line. At this pressure, the liquid starts to boil.
3. **The first bubble of vapor** that forms does not have the same composition as the liquid. Its composition is found by moving horizontally (at the same pressure) until we hit the dew point line, which gives y_B^f. As expected, the vapor is richer in the more volatile component, B.
4. **Inside the coexistence region**, any horizontal line (called a *tie line*) connects a liquid and a vapor in equilibrium with each other. Since there are only two degrees of freedom inside this region, and the temperature is fixed, once we fix the pressure, the compositions of both phases are determined.

13.2.3. Tx_B phase diagrams and fractional distillation

In the lab, we usually boil liquids at constant (atmospheric) pressure by increasing the temperature, rather than by reducing the pressure. It is therefore more useful to look at the phase diagram of a 2-component ideal solution as a function of temperature at constant pressure. The Tx_B diagram for two volatile components is reported in Figure 13.4. As in the previous diagrams, the more volatile component is B (benzene), which has the lower boiling point, T_b^B.

A few important considerations can be made by analyzing Figure 13.4:

1. **The phases are in reversed order.** Compared to the Px_B diagram of Figure 13.3, the liquid is now at the bottom (low temperature), and




Figure 13.4.: The Temperature–Composition Phase Diagram of an Ideal Solution of toluene (A) and benzene (B) at 1 atm.

the vapor is on top (high temperature).

2. **The two lines form a lens.** The liquidus and dew point lines are curved, and they enclose a lens-shaped region where liquid and vapor coexist. Inside the lens there are only two degrees of freedom, and since the pressure is kept constant, only one of them is visible in the plot: if we choose the temperature, the compositions of both phases are fixed, and vice versa.
3. **A mixture boils over a range of temperatures.** If we heat a liquid of composition x^i_B, it starts boiling when it hits the liquidus line. The first vapor that forms has composition y^f_B, which is richer in the more volatile component B. As the vapor leaves, the remaining liquid becomes richer in A, and its boiling temperature increases. Unlike a pure substance, a mixture does not have a single boiling point.

The difference in composition between the liquid and the vapor can be exploited to separate the two components. If we collect the vapor and condense it, we obtain a liquid that is richer in B than the one we started from. If we boil this new liquid again, its vapor will be even richer in B. Each evaporation and condensation step corresponds to a horizontal line (from the liquidus line to the dew point line) followed by a vertical line (from the dew point line down to the liquidus line), as in the staircase of Figure 13.5. Each of these steps is called a *theoretical plate*, and by repeating it enough times we can obtain almost pure B. This is the principle of *fractional distillation*.

In practice, the evaporations and condensations do not happen in separate flasks, but along a tall column filled with trays, as schematically depicted on the right of Figure 13.5. The mixture is heated at the bottom, and the temperature decreases with the height of the column. On each tray, the rising vapor partially condenses and the liquid partially evaporates, so that each tray works as one theoretical plate. The vapor collected at the




Figure 13.5.: The Fractional Distillation Process: Theoretical Plates Drawn on the Temperature–Composition Phase Diagram of Toluene and Benzene (Left), and a Schematic Distillation Column (Right).

top is rich in the most volatile component, while the liquid collected at the bottom is rich in the least volatile one. Counting the theoretical plates on the Tx_B diagram tells chemical engineers how many trays a column needs to reach the desired purity, which is how industrial distillation columns are sized.

13.3. Phase Diagrams of Non-Ideal Solutions

In most real solutions, the A–B interactions are not the same as the A–A and B–B ones, and Raoult's law is followed only over a small range of compositions. Let's start again from a solution with a single volatile component, A, whose typical behavior is reported in the Px_B plot of Figure 13.6.




Figure 13.6.: The Pressure–Composition Phase Diagram of a Non-Ideal Solution Where Only A Is Volatile (Model Mixture with a Positive Deviation).

A few important considerations can be made by analyzing Figure 13.6:

1. **When A is abundant ($x_\mathbf{B} \to 0$), Raoult's law holds.** In this region, A is the solvent, and almost every molecule of A is surrounded by other molecules of A, as in the pure liquid. Its escaping tendency is therefore the same as in pure A, as Raoult's law assumes.
2. **When A is dilute ($x_\mathbf{B} \to 1$), Henry's law holds.** In this region, A is the solute, and each molecule of A is surrounded almost exclusively by molecules of B. Its escaping tendency is now determined by the A–B interactions, which are different from the A–A ones. The partial pressure is still proportional to the mole fraction, but with a different proportionality constant, as shown by the green dotted line.
3. **In between, neither law holds**, and the curve must be measured experimentally.

The law that describes the dilute region was found by William Henry (1774–1836), who extensively studied the behavior of gases dissolved in liquids. **Henry's law** states that the partial pressure of a dilute solute i is proportional to its mole fraction in the solution:

$$P_i = k_{\mathrm{H},i}\, x_i \qquad (\text{for } x_i \to 0), \tag{13.7}$$

where the *Henry's law constant*, $k_{\mathrm{H},i}$, depends on the chemical nature of both the solute and the solvent, and on the temperature. Henry's law is commonly used for gases dissolved in liquids. For example, the amount of CO_2 dissolved in a carbonated drink is proportional to the pressure of CO_2 above it, which is why the drink goes flat when we open the bottle and the pressure drops. In a dilute solution, the solvent follows Raoult's law, while the solute follows Henry's law.

When both components are volatile, the total pressure is once again the sum of the two partial pressures. Two different behaviors are possible, depending on the strength of the A–B interactions, as reported in Figure 13.7:

- **Positive deviation** (left panel): the A–B interactions are weaker than the A–A and B–B ones. The molecules are held less strongly in the mixture than in the pure liquids, they escape more easily, and the vapor pressure is higher than the one predicted by Raoult's law. Mixing these liquids typically absorbs heat ($\Delta_{\mathrm{mix}}H > 0$). An example is the acetone/carbon disulfide mixture.
- **Negative deviation** (right panel): the A–B interactions are stronger than the A–A and B–B ones (for example, because A and B form hydrogen bonds with each other). The molecules are held more strongly, and the vapor pressure is lower than the one predicted by Raoult's law. Mixing these liquids typically releases heat ($\Delta_{\mathrm{mix}}H < 0$). Examples are the acetone/chloroform and the hydrochloric acid/water mixtures. Negative deviations are slightly less common than positive ones.




Figure 13.7.: The Pressure–Composition Phase Diagrams of Non-Ideal Solutions Containing Two Volatile Components at Constant Temperature (Model Mixtures).

If we move from the Px_B diagram to the Tx_B diagram, the behaviors observed in Figure 13.7 correspond to the diagrams in Figure 13.8. Since a higher vapor pressure means that the mixture boils at a lower temperature, a maximum in the Px_B diagram becomes a minimum in the Tx_B diagram, and vice versa.




Figure 13.8.: The Temperature–Composition Phase Diagrams of Non-Ideal Solutions Containing Two Volatile Components at Constant Pressure (Model Mixtures).

The minimum (left plot) and maximum (right plot) points in Figure 13.8 are called *azeotropes*. At an azeotrope, the liquidus and dew point lines touch, so the liquid and the vapor have the same composition. If we boil a mixture with the azeotropic composition, the vapor has the same composition as the liquid, and distillation cannot change it. The mixture boils at a single temperature, as if it was a pure substance. In practice, distillation can bring us *to* the azeotrope, but not past it. Two types of azeotropes exist, corresponding to the two types of deviation:

- **Positive (minimum-boiling) azeotrope** (left plot in Figure 13.8). A well-known example is the ethanol/water mixture at atmospheric pressure, with composition 95.6% ethanol by mass. This azeotrope boils at $T = 78.2$ °C, a temperature that is lower than the boiling points of both pure constituents (ethanol boils at $T = 78.4$ °C and

water at $T = 100\ ^\circ\text{C}$). This is why we cannot obtain pure ethanol from fermented mixtures by simple distillation.

- **Negative (maximum-boiling) azeotrope** (right plot in Figure 13.8). An example is the hydrochloric acid/water mixture at atmospheric pressure, with composition 20.2% hydrochloric acid by mass. This azeotrope boils at about $T = 110\ ^\circ\text{C}$, a temperature that is higher than the boiling points of both pure constituents (hydrochloric acid boils at $T = -84\ ^\circ\text{C}$ and water at $T = 100\ ^\circ\text{C}$).

13.4. Activity

To treat non-ideal solutions quantitatively, we need a quantity that plays the same role that the mole fraction plays in Raoult's law. We did something very similar for non-ideal gases in chapter 11, where we replaced the pressure with the fugacity, an *effective pressure*. For solutions, we will replace the mole fraction with an *effective mole fraction*, called the **activity**. Let's derive it step by step, using the vapor above the solution as a "probe" of what happens in the liquid.

1. **The vapor.** Assuming that the vapor behaves as an ideal gas, the chemical potential of component i in the vapor is given by eq. 11.29:

$$\mu_i^{\text{vapor}} = \mu_i^{\ominus} + RT \ln \frac{P_i}{P^{\ominus}}. \tag{13.8}$$

2. **Equilibrium with the solution.** If the vapor is in equilibrium with the solution, the chemical potential of i must be the same in both phases (eq. 12.4):

$$\mu_i^{\text{solution}} = \mu_i^{\text{vapor}} = \mu_i^{\ominus} + RT \ln \frac{P_i}{P^{\ominus}}. \tag{13.9}$$

3. **The pure liquid as a reference.** The same reasoning applies to the pure liquid i, which is in equilibrium with its vapor at the pressure P_i^*. Its chemical potential, μ_i^*, is therefore:

$$\mu_i^* = \mu_i^{\ominus} + RT \ln \frac{P_i^*}{P^{\ominus}}. \tag{13.10}$$

4. **Subtracting** eq. 13.10 from eq. 13.9, the standard chemical potential of the gas and the standard pressure cancel out, and we obtain:

$$\mu_i^{\text{solution}} = \mu_i^* + RT \ln \frac{P_i}{P_i^*}. \tag{13.11}$$

Eq. 13.11 tells us that the ratio P_i/P_i^* measures how much the chemical potential of i in the solution differs from that of the pure liquid. We call this ratio the **activity** of component i:

$$a_i = \frac{P_i}{P_i^*} \qquad \Rightarrow \qquad \mu_i^{\text{solution}} = \mu_i^* + RT \ln a_i. \tag{13.12}$$

A few important considerations can be made by analyzing eq. 13.12:

1. **For an ideal solution, the activity is the mole fraction.** Using Raoult's law, eq. 13.2, $a_i = x_i$, and eq. 13.12 becomes:

$$\mu_i^{\text{solution}} = \mu_i^* + RT \ln x_i. \tag{13.13}$$

   Since $x_i < 1$, the logarithm is negative, and the chemical potential of a component in an ideal solution is always lower than that of the pure liquid. This is the same result we found for mixtures of ideal gases in chapter 9, and it is the reason why ideal solutions form spontaneously.
2. **For a non-ideal solution, the activity is an effective mole fraction.** We can write it as the mole fraction multiplied by a correction factor, called the *activity coefficient*, γ_i:

$$a_i = \gamma_i x_i \qquad \Rightarrow \qquad \mu_i^{\text{solution}} = \mu_i^* + RT \ln (\gamma_i x_i). \tag{13.14}$$

3. **The activity coefficient is measured from the vapor pressure.** Combining eq. 13.12 and eq. 13.14:

$$\gamma_i = \frac{P_i}{x_i P_i^*} = \frac{P_i}{P_i^{\text{R}}}, \tag{13.15}$$

   where $P_i^{\text{R}} = x_i P_i^*$ is the partial pressure predicted by Raoult's law. For a positive deviation, the measured pressure is higher than the Raoult one, and $\gamma_i > 1$. For a negative deviation, it is lower, and $0 < \gamma_i < 1$. For an ideal solution, $\gamma_i = 1$. This procedure is illustrated in Figure 13.9.
4. **The activity is a relative quantity.** It measures the "escaping tendency" of a component *relative* to a reference state, which in this case is the pure liquid at the same temperature and pressure, for which $a_i = 1$. This choice of reference (*standard state*) is a convention. We could choose a different one, and the values of the activities would change accordingly, but the physics would not. For gases, the standard state is the ideal gas at $P^\ominus = 1$ bar, and the activity is $f/P^\ominus$.

As we already discussed in chapter 10, the activity is the most general quantity that we can use to define the equilibrium constant of a reaction (or the reaction quotient). The advantage of using the activity is that it's




Figure 13.9.: Activity Coefficients from the Vapor Pressure: Positive (Left) and Negative (Right) Deviation from Raoult's Law (Model Mixtures).

defined for ideal and non-ideal gases and mixtures of gases, as well as for ideal and non-ideal solutions in both the liquid and the solid phase.[1]

13.5. Colligative Properties

Colligative properties are properties of solutions that depend on the *number* of solute particles in the solution, and not on their chemical nature. They usually appear when we dissolve a nonvolatile solute (such as sugar or salt) in a volatile liquid solvent (such as water), and they are properties of the solvent, modified by the presence of the solute. We will discuss four of them: the lowering of the vapor pressure, the elevation of the boiling point, the depression of the melting point, and the osmotic pressure.

All four of them have the same origin, which we have already found in eq. 13.13. In an ideal solution, the chemical potential of the solvent is:

$$\mu^{\text{solution}}_{\text{solvent}} = \mu^*_{\text{solvent}} + RT \ln x_{\text{solvent}} < \mu^*_{\text{solvent}}. \tag{13.16}$$

In other words, *dissolving a solute always lowers the chemical potential of the solvent.* This lowering is not due to any special interaction between solute and solvent. In an ideal solution there is none: it is a purely entropic effect, due to the increased number of ways in which the molecules can be arranged in the mixture. This is also why the result depends only on the

[1] Notice that, since the activity is a relative measure, the equilibrium constant expressed in terms of the activities is also a relative concept. In other words, it measures equilibrium relative to a standard state. This fact, however, should not surprise us, since the equilibrium constant is also related to $\Delta_{\text{rxn}}G^{\ominus}$ using Gibbs' relation. This is why the definition of a universally agreed-upon standard state is such an essential concept in chemistry, and why it is defined by the International Union of Pure and Applied Chemistry (IUPAC) and followed systematically by chemists around the globe.

mole fraction, and not on what the solute is. At the same time, the phases that contain only pure solvent (the vapor above the solution, since the solute is nonvolatile, and the solid, since the solute usually does not dissolve in the solid solvent) are not affected at all. The liquid is therefore stabilized with respect to both the vapor and the solid, as shown in Figure 13.10. For non-ideal solutions, the formulas that we will derive below are only valid approximately, but they work well for dilute solutions.




Figure 13.10.: Reduction of the Chemical Potential of the Liquid Phase Due to the Addition of a Solute.

For dilute solutions, the most useful measure of concentration is the molality, m, defined as the number of moles of solute divided by the mass of the solvent in kilograms:[2]

$$m = \frac{n_{\text{solute}}}{m_{\text{solvent}}}. \tag{13.17}$$

For a dilute solution, the mole fraction of the solute is related to the molality by a simple approximation. Since $n_{\text{solute}} \ll n_{\text{solvent}}$:

$$x_{\text{solute}} = \frac{n_{\text{solute}}}{n_{\text{solute}} + n_{\text{solvent}}} \approx \frac{n_{\text{solute}}}{n_{\text{solvent}}} = \frac{n_{\text{solute}}}{m_{\text{solvent}}/M} = mM, \tag{13.18}$$

where M is the molar mass of the solvent, in kg/mol.

13.5.1. Vapor pressure lowering

As we have already seen in Figure 13.1, the vapor pressure above a solution of a nonvolatile solute follows Raoult's law. Its difference with respect to the vapor pressure of the pure solvent is:

[2] Molality is preferred over molarity because it does not depend on the temperature, since masses, unlike volumes, do not change when the solution is heated or cooled.

$$\begin{aligned} P^*_{\text{solvent}} - P_{\text{solution}} &= P^*_{\text{solvent}} - x_{\text{solvent}} P^*_{\text{solvent}} \\ &= (1 - x_{\text{solvent}})\, P^*_{\text{solvent}} = x_{\text{solute}} P^*_{\text{solvent}}, \end{aligned} \tag{13.19}$$

which shows that the vapor pressure lowering depends only on the mole fraction of the solute, and not on its nature. As such, it is a colligative property.

13.5.2. Boiling point elevation and melting point depression

Let's now look at Figure 13.10 again. Since the chemical potential of the liquid is lowered, its line crosses the line of the gas at a higher temperature, and the line of the solid at a lower temperature. Therefore, the boiling point increases, and the melting point decreases. To find out by how much, let's follow the boiling point step by step.[3]

1. **The equilibrium condition.** At the boiling point of the solution, T_{b}, the chemical potential of the pure vapor equals that of the solvent in the solution, eq. 13.16:

$$\mu^*_{\text{gas}}(T_{\text{b}}) = \mu^*_{\text{liquid}}(T_{\text{b}}) + RT_{\text{b}} \ln x_{\text{solvent}} \quad \Rightarrow \quad \ln x_{\text{solvent}} = \frac{\mu^*_{\text{gas}} - \mu^*_{\text{liquid}}}{RT_{\text{b}}} = \frac{\Delta_{\text{vap}}G}{R} \tag{13.20}$$

   where $\Delta_{\text{vap}}G$ is the molar Gibbs energy of vaporization of the *pure* solvent.
2. **The Gibbs–Helmholtz equation.** We know that $\Delta_{\text{vap}}G = 0$ at the boiling point of the pure solvent, T^*_{b}. We can find its value at T_{b} by integrating the Gibbs–Helmholtz equation, eq. 9.9, between T^*_{b} and T_{b}, assuming that $\Delta_{\text{vap}}H$ is constant:

$$\frac{\Delta_{\text{vap}}G(T_{\text{b}})}{T_{\text{b}}} = \Delta_{\text{vap}}H \left(\frac{1}{T_{\text{b}}} - \frac{1}{T^*_{\text{b}}} \right) \quad \Rightarrow \quad \ln x_{\text{solvent}} = \frac{\Delta_{\text{vap}}H}{R} \left(\frac{1}{T_{\text{b}}} - \frac{1}{T^*_{\text{b}}} \right). \tag{13.21}$$

3. **The dilute-solution approximations.** For a dilute solution, $\ln x_{\text{solvent}} = \ln(1 - x_{\text{solute}}) \approx -x_{\text{solute}}$, and since T_{b} and T^*_{b} are very close to each other, $\frac{1}{T_{\text{b}}} - \frac{1}{T^*_{\text{b}}} = \frac{T^*_{\text{b}} - T_{\text{b}}}{T_{\text{b}} T^*_{\text{b}}} \approx -\frac{\Delta T_{\text{b}}}{(T^*_{\text{b}})^2}$. Replacing both into eq. 13.21, and using eq. 13.18 for the mole fraction of the solute:

$$\Delta T_{\text{b}} = \frac{R\,(T^*_{\text{b}})^2}{\Delta_{\text{vap}}H}\, x_{\text{solute}} = \underbrace{\frac{RM\,(T^*_{\text{b}})^2}{\Delta_{\text{vap}}H}}_{K_{\text{b}}}\, m. \tag{13.22}$$

[3] This is a plausibility argument rather than a rigorous proof, since we will use two approximations that are valid only for dilute solutions.

The constant K_b is called the *ebullioscopic constant* of the solvent, and it depends only on the properties of the pure solvent. For example, for water, using $M = 0.018$ kg/mol, $T_\mathrm{b}^* = 373$ K, and $\Delta_\mathrm{vap}H = 40.7$ kJ/mol, we obtain $K_\mathrm{b} = 0.51 \frac{\mathrm{K\ kg}}{\mathrm{mol}}$, in excellent agreement with the experimental value of $0.512 \frac{\mathrm{K\ kg}}{\mathrm{mol}}$.

So far, we have assumed that each unit of solute produces one particle in solution. Since colligative properties depend on the *number* of particles, if a solute dissociates into ions, its effect is multiplied. We account for this with the *van 't Hoff factor*, i, which counts the number of particles produced by each formula unit of solute. The final formula for the boiling point elevation is:

$$\Delta T_\mathrm{b} = T_\mathrm{b}^\mathrm{solution} - T_\mathrm{b}^\mathrm{solvent} = iK_\mathrm{b}m. \tag{13.23}$$

For a solute that does not dissociate in solution, such as sugar, $i = 1$. For example, the strong electrolyte $CaCl_2$ completely dissociates into three particles in solution, one Ca^{2+} and two Cl^-, and $i = 3$. For cases of partial dissociation, such as weak acids, weak bases, and their salts, i can assume non-integer values.

The depression of the melting point is obtained with exactly the same procedure, using the equilibrium between the pure solid and the solution instead of the one between the pure vapor and the solution. The result is:

$$\Delta T_\mathrm{m} = T_\mathrm{m}^\mathrm{solution} - T_\mathrm{m}^\mathrm{solvent} = -iK_\mathrm{m}m, \qquad \text{with} \qquad K_\mathrm{m} = \frac{RM\left(T_\mathrm{m}^*\right)^2}{\Delta_\mathrm{fus}H}, \tag{13.24}$$

where K_m is the *cryoscopic constant* of the solvent, and the minus sign accounts for the fact that the melting temperature decreases (ΔT_m is negative, while i, K_m, and m are all positive). For water, $K_\mathrm{m} = 1.86 \frac{\mathrm{K\ kg}}{\mathrm{mol}}$. This is why we spread salt on icy roads: a salt solution freezes at a lower temperature than pure water.

Notice from Figure 13.10 how the depression of the melting point is much larger than the elevation of the boiling point. To understand why, we can recall that the slope of each line in Figure 13.10 is $-S$ (eq. 12.2). When we lower the liquid line, the new crossing point moves more if the two crossing lines have similar slopes, and less if their slopes are very different. The slopes of the liquid and the solid lines differ by the entropy of fusion, which is small, while the slopes of the liquid and gas lines differ by the entropy of vaporization, which is large. Mathematically, since $\Delta H = T\Delta S$ at the transition, we can rewrite the two constants as $K = RMT^*/\Delta S$, where

ΔS is the entropy of the corresponding transition. For water, $\Delta_{\text{fus}}S = 22\ \text{J mol}^{-1}\,\text{K}^{-1}$ and $\Delta_{\text{vap}}S = 109\ \text{J mol}^{-1}\,\text{K}^{-1}$, which explains why K_{m} is almost four times larger than K_{b}.

13.5.3. Osmotic pressure

The osmotic pressure is probably the most important colligative property for biology and medicine. Consider the apparatus in Figure 13.11, where a solution and the pure solvent are separated by a *semi-permeable* (osmotic) membrane. This membrane is made of a material that lets the solvent molecules through, but blocks the solute ones.




Figure 13.11.: Osmotic Pressure of a Solution.

Since the chemical potential of the solvent in the solution is lower than that of the pure solvent, eq. 13.16, the solvent spontaneously flows from the pure side into the solution, across the membrane. As a consequence, the level of the solution rises, and its pressure increases. The flow stops when the extra pressure on the solution side raises the chemical potential of its solvent back to that of the pure solvent. This extra pressure, π, is called the **osmotic pressure**. We can calculate it step by step:

1. **The equilibrium condition.** At equilibrium, the chemical potential of the pure solvent at pressure P equals that of the solvent in the solution at pressure $P + \pi$:

$$\mu^*_{\text{solvent}}(P) = \mu^*_{\text{solvent}}(P + \pi) + RT \ln x_{\text{solvent}}. \tag{13.25}$$

2. **The effect of pressure.** As we saw in chapter 9, the chemical potential of a liquid increases with pressure as $d\mu = \overline{V}dP$, and, since liquids are essentially incompressible, $\mu^*_{\text{solvent}}(P + \pi) - \mu^*_{\text{solvent}}(P) =$

$\overline{V}\pi$, where $\overline{V}$ is the molar volume of the solvent. Replacing into eq. 13.25:

$$\overline{V}\pi = -RT \ln x_{\text{solvent}}. \tag{13.26}$$

3. **The dilute-solution approximation.** Using again $-\ln x_{\text{solvent}} \approx x_{\text{solute}} \approx n_{\text{solute}}/n_{\text{solvent}}$, and noticing that $n_{\text{solvent}}\overline{V}$ is essentially the volume of the solution, V:

$$\pi = \frac{n_{\text{solute}}}{V} RT = i\, cRT, \tag{13.27}$$

where c is the molar concentration of the solute, and we have introduced again the van 't Hoff factor, i, to account for dissociation.

Eq. 13.27 was proposed by van 't Hoff, and it is remarkably similar to the ideal gas law. Morse later refined it by using the molality instead of the molar concentration, which gives better results at higher concentrations.[4] Osmotic pressures can be surprisingly large: a solution with $c = 0.10$ mol/L of sugar at room temperature has $\pi \approx 2.5$ bar, enough to push a column of water up by about 25 m. This is why intravenous fluids must have the same osmotic pressure as blood: if the solution were too dilute, water would flow into the red blood cells, making them swell and burst. If we apply to the solution side a pressure higher than π, we can reverse the flow and push pure solvent out of the solution. This process, called *reverse osmosis*, is widely used to obtain drinkable water from seawater.

13.6. Chapter Review

13.6.1. Study Questions

1. What is an ideal solution?

a. A solution where the interactions between different molecules (A–B) are, on average, the same as those between equal molecules (A–A and B–B).
b. A solution where the molecules do not interact at all.
c. A solution whose vapor is an ideal gas.
d. A solution of a single component.
e. A solution that cannot be distilled.

---

2. What does Raoult's law state?

[4] The Morse equation reads $\pi = imRT$. For dilute aqueous solutions, molality and molarity are nearly equal, since 1 kg of water occupies about 1 L.

a. $P_i = y_i P_{\mathrm{TOT}}$.
b. $P_i = k_{\mathrm{H},i} x_i$.
c. $P_i = x_i P_i^*$.
d. $P_i = \frac{x_i}{P_i^*}$.
e. $P_i = x_i RT$.

---

3. What is the composition of the vapor above an ideal solution of two volatile components?

a. The same as the liquid.
b. Pure solvent.
c. Richer in the less volatile component.
d. Always 50% of each component.
e. Richer in the more volatile component.

---

4. How many degrees of freedom does a binary system have when a liquid and its vapor coexist?

a. 0.
b. 2.
c. 3.
d. 4.
e. 1.

---

5. Why is the melting point depression of water larger than its boiling point elevation, for the same amount of solute?

a. Because ice is less dense than water.
b. Because the solute dissolves in ice.
c. Because the vapor contains the solute.
d. Because the entropy of fusion is much smaller than the entropy of vaporization.
e. Because water has a high heat capacity.

---

6. When does a component of a solution follow Henry's law?

a. When it is dilute (its mole fraction is close to zero).
b. When it is the solvent.
c. When it is pure.
d. When the solution is ideal.
e. When it is not volatile.

---

7. What is the molecular origin of a positive deviation from Raoult's law?

a. The A–B interactions are stronger than the A–A and B–B ones.
b. The solution is ideal.
c. The A–B interactions are weaker than the A–A and B–B ones.
d. The solute is nonvolatile.
e. The vapor is not an ideal gas.

---

8. Why can an azeotrope not be separated by simple distillation?

a. Because it does not boil.
b. Because it boils at 100 °C.
c. Because it contains only one component.
d. Because its components react with each other.
e. Because the liquid and the vapor have the same composition.

---

9. What is the activity coefficient of a component that shows a positive deviation from Raoult's law?

a. $\gamma_i = 0$.
b. $\gamma_i > 1$.
c. $\gamma_i = 1$.
d. $0 < \gamma_i < 1$.
e. $\gamma_i < 0$.

---

10. What is the common origin of all colligative properties?

a. The solute reacts with the solvent.

b. The solute increases the vapor pressure of the solvent.
c. The solute increases the chemical potential of the solvent.
d. The solute lowers the chemical potential of the solvent, an entropic effect that depends only on the mole fraction.
e. The solute changes the molar mass of the solvent.

Answers

1.a, 2.c, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

14. Chemical Kinetics

From thermodynamics, we can determine the spontaneity of a reaction and its extent, using ΔG and K_{eq}, respectively. However, thermodynamics does not provide any information on how *fast* the reaction is going to happen. For example, while the reaction that converts solid carbon from its diamond allotropic form into hexagonal graphite is thermodynamically spontaneous, it is so slow as to be virtually non-existent. Diamond is effectively a metastable phase. The speed of a chemical reaction is the subject of a branch of physical chemistry called chemical kinetics.

A chemical kinetics study aims to find the *rate* of a reaction and to find the microscopic steps that compose it, determining its *mechanism*. In this last chapter, we will therefore leave equilibrium behind and look at how concentrations change with time, how we can measure the rate of a reaction, and why reactions speed up when we heat them.

14.1. Differential and integrated rate laws

The rate law of a chemical reaction is an equation that links the initial rate with the concentrations (or pressures) of the reactants. Rate laws usually include a constant parameter, k, called the *rate coefficient*, and several parameters found at the exponent of the concentrations of the reactants, and are called *reaction orders*. The rate coefficient depends on several conditions, including the reaction type, the temperature, the surface area of an adsorbent, light irradiation, and others. The rate coefficient is usually represented with the lowercase letter k, and it should not be confused with the thermodynamic equilibrium constant that is generally designated with the uppercase letter K. Another useful concept in kinetics is the half-life, usually abbreviated with $t_{1/2}$. The half-life is defined as the time required to reach half of the initial reactant concentration.

A reaction that happens in one single microscopic step is called elementary. Elementary reactions have reaction orders equal to the (integer) stoichiometric coefficients for each reactant. As such, only a limited number of elementary reactions are possible (four types are commonly observed), and they are classified according to their overall reaction order. The global

reaction order of a reaction is calculated as the sum of each reactant's individual orders and is, at most, equal to three. The number of molecules that take part in an elementary step is called its *molecularity*: an elementary step involving one molecule is *unimolecular*, one involving two molecules is *bimolecular*, and one involving three molecules is *termolecular*. Keep in mind that the order is an experimental property of the rate law, while the molecularity describes a single microscopic step: the two coincide only for elementary reactions. We examine in detail the four most common reaction orders below.

14.1.1. Zeroth-order reaction

For a zeroth-order reaction, the reaction rate is independent of the concentration of a reactant. In other words, if we have a reaction of the type:

$$\mathrm{A} \longrightarrow \text{products}$$

the differential rate law can be written:

$$-\frac{d[\mathrm{A}]}{dt} = k_0[\mathrm{A}]^0 = k_0, \tag{14.1}$$

which shows that any change in the concentration of A will have no effect on the speed of the reaction. The minus sign on the left-hand side is required because the rate is always defined as a positive quantity, while the derivative is negative because the concentration of the reactant is diminishing with time. Separating the variables [A] and t of eq. 14.1 and integrating both sides, we obtain the integrated rate law for a zeroth-order reaction as:

$$\begin{aligned} \int_{[\mathrm{A}]_0}^{[A]} d[\mathrm{A}] &= -k_0 \int_{t=0}^{t} dt \\ [\mathrm{A}] - [\mathrm{A}]_0 &= -k_0 t \end{aligned} \tag{14.2}$$

$$[\mathrm{A}] = [\mathrm{A}]_0 - k_0 t.$$

Using the integrated rate law, we notice that the concentration of the reactant diminishes linearly with respect to time. A plot of [A] as a function of t, therefore, will result in a straight line with a slope equal to $-k_0$, as in the plot of Figure 14.1.

Eq. 14.2 also suggests that the units of the rate coefficient for a zeroth-order reaction are of concentration divided by time, typically $\frac{\mathrm{M}}{\mathrm{s}}$, with M being




Figure 14.1.: Reaction Rate Plot for a Zeroth-Order Reaction.

the molar concentration in $\frac{\text{mol}}{\text{L}}$ and s the time in seconds. The half-life of a zero order reaction can be calculated from eq. 14.2, by replacing [A] with $\frac{1}{2}[\text{A}]_0$:

$$\begin{aligned} \frac{1}{2}[\text{A}]_0 &= [\text{A}]_0 - k_0 t_{1/2} \\ t_{1/2} &= \frac{[\text{A}]_0}{2k_0}. \end{aligned} \tag{14.3}$$

Zeroth-order reactions are common in several biochemical processes catalyzed by enzymes, such as the oxidation of ethanol to acetaldehyde in the liver by the alcohol dehydrogenase enzyme, which is zero-order in ethanol.

14.1.2. First-order reaction

In a first-order reaction, the rate is proportional to the concentration of a single reactant. If a first-order reaction is elementary, it involves a single molecule, and it is unimolecular (for example, an isomerization or a radioactive decay). However, many first-order reactions are not elementary, so we should not use the two words as synonyms. As for the previous case, if we consider a reaction of the type:

$$\text{A} \rightarrow \text{products}$$

the differential rate law for a first-order reaction is:

$$-\frac{d[\mathrm{A}]}{dt} = k_1[\mathrm{A}]. \tag{14.4}$$

Following the usual blueprint of separating the variables, and integrating both sides, we obtain the integrated rate law as:

$$\begin{aligned} \int_{[\mathrm{A}]_0}^{[A]} \frac{d[\mathrm{A}]}{[\mathrm{A}]} &= -k_1 \int_{t=0}^{t} dt \\ \ln \frac{[\mathrm{A}]}{[\mathrm{A}]_0} &= -k_1 t \end{aligned} \tag{14.5}$$

$$[\mathrm{A}] = [\mathrm{A}]_0 \exp(-k_1 t).$$

Using the integrated rate law to plot the concentration of the reactant, [A], as a function of time, t, we obtain an exponential decay, as in Figure 14.2.




Figure 14.2.: Reaction Rate Plot for a First-Order Reaction.

However, if we plot the logarithm of the concentration, ln[A], as a function of time, we obtain a line with slope $-k_1$, as in the plot of Figure 14.3. From eq. 14.5, we can also obtain the units for the rate coefficient for a first-order reaction, which typically is $\frac{1}{\mathrm{s}}$, independent of concentration. Since the rate coefficient for first-order reactions has units of inverse time, it is sometimes called the frequency rate.

The half-life of a first-order reaction is:




Figure 14.3.: Linear Plot for a First-Order Reaction. Notice that the Quantity on the y Axis is ln[A].

$$\ln \frac{\frac{1}{2}[\mathrm{A}]_0}{[\mathrm{A}]_0} = -k_1 t_{1/2}$$
$$t_{1/2} = \frac{\ln 2}{k_1}. \tag{14.6}$$

The half-life of a first-order reaction is independent of the initial concentration of the reactant. Therefore, the half-life can be used in place of the rate coefficient to describe the reaction rate. Typical examples of first-order reactions are radioactive decays. For radioactive isotopes, it is common to report their rate of decay in terms of their half-life. For example, the most stable uranium isotope, ^{238}U, has a half-life of 4.468×10^9 years, while the most common fissile isotope of uranium, ^{235}U, has a half-life of 7.038×10^8 years.[1] Other examples of first-order reactions in chemistry are the class of S_N1 nucleophilic substitution reactions in organic chemistry.

14.1.3. Second-order reaction

A reaction is second-order when the sum of the reaction orders is two. Elementary second-order reactions are also called *bimolecular reactions*. There are two possibilities, a simple one, where the reaction order of one reagent is two, or a more complicated one, with two reagents having each a reaction order of one.

[1] Notice how large these numbers are for uranium. To put these numbers in perspective, we can compare them with the half-life of a common isotope of plutonium, ^{241}Pu, which is $t_{1/2} = 14.3$ years.

- For the simple case, we can write the reaction as:

$$2\text{A} \rightarrow \text{products}$$

the differential rate law for a second-order reaction is:

$$-\frac{d[\text{A}]}{dt} = k_2[\text{A}]^2. \tag{14.7}$$

Following the same procedure used for the two previous cases, we can obtain the integrated rate law as:

$$\begin{aligned} \int_{[\text{A}]_0}^{[A]} \frac{d[\text{A}]}{[\text{A}]^2} &= -k_2 \int_{t=0}^{t} dt \\ \frac{1}{[\text{A}]} - \frac{1}{[\text{A}]_0} &= k_2 t \end{aligned} \tag{14.8}$$

$$\frac{1}{[\text{A}]} = \frac{1}{[\text{A}]_0} + k_2 t.$$

As for first-order reactions, the plot of the concentration as a function of time shows a non-linear decay. However, if we plot the inverse of the concentration, $\frac{1}{[\text{A}]}$, as a function of time, t, we obtain a line with slope $+k_2$, as in the plot of Figure 14.4.




Figure 14.4.: Linear Plot for a Second-Order Reaction. Notice that the Quantity on the y Axis is 1/[A].

Notice that the line has a *positive* slope, in contrast with the previous two cases, for which the slopes were negative. The units of k for a simple second order reaction are calculated from eq. 14.8 and typically are $\frac{1}{\text{M}\cdot\text{s}}$.

The half-life of a simple second-order reaction is:

$$\begin{aligned} \frac{1}{\frac{1}{2}[\mathrm{A}]_0} - \frac{1}{[\mathrm{A}]_0} &= k_2 t_{1/2} \\ t_{1/2} &= \frac{1}{k_2[\mathrm{A}]_0}, \end{aligned} \tag{14.9}$$

which, perhaps not surprisingly, depends on the initial concentration of the reactant, $[\mathrm{A}]_0$. Therefore, if we start with a higher concentration of the reactant, the half-life will be shorter, and the reaction will be faster. An example of simple second-order behavior is the reaction $\mathrm{NO_2} + \mathrm{CO} \rightarrow \mathrm{NO} + \mathrm{CO_2}$, which is second-order in $\mathrm{NO_2}$ and zeroth-order in CO.

- For the complex second-order case, the reaction is:

  $$\mathrm{A} + \mathrm{B} \rightarrow \text{products}$$

  and the differential rate law is:

  $$-\frac{d[\mathrm{A}]}{dt} = k_2'[\mathrm{A}][\mathrm{B}]. \tag{14.10}$$

  The differential equation in eq. 14.10 has two variables, and cannot be solved exactly unless an additional relationship is specified. If we assume that the initial concentrations of the two reactants are equal, then $[\mathrm{A}] = [\mathrm{B}]$ at any time t, and eq. 14.10 reduces to eq. 14.7. If the concentrations of the reactants are different, then the integrated rate law will assume the following shape:

  $$\frac{[\mathrm{A}]}{[\mathrm{B}]} = \frac{[\mathrm{A}]_0}{[\mathrm{B}]_0} \exp\left\{\left([\mathrm{A}]_0 - [\mathrm{B}]_0\right) k_2' t\right\}. \tag{14.11}$$

  The units of k for a complex second order reaction can be calculated from eq. 14.11, and are the same as those for the simple case, $\frac{1}{\mathrm{M \cdot s}}$. The half-life of a complex second-order reaction cannot be easily written since two different half-lives could, in principle, be defined for each of the corresponding reactants.

14.1.4. Third- and higher-order reactions

Although elementary reactions with order higher than two are possible, they are in practice infrequent, and only very few experimental third-order reactions are observed. Fourth-order or higher have never been observed because the probabilities for a simultaneous interaction between four molecules are essentially zero. Third-order elementary reactions are also called *termolecular reactions*. While termolecular reactions with three

identical reactants are possible in principle, there is no known experimental example. Some complex third-order reactions are known, such as:

$$2\mathrm{NO}_{(g)} + \mathrm{O}_{2(g)} \longrightarrow 2\mathrm{NO}_{2(g)}$$

for which the differential rate law can be written as:

$$-\frac{dP_{\mathrm{O}_2}}{dt} = k_3 P_{\mathrm{NO}}^2 P_{\mathrm{O}_2}. \tag{14.12}$$

14.2. Complex Rate Laws

It is essential to specify that the order of a reaction and its molecularity are equal only for elementary reactions. Reactions that follow complex laws are composed of several elementary steps, and they usually have non-integer reaction orders, for at least one of the reactants.

14.2.1. Consecutive reactions

A reaction that happens following a sequence of two elementary steps can be written as follows:

$$\mathrm{A} \xrightarrow{k_1} \mathrm{B} \xrightarrow{k_2} \mathrm{C}$$

Assuming that each of the steps follows a first order kinetic law, and that only the reagent A is present at the beginning of the reaction, we can write the differential change in concentration of each species with respect to infinitesimal time dt, using the following formulas:

$$\begin{aligned} -\frac{d[\mathrm{A}]}{dt} &= k_1[\mathrm{A}] \Rightarrow [\mathrm{A}] = [\mathrm{A}]_0 \exp(-k_1 t) \\ \frac{d[\mathrm{B}]}{dt} &= k_1[\mathrm{A}] - k_2[\mathrm{B}] \\ \frac{d[\mathrm{C}]}{dt} &= k_2[\mathrm{B}]. \end{aligned} \tag{14.13}$$

These three equations represent a system of differential equations with three unknown variables. Unfortunately, these equations are linearly dependent on each other, and they are not sufficient to solve the system for each variable. To do so, we need to include a fourth equation, coming from the conservation of mass:

$$[\mathrm{A}]_0 = [\mathrm{A}] + [\mathrm{B}] + [\mathrm{C}]. \tag{14.14}$$

Using the first equation in eq. 14.13, we can now replace the concentration [A] in the second equation and solve for [B]:

$$\frac{d[\mathrm{B}]}{dt} + k_2[\mathrm{B}] = k_1[\mathrm{A}]_0 \exp(-k_1 t), \tag{14.15}$$

which can be simplified by multiplying both sides by $\exp(k_2 t)$:

$$\begin{aligned} \left(\frac{d[\mathrm{B}]}{dt} + k_2[\mathrm{B}]\right)\exp(k_2 t) &= k_1[\mathrm{A}]_0 \exp[(k_2 - k_1)t] \\ \Rightarrow \frac{d\left\{[\mathrm{B}]\exp(k_2 t)\right\}}{dt} &= k_1[\mathrm{A}]_0 \exp[(k_2 - k_1)t], \end{aligned} \tag{14.16}$$

which can then be integrated remembering that $[B]_0 = 0$, and $\int \exp(kx) = \frac{1}{k}\exp(kx)$:

$$[\mathrm{B}] = \frac{k_1}{k_2 - k_1}[\mathrm{A}]_0[\exp(-k_1 t) - \exp(-k_2 t)]. \tag{14.17}$$

We can then use both [A], from eq. 14.13, and [B], from eq. 14.17, in eq. 14.14 to solve for [C]:

$$\begin{aligned} [\mathrm{C}] &= [\mathrm{A}]_0 - [\mathrm{A}] - [\mathrm{B}] \\ &= [\mathrm{A}]_0 - [\mathrm{A}]_0 \exp(-k_1 t) - \frac{k_1}{k_2 - k_1}[\mathrm{A}]_0[\exp(-k_1 t) - \exp(-k_2 t)] \\ &= [\mathrm{A}]_0 \left\{1 + \frac{-k_2 \exp(-k_1 t) + k_1 \exp(-k_2 t)}{k_2 - k_1}\right\}. \end{aligned} \tag{14.18}$$

From these results, we can distinguish two typical behaviors, depending on which of the two steps is the slowest. The slowest step in a sequence is called the *rate-determining step*, since, just like the narrowest point of a funnel, it limits how fast the whole process can go.

The first behavior is observed when the second step is slower than, or comparable to, the first one. For example, Figure 14.5 reports the concentrations with respect to time for $k_1 = 2k_2$. In this case, the rate-determining step is the second reaction. A is converted into B faster than B can be converted into C, so the intermediate accumulates: its concentration grows, reaches a maximum, and then decreases as A runs out. The product C




Figure 14.5.: Concentration Plot for a Process with Two Consecutive Reactions with the Second One Being the Rate-Determining Step.

forms slowly at the beginning (notice the S shape of its curve), since it has to wait for B to build up.

The second behavior is observed when the first step is much slower than the second one, $k_1 \ll k_2$, as in the plot of Figure 14.6. In this case, the rate-determining step is the first reaction. Every molecule of B is converted into C almost as soon as it is formed, so the concentration of the intermediate stays very small at all times, and C appears as fast as A disappears. As such, the process has the same rate law as an elementary reaction going directly from A to C.




Figure 14.6.: Concentration Plot for a Process with Two Consecutive Reactions with the First One Being the Rate-Determining Step.

Since, in this second case, the concentration of B is small and almost constant throughout the process, we can approximate its derivative to zero. This simplification is known as the *steady-state approximation*, and it allows us to eliminate the intermediate from the treatment. Using the second line of eq. 14.13:

$$\frac{d[\mathrm{B}]}{dt} = k_1[\mathrm{A}] - k_2[\mathrm{B}] \approx 0 \quad \Rightarrow \quad [\mathrm{B}] \approx \frac{k_1}{k_2}[\mathrm{A}], \tag{14.19}$$

which is indeed very small, since $k_1 \ll k_2$. Replacing eq. 14.19 into the third line of eq. 14.13, the rate of formation of the product becomes:


$$\frac{d[\mathrm{C}]}{dt} = k_2[\mathrm{B}] \approx k_1[\mathrm{A}], \tag{14.20}$$

which is exactly the rate law of an elementary first-order reaction going directly from A to C, with the rate coefficient of the slow step. The steady-state approximation is widely used to study processes that go through a series of very reactive intermediates, whose concentrations stay small and almost constant throughout the entire process:

$$\begin{aligned} &\mathrm{A} \xrightarrow{k_1} \mathrm{I}_1 \xrightarrow{k_2} \mathrm{I}_2 \longrightarrow \cdots \xrightarrow{k_n} \text{products} \\ &\quad \text{Steady State Approximation:} \\ &\mathrm{A} \longrightarrow \text{products} \end{aligned} \tag{14.21}$$

14.2.2. Competitive reactions

A process where two elementary reactions happen in parallel, competing with each other, can be written as follows:



Assuming that each step follows first-order kinetics, we can write:

$$
\begin{aligned}
-\frac{d[\mathrm{A}]}{dt} &= k_1[\mathrm{A}] + k_2[\mathrm{A}] \Rightarrow [\mathrm{A}] = [\mathrm{A}]_0 \exp\left[-(k_1 + k_2)t\right] \\
\frac{d[\mathrm{B}]}{dt} &= k_1[\mathrm{A}] \Rightarrow [\mathrm{B}] = \frac{k_1}{k_1 + k_2}[\mathrm{A}]_0 \left\{1 - \exp\left[-(k_1 + k_2)t\right]\right\} \\
\frac{d[\mathrm{C}]}{dt} &= k_2[\mathrm{A}] \Rightarrow [\mathrm{C}] = \frac{k_2}{k_1 + k_2}[\mathrm{A}]_0 \left\{1 - \exp\left[-(k_1 + k_2)t\right]\right\}.
\end{aligned}
\tag{14.22}
$$

The concentration of each of the species can then be plotted against time, obtaining the diagram reported in Figure 14.7. The final concentrations of the products, $[\mathrm{B}]_f$ and $[\mathrm{C}]_f$, will depend on the values of the two rate coefficients. For example, if $k_1 > k_2$, $[\mathrm{B}]_f > [\mathrm{C}]_f$, as in Figure 14.7, but if $k_1 < k_2$, $[\mathrm{B}]_f < [\mathrm{C}]_f$.




Figure 14.7.: Concentration Plot for a Process with Two Competitive Reactions.

An important relationship that can be derived from eq. 14.22 is that:

$$
\frac{[\mathrm{B}]}{[\mathrm{C}]} = \frac{k_1}{k_2}. \tag{14.23}
$$

14.2.3. Opposed reactions

Another case of complex kinetic law happens when a pair of forward and reverse reactions occur simultaneously:

$$
\mathrm{A} \underset{k_{-1}}{\overset{k_1}{\rightleftharpoons}} \mathrm{B}
$$

where the rate coefficients for the forward and backwards reaction, k_1 and k_{-1}, respectively, are not necessarily equal to each other, but comparable in magnitude. We can write the rate laws for each of these elementary steps as:

$$\begin{aligned} -\frac{d[\mathrm{A}]}{dt} &= k_1[\mathrm{A}] - k_{-1}[\mathrm{B}] = k_1[\mathrm{A}] - k_{-1}\left([\mathrm{A}]_0 - [\mathrm{A}]\right) \\ \frac{d[\mathrm{A}]}{dt} &= -(k_1 + k_{-1})[\mathrm{A}] + k_{-1}[\mathrm{A}]_0, \end{aligned} \tag{14.24}$$

which can then be integrated to:

$$\begin{aligned} [\mathrm{A}] &= [\mathrm{A}]_0 \frac{k_{-1} + k_1 \exp[-(k_1 + k_{-1})t]}{k_1 + k_{-1}} \\ [\mathrm{B}] &= [\mathrm{A}]_0 \left\{ 1 - \frac{k_{-1} + k_1 \exp[-(k_1 + k_{-1})t]}{k_1 + k_{-1}} \right\}. \end{aligned} \tag{14.25}$$

These formulas can then be used to obtain the plots in Figure 14.8.




Figure 14.8.: Concentration Plot for a Process with Two Opposed Reactions.

As can be seen from the plots in Figure 14.8, after a sufficiently long time, the system reaches a dynamic equilibrium, where the concentrations of A and B don't change. These equilibrium concentrations can be calculated replacing $t = \infty$ in eq. 14.25:

$$\begin{aligned}[\mathrm{A}]_{\mathrm{eq}} &= [\mathrm{A}]_0 \frac{k_{-1}}{k_1 + k_{-1}} \\ [\mathrm{B}]_{\mathrm{eq}} &= [\mathrm{A}]_0 \frac{k_1}{k_1 + k_{-1}}.\end{aligned} \tag{14.26}$$

Considering that the concentrations of the species don't change at equilibrium:

$$\begin{aligned} -\frac{d[\mathrm{A}]_{\mathrm{eq}}}{dt} &= \frac{d[\mathrm{B}]_{\mathrm{eq}}}{dt} = 0 \\ &\Rightarrow\ k_1[\mathrm{A}]_{\mathrm{eq}} = k_{-1}[\mathrm{B}]_{\mathrm{eq}} \\ &\Rightarrow\ \frac{k_1}{k_{-1}} = \frac{[\mathrm{B}]_{\mathrm{eq}}}{[\mathrm{A}]_{\mathrm{eq}}} = K_C, \end{aligned} \tag{14.27}$$

where K_C is the equilibrium constant as defined in chapter 10. This is a rare link between kinetics and thermodynamics and appears only for opposed reactions after sufficient time has passed so that the system can reach the dynamic equilibrium.

14.3. Experimental Methods for Determination of Reaction Orders

To experimentally measure the reaction rate, we need a method to measure concentration changes with respect to time. The simplest way to determine the reaction rate is to monitor the entire reaction as it proceeds and then plot the resulting data differently until a linear plot is found. A summary of the results obtained in section 14.1 and that is useful for this task is reported in the following table:

	Zeroth-Order	*First-Order*	*Simple Second-Order*	*Complex Second-Order*
Differential Rate Law	$-\frac{d[\mathrm{A}]}{dt} = k_0[\mathrm{A}]^0 = k_0$	$-\frac{d[\mathrm{A}]}{dt} = k_1[\mathrm{A}]$	$-\frac{d[\mathrm{A}]}{dt} = k_2[\mathrm{A}]^2$	$-\frac{d[\mathrm{A}]}{dt} = k_2'[\mathrm{A}][\mathrm{B}]$
Integrated Rate Law	$[\mathrm{A}] = [\mathrm{A}]_0 - k_0 t$	$[\mathrm{A}] = [\mathrm{A}]_0 e^{-k_1 t}$	$\frac{1}{[\mathrm{A}]} = \frac{1}{[\mathrm{A}]_0} + k_2 t$	$\frac{[\mathrm{A}]}{[\mathrm{B}]} = \frac{[\mathrm{A}]_0}{[\mathrm{B}]_0} e^{([\mathrm{A}]_0 - [\mathrm{B}]_0)k_2' t}$
Units of k	$\frac{\mathrm{M}}{\mathrm{s}}$	$\frac{1}{\mathrm{s}}$	$\frac{1}{\mathrm{M}\cdot\mathrm{s}}$	$\frac{1}{\mathrm{M}\cdot\mathrm{s}}$
Linear Plot vs. t	$[\mathrm{A}]$	$\ln[\mathrm{A}]$	$\frac{1}{[\mathrm{A}]}$	$\ln \frac{[\mathrm{A}]_0[\mathrm{B}]}{[\mathrm{B}]_0[\mathrm{A}]}$
Half-life	$t_{1/2} = \frac{[\mathrm{A}]_0}{2k_0}$	$t_{1/2} = \frac{\ln 2}{k_1}$	$t_{1/2} = \frac{1}{k_2[\mathrm{A}]_0}$	not easily defined

However, this method works only if the reaction has few reactants, and it requires several measurements, each of which might be complicated to make. More useful methods to determine the reaction rate are the *initial rate* and the *isolation* methods that we describe below.

14.3.1. Initial rates method

The *initial rates method* involves measuring the rate of a reaction as soon as it starts before any significant change in the concentrations of the reactants occurs. The initial rate method is practical only if the reaction is reasonably slow, but it can measure the rate unambiguously when more than one reactant is involved. For example, if we have a reaction with the following stoichiometry:

$$\alpha\mathrm{A} + \beta\mathrm{B} \xrightarrow{k} \text{products}$$

the initial rate method can be used to determine the coefficients of the rate law:

$$\text{Rate} = k[\mathrm{A}]^{\alpha}[\mathrm{B}]^{\beta} \tag{14.28}$$

by designing three experiments, where the initial concentrations of A and B are appropriately changed. For example, let's consider the following experimental data from three different experiments:

	$[\mathrm{A}]_0$ (M)	$[\mathrm{B}]_0$ (M)	initial rate $\left(\frac{M}{s}\right)$
Experiment 1:	0.10	0.10	4.32
Experiment 2:	0.15	0.10	9.70
Experiment 3:	0.10	0.20	4.29

we can calculate α by taking the ratio of the rates measured in experiment 1 and 2:

$$\begin{aligned}
\frac{\text{Rate}(1)}{\text{Rate}(2)} &= \frac{k(0.10\ \mathrm{M})^{\alpha}(0.10\ \mathrm{M})^{\beta}}{k(0.15\ \mathrm{M})^{\alpha}(0.10\ \mathrm{M})^{\beta}} \\
\frac{4.32}{9.70} &= \frac{(0.10\ \mathrm{M})^{\alpha}}{(0.15\ \mathrm{M})^{\alpha}} \\
0.445 &= 0.667^{\alpha} \ \rightarrow\ \ln 0.445 = \alpha \ln 0.667 \\
\alpha &= \frac{-0.81}{-0.405} = 2.
\end{aligned} \tag{14.29}$$

β can be calculated similarly by taking the ratio between experiments 1 and 3. Alternatively, we can also notice that the reaction rate does not change when the initial concentration $[\mathrm{B}]_0$ is doubled, therefore $\beta = 0$.

14.3.2. Isolation method

Another method that is widely used to determine reaction orders is the *isolation method*. This method is performed by using large excess concentrations of all reactants but one. For example, if we have the following reaction with three reagents and unknown rate law:

$$\alpha\mathrm{A} + \beta\mathrm{B} + \gamma\mathrm{C} \xrightarrow{k} \text{products}$$

we can perform three different experiments, in each of which we use an excess amount of all reagents but one, such as:

- Experiment 1: $[\mathrm{A}]_0 = 1$ M, $[\mathrm{B}]_0 = 1000$ M, $[\mathrm{C}]_0 = 1000$ M, in which the reaction order with respect to A is measured.
- Experiment 2: $[\mathrm{A}]_0 = 1000$ M, $[\mathrm{B}]_0 = 1$ M, $[\mathrm{C}]_0 = 1000$ M, in which the reaction order with respect to B is measured.
- Experiment 3: $[\mathrm{A}]_0 = 1000$ M, $[\mathrm{B}]_0 = 1000$ M, $[\mathrm{C}]_0 = 1$ M, in which the reaction order with respect to C is measured.

From each experiment we can determine the *pseudo-order* of the reaction with respect to the reagent that is in minority concentration. For example, for the reaction above, we can write the rate law as:

$$\text{Rate} = k[\mathrm{A}]^{\alpha}[\mathrm{B}]^{\beta}[\mathrm{C}]^{\gamma} \tag{14.30}$$

and we can write the initial concentrations, $[X]_0$, and the final concentrations, $[X]_f$, of each of the species in experiment 1, as:

$$\begin{aligned}
[\mathrm{A}]_0 = 1\ \mathrm{M} &\longrightarrow [\mathrm{A}]_f = 0\ \mathrm{M} && (100\%\ \text{change})\\
[\mathrm{B}]_0 = 1000\ \mathrm{M} &\longrightarrow [\mathrm{B}]_f = 1000 - 1 = 999\ \mathrm{M} \cong [\mathrm{B}]_0 && (0.1\%\ \text{change})\\
[\mathrm{C}]_0 = 1000\ \mathrm{M} &\longrightarrow [\mathrm{C}]_f = 1000 - 1 = 999\ \mathrm{M} \cong [\mathrm{C}]_0\,. && (0.1\%\ \text{change})
\end{aligned}$$

The coefficient α can then be determined by incorporating the concentration of the reactants in excess into the rate constant as:

$$\begin{aligned} \text{rate} &= k[\text{A}]^{\alpha} \underbrace{[\text{B}]^{\beta}[\text{C}]^{\gamma}}_{\text{constant}} \\ &= k'[\text{A}]^{\alpha} \end{aligned}$$

and then determine α by verifying which order the data collected for [A] at various times fits. This can be simply achieved by using the zero-, first-, and second-order kinetic plots, as reported in the table above. We can determine β and γ by repeating the same procedure for the data from the other two experiments. For example, if we find for a specific reaction that $\alpha = 1$, $\beta = 2$, and $\gamma = 0$, we can then say that the reaction is pseudo-order one in A, pseudo-order two in B, and pseudo-order zero in C, with an overall reaction order of three.

14.4. Temperature Dependence of the Rate Coefficients

The dependence of the rate coefficient, k, on the temperature is given by the **Arrhenius equation**. This formula was derived by Svante August Arrhenius (1859–1927) in 1889 and is based on the simple experimental observation that almost every chemical process gets faster when the temperature is increased. Working on data from equilibrium reactions previously reported by van 't Hoff, Arrhenius proposed the following simple exponential formula to explain the increase of k when T is increased:

$$k = A \exp\left(-\frac{E_a}{RT}\right), \tag{14.31}$$

where A is the so-called Arrhenius pre-exponential factor, and E_a is the activation energy. Both of these terms are independent of temperature,[2] and they represent experimental quantities that are unique to each individual reaction. Since the vast majority of reactions speed up when the temperature increases, both A and E_a are positive.[3] The pre-exponential factor units are the same as the rate constant and will vary depending on the order of the reaction. As suggested by its name, the activation energy has units of energy per mole of substance, $\frac{\text{J}}{\text{mol}}$ in SI.

A few important considerations can be made by analyzing eq. 14.31:

[2] In theory, both A and E_a show a weak temperature dependence. However, they can be considered constants at most experimental conditions, since kinetic studies are usually performed in a small temperature range.

[3] A few reactions, such as some recombinations of radicals, slow down when the temperature increases, and they show a negative *apparent* activation energy. These reactions are not elementary: their mechanism involves more than one step, and the measured E_a is a combination of the activation energies of the individual steps.

1. **The rate coefficient grows exponentially with temperature.** For a typical activation energy of 50 kJ/mol, increasing the temperature from 298 K to 308 K almost doubles k. This is the origin of the rule of thumb that reactions near room temperature roughly double their rate for every 10 °C.
2. **Reactions with larger activation energies are more sensitive to temperature.** The larger E_a, the more a change in T affects the exponential.
3. **The exponential is the fraction of molecules that can react.** As we will see below, E_a is the height of an energy barrier, and $\exp\left(-\frac{E_a}{RT}\right)$ is related to the fraction of collisions that have enough energy to overcome it, while A is related to how often the molecules attempt to react.

The Arrhenius equation is experimentally useful in its linearized form. Taking the logarithm of both sides of eq. 14.31, we obtain $\ln k = \ln A - \frac{E_a}{R}\frac{1}{T}$, which is a straight line in a plot of $\ln k$ versus $1/T$. Applying eq. 14.31 to two experiments taken at different temperatures, and taking the ratio between the results, we obtain:

$$\ln \frac{k_{T_2}}{k_{T_1}} = -\frac{E_a}{R}\left(\frac{1}{T_2} - \frac{1}{T_1}\right), \tag{14.32}$$

which gives the plot of Figure 14.9, from which E_a can be determined.




Figure 14.9.: Arrhenius Plot Obtained Using Experimental Data at Two Different Temperatures.

From empirical arguments, Arrhenius proposed the idea that reactants must acquire a minimum amount of energy before they can form any product.

He called this amount of minimum energy the activation energy. We can motivate this assumption by plotting energy of a reaction along the reaction coordinate, as in Figure 14.10. The reaction coordinate is defined as the minimum energy path that connects the reactants with the products. Along this path, the energy rises to a maximum, the *transition state*, before decreasing towards the products. The activation energy corresponds to the height of this barrier: only the molecules that collide with enough energy to reach the top of the barrier can turn into products. Notice that the barrier does not depend on whether the reaction is exothermic or endothermic: a reaction can be strongly spontaneous and still be extremely slow if its barrier is high, as in the diamond-to-graphite example at the beginning of this chapter.




Figure 14.10.: Energy Profile of a Reaction along the Reaction Coordinate (Schematic).

14.5. Chapter Review

14.5.1. Study Questions

1. How does the rate of a zeroth-order reaction depend on the concentration of the reactant?

a. It is proportional to the concentration.
b. It is proportional to the square of the concentration.
c. It is independent of the concentration.
d. It decreases exponentially with the concentration.
e. It is inversely proportional to the concentration.

---

2. Which plot gives a straight line for a first-order reaction?

a. $\ln[\mathrm{A}]$ versus t, with slope $-k_1$.
b. $[\mathrm{A}]$ versus t, with slope $-k_1$.
c. $\frac{1}{[\mathrm{A}]}$ versus t, with slope k_1.
d. $[\mathrm{A}]^2$ versus t.
e. $\ln[\mathrm{A}]$ versus $\frac{1}{T}$.

---

3. What is special about the half-life of a first-order reaction?

a. It is proportional to the initial concentration.
b. It is inversely proportional to the initial concentration.
c. It increases as the reaction proceeds.
d. It is always 1 second.
e. It does not depend on the initial concentration, since $t_{1/2} = \frac{\ln 2}{k_1}$.

---

4. Which plot gives a straight line for a simple second-order reaction?

a. $[\mathrm{A}]$ versus t.
b. $\frac{1}{[\mathrm{A}]}$ versus t.
c. $\ln[\mathrm{A}]$ versus t.
d. $\sqrt{[\mathrm{A}]}$ versus t.
e. $[\mathrm{A}]^2$ versus t.

---

5. When are the order of a reaction and its molecularity equal?

a. Always.
b. Never.
c. Only for first-order reactions.
d. Only for elementary reactions.
e. Only for reactions in the gas phase.

---

6. In the consecutive reactions $\mathrm{A} \to \mathrm{B} \to \mathrm{C}$ with $k_1 \ll k_2$, what happens to the intermediate B?

a. Its concentration stays small and almost constant, which justifies the steady-state approximation.
b. It accumulates and becomes the main product.
c. It is never formed.
d. Its concentration equals that of A.
e. It reacts back to A.

---

7. For two competitive first-order reactions, $\mathrm{A} \to \mathrm{B}$ (k_1) and $\mathrm{A} \to \mathrm{C}$ (k_2), what is the ratio of the products?

a. $\frac{[\mathrm{B}]}{[\mathrm{C}]} = 1$.
b. $\frac{[\mathrm{B}]}{[\mathrm{C}]} = \frac{k_2}{k_1}$.
c. $\frac{[\mathrm{B}]}{[\mathrm{C}]} = \frac{k_1}{k_2}$.
d. $\frac{[\mathrm{B}]}{[\mathrm{C}]} = k_1 k_2$.
e. It changes with time.

---

8. For opposed reactions, $\mathrm{A} \rightleftharpoons \mathrm{B}$, how is the equilibrium constant related to the rate coefficients?

a. $K_C = \frac{k_{-1}}{k_1}$.
b. $K_C = k_1 + k_{-1}$.
c. $K_C = k_1 k_{-1}$.
d. $K_C = k_1 - k_{-1}$.
e. $K_C = \frac{k_1}{k_{-1}}$.

---

9. How is the isolation method performed?

a. By measuring only the initial rate.
b. By using a large excess of all reactants but one.
c. By separating the products as they form.
d. By running the reaction at very low temperature.
e. By using equal concentrations of all reactants.

---

10. How can the activation energy be obtained from the Arrhenius equation?

a. From the intercept of a plot of k versus T.
b. From the half-life of the reaction.
c. From the equilibrium constant.
d. From the slope of a plot of $\ln k$ versus $\frac{1}{T}$, which is $-\frac{E_a}{R}$.
e. From the reaction enthalpy.

Answers

1.c, 2.a, 3.e, 4.b, 5.d, 6.a, 7.c, 8.e, 9.b, 10.d

A. Appendix

A.1. Thermodynamic Data of Inorganic Substances at 298 K

Substance:	$\Delta_f \hat{H}^\circ$[kJ/mol]	$\Delta_f \hat{G}^\circ$[kJ/mol]	$\hat{S}^\circ$[J/(mol K)]	C_P [J/(mol K)]
Ag(g)	284.9	246	173	20.8
Ag(s)	0	0	42.6	25.4
Ag^+(aq)	105.8	77.1	73.5	
AgCN(s)	146	156.9	107.2	66.7
Ag_2CO_3(s)	−505.8	−436.8	167.4	112.3
$AgNO_3$(s)	−124.4	−33.4	140.9	93.1
Ag_2O(s)	−31.1	−11.2	121.3	65.9
Ag_2S(s)	−32.6	−40.7	144	76.5
AgBr(s)	−100.4	−96.9	107.1	52.4
AgCl(s)	−127.0	−109.8	96.3	50.8
AgF(s)	−204.6	−187	84	
AgI(s)	−61.8	−66.2	115.5	56.8
Al(g)	330	289.4	164.6	21.4
Al(s)	0	0	28.3	24.2
Al_2O_3(s)	−1675.7	−1582.3	50.9	79.0
AlF_3(s)	−1510.4	−1431.1	66.5	75.1
AlI_3(s)	−302.9		195.9	
$AlBr_3$(s)	−527.2		180.2	100.6
$AlCl_3$(s)	−704.5	−628.11	112.3	91.1
$Al(OH)_3$(s)	−1277			
$Al(OH)_4^-$(aq)	−1490	−1297	117	
$AlPO_4$(s)	−1733.8	−1617.9	90.8	93.2
Ar(g)	0		154.9	20.8
B(s)	0	0	5.9	11.1
B(g)	565	521.0	153.4	20.8
BH(g)	442.7	412.7	171.8	29.2
BH_3(g)	89.2	93.3	188.2	36.0
B_2S_3(s)	−240.6		100.0	111.7
Ba(g)	180	146	170.2	
Ba(s)	0	0	62.5	28.1
$BaCO_3$(s)	−1213.0	−1134.4	112.1	86.0
BaH_2(s)	−177	−138.2	63.0	
$BaBr_2$(s)	−757.3	−736.8	146.0	
$BaCl_2$(s)	−855	−806.7	123.7	75.1
BaF_2(s)	−1207.1	−1156.8	96.4	71.2
BaI_2(s)	−602.1	−597	167.0	
BaO(s)	−548.0	−520.3	72.1	47.3
$BaSO_4$(s)	−1473.2	−1362.2	132.2	101.8
Be(g)	324	286.6	136.3	20.8
Be(s)	0	0	9.5	13.4
$BeBr_2$(s)	−353.5		108	69.4
$BeCl_2$(s)	−490.4	−445.6	75.8	62.4
BeF_2(s)	−1026.8	−979.4	53.4	51.8
BeI_2(s)	−192.5		121	71.1
BeO(s)	−609.4	−580.1	13.8	25.6
$Be(OH)_2$(s)	−902.5	−815.0	45.5	62.1
$BeSO_4$(s)	−1205.2	−1093.8	77.9	85.7
Bi(g)	207.1	168.2	187	20.8
Bi(s)	0	0	56.7	25.5
Bi_2O_3(s)	−573.9	−493.7	151.5	113.5
$BiCl_3$(s)	−379.1	−315.0	177.0	105.0
Br^-(aq)	−121.4	−104.0	82.6	
Br(g)	111.9	82.4	175	20.8
Br_2(g)	30.9	3.1	245.5	36.0
Br_2(l)	0	0	152.2	75.7
BrCl(g)	14.6	−1	240.1	35.0
BrF(g)	−93.8	−109.2	229	33.0
BrF_3(g)	−1136	1119.4	254.4	66.6
C(g)	716.7	671.3	158.1	0.8
C(s,diamond)	1.9	2.9	2.4	6.1

Substance:	$\Delta_f H^\circ$ [kJ/mol]	$\Delta_f G^\circ$ [kJ/mol]	S° [J/(mol K)]	C_P [J/(mol K)]
C(s,graphite)	0	0	5.7	8.5
CBr_4(g)	83.9	67	358.1	
CBr_4(s)	29.4	47.7	212.5	
CCl_2F_2(g)	−477.4	−439.4	300.8	
CCl_2O(g)	−219.1	−204.9	283.5	
CCl_4(g)	−95.7	−53.6	309.9	
CCl_4(l)	−128.2	−62.6	216.2	
CF_4(g)	−933.6	−888.3	261.6	
CS_2(g)	116.7	67.1	237.8	45.4
CS_2(l)	89	64.6	151.3	76.4
CO(g)	−110.5	−137.2	197.7	29.1
CO_2(g)	−393.5	−394.4	213.8	37.1
Ca(g)	177.8	144	154.9	20.8
Ca(s)	0	0	41.6	25.9
$Ca(OH)_2$(s)	−985.2	−897.5	83.4	87.5
$CaBr_2$(s)	−682.8	−663.6	130	
$CaCl_2$(s)	−795.4	−748.8	108.4	72.9
CaCN(s)	−184.5			
$CaCO_3$(s,arag.)	−1207.8	−1128.2	88	82.3
$CaCO_3$(s,calc.)	−1207.6	−1129.1	91.7	83.5
CaF_2(s)	−1228.0	−1175.6	68.5	67.0
CaH_2(s)	−181.5	−142.5	41.4	41.0
CaI_2(s)	−533.5	−528.9	142	
CaO(s)	−634.9	−603.3	38.1	42.0
$CaSO_4$(s)	−1434.5	−1322.0	106.5	99.7
Cd(g)	111.8		167.7	20.8
Cd(s)	0	0	51.8	26.0
$CdBr_2$(s)	−316.2	−296.3	137.2	76.7
$CdCl_2$(s)	−391.5	−343.9	115.3	74.7
$CdCO_3$(s)	−750.6	−669.4	92.5	
CdF_2(s)	−700.4	−647.7	77.4	
CdS(s)	−161.9	−156.5	64.9	
$CdSO_4$(s)	−933.3	−822.7	123.0	99.6
Cl^-(aq)	−167.1	−131.2	56.6	
Cl(g)	121.3	105.3	165.2	21.8
Cl_2(g)	0	0	223.1	33.9
ClF(g)	−50.3	−51.8	217.9	32.1
ClF_3(g)	−163.2	−123.0	281.6	63.9
ClO_2(g)	89.1	105	263.7	46.0
Cl_2O(g)	80.3	97.9	266.2	45.4
Co(g)	424.7	380.3	179.5	23.0
Co(s)	0	0	30	24.8
$CoCl_2$(s)	−312.5	−269.8	109.2	78.5
Cr(g)	396.6	351.8	174.5	20.8
Cr(s)	0	0	23.8	23.4
Cr_2O_3(s)	−1139.7	−1058.1	81.2	118.7
$CrCl_2$(s)	−395.4	−356	115.3	71.2
$CrCl_3$(s)	−556.5	−486.1	123	91.8
CrO_2(g)	−598			
CrO_3(g)	−292.9		266.2	56.0
Cs(g)	76.5	49.6	175.6	20.8
Cs(s)	0	0	85.2	32.2
CsCl(s)	−443.0	−414.5	101.2	52.5
Cu(g)	337.4	297.7	166.4	20.8
Cu(s)	0	0	33.2	24.2
Cu_2O(s)	−168.6	−146.0	93.1	63.6
CuO(s)	−157.3	−129.7	42.6	
Cu_2S(s)	−79.5	−86.2	120.9	76.3
CuS(s)	−53.1	−53.6	66.5	47.8
$CuSO_4$(s)	−771.4	−662.2	109.2	
CuBr(s)	−104.6	−100.8	96.1	54.7
$CuBr_2$(s)	−141.8			
CuCl(s)	−137.2	−119.9	86.2	48.5
$CuCl_2$(s)	−220.1	−175.7	108.1	71.9
CuCN(s)	96.2	111.3	84.5	
F^-(aq)	−335.4	−278.8	−13.8 | |	
F(g)	79.4	62.3	158.8	22.7
F_2(g)	0	0	202.8	32.3
F_2O(g)	24.5	41.8	247.5	43.3
FO(g)	109	105.3	216.4	32.0
FB(g)	−122.2	−149.8	200.5	58.6
Fe(g)	416.3	370.7	180.5	25.7
Fe(s)	0	0	27.3	25.1
FeO(s)	−272.0	−251.4	60.7	
Fe^{2+}(aq)	−89.1	−78.9	−137.7 | |	
Fe_2O_3(s)	−824.2	−742.2	87.4	103.9
Fe^{3+}(aq)	−48.5	−4.7	−315.9 | |	
Fe_3O_4(s)	−1118.4	−1015.4	146.4	143.4
$FeCO_3$(s)	−740.6	−666.7	92.9	82.1
FeS_2(s)	−178.2	−166.9	52.9	62.2
$FeCl_2$(s)	−341.8	−302.3	118	75.7
$FeCl_3$(s)	−399.5	−334.0	142.3	96.7
$FeBr_2$(s)	−249.8	−238.1	140.6	
$FeBr_3$(s)	−268.2			
Fe_3C(s)	25.1	20.1	104.6	105.9
H(g)	218.0	203.3	114.7	20.8

Substance:	$\Delta_f H^\ominus$[kJ/mol]	$\Delta_f G^\ominus$[kJ/mol]	$S^\ominus$[J/(mol K)]	C_P [J/(mol K)]
H^+(aq)	0	0	0	
H_2(g)	0	0	130.7	28.8
H_2O(g)	−241.8	−228.6	188.8	33.6
H_2O(l)	−285.8	−237.1	70.0	75.3
H_2O_2(g)	−136.3	−105.6	232.7	43.1
H_2O_2(l)	−187.8	−120.4	109.6	89.1
H_2S(g)	−20.6	−33.4	205.8	34.2
H_2Se(g)	29.7	15.9	219	34.7
H_2SO_4(aq)	−909.3	−744.5	20.1	
H_2SO_4(l)	−814.0	−690.0	156.9	138.9
H_3PO_4(l)	−1271.7	−1123.6	150.8	145.0
H_3PO_4(s)	−1284.4	−1124.3	110.5	106.1
HBr(aq)	−121.6	−104.0	82.4	
HBr(g)	−36.3	−53.4	198.7	29.1
HCl(aq)	−167.2	−131.2	56.5	
HCl(g)	−92.3	−95.3	186.9	29.1
HCN(g)	135.1	124.7	201.8	35.9
HCN(l)	108.9	125	112.8	70.6
HF(aq)	−332.6	−278.8	−13.8 | |	
HF(g)	−273.3	−275.4	173.8	
HI(aq)	−55.2	−51.6	111.3	
HI(g)	26.5	1.7	206.6	29.2
HNO_2(g)	−79.5	−46.0	254.1	
HNO_3(aq)	−207.4	−111.3	146.4	
HNO_3(g)	−133.9	−73.5	266.9	54.1
HNO_3(l)	−174.1	−80.7	155.6	109.9
He(g)	0	0	126.2	20.8
Hg(g)	61.4	31.8	175	
Hg(l)	0	0	75.9	28.0
Hg_2(g)	108.8	68.2	288.1	
HgO(s)	−90.8	−58.5	70.3	44.1
HgS(s,red)	−58.2	−50.6	82.4	48.4
Hg_2SO_4(s)	−743.1	−625.8	200.7	132.0
$HgSO_4$(s)	−707.5			
Hg_2Cl_2(s)	−265.4	−210.7	191.6	191.6
$HgCl_2$(s)	−224.3	−178.6	146.0	146.0
Hg_2Br_2(s)	−206.9	−181.1	218.0	218.0
$HgBr_2$(s)	−170.7	−153.1	172.0	172.0
Hg_2I_2(s)	−121.3	−111	233.5	233.5
HgI_2(s)	−105.4	−101.7	180.0	180.0
I^-(aq)	−56.8	−51.6	106.5	
I(g)	106.8	70.2	180.8	20.8
I_2(g)	62.4	19.3	260.7	36.9
I_2(s)	0	0	116.1	54.4
HIO_3(s)	−230.1			
IBr(g)	40.8	3.7	258.8	36.4
ICl(g)	17.8	−5.5	247.6	35.6
IF(g)	−95.7	−118.5	236.2	33.4
K(g)	89.0	60.5	160.3	20.8
K(s)	0	0	64.7	29.6
K_2CO_3(s)	−1151.0	−1063.5	155.5	114.4
K_2O(s)	−361.5	−322.1	94.1	
K_2O_2(s)	−494.1	−425.1	102.1	
K_2SO_4(s)	−1437.8	−1321.4	175.6	131.5
KBr(s)	−393.8	−380.7	95.9	52.3
KCl(s)	−436.5	−408.5	82.6	51.3
KF(s)	−567.3	−537.8	66.6	49.0
KI(s)	−327.9	−324.9	106.3	52.9
$KClO_3$(s)	−397.7	−296.3	143.1	100.3
$KMnO_4$(s)	−837.2	−737.6	171.7	117.6
KNO_2(s)	−369.8	−306.6	152.1	107.4
KNO_3(s)	−494.6	−394.9	133.1	96.4
KSCN(s)	−200.2	−178.3	124.3	88.5
Kr(g)	0	0	164.1	20.8
Li(g)	159.3	126.6	138.8	20.8
Li(s)	0	0	29.1	24.9
Li^+(aq)	−278.5	−293.3	12.4	
Li_2O(s)	−597.9	−561.2	37.6	54.1
LiOH(s)	−487.5	−441.5	42.8	49.6
$LiNO_3$(s)	−483.1	−381.1	90.0	
LiBr(s)	−351.2	−342	74.3	
LiCl(s)	−408.6	−384.4	59.3	48.0
LiF(s)	−616	−587.7	35.7	41.6
LiI(s)	−270.4	−270.3	86.8	51.0
Mg(g)	147.1	112.5	148.6	20.8
Mg(s)	0	0	32.7	24.9
MgO(s)	−601.6	−569.3	27.0	37.2
$Mg(OH)_2$(s)	−924.5	−833.5	63.2	77.0
MgS(s)	−346.0	−341.8	50.3	45.6
$MgSO_4$(s)	−1284.9	−1170.6	91.6	96.5
$MgBr_2$(s)	−524.3	−503.8	117.2	
$MgCl_2$(s)	−641.3	−591.8	89.6	71.4
MgF_2(s)	−1124.2	−1071.1	57.2	61.6
Mn(g)	280.7	238.5	173.7	20.8
Mn(s)	0	0	32	26.3
MnO(s)	−385.2	−362.9	59.7	45.4

Substance:	$\Delta_f H^\circ$[kJ/mol]	$\Delta_f G^\circ$[kJ/mol]	S°[J/(mol K)]	C_P [J/(mol K)]
MnO_2(s)	−520.0	−465.1	53.1	54.1
MnO_4^-(aq)	−541.4	−447.2	191.2	
$MnBr_2$(s)	−384.9			
$MnCl_2$(s)	−481.3	−440.5	118.2	72.9
Mo(g)	658.1	612.5	182	20.8
Mo(s)	0	0	28.7	24.1
MoO_2(s)	−588.9	−533.0	46.3	56.0
MoO_3(s)	−745.1	−668.0	77.7	75.0
MoS_2(s)	−235.1	−225.9	62.6	63.6
MoS_3(s)	−364	−354	119	
N(g)	472.7	455.5	153.3	20.8
N_2(g)	0	0	191.6	29.1
NF_3(g)	−132.1	−90.6	260.8	53.4
NH_3(g)	−45.9	−16.4	192.8	35.1
NH_4^+(aq)	−133.3	−79.3	111.2	
NH_4Cl(s)	−314.4	−202.9	94.6	84.1
NH_4NO_3(s)	−365.6	−183.9	151.1	139.3
NH_4OH(l)	−361.2	−254.0	165.6	154.9
$(NH_4)_2SO_4$(s)	−1180.9	−901.7	220.1	187.5
N_2H_4(g)	95.4	159.4	238.5	
N_2H_4(l)	50.6	149.3	121.2	
NO_2(g)	33.2	51.3	240.1	37.2
N_2O(g)	81.6	103.7	220	38.6
NO(g)	91.3	87.6	210.8	
N_2O_4(g)	11.1	99.8	304.4	79.2
N_2O_4(l)	−19.5	97.5	209.2	142.7
Na(g)	107.5	77	153.7	20.8
Na(s)	0	0	51.3	28.2
Na^+(aq)	−240.2	−261.9	58.5	
Na_2CO_3(s)	−1130.7	−1044.4	135	112.3
Na_2O(s)	−414.2	−375.5	75.1	69.1
Na_2O_2(s)	−510.9	−447.7	95	89.2
Na_2SO_4(s)	−1387.1	−1270.2	149.6	128.2
NaBr(aq)	−361.7	−365.8	141.4	
NaBr(g)	−143.1	−177.1	241.2	36.3
NaBr(s)	−361.1	−349.0	86.8	51.4
NaCl(aq)	−407.3	−393.1	115.5	
NaCl(s)	−411.2	−384.1	72.1	50.5
NaCN(s)	−87.5	−76.4	115.6	70.4
NaF(aq)	−572.8	−540.7	45.2	
NaF(s)	−576.6	−546.3	51.1	46.9
NaN_3(s)	21.7	93.8	96.9	76.6
$NaNO_3$(aq)	−447.5	−373.2	205.4	
$NaNO_3$(s)	−467.9	−367.0	116.5	92.9
NaO_2(s)	−260.2	−218.4	115.9	72.1
NaOH(s)	−425.8	−379.7	64.4	59.5
NaH(s)	−56.3	−33.6	40	36.4
Ne(g)	0	0	146.3	20.8
Ni(g)	429.7	384.5	182.2	23.4
Ni(s)	0	0	29.9	26.1
Ni_2O_3(s)	−489.5			
$Ni(OH)_2$(s)	−529.7	−447.2	88	
$NiBr_2$(s)	−212.1			
$NiCl_2$(s)	−305.3	−259.0	97.7	71.7
NiF_2(s)	−651.4	−604.1	73.6	64.1
O(g)	249.2	231.7	161.1	21.9
O_2(g)	0	0	205.2	29.4
O_3(g)	142.7	163.2	238.9	39.2
OH^-(aq)	−230.0	−157.2	−10.9 | |	
Os(g)	791	745	192.6	20.8
Os(s)	0	0	32.6	24.7
OsO_4(g)	−337.2	−292.8	293.8	74.1
OsO_4(s)	−394.1	−304.9	143.9	
P(g,white)	316.5	280.1	163.2	20.8
P(s,black)	−39.3			
P(s,red)	−17.6	−12.5	22.8	21.2
P(s,white)	0	0	41.1	23.8
P_2(g)	144.0	103.5	218.1	
P_4(g)	58.9	24.4	280.0	
PCl_3(g)	−287.0	−267.8	311.8	71.8
PCl_3(l)	−319.7	−272.3	217.1	
PCl_5(g)	−374.9	−305.0	364.6	112.8
PH_3(g)	5.4	13.5	210.2	37.1
$POCl_3$(g)	−558.5	−512.9	325.5	
$POCl_3$(l)	−597.1	−520.8	222.5	
Pb(g)	195.2	162.2	175.4	20.8
Pb(s)	0	0	64.8	26.8
$PbCl_2$(s)	−359.4	−314.1	136	
$PbCO_3$(s)	−699.1	−625.5	131	87.4
PbO(s,litharge)	−219.0	−188.9	66.5	45.8
PbO(s,massic.)	−217.3	−187.9	68.7	45.8
PbO_2(s)	−277.4	−217.3	68.6	64.6
$Pb(NO_3)_2$(aq)	−416.3	−246.9	303.3	
$Pb(NO_3)_2$(s)	−451.9			
PbS(s)	−100.4	−98.7	91.2	49.5

Substance:	$\Delta_f H^\ominus$[kJ/mol]	$\Delta_f G^\ominus$[kJ/mol]	$S^\ominus$[J/(mol K)]	C_P [J/(mol K)]
$PbSO_4$(s)	−920.0	−813.0	148.5	103.2
Rb(g)	80.9	53.1	170.1	20.8
Rb(s)	0	0	76.8	31.1
RbCl(s)	−435.4	−407.8	95.9	52.4
S(g,rhombic)	277.2	236.7	167.8	23.7
S(s,rhombic)	0	0	32.1	22.6
SO_2(g)	−296.8	−300.1	248.2	39.9
SO_3(g)	−395.7	−371.1	256.8	50.7
SO_4^{2-}(aq)	−909.3	−744.5	18.5	
$SOCl_2$(g)	−212.5	−198.3	309.8	
Se(g,gray)	227.1	187	176.7	
Se(s,gray)	0	0	42.4	25.4
Si(g)	450	405.5	168.0	22.3
Si(s)	0	0	18.8	20.0
SiC(s,cubic)	−65.3	−62.8	16.6	26.9
SiC(s,hexag.)	−62.8	−60.2	16.5	26.7
$SiCl_4$(g)	−657.0	−617.0	330.7	
$SiCl_4$(l)	−687.0	−619.8	239.7	
SiH_4(g)	34.3	56.9	204.6	42.8
Sn(g,white)	301	266.2	168.5	21.3
Sn(s,gray)	−2.1	0.1	44.1	25.8
Sn(s,white)	0	0	51.2	27.0
$SnCl_4$(g)	−471.5	−432.2	365.8	98.3
$SnCl_4$(l)	−511.3	−440.1	258.6	165.3
SnO_2(s)	−557.6	−515.8	49	52.6
Ti(g)	473	428.4	180.3	24.4
Ti(s)	0	0	30.7	25.1
$TiCl_2$(s)	−513.8	−464.4	87.4	69.8
$TiCl_3$(s)	−720.9	−653.5	139.7	97.2
$TiCl_4$(g)	−763	−726.3	353	95.4
$TiCl_4$(l)	−804.2	−737.2	252.3	145.2
TiO_2(s)	−944.0	−888.8	50.6	55.0
U(g)	533	488.4	199.8	23.7
U(s)	0	0	50.2	27.7
UF_4(g)	−1598.7	−1572.7	368	91.2
UF_4(s)	−1914.2	−1823.3	151.7	116.0
UF_6(g)	−2147.4	−2063.7	377.9	129.6
UF_6(s)	−2197.0	−2068.5	227.6	166.8
UO_2(g)	−465.7	−471.5	274.6	51.4
UO_2(s)	−1085.0	−1031.8	77.0	63.6
V(g)	514.2	754.4	182.3	26.0
V(s)	0	0	28.9	24.9
V_2O_5(s)	−1550.6	−1419.5	131.0	127.7
VCl_3(s)	−580.7	−511.2	131.0	93.2
VCl_4(g)	−525.5	−492.0	362.4	96.2
VCl_4(l)	−569.4	−503.7	255.0	
Xe(g)	0	0	169.7	20.8
Zn(g)	130.4	94.8	161.0	20.8
Zn(s)	0	0	41.6	25.4
$ZnBr_2$(s)	−328.7	−312.1	138.5	
$ZnCl_2$(s)	−415.1	−369.4	111.5	71.3
ZnF_2(s)	−764.4	−713.3	73.7	65.7
ZnI_2(s)	−208.0	−209.0	161.1	
$Zn(NO_3)_2$(s)	−483.7			
ZnS(s,sphaler.)	−206.0	−201.3	57.7	46.0
$ZnSO_4$(s)	−982.8	−871.5	110.5	99.2
Zr(g)	608.8	566.5	181.4	26.7
Zr(s)	0	0	39	25.4
$ZrCl_2$(s)	−502.0	−386	110	
$ZrCl_4$(s)	−980.5	−889.9	181.6	119.8

A.2. Thermodynamic Data of Organic Substances at 298 K

Formula:	Name:	$\Delta_f H^\ominus$[kJ/mol]	$\Delta_f G^\ominus$[kJ/mol]	$S^\ominus$[J/(mol K)]	C_P [J/(mol K)]
$CHBr_3$	Bromoform(g)	25	16	331	71
$CHCl_3$	Chloroform(l)	−134.1	−73.7	201.7	114.2
$CHCl_3$	Chloroform(g)	−102.7	6.0	295.7	65.7
CH_2O_2	Formic acid(l)	−425	−361.4	129	99
CH_2O_2	Formic acid(g)	−378.7			
CH_3	Methyl(g)	145.7	47.9	194.2	38.7
CH_3Br	Bromomethane(l)	−59.8			
CH_3Br	Bromomethane(g)	−35.4	−26.3	246.4	42.4

Formula:	Name:	$\Delta_f H^\circ$[kJ/mol]	$\Delta_f G^\circ$[kJ/mol]	S°[J/(mol K)]	C_P [J/(mol K)]
CH_3Cl	Chloromethane(g)	−81.9	−63	234.6	40.8
CH_3F	Fluoromethane(g)	−234	−210	222.9	37.5
CH_3I	Iodomethane(l)	−13.6		136.2	126
CH_3I	Iodomethane(g)	14.4	16	254.1	44.1
CH_3NO_2	Nitromethane(l)	−112.6	−14.4	171.8	106.6
CH_3NO2	Nitromethane(g)	−80.8	−7	282.9	55.5
CH_4	Methane(g)	−74.6	−50.5	186.3	35.7
CH_4O	Methanol(l)	−239.2	−166.6	126.8	81.1
CH_4O	Methanol(g)	−201	−162.3	239.9	44.1
CH_5N	Methylamine(l)	−47.3	35.7	150.2	102.1
CH_5N	Methylamine(g)	−22.5	32.7	242.9	50.1
C_2H_2	Ethyne (acetylene)(g)	226.9	209	201	44
C_2H_4	Ethene(g)	52.5	68.4	219.3	42.9
C_2H4O_2	Acetic acid(l)	−484.3	−389.9	159.8	123.3
C_2H4O_2	Acetic acid(g)	−432.2	−374.2	283.5	63.4
C_2H_5Br	Bromoethane(l)	−90.5	−25.8	198.7	100.8
C_2H_5Br	Bromoethane(g)	−61.9	−23.9	286.7	64.5
C_2H_5Cl	Chloroethane(l)	−136.8	−59.3	190.8	104.3
C_2H_5Cl	Chloroethane(g)	−112.1	−60.4	276	62.8
$C2H_5NO_2$	Nitroethane(l)	−143.9			134.4
$C2H_5NO_2$	Nitroethane(g)	−103.8	−5	320.5	79
C_2H_6	Ethane(g)	−84	−32	229.2	52.5
C_2H_6O	Ethanol(l)	−277.6	−174.8	160.7	112.3
C_2H_6O	Ethanol(g)	−234.8	−167.9	281.6	65.6
C_2H_6O	Methoxymethane(l)	−203,3			
C_2H_6O	Methoxymethane(g)	−184.1	−112.6	266.4	
C_2H_7N	Ethylamine(l)	−74.1			130
C_2H_7N	Ethylamine(g)	−47.5	36.3	283.8	71.5
C_3H_4	Cyclopropene(g)	277.1	286	244	53
C_3H_4	Propyne(g)	185	194	248	61
C_3H_6	Cyclopropane(l)	35.2			
C_3H_6	Cyclopropane(g)	53.3	104.5	237.5	55.6
C_3H_6	Propene(g)	20	62	267	64
C_3H_6O	Acetone(l)	−248.4		199.8	126.3
C_3H_6O	Acetone(g)	−217.1	−152.7	295.3	74.5
$C_3H_6O_2$	Propanoic acid(l)	−510.7		191	152.8
$C_3H_6O_2$	Propanoic acid(g)	−455.7			
C_3H_8	Propane(l)	−120.9			
C_3H_8	Propane(g)	−103.8	−23.4	270.3	73.6
C_3H_8O	1-Propanol(l)	−302.6		193.6	143.9
C_3H_8O	1-Propanol(g)	−255.1		322.6	85.6
C_3H_8O	2-Propanol(l)	−318.1		181.1	156.5
C_3H_8O	2-Propanol(g)	−272.6		309.2	89.3
C_3H_9N	1-Propanamine(g)	−72	40	324	
C_4H_6	1-Butyne(l)	141.4			
C_4H_6	1-Butyne(g)	165.2	202	291	81
C_4H_6	2-Butyne(l)	119.1			
C_4H_6	2-Butyne(g)	145.7	185	283	78
C_4H_6	Cyclobutene(g)	156.7	175	64	64
C_4H_8	2-Methyl-1-propene(g)	−17	58	294	89
C_4H_8	1-Butene(l)	−20.8		227	118
C_4H_8	1-Butene(g)	0.1	71	306	86
C_4H_8	Cyclobutane(l)	3.7			
C_4H_8	Cyclobutane(g)	27.7	110	265	
$C_4H_8O_2$	Butanoic acid(l)	−533.8		222.2	178.6
$C_4H_8O_2$	Butanoic acid(g)	−475.9			
C_4H_{10}	2-Methylpropane(g)	−135	−21	295	97
C_4H_{10}	Butane(l)	−147.3			140.9
C_4H_{10}	Butane(g)	−125.7	−17	310	98
$C_4H_{10}O$	1-Butanol(l)	−327.3		225.8	177.2
$C_4H_{10}O$	1-Butanol(g)	−274.9			
$C_4H_{10}O$	2-Butanol(l)	−342.6		214.9	196.9
$C_4H_{10}O$	2-Butanol(g)	−292.8		359.5	112.7
C_5H_8	1-Pentyne(g)	144	210	330	105
C_5H_8	2-Pentyne(g)	129	194	332	99
C_5H_8	Cyclopentene(l)	4.3		201.2	122.4
C_5H_8	Cyclopentene(g)	34	111	290	75
C_5H_{10}	1-Pentene(l)	−46.9		262.6	154
C_5H_{10}	1-Pentene(g)	−21.1	79	346	110
C_5H_{10}	2-Methyl-1-butene(g)	−35.2	66	340	112
C_5H_{10}	2-Methyl-1-butene(l)	−61.1		254	157.2
C_5H_{10}	Cyclopentane(l)	−105.1		204.5	128.8
C_5H_{10}	Cyclopentane(g)	−76.4	39	293	83
$C_5H_{10}O_2$	Pentanoic acid(l)	−559.4		259.8	210.3
$C_5H_{10}O_2$	Pentanoic acid(g)	−491.9			
C_5H_{12}	2,2-Dimethylpropane(g)	−166	−15	306	122
C_5H_{12}	2-Methylbutane(g)	−155	−15	344	119
C_5H_{12}	Pentane(l)	−173.5			167.2
C_5H_{12}	Pentane(g)	−146.9	−8	349	120
$C_5H_{12}O$	1-Pentanol(l)	−351.6			208.1

Formula:	Name:	$\Delta_f H^\circ$[kJ/mol]	$\Delta_f G^\circ$[kJ/mol]	S°[J/(mol K)]	C_P [J/(mol K)]
$C_5H_{12}O$	1-Pentanol(g)	–294.6			
$C_5H_{12}O$	2-Pentanol(l)	–365.2			
$C_5H_{12}O$	2-Pentanol(g)	–311			
$C_5H_{12}O$	3-Pentanol(l)	–368.9			239.7
$C_5H_{12}O$	3-Pentanol(g)	–314.9			
$C_5H_{12}O$	Methyl tert-butyl ether(l)	–313.6		265.3	187.5
$C_5H_{12}O$	Methyl tert-butyl ether(g)	–283.7			
C_6H_6	Benzene(l)	49.1	124.5	173.4	136
C_6H_6	Benzene(g)	82.9	129.7	269.2	82.4
C_6H_7N	Aniline(l)				191.9
C_6H_7N	Aniline(g)	87.5	–7	317.9	107.9
C_6H_{10}	1-Hexyne(g)	124	219	369	128
C_6H_{10}	Cyclohexene(l)	–28.5		214.6	148.3
C_6H_{10}	Cyclohexene(g)	–5	107	311	105
C_6H_{12}	1-Hexene(l)	–74.2		295.2	183.3
C_6H_{12}	1-Hexene(g)	–43.5	87	385	132
C_6H_{12}	2-Methyl-1-pentene(g)	–59.4			
C_6H_{12}	2-Methyl-1-pentene(l)	–90			
C_6H_{12}	Cyclohexane(l)	–156.4			154.9
C_6H_{12}	Cyclohexane(g)	–123.4	32	298	106
C_6H_{12}	Methylcyclopentane(g)	–106.2			
C_6H_{12}	Methylcyclopentane(l)	–137.9			
$C_6H_{12}O_2$	Hexanoic acid(l)	–583.8			
$C_6H_{12}O_2$	Hexanoic acid(g)	–511.9			
C_6H_{14}	2,2-Dimethylbutane(g)	–185.9	–10	358	142
C_6H_{14}	2,2-Dimethylbutane(l)	–213.8		272.5	191.9
C_6H_{14}	2-Methylpentane(g)	–174.6	–5	381	144
C_6H_{14}	2-Methylpentane(l)	–204.6		290.6	193.7
C_6H_{14}	3-Methylpentane(g)	–171.9	–2	380	143
C_6H_{14}	3-Methylpentane(l)	–202.4		292.5	190.7
C_6H_{14}	Hexane(l)	–198.7			195.6
C_6H_{14}	Hexane(g)	–166.9	–0.3	388	143
$C_6H_{14}O$	1-Hexanol(l)	–377.5		287.4	240.4
$C_6H_{14}O$	1-Hexanol(g)	315.9			
$C_6H_{14}O$	2-Hexanol(l)	–392			
$C_6H_{14}O$	2-Hexanol(g)	–333.5			
C_7H_6O	Phenol(s)	–165.1		144	127.4
C_7H_6O	Phenol(g)	–96.4	–33	316	104
C_7H_8	Methylbenzene(l)	12.0		220	156
C_7H_8	Methylbenzene(g)	50.0	122	321	104
C_7H_{14}	1-Heptene(l)	–97.9		327.6	211.8
C_7H_{14}	1-Heptene(g)	–62.3	96	424	15
C_7H_{14}	Cycloheptane(l)	–156.6			
C_7H_{14}	Cycloheptane(g)	–118.1			
C_7H_{14}	Ethylcyclopentane(l)	–163.4		279.9	
C_7H_{14}	Ethylcyclopentane(g)	–126.9			
C_7H_{14}	Methylcyclohexane(g)	–154.7			
C_7H_{14}	Methylcyclohexane(l)	–190.1			184.8
$C_7H_{14}O_2$	Heptanoic acid(l)	–610.2			265.4
$C_7H_{14}O_2$	Heptanoic acid(g)	–536.2			
C_7H_{16}	2,2-Dimethylpentane(g)	–205.7			
C_7H_{16}	2,2-Dimethylpentane(l)	–238.3		300.3	221.1
C_7H_{16}	2-Methylhexane(g)	–194.5			
C_7H_{16}	2-Methylhexane(l)	–229.5		323.3	222.9
C_7H_{16}	3-Methylhexane(g)	–191.3			
C_7H_{16}	3-Methylhexane(l)	–226.4			
C_7H_{16}	Heptane(l)	–224.2			224.7
C_7H_{16}	Heptane(g)	–187.6	8	428	166
$C_7H_{16}O$	1-Heptanol(l)	–403.3			272.1
$C_7H_{16}O$	1-Heptanol(g)	–336.5			
C_8H_{10}	Ethylbenzene(l)	–12.3			183.2
C_8H_{10}	Ethylbenzene(g)	29.9	131	361	128
C_8H_{16}	1-Octene(l)	–124.5			241
C_8H_{16}	1-Octene(g)	–81.3	104	463	178
C_8H_{16}	Cyclooctane(l)	–167.7			

Formula:	Name:	$\Delta_f H^\circ$[kJ/mol]	$\Delta_f G^\circ$[kJ/mol]	S°[J/(mol K)]	C_P [J/(mol K)]
C_8H_{16}	Cyclooctane(g)	−124.4			
C_8H_{16}	Ethylcyclohexane(l)	−212.1		280.9	211.8
C_8H_{16}	Ethylcyclohexane(g)	−171.5			
$C_8H_{16}O_2$	Octanoic acid(l)	−636			297.9
$C_8H_{16}O_2$	Octanoic acid(g)	−554.3			
C_8H_{18}	2-Methylheptane(g)	−215.3			
C_8H_{18}	2-Methylheptane(l)	−255		356.4	252
C_8H_{18}	3-Methylheptane(g)	−212.5			
C_8H_{18}	3-Methylheptane(l)	−252.3		362.6	250.2
C_8H_{18}	Octane(l)	−250.1			254.6
C_8H_{18}	Octane(g)	−208.5	16	467	189
$C_8H_{18}O$	1-Octanol(l)	−426.5			305.2
$C_8H_{18}O$	1-Octanol(g)	−355.6			
C_8H_{19}	2,2-Dimethylhexane(g)	−224.5			
C_8H_{19}	2,2-Dimethylhexane(l)	−261.9			
C_9H_{18}	Propylcyclohexane(g)	−192		420	242
C_9H_{12}	Propylbenzene(g)	8	137	401	154
C_9H_{16}	1-Nonyne(l)	16.3			
C_9H_{16}	1-Nonyne(g)	62.3			
$C_9H_{18}O_2$	Nonanoic acid(l)	−659.7			362.4
$C_9H_{18}O_2$	Nonanoic acid(g)	−577.3			
C_9H_{20}	2,2-Dimethylheptane(g)	−246			
C_9H_{20}	2,2-Dimethylheptane(l)	−288.1			
C_9H_{20}	Nonane(l)	−274.7			284.4
C_9H_{20}	Nonane(g)	−228.2	25	506	212
$C_9H_{20}O$	1-Nonanol(l)	−453.4			
$C_9H_{20}O$	1-Nonanol(g)	−376.5			
$C_{10}H_8$	Naphthalene(g)	151	224	336	
$C_{10}H_{14}$	Butylbenzene(l)	−63.2		321.2	243.4
$C_{10}H_{14}$	Butylbenzene(g)	−11.8			
$C_{10}H_{20}$	1-Decene(l)	−173.8		425	300.8
$C_{10}H_{20}$	1-Decene(g)	−123.3			301
$C_{10}H_{20}$	Butylcyclohexane(l)	−263.1		345	271
$C_{10}H_{20}$	Butylcyclohexane(g)	−213.7			
$C_{10}H_{20}O_2$	Decanoic acid(s)	−713.7			
$C_{10}H_{20}O_2$	Decanoic acid(l)	−684.3			
$C_{10}H_{20}O_2$	Decanoic acid(g)	−594.9			
$C_{10}H_{22}$	2-Methylnonane(g)	−260.2			
$C_{10}H_{22}$	2-Methylnonane(l)	−309.8		420.1	313.3
$C_{10}H_{22}$	Decane(l)	−300.9			314.4
$C_{10}H_{22}$	Decane(g)	−249.5	33	545	235
$C_{10}H_{22}O$	1-Decanol(l)	−478.1			370.6
$C_{10}H_{22}O$	1-Decanol(g)	−396.6			
$C_{11}H_{10}$	1-Methylnaphthalene(l)	56.3		254.8	224.4
$C_{11}H_{10}$	2-Methylnaphthalene(s)	44.9		220	196
$C_{11}H_{10}$	2-Methylnaphthalene(g)	106.7			
$C_{11}H_{22}$	1-Undecene(g)				344.9
$C_{11}H_{24}$	Undecane(l)	−327.2			344.9
$C_{11}H_{24}$	Undecane(g)	−270.8	42	584	257
$C_{11}H_{24}O$	1-Undecanol(l)	−504.8			
$C_{12}H_{24}$	1-Dodecene(l)	−226.2		484.8	360.7
$C_{12}H_{24}$	1-Dodecene(g)	−165.4			
$C_{12}H_{24}O_2$	Dodecanoic acid(s)	−774.6			404.3
$C_{12}H_{24}O_2$	Dodecanoic acid(l)	−737.9			
$C_{12}H_{24}O_2$	Dodecanoic acid(g)	642			
$C_{12}H_{26}$	Dodecane(l)	−350.9			375.8
$C_{12}H_{26}$	Dodecane(g)	−289.4	50	623	280
$C_{12}H_{26}O$	1-Dodecanol(l)	−528.5			438.1
$C_{12}H_{26}O$	1-Dodecanol(g)	−436.6			
$C_{14}H_{10}$	Anthracene(g)	231			
$C_{14}H_{10}$	Phenanthrene(g)	207			
$C_{15}H_{30}$	Decylcyclopentane(l)	−367.3			
$C_{16}H_{26}$	Decylbenzene(l)	−218.3			
$C_{16}H_{26}$	Decylbenzene(g)	−138.6			
$C_{16}H_{32}$	1-Hexadecene(l)	−328.7		587.9	488.9

Formula:	Name:	$\Delta_f H^\circ$[kJ/mol]	$\Delta_f G^\circ$[kJ/mol]	S°[J/(mol K)]	C_P [J/(mol K)]
$C_{16}H_{32}$	1-Hexadecene(g)	−248.4			
$C_{16}H_{32}O_2$	Hexadecanoic acid(s)	−891.5		452.4	460.7
$C_{16}H_{32}O_2$	Hexadecanoic acid(l)	−838.1			
$C_{16}H_{32}O_2$	Hexadecanoic acid(g)	−737.1			
$C_{16}H_{34}$	Hexadecane(l)	−456.1			501.6
$C_{16}H_{34}$	Hexadecane(g)	−374.8			
$C_{18}H_{12}$	Chrysene(s)	145.3			
$C_{18}H_{12}$	Chrysene(g)	269.8			