SERVMS User Manual

Operating instructions for the South Eastern Railway Vendor Management System — vendor and contractor registry, unit and location masters, ID card issuance, complaints, inspections, penalty recovery, and reporting.

Edition 1.0 · **Basis** current implementation, branch `servms-updates` · **Roles covered** 8 · **Modules covered** 14

CONTENTS

1 Introduction
2 System Requirements
3 Login & Authentication
4 Dashboard
5 Navigation
6 Roles & Permissions
7 User Management
8 Role Management
9 Location & Unit Management
10 Contractor Management
11 Vendor Management
12 ID Card & QR
13 Vendor Renewals
14 Complaints
15 Inspections
16 Penalties & Recovery
17 Reports
18 Import & Export
19 Notification Centre
20 Audit Logs
21 Document Uploads
22 Error Messages
23 Security Guidelines
24 FAQ

SECTION 1

Introduction

Application name

SERVMS — South Eastern Railway Vendor Management System. The application titles itself *SERVMS Admin* in the sidebar and *South Eastern Railway* as its sub-title. The login screen is branded "Secure Sign In — Access the Vendor Management System dashboard" and carries the footer "© 2026 Centre for Railway Information Systems (CRIS)".

Purpose

SERVMS is the single register of record for commercial vendors and contractors operating on South Eastern Railway premises — platforms, stalls, and on-board train services. It replaces separate divisional registers with one role-scoped system that holds the vendor identity record, the contractor commercial record, the physical unit each contract relates to, and every downstream compliance event: police and medical verification, ID card issuance, public credential verification, complaints, inspections, and penalty recovery.

Intended users

SERVMS is an internal, staff-only application. The login page states **"Internal Intranet Access Only"**. There is no vendor-facing or public-facing self-service portal — vendors and contractors never log in. Accounts belong to railway staff in eight roles across two tiers (HQ and Divisional) plus three operational roles: see Section 6.

The single exception is the **public ID card verification page** at `/verify/<card number>`, reached by scanning the QR code on a printed vendor ID card. This page requires no login and is intended for on-platform checking staff, RPF, and the travelling public.

Main objectives

- Maintain one authoritative vendor and contractor register, scoped so each division sees its own data.
- Enforce that no vendor ID card is issued without a nominated *Card Signing Authority* approving it.
- Make a vendor credential verifiable in seconds from a platform by QR scan.
- Route every complaint and inspection through a recorded Action Taken Report review chain.
- Track penalty imposition through to recovery and independent verification of the recovery.
- Record every create, update, delete, approve, and reject action in a tamper-evident audit trail.

Scope

This manual documents only functionality that is implemented and reachable through the user interface in the current build. Where an API endpoint or database column exists without a corresponding screen, or where a screen element does not do what its label implies, that is stated explicitly and flagged. Nothing in this manual is aspirational.

System overview

TIER 1	TIER 2	TIER 3	STORAGE
Browser	**API**	**Database**	**File store**
React single-page application	Express service under `/api`, JWT-authenticated	MySQL, 38 tables	Uploaded documents and generated card PDFs served from `/uploads`

Every screen you use talks only to the API; the API alone reads and writes the database. Permission is checked twice — the browser hides what your role cannot use, and the API independently rejects it. Hiding a button is a convenience, not the security boundary.

SECTION 2

System Requirements

Browser

SERVMS is a modern single-page application. It requires an evergreen browser released within roughly the last three years — current versions of Google Chrome, Microsoft Edge, Mozilla Firefox, or Safari. It uses ES2020-era JavaScript, CSS Grid, CSS custom properties, and the Fetch API. Internet Explorer is not supported and the application will not render on it.

The following browser features must be enabled or the application will not work correctly:

FEATURE	USED FOR	IF DISABLED
JavaScript	The entire application	Blank page
`localStorage`	Session token, notification read-state, notification preferences	You are signed out on every page load
Pop-ups / downloads	CSV, Excel, and PDF exports; ID card PDF download	Exports silently fail to save
Inline PDF viewer	Document preview inside vendor document modals	Preview pane is blank; Download still works

Network

SERVMS is designed for railway intranet access. The browser must be able to reach both the web front end and the API host — these may be different addresses. Uploads accept files up to **20 MB**, so a connection that can sustain a 20 MB POST without timing out is required for document-heavy work.

The public verification page (`/verify/<card number>`) must be reachable from whichever network the scanning device is on. If ID cards are to be verified from personal mobile phones on a platform, that page must be published beyond the intranet.

Display

The application uses a fixed 250 px navigation sidebar alongside a fluid content area, and its widest screens — the Role Management permission matrix (14 rows × 6 permission columns) and the Penalties ledger (8 columns) — are built for desktop. A minimum of **1366 × 768** is recommended; **1920 × 1080** is comfortable. The layout is not optimised for phones or small tablets; tables will require horizontal scrolling.

Access requirements

- An active SERVMS account, created for you by an administrator. There is **no self-registration**.
- Your **username** and password. Note that the login field is labelled “Employee ID / Username” but the system authenticates on *username* only — entering your Employee Number will not sign you in unless it happens to be identical to your username.
- A role that grants `view` on at least one module. A user with no permissions can sign in but will see an empty sidebar.

SECTION 3

Login and Authentication

3.1 Reaching the application

01 Open your browser and go to the SERVMS address supplied by your division administrator.

02 Any address you enter while signed out redirects to `/login`. There is no landing or marketing page.

03 The login screen shows the SERVMS crest, the badge **“Internal Intranet Access Only”**, and the sign-in card.

3.2 Signing in

01 In **Employee ID / Username**, type your username.

02 In **Password**, type your password. Use the eye button at the right of the field to reveal what you typed if you need to check it.

03 Press **Secure Login** →. The button changes to “Signing in…” while the request is in flight.

04 On success you land on the **Dashboard**. On failure a red banner appears above the button.

There is no captcha, no one-time password, and no second factor.

3.3 Password rules

Password rules are enforced only at the point an administrator *sets* a password, not at login:

RULE	VALUE	WHERE ENFORCED
Minimum length	6 characters	Add New User; user update; change password
Complexity	None — no uppercase, digit, or symbol requirement	—
Expiry / rotation	None	—
Reuse prevention	None	—
Lockout after failed attempts	None — attempts are unlimited	—
Storage	bcrypt hash, cost factor 12	Server

> CAUTION
>
> Because there is no lockout and no complexity rule, the strength of a SERVMS account rests entirely on the password an administrator chooses. Choose a long passphrase when creating accounts, not a six-character minimum.

3.4 Forgotten passwords

> NOT IMPLEMENTED
>
> The **Forgot Password?** link on the login screen is not connected to anything. It is an inert anchor that changes the page address to `#forgot` and does nothing else. **There is no self-service password reset.**

To recover a forgotten password you must contact an administrator, who follows the assisted reset procedure in Section 7.4. The reset produces a temporary password that the administrator relays to you verbally or in person.

3.5 Session behaviour

BEHAVIOUR	DETAIL
Session length	12 hours from sign-in. The token carries a fixed expiry and is not extended by activity.
Idle timeout	None. A session left open stays valid for its full 12 hours.
Where the session lives	Browser `localStorage`. It survives closing the tab and restarting the browser.
Concurrent sessions	Permitted. Signing in elsewhere does not end your session.
Expiry behaviour	The next action returns “Session expired, please log in again”; you are cleared and returned to `/login`.
Permission changes mid-session	Module permissions are re-fetched from the server as you use the application, so a permission change takes effect without a re-login. Your role, division, and name are read from the token and only refresh on your next sign-in.

3.6 Signing out

Press **Logout** at the foot of the left sidebar. This clears the stored token and user record from your browser and returns you to the login screen. Logging out is a browser-side action — the token is discarded, not revoked server-side.

3.7 Unauthorised access

SITUATION	WHAT HAPPENS
Not signed in, any protected address	Redirected to `/login`
Signed in, address for a module your role cannot view	Redirected to `/dashboard`. The page never renders.
Action your role cannot perform	Red banner: "You do not have permission to *<action>* *<module>*"
Record outside your division	"Record not found" — deliberately identical to a genuinely missing record, so you cannot infer that a record exists elsewhere
Tampered or invalid token	"Invalid token" and forced sign-out

> KNOWN GAP
>
> **Account status is not checked at sign-in.** Setting a user to Inactive through the **Toggle** action stops nothing — that user can still sign in and use the system normally. Until this is corrected, deactivating an account must not be relied on to remove access. To reliably cut off a departing member of staff, an administrator must change their password to a value they do not know, using the assisted reset in Section 7.4.

SECTION 4

Dashboard

The Dashboard is the landing screen for every role that holds `dashboard: view` — which is all eight roles. Its sub-title reads “Role-scoped overview of units, contractors, vendors, penalties, and pending actions.” Your role is shown as a tag at the top right. Figures refresh automatically on a polling interval while the page is open.

4.1 Layout

ROW 1	ROW 2	ROW 3	ROW 4
Division toggle HQ roles only	**Filter bar** From, To, Unit, Contractor, Vendor	**Group cards** Five expandable count cards	**Critical Alerts** Seven compliance panels

4.2 Division toggle (HQ roles only)

Super Admin HQ, HQ Admin, and HQ Sub Admin see a row of toggle buttons: `All` `ADRA` `CKP` `KGP` `RNC` `HQ`. Selecting a division code narrows every figure on the page to that division. **HQ** shows only records that carry no division at all — typically RailMadad complaints imported with a division code of HQ. **All** is the unrestricted org-wide view.

Divisional Admin, Divisional Sub Admin, and Complaint Cell do not see this toggle; their figures are always locked to their own division. Inspector sees only inspections they filed themselves; Dealing Section sees only inspections currently delegated to them.

> NOTE
>
> The toggle offers four division codes only. Any other division that exists in the database is still counted in **All** but has no button of its own.

4.3 Filter bar

Five filters narrow the figures below. They combine with each other and with the division toggle.

FILTER	TYPE	EFFECT
From / To	Date pickers	Restricts counts to records created in the range
Unit	Dropdown, all units	Restricts to one unit where the record type has a unit
Contractor	Dropdown, all contractors	Restricts to one contractor
Vendor	Dropdown, all vendors	Restricts to one vendor

There is no “Clear filters” button on the Dashboard. Set each dropdown back to its *All…* option and clear the two date fields to return to the unfiltered view.

4.4 Group cards

Five cards, each showing a headline total, a set of sub-group counts, and a “Last updated” timestamp.

CARD	HEADLINE TOTAL	SUB-GROUPS
Registered Units	All units	Active · Idle · Inactive
Registered Contractors	All contractors	Active · Inactive · Blacklisted
Registered Vendors	All vendors	Active · Inactive · Blacklisted
Penalty	Penalties imposed	Imposed · Recovered · Due Within 7 / 14 / 30 Days · Overdue
Pending Action	Sum of the five sub-groups	Complaints Pending ATR · Inspections Pending ATR · License Fee Due Within 7 / 14 Days · License Fee Overdue

Drilling through

Every sub-group figure is a button. Pressing it opens the matching listing page with the filters already applied — for example *Penalty → Overdue* opens Penalties filtered to recovery pending with a due date before today, in the currently selected division.

> CAUTION
>
> The three **License Fee** sub-groups on the Pending Action card open Location & Unit Management scoped to the division only — that page has no licence-fee-due filter, so the figure you clicked will not be reproduced by the list you land on. Treat the figure as the authority, not the resulting list.

Charts

Press the header of any group card to expand a chart of its sub-group breakdown. Three chart types are offered: `doughnut` `pie` `bar`. Doughnut is the default. Clicking a segment drills through to the same destination as the matching sub-group button. Only one card can be expanded at a time.

4.5 Critical Alerts

A panel of seven compliance cards below the group cards. Each row shows a count; counts above zero are highlighted. Pressing any row navigates to the relevant module scoped to the current division.

ALERT CARD	ROWS	OPENS
Contract Expiry	Expired · Expiring within 7 Days · Expiring within 30 Days	Contractor Management
Unit Compliance — License Fees	Expired · Due Soon	Location & Unit Management
Unit Compliance — Electric Bill	Expired · Due Soon	Location & Unit Management
Unit Compliance — FSSAI	Expired · Due Soon	Location & Unit Management
Vendor Compliance — PVR	Expired · Due Soon	Vendor Management
Vendor Compliance — Medical	Expired · Due Soon	Vendor Management
Penalty Overdue	Total Overdue	Penalties, filtered to overdue

Dashboard drill-through clicks are recorded against your account for usage analysis.

SECTION 5

Navigation

5.1 The application shell

Every signed-in screen shares the same frame:

- **Left sidebar** — the SERVMS crest, the navigation list, and the **Logout** button at the foot.
- **Top bar** — a search field, a bell icon with an unread badge, and your name, initial, and role.
- **Content area** — the current screen.

> NOT IMPLEMENTED
>
> The top-bar field reading **"Search across SERVMS…"** is decorative. It accepts typing but has no behaviour attached — pressing Enter does nothing and no results appear. **There is no global search.** Use the search box inside each module instead; every listing screen has its own.

The bell icon opens the **Notification Centre**. Its badge counts unread items, displaying `9+` above nine.

5.2 Sidebar menu

Thirteen items. Each appears only if your role holds `view` on the module behind it, so two people signed in side by side may see different menus.

MENU ITEM	ADDRESS	GOVERNING PERMISSION	PURPOSE
Dashboard	`/dashboard`	`dashboard`	Role-scoped overview and drill-through
User Management	`/users`	`user_management`	Staff accounts, password reset and transfer requests
Role Management	`/roles`	`role_management`	Roles and the permission matrix
Location Masters	`/locations`	`location_management`	Units, Stations, Trains, Clusters
Vendor Management	`/vendors`	`vendor_management`	Vendor register, verification, documents
Contractor Management	`/contractors`	`contractor_management`	Contractor register and unit assignment
ID Card / QR	`/id-cards`	`id_card_management`	Card request, approval, signing, PDF
Vendor Renewals	`/renewals`	`vendor_management`	PVR and medical certificate renewals
Complaints	`/complaints`	`complaint_management`	Complaint register and ATR chain
Inspections	`/inspections`	`inspection_management`	Inspection register and ATR chain
Penalties	`/penalties`	`penalty_management`	Penalty ledger and recovery
Audit Logs	`/audit-logs`	`audit_logs`	System activity trail
Reports	`/reports`	`reports`	Report hub, builder, exports, imports

5.3 Screens reached from within a module

Nine further screens have no sidebar entry and are reached only by a button on their parent screen.

SCREEN	ADDRESS	REACHED FROM
Vendor Registration wizard	`/vendors/new`	Vendor Management → **+ Onboard New Vendor**
Contractor Registration	`/contractors/new`	Contractor Management → **+ Register Contractor**
Complaint Registration	`/complaints/new`	Complaints → **+ Register Complaint**
RailMadad Import	`/complaints/import`	Complaints → **Import**
Complaint Type Master	`/complaints/types`	Complaints → **Manage Types**
Inspection form	`/inspections/new` , `/inspections/:id/edit`	Inspections → **+ New Inspection** or the edit action
Inspection Type Master	`/inspections/types`	Inspections → **Manage Types**
Report Builder / Saved Reports / Export History / Import Management	`/reports/builder` , `/saved` , `/exports` , `/import`	Reports hub buttons
Notification Centre	`/notifications`	Bell icon in the top bar

The Notification Centre is the only screen not gated on a module permission — every signed-in user can reach it, because its contents are personal.

> UNREACHABLE
>
> Two placeholder screens — **Settings** and **Help Center** — exist in the codebase but are not registered as addresses and have no menu entry. They cannot be opened by any means, and both contain only a single line of placeholder text. There is no settings screen in SERVMS. The only user-adjustable preferences anywhere are the notification preferences described in Section 19.

SECTION 6

User Roles and Permissions

6.1 The eight roles

ROLE	TIER	DATA SCOPE	PURPOSE
Super Admin HQ	HQ	Everything, all divisions	Complete control. Bypasses the permission matrix entirely.
HQ Admin	HQ	All divisions	Full HQ-level operational and approval authority.
HQ Sub Admin	HQ	All divisions	Create and edit at HQ level; approval withheld except ID cards.
Divisional Admin	Divisional	Own division only	Full authority inside one division.
Divisional Sub Admin	Divisional	Own division only	Create and edit inside one division; approval withheld except ID cards.
Inspector	Field	Own inspections only	Files inspections and registers complaints. Read-only elsewhere.
Dealing Section	Field	Inspections delegated to them	Prepares Action Taken Reports and records penalty recovery.
Complaint Cell	Divisional	Own division only	Complaint intake and handling. No access to penalties, contractors, inspections, or ID cards.

6.2 How permission is decided

Permission is a grid of **14 modules × 6 actions**. Every role holds one row per module recording whether it may View, Add, Edit, Delete, Approve/Reject, and Export. A missing entry is a denial.

Three rules sit above the grid:

1. **Super Admin HQ bypasses the grid.** Every check passes regardless of what the grid records.
2. **Division scoping applies after permission.** Divisional Admin, Divisional Sub Admin, and Complaint Cell only ever act on their own division's records; Inspector only on inspections they filed; Dealing Section only on inspections delegated to them.
3. **Some actions name roles directly**, bypassing the grid — complaint and inspection type masters, permission-matrix editing, and penalty recovery entry. These are noted where they occur.

6.3 Permission matrix

The definitive grid as configured. **Y** = permitted, – = denied.

ACTIONS: V VIEW · A ADD · E EDIT · D DELETE · P APPROVE/REJECT · X EXPORT

MODULE	SUPER ADMIN HQ	HQ ADMIN	HQ SUB ADMIN	DIVISIONAL ADMIN	DIVISIONAL SUB ADMIN	INSPECTOR	DEALING SECTION	COMPLAINT C
Dashboard	VAEDPX	V	V	V	V	V	V	V
User Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	–	–	–
Role Management	VAEDPX	VAEDPX	–	VAEDPX	–	–	–	–
Location Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	V	V	V
Unit Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	V	V	V
Vendor Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	V	V	V
Contractor Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	V	V	–
ID Card Management	VAEDPX	VAEPX	VAEP	VAEPX	VAEP	V	V	–
Complaint Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	VA	VE	VAE
Inspection Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	VAE	VE	–
Penalty Management	VAEDPX	VAEPX	VAE	VAEPX	VAE	V	VE	–
Reports	VAEDPX	VAEPX	VX	VAEPX	V	V	VX	V
Audit Logs	VAEDPX	VX	–	VX	–	–	–	–
Admin Module	VAEDPX	VAEPX	–	–	–	–	–	–

> READING THE MATRIX
>
> `VAEPX` means View, Add, Edit, Approve/Reject and Export are permitted but Delete is not. **Only Super Admin HQ can delete anything** in any module — every other role, including HQ Admin and Divisional Admin, is denied Delete throughout. Delete buttons visible to other roles will be rejected by the server.

6.4 Rules that override the matrix

ACTION	WHO MAY PERFORM IT
Create, edit, or disable an Admin-tier account (Super Admin HQ, HQ Admin, Divisional Admin)	Super Admin HQ only, regardless of User Management permission
Save the permission matrix for a role	Super Admin HQ, HQ Admin, Divisional Admin
Manage Complaint Type / Sub-Type and **Inspection Category / Type** masters	Super Admin HQ, HQ Admin, HQ Sub Admin, Divisional Admin, Divisional Sub Admin
Approve and sign an ID card	Any user flagged *Card Signing Authority* who also holds ID Card approve permission, plus Super Admin HQ
Record penalty recovery	Dealing Section only, plus Super Admin HQ
Upload penalty documents	HQ Admin, Divisional Admin, Dealing Section, plus Super Admin HQ
Delete complaint import history	HQ Admin, Divisional Admin, plus Super Admin HQ

> KNOWN GAP
>
> **Vendor Renewals is not permission-checked.** Every action on that screen — creating a renewal, approving it, rejecting it — is available to any signed-in user, whatever their role. The sidebar link is hidden from roles without Vendor Management view, but the underlying operations are not protected and the screen's own buttons are not permission-gated. Treat Vendor Renewals as open to all staff until this is corrected.

6.5 Card Signing Authority

A separate credential from the role, set per user. It is the only thing that permits approving and digitally signing a vendor ID card. To be eligible a user must satisfy both conditions:

- Role is HQ Admin, HQ Sub Admin, Divisional Admin, or Divisional Sub Admin, *and*
- Designation Grade is `JS` or `SS`.

An eligible user must additionally be given an **Authority Designation** — the wording printed on issued cards, for example “Divisional Administrator, Kharagpur Division”. A signature image should also be uploaded, or cards will be produced without a visible signature.

SECTION 7

User Management

Address `/users` · **Breadcrumb** Admin Console > User Management · **Available to** Super Admin HQ, HQ Admin, HQ Sub Admin, Divisional Admin, Divisional Sub Admin

7.1 The listing

COLUMN	SHOWS
User	Initial avatar, full name, then Employee ID · username
Designation	Free-text designation, or —
Role	Role name as a tag
Division	Division, falling back to Zone, or —
Signing Authority	"Yes" or —
Status	Active in green, anything else in red
Last Login	Date and time, or "Never"
Actions	Toggle · Reset Password · Transfer

Ten rows per page, paginated at the foot of the table.

Search, filter and sort

Search matches full name, username, or Employee ID, and is applied as you type. Filters: **Role**, **Status** (All / Active / Inactive), and — under **Advanced Filters** — **Division**. All filtering happens in your browser across the complete user list, so results are instant. Columns are not sortable; rows are always ordered newest-created first.

Export CSV

Export CSV downloads `user-management.csv` containing exactly the rows matching your current filters, with columns Employee ID, HRMS ID, Full Name, Username, Designation, Role, Division, Zone, Status, Last Login.

Statistics

Super Admin HQ, HQ Admin, and Divisional Admin see two cards below the table: **Active Users** (with the inactive and total counts beneath) and **Total Active in Last 7 Days**. Other roles do not.

7.2 Adding a user

Press **+ Add New User** to open the Add New User dialog. All fields are on one screen.

FIELD	REQUIRED	INPUT	NOTES AND VALIDATION
Employee Number	Yes	Text	Must not be blank. Typing here auto-fills Username until you edit Username yourself.
Username	Yes	Text	3–50 characters. This is the value used to sign in.
HRMS ID	No	Text	Free text.
Temporary Password	Yes	Password	Minimum 6 characters. Communicate it to the user out-of-band.
Full Name	Yes	Text	Must not be blank.
Designation	No	Text	Free text, e.g. "Station Inspector".
Designation Grade	No	Dropdown	JAG · SG · Sr. Supervisor · JS · SS · Other. Must be JS or SS for Card Signing Authority.
Email	No	Email	Must be a valid address if supplied.
Mobile Number	Yes	Text	Required by the form. No format check is applied.
Role	Yes	Dropdown	Only Super Admin HQ sees Admin-tier roles in this list.
Zone	No	Dropdown	Optional.
Division	No	Dropdown	Optional by the form, but a divisional role without a division sees no data.
Station	No	Dropdown	Optional. Lists every station regardless of the division chosen.
Card Signing Authority	No	Yes / No	Disabled unless Role and Designation Grade are both eligible.
Authority Designation	Yes, if signing authority is Yes	Text	Printed on issued ID cards.
Signature Upload	No	File	JPG or PNG only, maximum 2 MB. Applied automatically to cards this user approves.

01 Complete the required fields.

02 If the account is to sign ID cards, set Role and Designation Grade first — the Card Signing Authority control stays disabled until both qualify.

03 Press **Create User**. On failure a red banner names the specific problem.

04 Give the temporary password to the user in person or by phone. Never send it by email.

> CAUTION
> Division is optional on this form but is not optional in practice. A Divisional Admin, Divisional Sub Admin, or Complaint Cell user created without a division will sign in successfully and see empty lists everywhere, because every query filters on their division.

7.3 Editing and deleting users

> NOT IMPLEMENTED
> **There is no way to edit or delete a user through the interface.** The listing offers only Toggle, Reset Password, and Transfer. Once a user is created, their name, Employee Number, username, designation, grade, email, mobile, signing authority, station, and signature can never be changed on screen. Role and division can be changed only by raising and approving a **Transfer** request. Correcting a typo in a name requires a database change.

Toggle (activate / deactivate)

Press **Toggle** to flip a user between Active and Inactive. There is no confirmation prompt and the change is immediate. The button is hidden for Admin-tier accounts unless you are Super Admin HQ.

> KNOWN GAP
> Setting a user Inactive does **not** stop them signing in — see Section 3.7. Toggle changes the badge in the Status column and nothing else.

7.4 Password reset (assisted)

SERVMS uses a two-person reset: one administrator raises the request, another approves it. Both parties need User Management permissions — raising needs Edit, approving needs Approve/Reject.

STEP 1	STEP 2	STEP 3	STEP 4	STEP 5
Raise	**Notify**	**Queue**	**Decide**	**Relay**
Administrator submits with an optional reason	Email sent to the HQ admin mailbox	Appears under Pending Requests	Approve or Reject	Temporary password shown once

01 Find the user and press **Reset Password**.

02 Optionally record a reason, then press **Submit Request**. A confirmation states the request has been routed for review.

03 An approver opens **Pending Requests** and selects the **Password Resets** tab, which shows User, Requested By, Reason, and Date.

04 Press **Approve**. A green banner displays a freshly generated temporary password of roughly eight characters.

05 Copy it now. It is shown once, is never emailed, and cannot be retrieved afterwards. If it is lost, raise a fresh request.

06 Relay it to the user securely. Pressing **Reject** instead closes the request and leaves the password untouched.

> KNOWN GAP
> An approved reset marks the account as holding a temporary password, but **there is no screen on which a user can change their own password.** The user signs in with the temporary password and is never prompted to replace it — the temporary password simply becomes their permanent one. To change it again, another assisted reset must be raised.

7.5 Transfer requests

The only mechanism for changing a user's division or role after creation. Same two-person pattern as password reset.

01 Press **Transfer** on the user's row. Current Division and Current Role are shown read-only.

02 Choose a **New Division**, a **New Role**, or both. Leaving both as "No change" is rejected with "Select a new division and/or role to request a transfer."

03 Optionally record a reason and press **Submit Request**.

04 An approver opens **Pending Requests → Transfers**, which shows the user, the proposed change as

from → *to*, who requested it, and when.

05 Press **Approve** to apply the change to the account, or **Reject** to close the request unchanged.

The Transfer button is hidden for Admin-tier accounts unless you are Super Admin HQ.

> **NOTE**
>
> An approved transfer changes the stored account, but the affected user keeps their existing session with the old role and division until they sign out and back in. Ask them to sign out and in again after a transfer is approved.

SECTION 8

Role Management

Address `/roles` · **Available to** Super Admin HQ, HQ Admin, Divisional Admin

8.1 The role list

Three summary cards head the page: **Total Roles**, **Active Users** (the sum of all role user counts), and **System Modules** (14). Below them, three tabs filter the list: `ALL` `ADMIN` `FIELD`. FIELD contains only the Inspector role; every other role is classed as ADMIN.

Columns: Role Name, Description, User Count, Status, Actions. Ten rows per page. There is no search box on this screen.

8.2 Adding a role

01 Press **+ Add New Role**.

02 Enter a **Role Name** (required) and an optional **Description**.

03 Press **Create Role**.

> CAUTION
>
> A newly created role starts with **no permissions at all**. It must be selected in the list and given permissions in the matrix before anyone assigned to it can do anything. Note also that the role name you type is stored raw — only the eight built-in roles have friendly display names, so a custom role will show its raw name wherever roles are listed.

8.3 Editing a role

Press the pencil icon on a role's row. Only two properties can be changed: **Description** and **Status** (Active / Inactive). The role name cannot be changed after creation.

8.4 Deleting a role

Press the bin icon. A browser confirmation asks “Delete role ‘…’? This cannot be undone.” Only Super Admin HQ holds Delete on Role Management, so for every other role the button either does not appear or the action is refused. If the role is in use the server refuses and the reason appears in a red banner.

8.5 The permission matrix

Selecting any row in the role list loads its permission matrix below the table, headed **Permission Matrix — <role>**. Fourteen module rows against six checkbox columns: View, Add / Create, Edit / Update, Delete, Approve / Reject, Export Data.

01 Select the role whose permissions you want to change.

02 Tick or untick the boxes. Use **Select All** above the table to set or clear every box at once.

03 Press **Save Changes**. The button reads “Saved ✓” on success.

Only Super Admin HQ, HQ Admin, and Divisional Admin can save. For every other role the checkboxes render disabled and the Save button is hidden.

> MISLEADING CONTROL
>
> The button labelled **Reset to Default** does not reset anything to a default. It re-reads the currently saved permissions from the server, discarding unsaved ticks on screen. Read it as *“Discard my changes”*. There is no way to restore a role's original shipped permissions once they have been saved over.

> CAUTION
>
> Changes take effect the moment they are saved, for every user holding that role, without them signing out. Removing View on a module removes it from their sidebar mid-session. Take particular care with Super Admin HQ: its permissions are ignored in favour of an unconditional bypass, so editing that row has no effect and cannot lock anyone out — but editing HQ Admin or Divisional Admin can.

SECTION 9

Location and Unit Management

Address `/locations` · **Menu label** Location Masters · **Page title** Location & Unit Management

Four tabs: **Units**, **Stations**, **Trains**, **Clusters**. Units is the operational register — the physical stalls and service points a contract attaches to. The other three are the geography those units sit in.

9.1 Units tab

Columns: Unit, Location, Contract Type, Category, Inspector, Status, Actions.

Filters

FILTER	OPTIONS
Search	Free text against unit name and code
Division	All Divisions, or one division
Location Type	All · Station · Train · Cluster
Status	Active · Expiring · Inactive · Pending
Contract Type	All Types · Earning · Expenditure

Adding a unit

FIELD	REQUIRED	INPUT	NOTES
Division	Yes	Dropdown	Determines which stations, trains, and clusters are offered.
Location Type	Yes	Station / Train / Cluster	Controls which of the next three fields appears.
Station *or* Train *or* Cluster	Yes	Dropdown	Only the one matching Location Type is shown.
Contract Type	Yes	Earning / Expenditure	Earning: the contractor pays the railway. Expenditure: the railway pays the contractor.
Contract Category	No	Dropdown	Drawn from the managed `contract_category` list, filtered by division.
Unit Name	Yes	Text	The display name throughout the system.
Unit Code / ID	Yes	Text	Short identifier.
Area (sq. ft.)	No	Text	Free-text area description.
Sketch (attachment)	No	File	Site sketch or plan.
Contractor	No	Dropdown	May be left unassigned and linked later from Contractor Management.
Annual License Fee (₹)	No	Number	Annual licence fee.
Status	No	Dropdown	Active · Expiring · Inactive · Pending.

Editing and deactivating

The pencil icon opens the same form pre-filled. The bin icon is labelled **Deactivate unit** — a unit is deactivated rather than erased, so its history in complaints, inspections, and penalties survives. Only Super Admin HQ holds Delete on Unit Management.

9.2 Stations tab

Columns: Station Name, Station Code, Division, No. of Platforms, Actions. Filter by Division.

Fields when adding: **Division**, **Station Name**, **Station Code**, **No. of Platforms**. Edit and remove actions are on each row.

Bulk import

Stations can be loaded in bulk from a single-sheet Excel workbook whose columns are titled exactly **Division**, **Station Name**, **Station Code**, and **No of Platforms**. See Section 18.

9.3 Trains tab

Columns: Train, Route, Opposite Direction, Owning Division, Actions. Filter by Owning Division.

A train record captures both directions of a service in one row. Fields: **Owning Division**, **Train Number**, **Train Name**, **Source**, **Destination**, and four opposite-direction fields — **Opposite Direction Train Number**, **Train Name**, **Source**, and **Destination**. Edit and remove actions are on each row.

9.4 Clusters tab

A cluster groups several stations or several trains so one unit can serve them all. Columns: Cluster Name, Type, Division, Members, Actions. Filter by Division.

Fields: **Division**, **Cluster Type** (Station Cluster or Train Cluster), **Cluster Name**, and the member stations or trains.

NOT IMPLEMENTED

The Clusters tab offers only **Remove cluster**. There is no edit action, so a cluster's name, type, or membership cannot be changed after creation — it must be removed and recreated. The other three tabs all have edit actions.

SECTION 10

Contractor Management

Address `/contractors` · **Page title** Master Contractor Listing · **Not available to** Complaint Cell

10.1 The listing

Columns: Contractor Name, License Number, Contract Value, Award Date, Status, Vendor Count, Actions.

Filters: **Search**, **Status**, and **Division**. The Status filter includes an *Inactive (Non-Active)* option, which is a roll-up of every non-active state rather than a status a contractor can actually hold.

STATUS	MEANING
`active`	Trading normally
`pending_approval`	Registered, awaiting approval
`suspended`	Temporarily stopped
`expired`	Contract or licence lapsed
`blacklisted`	Barred. Settable only through the status-change action, never on a form.

10.2 Registering a contractor

+ Register Contractor opens a full-page form at `/contractors/new`. The contractor code is generated automatically in the form `CON-001`.

FIELD	REQUIRED	INPUT	VALIDATION
Contractor/Company Name	Yes	Text	Must not be blank
Primary Contact Person	No	Text	—
Registered Office Address	No	Textarea	—
PAN Number	No	Text	Exactly 10 characters if supplied
GST Identification (GSTIN)	No	Text	Exactly 15 characters if supplied
License Validity	No	Date	Must be a valid date. Drives the Contract Expiry alert.
Annual Registration Fee (₹)	No	Number	Zero or greater
Award Date	No	Date	Must be a valid date
Tenure (months)	No	Number	At least 1
Annual Contract Value (₹)	No	Number	Zero or greater
Official Email Address	No	Email	Must be a valid address
Mobile Number	No	Text	No format check
Division	Yes	Dropdown	Required by the server
Company logo	No	File	Previewed before submission

10.3 Editing a contractor

Open a contractor and press Edit. Nine fields can be changed: Primary Contact, Mobile, Email, License Number, License Validity, Annual Registration Fee, Award Date, Tenure, and Annual Contract Value.

> CAUTION
>
> The edit form is narrower than the registration form. **Company Name, PAN, GSTIN, Registered Address, and Division cannot be changed after registration.** Verify these five carefully at registration — correcting them later requires a database change.

10.4 Changing status

Requires Approve/Reject on Contractor Management. Choose the new status and supply a reason; the change and its reason are written to the audit trail. Blacklisting is available only here.

10.5 Deleting a contractor

> NOT IMPLEMENTED
>
> There is no Delete action for contractors anywhere in the interface, for any role, although the capability exists behind the API. Use **status change** to Suspended, Expired, or Blacklisted to take a contractor out of service. This is the correct approach in any case — it preserves the contractor's history.

10.6 Unit assignment

Opening a contractor shows the units assigned to them, with columns Unit, Station, Status, and (with Edit permission) Actions.

01 Choose an unassigned unit from the picker — only units with no contractor are offered.

02 Press Assign. The unit now belongs to this contractor and its vendor count updates.

03 To release a unit, press the unassign action on its row. The unit returns to the unassigned pool; it is not deleted.

10.7 Contractor detail

The detail view shows Primary Contact, Mobile, Email, License Number, License Validity, Annual Registration Fee, Award Date, Tenure, Annual Contract Value, and Status, alongside the assigned units and a change history of When / Action / By / Details.

> **NOTE**
>
> Four stored contractor attributes — *Compliance Rate*, *Penalty Index*, *IRCTC Licensed*, and *Joined Date* — are held in the database but appear on no screen and can be set through no form. They are dormant and should be disregarded.

SECTION 11

Vendor Management

Address `/vendors` · **Page title** Vendor Master Listing

11.1 The listing

Columns: Vendor ID, Vendor Name, Contractor Entity, Unit, Verification, Actions. The Verification column stacks two lines — Police and Medical — each colour-coded: green Verified, amber Pending, red Rejected or Expired. Ten rows per page; paging is done on the server.

Filters

Search Database matches vendor ID, vendor name, or contractor name. **Unit / Division** selects a division. **Validity** filters by status. **More Filters** reveals a **Unit** picker, restricted to the chosen division.

> NOTE
> The Validity filter's *Inactive (Non-Active)* option is a roll-up of Pending and Expired used by the Dashboard, not a status a vendor can hold. The four real statuses are Active, Pending, Expired, and Blacklisted.

Statistics

Six cards below the table: Total Active Vendors, Police Verified, Expired Medicals, Expired PVR, Expiring Soon (30 days), Awaiting Approval.

Export to Excel

Export to Excel downloads `vendor-master-listing.csv` — a CSV file despite the button label. It contains the rows matching your current filters, capped at 2,000, with columns Vendor ID, Vendor Name, Contractor Entity, Unit, Division, Police Verification, Medical Verification, Validity End, and Status.

11.2 Onboarding a vendor

+ Onboard New Vendor opens a five-step wizard at `/vendors/new`. Vendor codes are generated automatically as `V-2026-1234`.

STEP 1	STEP 2	STEP 3	STEP 4	STEP 5
Personal Details	**Deployment**	**Verification**	**Documents**	**Submit**

Step 1 — Personal Details

FIELD	REQUIRED	INPUT	VALIDATION
Full Name (As per Aadhaar)	Yes	Text	Must not be blank
Father's Name	No	Text	—
Date of Birth	No	Date	—
Aadhaar Number	No	Text, 12 max	Exactly 12 digits if supplied
Blood Group	No	Dropdown	A+ A− B+ B− AB+ AB− O+ O−
Photograph	No	Image	Previewed. Printed on the ID card.
Signature	No	Image	Previewed. Printed on the ID card.
Mobile Number	Yes	Text	Must not be blank
Address	Yes	Textarea	Must not be blank

Step 2 — Deployment

FIELD	REQUIRED	INPUT	VALIDATION
Vendor Type	No	Dropdown	Train TSV · Station PF · Station Stall · Station Others
Division	Yes	Dropdown	Required. Filters Station, Unit, and Contractor.
Station	Conditional	Dropdown	Required only if the chosen division has stations configured. Otherwise the label reads "Station (optional)".
Contractor / Agency	Yes	Dropdown	Required
Platform Unit / Stall	Conditional	Dropdown	Required only if units exist for the chosen station or division
Validity Start	No	Date	Must be a valid date
Validity End	No	Date	Must be a valid date

Step 3 — Verification

Two identical blocks, Police Verification and Medical Verification. Each holds a **Verification Status** (Pending / Verified / Rejected), **Issue Date**, a number, a **Valid Till Date**, and optional **Remarks**.

Police Verification Number and **Medical Fitness Certificate Number** are both mandatory — a vendor cannot be created without them. A Valid Till date earlier than its Issue Date is rejected.

> TIP
> The Valid Till dates matter beyond compliance reporting: an ID card's expiry is taken from one of them (see Section 12). A vendor with no Valid Till date on the chosen verification cannot be issued a card at all.

Step 4 — Documents

Three upload slots — Aadhaar, Medical Verification, and Police Verification — each accepting PDF, JPG, or PNG. All three are optional at onboarding and can be added later from the vendor's document folder.

Step 5 — Submit

A read-only review of everything entered. Use **Back** to correct any step, then submit. Validation failures return a red banner naming the specific field.

11.3 Vendor detail

The eye icon opens a detail view showing Vendor Code, Vendor Type, Mobile, Blood Group, Address, Contractor, Division, Station, Unit, Validity, and Status, together with both verification cards and — with Edit permission — the Transfer panel.

> NOTE
> Father's Name, Date of Birth, and Aadhaar Number are captured at onboarding but do not appear in this detail view. Aadhaar is visible only on the issued ID card, in its QR payload, and on the public verification page.

11.4 Editing and deleting vendors

> NOT IMPLEMENTED
> **There is no edit-vendor form and no delete-vendor action** anywhere in the interface. Once onboarded, a vendor's name, father's name, date of birth, Aadhaar number, mobile, address, blood group, vendor type, photograph, signature, and validity dates cannot be corrected on screen.
>
> Only four things about a vendor can be changed after onboarding: **status**, **police verification**, **medical verification**, and **unit or contractor by transfer**. Everything else is fixed at onboarding, so check Step 1 carefully before submitting.

11.5 Changing vendor status

Requires Approve/Reject. In the detail view, Status becomes a dropdown offering Active, Pending, Expired, and Blacklisted. Selecting Blacklisted raises a confirmation: “Blacklist this vendor? This should only be done for serious violations.” The change takes effect immediately.

11.6 Updating verification

Requires Edit. Both verification cards carry an **Update Verification** button.

01 Press **Update Verification** on the Police or Medical card.

02 Set the **Verification Status** to Pending, Verified, or Rejected.

03 Enter the certificate number. This is mandatory — leaving it blank gives “Police Verification Number is required.”

04 Set **Issue Date** and **Valid Till Date**. Valid Till may not precede Issue Date.

05 Optionally add Remarks and attach a replacement document (PDF, JPG, or PNG, up to 5 MB).

06 Press **Save**.

When not being edited, each card shows the number, dates, remarks, and **View** / **Download** links for the attached document.

11.7 Transfers

Requires Edit. Two independent transfers are offered in the detail view:

- **Transfer to Unit** — move a vendor to a different platform unit or stall.
- **Transfer to Contractor** — move a vendor to a different contracting agency.

Choose a target and press Transfer. Both are recorded in the audit trail.

11.8 Documents

The folder icon opens Vendor Documents, listing the three document types with the uploaded file name, upload date, and uploader, or “Not uploaded”.

- **Upload** / **Replace** — PDF, JPG, or PNG up to 5 MB. Uploading over an existing document replaces it.
- **View** — PDFs open in an inline frame; images render directly.

- **Download** — saves the original file.

There is no delete action for a vendor document; replacing it is the only way to change it.

SECTION 12

ID Card and QR Management

Address `/id-cards` · **Not available to** Complaint Cell

This module carries the workflow described on its own sub-title: *issue-request → Sub Admin approval → automatic digital signature → QR → PDF*.

12.1 Layout

Three statistic cards head the page — **Approved & Issued**, **Pending Approval**, **Total Vendors**. Below, a two-column layout: a searchable vendor list on the left, and the selected vendor's card panel on the right. Search matches name or vendor code.

Each vendor in the list shows their card state:

STATE	DISPLAYED AS	MEANING
`draft`	Not Requested	No card has been requested
`pending_approval`	Pending Sub Admin Approval	Requested, awaiting a signing authority
`approved`	Approved & Issued	Signed, QR generated, PDF available
`rejected`	Rejected	Refused, with a reason recorded

12.2 Card formats

FORMAT	DESCRIPTION
Format 1 — Indian Railway	Annexure B. Plain header, no side strip. Masked Aadhaar on the back.
Format 2 — Entry Pass	Annexure-II. Orange “ON CONTRACT” side strip with an Entry Pass header. Contractor name, contract validity, and date of issue on the back.

12.3 Requesting a card

Requires Add on ID Card Management.

01 Select the vendor in the left-hand list.

02 Choose the format under **ID Card Format**.

03 Press **Request ID Card** — or **Re-issue ID Card** if one has already been issued.

04 Choose the **ID Card Expiry Driver**: *Use Medical Expiry* or *Use Police Verification Expiry*. The card's expiry date is copied from whichever you choose.

05 Press **Submit Request**. The state becomes Pending Sub Admin Approval.

> CAUTION
>
> If the chosen verification has no Valid Till date on file, the request is refused with “Cannot use medical expiry — no valid-till date on file”. Complete the vendor's verification dates first (Section 11.6).
>
> Re-issuing an approved card returns it to Pending Approval and clears the previous approval — the vendor has no valid card until a signing authority approves again.

12.4 Approving and signing

The **Approve & Sign** and **Reject** buttons appear only when the card is pending *and* you are a designated Card Signing Authority (or Super Admin HQ). Approve/Reject permission alone is not enough.

01 Select a vendor whose card is Pending Sub Admin Approval.

02 Press **Approve & Sign**. In one action the system applies your stored signature image, generates the QR code, renders the PDF, sets the issue date to today, and marks the card Active.

03 To refuse instead, press **Reject**, enter a **Rejection Reason** (mandatory) and confirm. The reason is shown on the card panel afterwards.

A divisional signing authority may only act on vendors in their own division; attempting otherwise returns “You can only approve ID cards for vendors in your own division.”

12.5 The issued card

Once approved, the panel shows a live front-and-back preview with the QR code. Both formats can be downloaded as PDF regardless of which was requested — **Download Format 1 — Indian Railway** and **Download Format 2 — Entry Pass**.

The printed card carries: vendor name and photograph, vendor signature, vendor type, contractor name and mobile, unit, station, blood group, the department line “Commercial Department”, card number, contract validity dates, issue date, expiry date, the signing authority's name, their authority designation, their signature image, and the QR code.

12.6 The QR code

The QR encodes plain text, identical in the on-screen preview and the printed PDF:

LINE	CONTENT
Name & Address	Vendor name and address
Aadhaar No	Aadhaar number
PVR Validity	Police verification valid-till date
Medical Validity	Medical verification valid-till date
Unit	Assigned unit
Vendor Type	Train TSV / Station PF / Station Stall / Station Others
Contractor	Contracting agency
Validity of ID Card	Card expiry date
Issuing Authority	Approver name and authority designation
Verify	Link to the public verification page
Check ID Card Status	Link to the status spreadsheet

> DATA PROTECTION
>
> The QR payload contains the vendor's **full Aadhaar number and home address in plain text**. Anyone who scans a printed card obtains both. Handle printed cards accordingly and take this into account when deciding whether to publish the verification page beyond the intranet.

12.7 Public verification

Scanning the QR, or opening `/verify/<card number>`, reaches the **Identity Verification Result** page. No sign-in is required.

PANEL	SHOWS
Status	`VALID` when the card is Active and Approved; `NOT ISSUED` when not approved; otherwise the card state. Plus “Last Checked”.
Vendor Information	Full Name, Vendor Type, Contractor / Agency, Assigned Unit, Aadhaar Number, Blood Group, Address
Validity	ID Card Validity date and Days Remaining
Verification Step	Police Verification and Medical Verification completion indicators

Every scan updates the card's “Last Checked” timestamp, so the page shows when it was last verified by anyone.

12.8 Per-card status link

> NOT IMPLEMENTED
>
> Each card can carry its own “Check ID Card Status” spreadsheet link, overriding the system-wide default, but **no screen exposes this setting**. Every card therefore uses the single system-wide link configured by the administrator. Setting a per-card link requires a direct API call.

SECTION 13

Vendor Renewals

Address `/renewals` · **Page title** Vendor ID Renewal · **Menu entry** shown to roles with Vendor Management view

This module records the renewal of a vendor's Police Verification Report or medical fitness certificate, and pushes the new expiry date onto the vendor record when approved.

> KNOWN GAP
>
> **This module performs no permission checks.** Any signed-in user who reaches the address — including Inspector, Dealing Section, and Complaint Cell — can create, approve, and reject renewals. The screen's Approve and Reject buttons are shown to everyone. Until this is corrected, apply the restriction by procedure rather than relying on the system to enforce it.

13.1 The listing

Columns: Vendor, Renewal Type, Renewal Period, New Expiry, Reference, Status, Actions.

STATUS	MEANING
`draft`	Saved but not submitted
`pending_approval`	Awaiting a decision. Approve and Reject appear only on these rows.
`approved`	Accepted; the vendor record has been updated
`rejected`	Refused; the vendor record is unchanged

13.2 Raising a renewal

01 Press **+ New Renewal**.

02 Select the **Vendor**.

03 Select the **Renewal Type**: Police Verification Report (PVR), Medical Certificate, or Both.

04 Enter the **Renewal Period** and the **New Projected Expiry**.

05 For a PVR renewal, supply the **PVR Number**, **PVR Issue Date**, and **PVR Document**.

06 For a medical renewal, supply the **Medical Certificate No.**, **Issue Date**, and **Document**.

07 Submit. The renewal is created as Pending Approval.

Choosing *Both* shows both sets of fields.

13.3 Deciding a renewal

On any Pending Approval row press **Approve** or **Reject**. There is no confirmation prompt and no remarks field — the decision is applied immediately.

> WHAT APPROVAL DOES
>
> Approving copies the **New Projected Expiry** onto the vendor's validity end date and sets the vendor's status to **Active**. This is how an expired vendor is returned to service. Rejecting changes nothing on the vendor record.

SECTION 14

Complaints

Address `/complaints` · **Available to** all roles except Inspector's write actions being limited to registration; not available to Dealing Section for creation

14.1 The complaint lifecycle

1	2	3	4	5	6
Pending	**Assigned**	**Action Taken**	**Under Review**	**Approved / Rejected**	**Closed**
Registered or imported	Given to a unit	ATR submitted	Sub Admin forwarded it	Admin decision	Case finished

An Admin may also send an ATR back, which returns the complaint to **Assigned** for a fresh report.

14.2 The listing

Columns: Complaint, Source, Date, Division, Type / Sub-Type, Concerned Unit, Priority, Status, Actions.

Above the table, four breakdown charts: **Division Wise**, **Complaint Type Wise**, **Status Wise**, and **Monthly Trend**.

Filters

FILTER	OPTIONS
Global Search	Complaint code, description, complainant
Reference No.	External reference number
Source	All · RailMadad · CPGRAMS · Manual
Status	All, or any of the seven statuses
Priority	All · Low · Medium · High
Division	All Divisions, or one division
More Filters reveals: Station · Train · Concerned Unit · Complaint Type · Complaint Sub-Type · Date Range	

Clear Filters resets everything; **Refresh** re-reads the list from the server.

Export

Two server-generated exports, both applying your current filters: **Export CSV** and **Export Excel** (a genuine `.xlsx` workbook). Requires Export on Complaint Management — held by Super Admin HQ, HQ Admin, and Divisional Admin only.

14.3 Registering a complaint

Requires Add. **+ Register Complaint** opens a sectioned form at `/complaints/new`. Codes are generated as `CMP-1234`.

Source and reference

FIELD	REQUIRED	NOTES
Complaint Source	Yes	RailMadad · CPGRAMS · Manual
Portal Registration Number	Yes for CPGRAMS	"Portal Registration Number is required for CPGRAMS complaints"
RailMadad Reference Number	Yes for RailMadad	"RailMadad Reference Number is required"
Manual Dak Reference Number	No	Shown for Manual source
E-Office Computer Number	No	Shown for Manual source

Location

Division, plus **Train (if applicable)** and **Station (if applicable)**, both filtered by the chosen division and both optional.

Classification

FIELD	REQUIRED	NOTES
Complaint Type	Yes	From the managed type master
Complaint Sub-Type	Yes	Locked until a Type is chosen: "Select Type first"
Concerned Unit	Yes	The unit the complaint is about
Detailed Description	Yes	Free text

Complainant and incident

Complainant Name, **Mobile Number**, and **Email** (validated as an address), then **Occurrence Date** and **Occurrence Time**. All optional.

Evidence

Multiple images or PDFs may be attached. Images are previewed before submission.

14.4 Editing a complaint

Requires Edit. The pencil icon opens a compact form — the editable fields are limited, and **Priority** (Low / Medium / High) is the principal one. To change unit ownership use **Assign** or **Transfer** rather than editing.

14.5 Complaint detail

The eye icon opens the detail view, headed with the complaint code and its source. It shows Reference No., Status, Division, Station / Train, Concerned Unit, Priority, Complaint Type, Complaint Sub-Type, Complainant, Mobile, Registered On, Registered By, and the full description, followed by attached documents, the assignment history, the ATR chain, and the status history.

14.6 Assignment

Requires Edit. Three actions, each recorded with remarks in the assignment history:

ACTION	WHEN AVAILABLE	EFFECT
Assign	No unit assigned yet	Sets the unit; a Pending complaint becomes Assigned
Reassign	A unit is already assigned	Moves it to a different unit
Transfer	A unit is already assigned	Moves it, recorded as a transfer rather than a reassignment

Assignment also re-derives the complaint's division from the receiving unit, so a complaint moved to another division's unit follows it there.

> PARTIALLY IMPLEMENTED
>
> The assignment dialog offers a **Unit** and remarks only. Assignment to a named individual is supported by the system but has no control on the form, so complaints can only be assigned to units, never to people.

14.7 Action Taken Reports

1	2	3	4
Submit	**Review**	**Decide**	**Close**
Dealing Section writes the ATR	Sub Admin forwards it	Admin accepts, rejects, or sends back	Admin closes the case

Submitting

Requires Edit. Available only while the complaint is Assigned, Under Review, or Action Taken. Enter remarks and attach supporting documents. Submitting moves the complaint to **Action Taken** and marks the report *pending review*.

An ATR may be edited only while it is still pending review, and only by the person who submitted it — otherwise: “Only the submitter can edit this Action Taken Report.”

Reviewing

A Sub Admin reviews a pending report and forwards it, optionally with review remarks. The report becomes *sub admin reviewed* and the complaint moves to **Under Review**.

Deciding

Requires Approve/Reject, and only after Sub Admin review — attempting earlier gives “Cannot decide an Action Taken Report before Sub-admin review.”

DECISION	COMPLAINT BECOMES	EFFECT
Accept	`Approved`	The action taken is accepted; the complaint can now be closed
Reject	`Rejected`	The action is refused; the complaint can be closed
Send Back	`Assigned`	Returns to the Dealing Section for a fresh report. Remarks are prefixed “Sent back to Dealing Section:”

Closing

Requires Approve/Reject, and only from Approved or Rejected. Closing stamps who closed it and when. This is the terminal state.

14.8 Complaint Type master

Reached from **Manage Types**. Two levels: Complaint Types, each holding Sub-Types. Each entry has a value, a label, and a sort order, and can be created, edited, deactivated, and reactivated.

INCONSISTENCY

The **Manage Types** button is shown only to roles holding Admin Module add or Complaint Management approve — effectively Super Admin HQ, HQ Admin, and Divisional Admin. The underlying capability is granted to **HQ Sub Admin and Divisional Sub Admin as well**. Sub Admins are entitled to manage complaint types but cannot see the button that would let them.

SECTION 15

Inspections

Address `/inspections` · **Not available to** Complaint Cell

15.1 The inspection lifecycle

1	2	3	4	5	6	7
Draft Being written by the Inspector	**Submitted** Sent for review	**Assigned** Delegated to a unit	**ATR Submitted** Action Taken Report filed	**Under Review** Forwarded by Sub Admin	**Approved / Rejected** Admin decision	**Closed** Case finished

Returned is an additional state: a Sub Admin may send a submitted inspection back to its Inspector for correction before it is ever assigned.

15.2 Who sees what

- **Inspector** — only inspections they filed themselves. No divisional or org-wide view.
- **Dealing Section** — only inspections currently delegated to them.
- **Divisional roles** — their own division.
- **HQ roles** — everything.

15.3 The listing

Columns: Inspection No., Date, Division, Unit, Category / Type, Inspector, Priority, Status, Actions. Six breakdown charts sit above: Division Wise, Unit Wise, Category Wise, Status Wise, Inspector Wise, and Monthly Trend.

Filters: Global Search, Inspection No., Status, Priority, Division; and under More Filters — Station, Train, Unit, Inspection Category, Inspection Type, Date Range. Exports are offered as CSV and Excel and follow the current filters.

15.4 Filing an inspection

Requires Add. Inspection numbers are generated as `INSP-2026-000001`.

FIELD	REQUIRED	INPUT	NOTES
Date of Inspection	Yes	Date	“Date of Inspection is required”
Unit of Inspection	Yes	Dropdown	“Unit of Inspection is required”
Inspecting Official Name	No	Text	—
Designation	No	Text	—
Place of Posting	No	Text	—
Division	No	Dropdown	Filters Station and Train
Station	No	Dropdown	—
Train	No	Dropdown	—
Inspection Category	Yes	Dropdown	From the category master
Inspection Type	Yes	Dropdown	Locked until a Category is chosen
Observations	No	Textarea	—
Deficiencies	No	Textarea	—
Recommendations	No	Textarea	—
Remarks	No	Textarea	—
Priority	No	Dropdown	Low · Medium · High
Attachments	No	Files	PDF, DOC, DOCX, JPG, PNG — multiple files

Inspection attachments accept Word documents in addition to the PDF and image types allowed elsewhere in the system.

15.5 Submitting and returning

Submit is available on Draft and Returned inspections, and **only to the Inspector who created it** — otherwise: “Only the inspector who created this inspection can submit it.”

Return to Inspector is available only on a Submitted inspection and sends it back with remarks, setting it to Returned. The Inspector corrects it and submits again.

15.6 Assignment

Assign, Reassign, and Transfer work exactly as for complaints (Section 14.6) — a target unit and remarks, recorded in the assignment history. As with complaints, assignment to a named individual is supported by the system but has no control on the form.

15.7 Action Taken Reports

The inspection ATR is drafted before submission, unlike the complaint ATR.

01 **Draft** — create an ATR with **Action Description** (required), **Action Date**, **Completion Status** (In Progress / Partially Completed / Completed), **Remarks**, and attachments. An ATR can be edited freely while in draft.

02 **Submit** — sends the ATR for review and moves the inspection to **ATR Submitted**. It can no longer be edited.

03 **Review** — a Sub Admin either *forwards* it to Admin or *sends it back* for correction.

04 **Decide** — requires Approve/Reject. Accept, Reject, or Send Back, exactly as for complaints.

05 **Close** — requires Approve/Reject. Available from Approved or Rejected.

15.8 Deleting an inspection

A delete action appears on rows for roles holding Delete on Inspection Management — Super Admin HQ only. Documents attached to an inspection can be removed individually from the detail view by anyone with Edit.

15.9 Inspection Category and Type master

Reached from **Manage Types**. Two levels: Inspection Categories, each holding Types. Entries can be created, edited, deactivated, and reactivated.

> INCONSISTENCY
>
> As with complaint types, the button appears only for roles holding Inspection Management approve — but HQ Sub Admin and Divisional Sub Admin are entitled to manage these masters and cannot see it.

SECTION 16

Penalties and Recovery

Address `/penalties` · **Not available to** Complaint Cell

A penalty carries three independent states: an **approval** state, a **recovery** state, and a **recovery verification** state. Money is only tracked once the penalty is approved.

16.1 The two-stage lifecycle

STAGE 1	STAGE 2	STAGE 3	STAGE 4	STAGE 5
Impose	**Approve**	**Recover**	**Verify**	**Close**
Penalty raised → Pending Approval	Approved, or Rejected	Dealing Section records payment	Recovery documents checked	Verified → Closed

STATE FAMILY	VALUES
Approval	`pending_approval` `approved` `rejected` `revoked`
Recovery	`pending` `partially_recovered` `recovered` `closed`
Verification	`not_applicable` `pending` `verified` `rejected`

16.2 The ledger

Columns: Ref No, Contractor / Vendor, Unit, Amount, Due Date, Approval, Recovery, Actions.

Filters: **Search**, **Approval Status**, **Recovery Status**, **Division**, **Contractor**, **Vendor**, **Due Date From**, and **Due Date To**.

Export Ledger downloads a CSV of the rows matching your filters, capped at 2,000.

16.3 Raising a penalty

Requires Add. Codes are generated as `PNL-2026-1234`. New penalties begin at Pending Approval with recovery Pending.

FIELD	REQUIRED	INPUT	VALIDATION
Origin	No	None / Complaint / Inspection	Links the penalty to its source case
Complaint	Yes, if Origin is Complaint	Dropdown	—
Inspection	Yes, if Origin is Inspection	Dropdown	—
Contractor	Yes	Dropdown	“contractor_id is required”
Vendor	No	Dropdown	—
Unit ID	No	Number	—
Amount (₹)	Yes	Number	Must be greater than zero
Due Date	No	Date	Must be a valid date
Reason	Yes	Textarea	“Reason for imposing penalty is required”

> NOTE
>
> The **+ Add Penalty** button is disabled while no contractors exist, since a penalty must always name a contractor.

16.4 Approving, rejecting, revoking

All three require Approve/Reject on Penalty Management.

ACTION	AVAILABLE ON	CAPTURES	EFFECT
Approve	Pending Approval	Recovery Due Date, Penalty Order Number, Order Date, Remarks	Penalty becomes enforceable and recovery tracking opens
Reject	Pending Approval	Remarks	Penalty is refused; no recovery follows
Revoke	Approved only	Revocation Reason (required)	Cancels an already-approved penalty

Revoking anything not currently approved is refused: “Only an approved penalty can be revoked.”

16.5 Recording recovery

Dealing Section only (plus Super Admin HQ). Recovery can only be recorded against an approved penalty.

FIELD	NOTES
Recovery Status	Pending · Partially Recovered · Recovered. *Closed* cannot be set here — it is reached only through verification.

FIELD	NOTES
Recovery Amount	Between zero and the penalty amount
Date of Receipt	Date the money was received
Payment Reference Details	Free text
MR Number / MR Date	Money receipt reference
Payment Receipt / Recovery Proof	Supporting document
Remarks	Free text

Three rules are enforced:

- Recovery status may never move backward — "Recovery status cannot move backward from 'recovered' to 'pending'."
- Marking *Partially Recovered* requires a recovery amount above zero.
- Marking *Recovered* requires the recovery amount to equal the full penalty amount.

16.6 Verifying recovery

Requires Approve/Reject. Available only once recovery is marked *Recovered*: "Only a penalty marked 'recovered' by Dealing Section can be verified."

01 Press the **Verify recovery documents** action on the row.

02 Review the recorded amount, reference, and uploaded proof.

03 Choose **Verified** or **Rejected**, optionally with remarks.

DECISION	EFFECT
Verified	Recovery becomes `closed` and the resolution date is stamped. The case is complete.
Rejected	Recovery stays *recovered* so the Dealing Section can correct it and resubmit. A **Resubmit recovery** action appears on the row.

A verification decision can only be made once: "This recovery entry has already been decided — no verification is pending."

16.7 Penalty documents

Uploadable by HQ Admin, Divisional Admin, Dealing Section, and Super Admin HQ. Four categories: **Penalty Order**, **Approval**, **Recovery Receipt**, and **Other**. Admin tiers typically upload the first two; Dealing Section uploads recovery receipts.

16.8 Penalty metrics

Metrics count **approved penalties only** — pending, rejected, and revoked penalties are excluded from every figure. Available: Total Cases, Total Imposed, Total Recovered, Outstanding Amount, Overdue Amount, Overdue Count, Recovery Rate, and pending ageing buckets of within 7, 14, 30, and over 30 days.

SECTION 17

Reports

Address `/reports` · **Available to** all eight roles (view)

17.1 The Reports hub

Four statistic cards — Total Reports Generated, Total Exports, Modules Reported On, Most Used Report — followed by four navigation buttons, two activity panels (Recent Exports and Most Used Reports), and module summary blocks for Vendor Management, Contractor Database, Complaints & Grievances, and Penalties & Fines.

> NOTE
>
> The **Export Summary** button on this page downloads `servms-report-summary.json` — a raw JSON data file of the four metric blocks, not a formatted report. It is a developer-oriented dump rather than a document for circulation. Use the Report Builder for anything that will be shared.

17.2 Report Builder

Requires Add on Reports. Eight modules can be reported on: **Vendors**, **Contractors**, **Units**, **Penalties**, **ID Cards**, **Users**, **Complaints**, and **Inspections**.

01 **Select Module.** The available fields load for that module.

02 **Choose fields.** Tick the columns to include.

03 **Add filters.** Press *Add filter* for each condition. The operators offered depend on the field type — date and number fields offer ranges and comparisons; text fields offer contains-style matching; enumerated fields offer set membership.

04 **Set sorting.** Choose a field and Asc or Desc.

05 **Group and aggregate** if you want totals rather than rows.

06 **Preview.** Returns the first 20 rows so you can check the shape before exporting.

07 **Export** as CSV or Excel, or **Save** as a reusable template.

17.3 Saving templates

Saving captures the module, fields, filters, sort, and grouping under a **Name** and optional **Description**. Mark a template **Shared** to make it available to colleagues; leave it unshared to keep it private.

17.4 Saved Reports

Columns: Name, Module, Created By, Shared, Usage, Last Used, Actions. Actions: **Run** (opens the builder pre-loaded), toggle sharing, and delete. Usage counts and last-used dates are maintained automatically.

17.5 Export History

A read-only log at `/reports/exports` with columns Module, Report, Format, Rows, Exported By, and Date. Every builder export is recorded here, giving a complete record of who extracted what data and when.

> NOTE
>
> Only Report Builder exports appear here. The per-module exports — the Vendor, Penalty, User, Complaint, Inspection, and Audit Log downloads — are not recorded in Export History.

SECTION 18

Import and Export

18.1 What can be imported

SERVMS has exactly three import paths.

IMPORT	WHERE	FORMAT	TEMPLATE
RailMadad complaints	Complaints → Import	RailMadad Excel export	None — use RailMadad's own file
Stations (master import)	Reports → Import Management	Excel	Downloadable
Stations (bulk import)	Location Masters → Stations	Excel	Column names published on screen

> NOTE
>
> **Stations is the only importable master.** Vendors, contractors, units, trains, clusters, and users cannot be bulk-loaded and must be entered one at a time.

18.2 Importing RailMadad complaints

Requires Add on Complaint Management.

01 Open Complaints and press **Import**.

02 Upload the RailMadad Excel export unmodified. SERVMS reads the first worksheet and maps RailMadad's own column names — complaint reference number, created date, complaint mode, train or station, type and sub-type names, division code, status, description, remarks, and user mobile.

03 The import runs and returns a summary: **Total Records**, **Imported**, **Duplicates**, and **Failed**.

04 Rows that failed are listed with a row number and reason.

BEHAVIOUR	DETAIL
Duplicates	Rows whose reference number already exists are skipped, not overwritten. Re-running the same file imports nothing new.
Unknown types	A complaint type or sub-type RailMadad uses that SERVMS does not recognise is **added to the type master automatically** rather than discarded.
Status mapping	closed → Closed; open and pending → Pending; in progress → Action Taken.
Dates	RailMadad's `DD-MM-YY HH:mm` format is converted automatically.
Long numbers	Reference and mobile numbers are read as text so no digits are lost.

Every import is recorded in **Import History** on the same page, showing the file name, who imported it, when, and the four counts. HQ Admin and Divisional Admin can delete a history entry; deleting the record does not remove the imported complaints.

18.3 Importing stations

From Import Management

01 Open Reports → **Import Management**.

02 Select **Stations** as the Master Data Type.

03 Press **Download Template** — the button also names the required columns: Division, Station Name, Station Code, No of Platforms.

04 Fill the template. Division must match an existing division name.

05 Upload the completed `.xlsx` or `.xls`.

06 Review the summary: Total Records, Imported, Duplicates, Failed — with a row-by-row Error Report for failures.

From Location Masters

The Stations tab offers the same import. The required column titles are stated on screen. Duplicates are skipped automatically.

18.4 What can be exported

EXPORT	WHERE	FORMAT	SCOPE
Users	User Management → Export CSV	CSV	Current filters, all matching rows
Vendors	Vendor Management → Export to Excel	CSV *(despite the label)*	Current filters, first 2,000 rows
Penalties	Penalties → Export Ledger	CSV	Current filters, first 2,000 rows
Complaints	Complaints → Export CSV / Export Excel	CSV and true XLSX	Current filters, server-generated

EXPORT	WHERE	FORMAT	SCOPE
Inspections	Inspections → Export CSV / Export Excel	CSV and true XLSX	Current filters, server-generated
Audit logs	Audit Logs → Export Excel / Export PDF	CSV and PDF	Current filters, server-generated
Custom reports	Report Builder → Export	CSV and true XLSX	Your chosen fields and filters
Report summary	Reports → Export Summary	JSON	Four metric blocks

> **CAUTION**
>
> Two buttons labelled “Excel” produce CSV files: **Vendor Management → Export to Excel** and **Audit Logs → Export Excel**. Both open correctly in Excel. Only Complaints, Inspections, and the Report Builder produce genuine `.xlsx` workbooks.
>
> The Vendor and Penalty exports are capped at 2,000 rows with no warning when the cap is reached. For larger extracts, use the Report Builder.

SECTION 19

Notification Centre

Address `/notifications` · **Available to** every signed-in user, regardless of role

Notifications are derived live from current data rather than stored as messages. There is no inbox — the list is recomputed each time you open it, so an item disappears once the underlying condition is resolved.

19.1 Filters

Filter by module: `All` `Vendor Master` `Complaints` `Penalties` `User Management` `Inspections`. Six items are shown initially with an option to load more.

19.2 What generates a notification

MODULE	TRIGGER	SEVERITY
Vendor Master	Contractor licence expiring within 30 days or already expired	Critical within 7 days, otherwise Warning
Vendor Master	Vendor renewal awaiting approval	Warning
Complaints	Complaint pending, assigned, under review, or action taken	By priority
Complaints	Complaint assigned, reassigned, or transferred	Info
Complaints	ATR submitted, reviewed, or decided	Info
Complaints	Complaint closed	Info
Penalties	Recovery due	Warning
Penalties	Recovery overdue	Critical
Penalties	Amount recovered	Info
Inspections	Inspection in an open state	By priority
Inspections	Inspection assigned or transferred	Info
Inspections	Inspection ATR reviewed or decided	Info

The feed is scoped like everything else: divisional roles see only their division; Inspector sees only their own inspections; Dealing Section sees only inspections delegated to them.

19.3 Read state

Marking an item read stores that fact **in your own browser**, not on the server. Read state does not follow you to another computer or another browser, and is lost if browser data is cleared. The bell badge counts items you have not marked read in this browser.

19.4 Notification preferences

The lower half of the page offers channel preferences — Email Alerts, SMS Alerts, Push Notifications; per-category channel choices for Vendor Compliance, Staff & Roles, and Financial Audits; and a digest frequency of Instant, Daily, or Weekly. **Save Changes** and **Restore Defaults** act on them.

> NOT CONNECTED
>
> These preferences are saved to your browser only and **have no effect on anything**. SERVMS sends no emails, SMS, or push notifications for any of these events — the only email the system ever sends is the password-reset request notice to the HQ admin mailbox, which these settings do not control. Treat this panel as a placeholder. Notifications exist only inside the application.

SECTION 20

Audit Logs

Address `/audit-logs` · **Available to** Super Admin HQ, HQ Admin, Divisional Admin

20.1 What is recorded

Every log entry captures: the user, their role, the action, the module, the record identifier, the data before the change, the data after the change, free-text details, the IP address, the browser user-agent, and the timestamp. Passwords are stripped before anything is written.

Actions are recorded across User Management, Roles, Vendors, Contractors, Units, Trains, Clusters, ID Cards, Complaints, Complaint Types, Inspections, Inspection Types, Penalties, Renewals, Reports, Dropdowns, Imports, Exports, Assignments, and ATR decisions.

20.2 Filters

Module and **Action** are always visible. **Advanced Filters** adds **Record ID**, **User ID**, and a **From** / **To** date range. Twenty entries per page.

20.3 Reading an entry

Each row summarises one action. Expanding a row reveals the before and after data, so you can see exactly which values changed.

20.4 Exporting

Requires Export on Audit Logs. **Export Excel** produces a CSV file; **Export PDF** produces a formatted PDF. Both apply your current filters.

> KNOWN GAP
>
> The Action filter offers **Login**, **Logout**, **Download**, **Print**, **Password Reset**, **Recover**, **Renew**, and **Issue**, but **no part of the system writes entries with these actions**. In particular, **sign-in and sign-out are not audited at all**. Filtering by Login always returns an empty result. The only record of a sign-in anywhere in SERVMS is the “Last Login” column in User Management, which holds the most recent time only.
>
> If a sign-in audit trail is a compliance requirement for your division, it is not currently satisfied.

SECTION 21

Document Uploads

21.1 Accepted types and sizes

UPLOAD	ACCEPTED	MAXIMUM SIZE
Vendor documents — Aadhaar, Medical, Police Verification	PDF, JPG, PNG	5 MB (checked in the browser)
Vendor verification attachment	PDF, JPG, PNG	5 MB
Vendor renewal documents	PDF, JPG, PNG	20 MB
Inspection and inspection-ATR attachments	PDF, **DOC, DOCX**, JPG, PNG	20 MB
Complaint evidence and complaint-ATR attachments	Images and PDF	20 MB
Penalty documents	Any type	20 MB
User signature	JPG, PNG only	**2 MB**
Vendor photograph and signature	Images	20 MB
Contractor logo	Images	20 MB
Unit sketch or plan	Any type	20 MB
Excel imports	`.xlsx`, `.xls`	20 MB

21.2 Which documents are required

No document upload is mandatory anywhere in SERVMS. Vendors can be onboarded, complaints registered, inspections filed, and penalties raised with no attachment. Certificate *numbers* are mandatory for vendor verification; the certificate *files* are not.

21.3 Uploading, viewing, replacing

01 Press **Upload** — or **Replace** where a document already exists — and choose a file.

02 The upload begins immediately. The button reads “Uploading…”.

03 Use **View** to preview: PDFs open in an inline frame, images render directly, other types offer “Open in new tab”.

04 Use **Download** to save the original file.

Replacing is the only way to change a vendor document — there is no delete. Inspection attachments *can* be deleted individually by anyone with Edit on Inspection Management.

21.4 Upload errors

MESSAGE	CAUSE	FIX
Only PDF, JPG, and PNG files are allowed	Wrong file type for an identity document	Convert the file, or scan to PDF
Only PDF, DOC, DOCX, JPG, and PNG files are allowed	Wrong type for an inspection attachment	Convert the file
Only JPG and PNG files are allowed for a signature	A PDF or other type was chosen for a signature	Export the signature as PNG
File is too large. Maximum size is 5MB.	Vendor document above the browser limit	Compress or re-scan at lower resolution
File is too large for field “…”	Above the 20 MB server limit	Compress the file
Unexpected file field “…”	Form and server disagree on the field name — a defect, not a user error	Report it with the exact message

> CAUTION
>
> Uploaded files are served from a public path. Anyone holding a document's address can open it **without signing in**. Addresses are not guessable, but they are also not protected — do not forward a document link to anyone who should not see the document itself.

SECTION 22

Error Messages and Troubleshooting

22.1 Sign-in and session

MESSAGE OR SYMPTOM	CAUSE	WHAT TO DO
User not found!	The username does not exist	Check spelling. Remember the field takes your *username*, not your Employee Number.
Invalid username or password	Wrong password	Retry. There is no lockout. If forgotten, ask an administrator for an assisted reset.
Session expired, please log in again	The 12-hour session ended	Sign in again. Unsaved form data is lost.
Invalid token	Corrupted or tampered session	Sign in again. If it recurs, clear browser data for the site.
Returned to the Dashboard when opening a page	Your role has no view permission for that module	Expected behaviour. Ask an administrator if you need access.
Signed out on every page load	`localStorage` blocked or private browsing	Use a normal window and allow site data.

22.2 Permission

MESSAGE	CAUSE	WHAT TO DO
You do not have permission to *<action> <module>*	Your role lacks that action	Ask a role administrator, or route the task to someone who holds it
You do not have permission to perform this action	An action restricted to named roles	See the override table in Section 6.4
Only Super Admin HQ can create or manage Admin-tier accounts	Creating or editing a Super Admin HQ, HQ Admin, or Divisional Admin account	Refer the request to Super Admin HQ
Record not found	The record does not exist, or is outside your division	Deliberately ambiguous. Confirm the division with a colleague who has wider scope.

22.3 Vendors and ID cards

MESSAGE	CAUSE	WHAT TO DO
Police verification number is required	Blank at onboarding or update	Obtain the number before creating the vendor
Medical fitness certificate number is required	Blank at onboarding or update	Obtain the number before creating the vendor
Aadhaar number must be exactly 12 digits	Wrong length	Enter 12 digits with no spaces
Station selection is required for this division	The division has stations configured	Choose a station
Platform unit stall selection is required for this division	Units exist for that station or division	Choose a unit, or create one first
Valid till date cannot be before the issue date	Dates reversed	Correct the order
Cannot use medical expiry — no valid-till date on file	Requesting a card against a verification with no expiry date	Complete the verification dates, or choose the other expiry driver
Only a designated Card Signing Authority can approve ID cards	Approving without the credential	Route to a signing authority
You can only approve ID cards for vendors in your own division	Divisional signing authority acting outside their division	Route to that division's signing authority
Cannot approve a card in "approved" state	The card is already issued	Use **Re-issue** to start a fresh request
No ID card request found for this vendor	Approving before a card was requested	Request the card first

22.4 Complaints and inspections

MESSAGE	CAUSE	WHAT TO DO
Complaint Type and Sub-Type are required	Classification incomplete	Choose a Type, then a Sub-Type
Portal Registration Number is required for CPGRAMS complaints	Source is CPGRAMS	Enter the portal number
RailMadad Reference Number is required	Source is RailMadad	Enter the reference number
Cannot submit an Action Taken Report while the complaint is "pending"	The complaint has not been assigned	Assign it to a unit first
Only the submitter can edit this Action Taken Report	Editing someone else's ATR	Ask the author, or send it back for a fresh report
Cannot edit an Action Taken Report once it is "sub_admin_reviewed"	The ATR has moved on	Ask the Admin to send it back
Cannot decide an Action Taken Report before Sub-admin review	Skipping the review step	Have a Sub Admin review it first
Cannot close a complaint that is "assigned"	Closing before a decision	Complete the ATR chain to Approved or Rejected
Only the inspector who created this inspection can submit it	Submitting someone else's inspection	Ask the author to submit
Cannot return an inspection that is "draft"	Returning before submission	Only Submitted inspections can be returned

22.5 Penalties

MESSAGE	CAUSE	WHAT TO DO
Reason for imposing penalty is required	Reason blank	Record the grounds
Amount must be a positive number	Zero or negative	Enter an amount above zero
Cannot approve a penalty in "approved" state	Already decided	No action needed

MESSAGE	CAUSE	WHAT TO DO
Only an approved penalty can be revoked	Revoking a pending or rejected penalty	Reject it instead if it is still pending
Recovery can only be tracked on an approved penalty	Recording recovery too early	Have the penalty approved first
Recovery status cannot move backward	Reducing the recovery state	Recovery only advances. Contact an administrator if a correction is genuinely needed.
Recovery amount must equal the full penalty amount to mark it as recovered	Marking Recovered on a part payment	Use *Partially Recovered* until the balance is received
Recovery amount is required when marking a penalty as partially recovered	Amount left at zero	Enter the amount received
Only a penalty marked “recovered” can be verified	Verifying too early	Wait for the Dealing Section to mark it fully recovered
This recovery entry has already been decided	Verifying twice	No action needed

22.6 Users and roles

MESSAGE	CAUSE	WHAT TO DO
Password must be at least 6 characters	Too short	Use a longer passphrase
Username must be 3–50 chars	Outside the range	Adjust the username
Only HQ/Divisional Admin or Sub Admin roles can be granted Card Signing Authority	Wrong role	Only those four roles qualify
Card Signing Authority requires a JS or SS designation grade	Wrong grade	Set the grade to JS or SS, if correct for that person
Authority Designation is required for a Card Signing Authority	Blank designation	Enter the wording to print on cards
Select a new division and/or role to request a transfer	Both left as “No change”	Choose at least one change
This request has already been approved	Deciding a request twice	No action needed
Unable to toggle status	Server refused, often an Admin-tier restriction	Refer to Super Admin HQ

22.7 Behaviour that looks like a fault but is not

SYMPTOM	EXPLANATION
The top-bar search does nothing	It is decorative. There is no global search. Use each module’s own search.
Forgot Password does nothing	Not implemented. Ask an administrator for an assisted reset.
“Reset to Default” does not restore original permissions	It discards unsaved changes only.
No edit button for a vendor or user	Correct — no edit screen exists for either.
Deactivated user can still sign in	Account status is not checked at sign-in. See Section 3.7.
Notification preferences change nothing	No email, SMS, or push channel exists. See Section 19.4.
Filtering audit logs by Login returns nothing	Sign-ins are not audited. See Section 20.4.
A licence-fee figure on the Dashboard does not match the list it opens	The destination has no licence-fee filter. See Section 4.4.
Export stops at 2,000 rows	Vendor and Penalty exports are capped. Use the Report Builder.

SECTION 23

Security Guidelines

23.1 Your password

- Choose a long passphrase. The six-character minimum is a floor, not a target — there is no complexity rule and no lockout to fall back on.
- Never reuse your SERVMS password on another system.
- Never share it. There is no legitimate reason for anyone, including an administrator, to ask for it — an administrator who needs to help you can reset it instead.
- Change it if you suspect it is known. Because there is no self-service change, this means asking for an assisted reset.
- Administrators: relay temporary passwords in person or by phone, never by email or chat.

23.2 Sessions

- Press **Logout** when you leave your desk. The session lasts 12 hours and does not time out on idle.
- Lock your workstation as well — the session lives in the browser and survives closing the tab.
- Never sign in on a shared or public machine. If you must, use a private window and sign out explicitly.

23.3 Accounts and access

- Never work under someone else's account. Every action is attributed to the signed-in user, so borrowing an account falsifies the audit trail.
- Grant the least permission the job needs. Approve/Reject and Export are the two most consequential.
- Review the user list periodically for accounts whose Last Login is “Never” or long past.
- **To remove access from a departing member of staff, have their password reset to a value they do not know.** Deactivating alone does not block sign-in.

23.4 Documents

- Upload only documents that belong on the record you are attaching them to.
- Treat every document address as public. Anyone with the link can open the file without signing in — never forward a link to someone who should not see the document.
- Download identity documents only when there is an operational need, and delete local copies afterwards.

23.5 ID cards and QR codes

- The QR on a printed card contains the vendor's **full Aadhaar number and home address in plain text**. Anyone who scans it obtains both.
- Card PDFs are the same — treat a downloaded card as an identity document.
- Never approve a card for a vendor whose verifications you have not checked. Your name and designation are printed on it and encoded in the QR.
- Card Signing Authority is a personal credential. Never let a colleague approve cards from your session.

23.6 Reporting a concern

Report a suspected compromise, an unexpected permission, or a record you should not be able to see to your division administrator immediately, and to the CRIS support desk. Include the exact wording of any message, the screen, and the time — the audit trail can then be matched against your report.

SECTION 24

Frequently Asked Questions

I have forgotten my password. How do I reset it myself?

You cannot. The Forgot Password link on the login screen is not connected to anything. Contact an administrator, who raises a reset request for a second administrator to approve; you are then given a temporary password (Section 7.4).

Why does my colleague see more menu items than I do?

The sidebar shows only modules your role can view. Different roles see different menus.

I typed my Employee Number and could not sign in.

The field is labelled “Employee ID / Username” but only the username works. Ask an administrator for your username — it is shown next to your Employee ID in User Management.

How do I correct a spelling mistake in a vendor's name?

You cannot through the interface — there is no edit-vendor screen. Only status, the two verifications, and unit or contractor transfers can be changed after onboarding. A name correction requires a database change through the CRIS support desk. Check Step 1 of the wizard carefully before submitting.

How do I change a user's name, email, or mobile number?

You cannot. There is no edit-user screen. Role and division can be changed through a Transfer request; nothing else can be changed on screen.

Why can I not delete anything?

Only Super Admin HQ holds Delete on any module. This is deliberate — records referenced by complaints, inspections, penalties, and the audit trail should be deactivated rather than erased. Use status changes and deactivation instead.

I set a user to Inactive but they can still sign in.

Correct — account status is not checked at sign-in. To reliably remove access, have their password reset to a value they do not know.

Why can I not approve an ID card even though I am an Admin?

Card approval needs the *Card Signing Authority* credential, which is separate from your role. It requires an HQ or Divisional Admin or Sub Admin role *and* a JS or SS designation grade, and it must be granted on the user record.

The vendor has no ID card option and I cannot request one.

Requesting requires Add on ID Card Management. If the request is refused with “no valid-till date on file”, complete the vendor's police or medical verification dates first — the card's expiry is copied from one of them.

What happens to an existing card if I re-issue?

It returns to Pending Approval and the previous approval is cleared. The vendor has no valid card until a signing authority approves again. Do not re-issue unless a fresh card is genuinely needed.

Someone scanned a card and the page said NOT ISSUED.

The card exists but is not in the Approved state — it is pending, was rejected, or has been re-issued and is awaiting approval. Check the card in ID Card / QR Management.

Can vendors or contractors log in?

No. SERVMS is staff-only. The only page a non-staff member can reach is the public ID card verification page.

Why does the Dashboard show a figure the list does not reproduce?

The three licence-fee sub-groups link to a screen with no licence-fee filter, so the list is division-scoped only. Trust the Dashboard figure.

Why is my Excel export actually a CSV file?

Two buttons labelled Excel produce CSV: Vendor Management and Audit Logs. Both open correctly in Excel. Complaints, Inspections, and the Report Builder produce genuine `.xlsx` workbooks.

My export seems to be missing rows.

Vendor and Penalty exports are capped at 2,000 rows with no warning. Use the Report Builder for larger extracts.

Can I bulk-upload vendors or contractors?

No. Stations are the only master that can be imported, plus RailMadad complaints. Everything else is entered individually.

Will SERVMS email or text me when something needs attention?

No. Despite the preference switches in the Notification Centre, no email, SMS, or push notification is ever sent. Check the Notification Centre inside the application.

Why did my notification badge reset on a different computer?

Read state is stored in your browser, not on the server, so it does not follow you between machines or browsers.

Where are the Settings and Help pages?

Neither exists. Placeholder files are present in the codebase but are not reachable from anywhere in the application.

Can I see who viewed a record?

No. The audit trail records changes — create, update, delete, approve, reject, transfer — not reads. Sign-ins are not recorded either.

Why does “Record not found” appear for a record I know exists?

It is outside your division. The message is deliberately identical for “does not exist” and “exists but is not yours”, so scope cannot be probed. Ask a colleague with wider scope.

I changed a role's permissions but the affected user still sees the old menu.

Module permissions refresh as the application is used, so the change should appear within moments. Role and division changes from a Transfer, however, require the user to sign out and in again.
