# Electrical Network Calculations in Random Walks in Random Environments

Jonathon Peterson

School of Mathematics University of Minnesota

February 4, 2008

Much of this talk is based on the book Random Walks and Electric **Networks** by Peter G. Doyle and J. Laurie Snell.

Free download available at

http://arxiv.org/abs/math/0001057

Some of the graphics in this talk are also from this book.

## Outline

- Markov Chains
- 2 Electrical Networks and Reversible Markov Chains
- Probability Calculations → Electrical Calculations
- Simple Random Walks
- Random Walks in Random Environments

## Markov Chains

## **Markov chain:** a random process $X_n$ with short term memory.

Movement governed by transition probabilities:

$$P(X_{n+1}=y|X_n=x)=p_{x,y}$$

#### **Example:**



$$p_{0,0} = 1$$
 $p_{i,i+1} = p_{i,i-1} = 1/2$  if  $i = 1, 2, 3$ , or  $4$ 
 $p_{5,5} = 1$ 

## **Markov Chains**

**Markov chain:** a random process  $X_n$  with short term memory.

Movement governed by transition probabilities:

$$P(X_{n+1}=y|X_n=x)=p_{x,y}$$

Example:



$$p_{0,0} = 1$$
 $p_{i,i+1} = p_{i,i-1} = 1/2$  if  $i = 1, 2, 3$ , or 4
 $p_{5,5} = 1$ 


## **Markov Chains**

**Markov chain:** a random process  $X_n$  with short term memory.

Movement governed by transition probabilities:

$$P(X_{n+1}=y|X_n=x)=p_{x,y}$$


#### **Example:**



$$p_{0,0} = 1$$
 $p_{i,i+1} = p_{i,i-1} = 1/2$  if  $i = 1, 2, 3$ , or 4
 $p_{5,5} = 1$ 


## Examples

- **Population models:**  $X_n = \text{size of population on day } n$ .
- Stock market:  $X_n$  = price of stock on day n.
- **Spread of disease:**  $X_n$  = subset of population infected on day n.




## **Examples**

- **Population models:**  $X_n = \text{size of population on day } n$ .
- Stock market:  $X_n$  = price of stock on day n.
- Spread of disease:  $X_n$  = subset of population infected on day n.



## **Examples**

- **Population models:**  $X_n = \text{size of population on day } n$ .
- Stock market:  $X_n$  = price of stock on day n.
- **Spread of disease:**  $X_n$  = subset of population infected on day n.




#### **Electrical Networks**


 $R_{x,y}$  resistance of the edge from x to y.

 $C_{x,y} = \frac{1}{R_{x,y}}$  conductance of the edge from x to y.


 $C_x = \sum_v C_{x,y}$ . Total conductance at x.



Given an electrical network, let  $p_{x,y} = \frac{C_{x,y}}{C_{x,y}}$ .




Given an electrical network, let  $p_{x,y} = \frac{C_{x,y}}{C_{x}}$ .



**Example:**  $p_{b,c} = 1/3$  and  $p_{b,d} = 2/3$ .

Given an electrical network, let  $p_{x,y} = \frac{C_{x,y}}{C_x}$ .




**Example:**  $p_{b,c} = 1/3$  and  $p_{b,d} = 2/3$ .

These Markov chains are called reversible Markov chains.

When is a Markov chain reversible?



Given an electrical network, let  $p_{x,y} = \frac{C_{x,y}}{C_{x,y}}$ .



**Example:**  $p_{b,c} = 1/3$  and  $p_{b,d} = 2/3$ .

These Markov chains are called reversible Markov chains. When is a Markov chain reversible?

**Hitting times:**  $T_y := \inf\{n \ge 0 : X_n = y\}.$ 

We want to calculate hitting probabilities:

$$h(x) := P(T_a < T_b | X_0 = x) = P^x(T_a < T_b).$$

Obviously h(a) = 1 and h(b) = 0. For  $x \neq a, b$ 

$$h(x) = \sum_{y} p_{x,y} P^{y} (T_{a} < T_{b}) = \sum_{y} p_{x,y} h(y)$$

h(x) is a harmonic function.



**Hitting times:**  $T_v := \inf\{n \ge 0 : X_n = y\}.$ 

We want to calculate **hitting probabilities**:

$$h(x) := P(T_a < T_b | X_0 = x) = P^x(T_a < T_b).$$

Obviously h(a) = 1 and h(b) = 0.

$$h(x) = \sum_{y} \rho_{x,y} P^{y} (T_{a} < T_{b}) = \sum_{y} \rho_{x,y} h(y)$$



**Hitting times:**  $T_y := \inf\{n \ge 0 : X_n = y\}.$ 

We want to calculate hitting probabilities:

$$h(x) := P(T_a < T_b | X_0 = x) = P^x(T_a < T_b).$$

Obviously h(a) = 1 and h(b) = 0. For  $x \neq a, b$ 

$$h(x) = \sum_{y} p_{x,y} P^{y} (T_{a} < T_{b}) = \sum_{y} p_{x,y} h(y)$$

h(x) is a harmonic function.



**Hitting times:**  $T_y := \inf\{n \ge 0 : X_n = y\}.$ 


We want to calculate hitting probabilities:

$$h(x) := P(T_a < T_b | X_0 = x) = P^x(T_a < T_b).$$

Obviously h(a) = 1 and h(b) = 0. For  $x \neq a, b$ 

$$h(x) = \sum_{y} p_{x,y} P^{y} (T_{a} < T_{b}) = \sum_{y} p_{x,y} h(y)$$

h(x) is a harmonic function.



Graph G with edge weights  $p_{x,y}$ . Subset of vertices B called the **boundary**. h(x) is (G, B, p)-harmonic if

$$h(x) = \sum_{y} p_{x,y} h(y)$$
 for all  $x \notin B$ .

#### Theorem (Maximum (Minimum) Principle

If h(x) is (G, B, p)-harmonic, then h(x) takes on its maximum (and minimum) values on the boundary.

Graph G with edge weights  $p_{x,v}$ . Subset of vertices B called the **boundary**. h(x) is (G, B, p)-harmonic if

$$h(x) = \sum_{y} p_{x,y} h(y)$$
 for all  $x \notin B$ .

#### Theorem (Maximum (Minimum) Principle)

If h(x) is (G, B, p)-harmonic, then h(x) takes on its maximum (and minimum) values on the boundary.

An easy consequence of the Maximum Principle is:

#### Theorem (Uniqueness Principle)

If h(x) and v(x) are both (G, B, p)-harmonic functions with h(x) = v(x) for all boundary points  $x \in B$ , then v(x) = u(x) for all x.

#### Proof.

$$u(x) = h(x) - v(x)$$
 is also  $(G, B, p)$ -harmonic.

$$u(x) = 0$$
 for all  $x \in B$ .

By the Maximum (and minimum) principle, u(x) = 0 for all x.

An easy consequence of the Maximum Principle is:

#### Theorem (Uniqueness Principle)

If h(x) and v(x) are both (G, B, p)-harmonic functions with h(x) = v(x) for all boundary points  $x \in B$ , then v(x) = u(x) for all x.

#### Proof.

$$u(x) = h(x) - v(x)$$
 is also  $(G, B, p)$ -harmonic.

u(x) = 0 for all  $x \in B$ 

By the Maximum (and minimum) principle, u(x) = 0 for all x

An easy consequence of the Maximum Principle is:

#### Theorem (Uniqueness Principle)

If h(x) and v(x) are both (G, B, p)-harmonic functions with h(x) = v(x) for all boundary points  $x \in B$ , then v(x) = u(x) for all x.

#### Proof.

$$u(x) = h(x) - v(x)$$
 is also  $(G, B, p)$ -harmonic.

u(x) = 0 for all  $x \in B$ .

By the Maximum (and minimum) principle, u(x) = 0 for all x.

An easy consequence of the Maximum Principle is:

#### Theorem (Uniqueness Principle)

If h(x) and v(x) are both (G, B, p)-harmonic functions with h(x) = v(x) for all boundary points  $x \in B$ , then v(x) = u(x) for all x.

#### Proof.

$$u(x) = h(x) - v(x)$$
 is also  $(G, B, p)$ -harmonic.

u(x) = 0 for all  $x \in B$ .

By the Maximum (and minimum) principle, u(x) = 0 for all x.



An easy consequence of the Maximum Principle is:

#### Theorem (Uniqueness Principle)

If h(x) and v(x) are both (G, B, p)-harmonic functions with h(x) = v(x) for all boundary points  $x \in B$ , then v(x) = u(x) for all x.

#### Proof.


$$u(x) = h(x) - v(x)$$
 is also  $(G, B, p)$ -harmonic.

u(x) = 0 for all  $x \in B$ .

By the Maximum (and minimum) principle, u(x) = 0 for all x.




Connect a 1V battery to nodes a and b.



 $i_{X,V}$  is the current from x to y. v(x) is the voltage at node x. v(a) = 1 and v(b) = 0.

**Kirchoff's Current Law:**  $\sum_{y} i_{x,y} = 0$ , for  $x \neq a, b$ .

Connect a 1V battery to nodes a and b.




 $i_{X,V}$  is the current from x to y.

v(x) is the voltage at node x. v(a) = 1 and v(b) = 0.

**Ohm's Law:**  $i_{x,y} = (v(x) - v(y))C_{x,y}$ .

**Kirchoff's Current Law:**  $\sum_{y} i_{x,y} = 0$ , for  $x \neq a, b$ .

Connect a 1V battery to nodes a and b.



 $i_{X,V}$  is the current from x to y.

v(x) is the voltage at node x. v(a) = 1 and v(b) = 0.

**Ohm's Law:**  $i_{x,y} = (v(x) - v(y))C_{x,y}$ .

**Kirchoff's Current Law:**  $\sum_{y} i_{x,y} = 0$ , for  $x \neq a, b$ .

For  $x \notin \{a, b\}$ ,

$$0 = \sum_{y} i_{x,y}$$
 (Kirchoff's Law)  

$$= \sum_{y} (v(x) - v(y))C_{x,y}$$
 (Ohm's Law)  

$$= v(x)C_{x} - \sum_{y} v(y)C_{x,y}.$$

$$v(x) = \sum_{y} \frac{C_{x,y}}{C_x} v(y), \quad \forall x \notin \{a,b\},\$$



For  $x \notin \{a, b\}$ ,

$$0 = \sum_{y} i_{x,y}$$
 (Kirchoff's Law)  

$$= \sum_{y} (v(x) - v(y))C_{x,y}$$
 (Ohm's Law)  

$$= v(x)C_{x} - \sum_{y} v(y)C_{x,y}.$$

Therefore

$$v(x) = \sum_{y} \frac{C_{x,y}}{C_x} v(y), \quad \forall x \notin \{a,b\},\$$


and so voltage is a harmonic function.




# Hitting Probabilities and Voltage

For a Markov chain with transition probabilities  $p_{x,y} = \frac{C_{x,y}}{C_x}$ 

$$h(x) = P^{x}(T_{a} < T_{b}) = v(x).$$



## Example: Hitting Probabilities on an Interval



*i* is the total current flowing through the circuit.

 $R(x \leftrightarrow y)$  is the **effective resistance** between x and y.

 $C(x \leftrightarrow y) = \frac{1}{R(x \leftrightarrow y)}$  is the **effective conductance** between x and y.


By Ohm's Law: 
$$v(x) = v(x) - v(b) = iR(x \leftrightarrow b)$$
.

Since v(a) = 1 this gives  $i = \frac{1}{B(a \mapsto b)}$ , and therefore

$$P^{x}(T_{a} < T_{b}) = v(x) = \frac{R(x \leftrightarrow b)}{R(a \leftrightarrow b)}$$



## Example: Hitting Probabilities on an Interval



*i* is the total current flowing through the circuit.

 $R(x \leftrightarrow y)$  is the **effective resistance** between x and y.

$$C(x \leftrightarrow y) = \frac{1}{R(x \leftrightarrow y)}$$
 is the **effective conductance** between  $x$  and  $y$ .

By Ohm's Law: 
$$v(x) = v(x) - v(b) = iR(x \leftrightarrow b)$$
.

Since v(a) = 1 this gives  $i = \frac{1}{R(a \mapsto b)}$ , and therefore

$$P^{x}(T_{a} < T_{b}) = v(x) = \frac{R(x \leftrightarrow b)}{R(a \leftrightarrow b)}$$

# Simple Symmetric Random Walk

$$p_{i,i-1} = p_{i,i+1} = \frac{1}{2}$$


1 Ohm resistors at every edge.



$$P^0(T_r < T_{-\ell}) = \frac{R(0 \leftrightarrow -\ell)}{R(r \leftrightarrow -\ell)} = \frac{\ell}{r + \ell}.$$

$$P^{0}(T_{r}<\infty)=\lim_{\ell\to\infty}P^{0}(T_{r}< T_{-\ell})=\lim_{\ell\to\infty}\frac{\ell}{r+\ell}=1.$$

Simple symmetric random walk is recurrent



# Simple Symmetric Random Walk

$$p_{i,i-1} = p_{i,i+1} = \frac{1}{2}$$

1 Ohm resistors at every edge.



$$P^0(T_r < T_{-\ell}) = \frac{R(0 \leftrightarrow -\ell)}{R(r \leftrightarrow -\ell)} = \frac{\ell}{r + \ell}.$$

$$P^0(T_r < \infty) = \lim_{\ell \to \infty} P^0(T_r < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\ell}{r + \ell} = 1.$$

Simple symmetric random walk is recurrent.



# Simple Symmetric Random Walk

$$p_{i,i-1} = p_{i,i+1} = \frac{1}{2}$$

1 Ohm resistors at every edge.



$$P^0(T_r < T_{-\ell}) = \frac{R(0 \leftrightarrow -\ell)}{R(r \leftrightarrow -\ell)} = \frac{\ell}{r+\ell}.$$

$$P^0(T_r < \infty) = \lim_{\ell \to \infty} P^0(T_r < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\ell}{r + \ell} = 1.$$

Simple symmetric random walk is recurrent.



$$p_{i,i-1} = p_{i,i+1} = \frac{1}{2}$$

1 Ohm resistors at every edge.



$$P^0(T_r < T_{-\ell}) = \frac{R(0 \leftrightarrow -\ell)}{R(r \leftrightarrow -\ell)} = \frac{\ell}{r+\ell}.$$


$$P^0(T_r < \infty) = \lim_{\ell \to \infty} P^0(T_r < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\ell}{r + \ell} = 1.$$

Simple symmetric random walk is recurrent.



Let  $\frac{1}{2} < \omega < 1$ .

$$p_{i,i+1} = \omega$$
 and  $p_{i,i-1} = 1 - \omega$ 



If 
$$R_{0,1} = 1$$
, then  $\omega = \frac{C_{1,2}}{1 + C_{1,2}}$ .

Thus 
$$C_{1,2}=rac{\omega}{1-\omega}$$
, or equivalently  $R_{1,2}=rac{1-\omega}{\omega}$ 

Define 
$$\rho := \frac{1-\omega}{\omega} < 1$$



Let  $\frac{1}{2} < \omega < 1$ .


$$p_{i,i+1} = \omega$$
 and  $p_{i,i-1} = 1 - \omega$ 




If 
$$R_{0,1} = 1$$
, then  $\omega = \frac{C_{1,2}}{1 + C_{1,2}}$ .

Thus 
$$C_{1,2} = \frac{\omega}{1-\omega}$$
, or equivalently  $R_{1,2} = \frac{1-\omega}{\omega}$ .

Define 
$$\rho := \frac{1-\omega}{\omega} < 1$$
.



Let 
$$\frac{1}{2} < \omega < 1$$
,  $\rho = \frac{1-\omega}{\omega} < 1$ .



Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \dots + \rho^{r-1} = \frac{1 - \rho^r}{1 - \rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.

Therefore 
$$R(r \leftrightarrow -\ell) = rac{
ho^{-\ell} - 
ho^r}{1-
ho}$$

$$P^{0}(T_{r} < \infty) = \lim_{\ell \to \infty} P^{0}(T_{r} < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^{r}} = 1$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_r) = \lim_{r \to \infty} \frac{1 - \rho^r}{\rho^{-\ell} - \rho^r} = \rho^{\ell} < 1$$

Let 
$$\frac{1}{2} < \omega < 1$$
,  $\rho = \frac{1-\omega}{\omega} < 1$ .

Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \dots + \rho^{r-1} = \frac{1-\rho^r}{1-\rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.

Therefore 
$$R(r \leftrightarrow -\ell) = \frac{\rho^{-\ell} - \rho^r}{1 - \rho}$$

$$P^{0}(T_{r} < \infty) = \lim_{\ell \to \infty} P^{0}(T_{r} < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^{r}} = 1$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_r) = \lim_{r \to \infty} \frac{1 - \rho^r}{\rho^{-\ell} - \rho^r} = \rho^{\ell} < 1$$

Let 
$$\frac{1}{2}<\omega<$$
 1,  $\rho=\frac{1-\omega}{\omega}<$  1.

Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \dots + \rho^{r-1} = \frac{1 - \rho^r}{1 - \rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.

Therefore 
$$R(r \leftrightarrow -\ell) = \frac{\rho^{-\ell} - \rho^r}{1 - \rho}$$
.

$$P^{0}(T_{r} < \infty) = \lim_{\ell \to \infty} P^{0}(T_{r} < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^{r}} = 1.$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_r) = \lim_{r \to \infty} \frac{1 - \rho^r}{\rho^{-\ell} - \rho^r} = \rho^{\ell} < 1$$

Let 
$$\frac{1}{2} < \omega < 1$$
,  $\rho = \frac{1-\omega}{\omega} < 1$ .

Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \cdots + \rho^{r-1} = \frac{1-\rho^r}{1-\rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.

Therefore 
$$R(r \leftrightarrow -\ell) = \frac{\rho^{-\ell} - \rho^r}{1 - \rho}$$
.

$$P^0(T_r < \infty) = \lim_{\ell \to \infty} P^0(T_r < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^r} = 1.$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_r) = \lim_{r \to \infty} \frac{1 - \rho^r}{\rho^{-\ell} - \rho^r} = \rho^{\ell} < 1$$

Let 
$$\frac{1}{2} < \omega < 1$$
,  $\rho = \frac{1-\omega}{\omega} < 1$ .

Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \dots + \rho^{r-1} = \frac{1-\rho^r}{1-\rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.


Therefore 
$$R(r \leftrightarrow -\ell) = \frac{\rho^{-\ell} - \rho^r}{1 - \rho}$$
.

$$P^{0}(T_{r} < \infty) = \lim_{\ell \to \infty} P^{0}(T_{r} < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^{r}} = 1.$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_{r}) = \lim_{r \to \infty} \frac{1 - \rho^{r}}{\rho^{-\ell} - \rho^{r}} = \rho^{\ell} < 1.$$

←□ → ←□ → ←□ → □ → ○ へ ○

Let 
$$\frac{1}{2} < \omega < 1$$
,  $\rho = \frac{1-\omega}{\omega} < 1$ .



Then 
$$R(0 \leftrightarrow r) = 1 + \rho + \dots + \rho^{r-1} = \frac{1 - \rho^r}{1 - \rho}$$
.

and 
$$R(0 \leftrightarrow -\ell) = \rho^{-1} + \rho^{-2} + \dots + \rho^{-\ell} = \frac{\rho^{-\ell} - 1}{1 - \rho}$$
.

Therefore 
$$R(r \leftrightarrow -\ell) = \frac{\rho^{-\ell} - \rho^r}{1 - \rho}$$
.

$$P^{0}(T_{r} < \infty) = \lim_{\ell \to \infty} P^{0}(T_{r} < T_{-\ell}) = \lim_{\ell \to \infty} \frac{\rho^{-\ell} - 1}{\rho^{-\ell} - \rho^{r}} = 1.$$

$$P^{0}(T_{-\ell} < \infty) = \lim_{r \to \infty} P^{0}(T_{-\ell} < T_{r}) = \lim_{r \to \infty} \frac{1 - \rho^{r}}{\rho^{-\ell} - \rho^{r}} = \rho^{\ell} < 1.$$

Simple asymmetric random walk is **transient**. 4 D > 4 D > 4 E > 4 E > E 990

### First pick **Random Environment**: i.i.d. sequence $\omega_x$ , $x \in \mathbb{Z}$ .

- When 
$$P^0(X_1=1) > \frac{1}{2}$$
?

18 / 23

First pick **Random Environment**: i.i.d. sequence  $\omega_x$ ,  $x \in \mathbb{Z}$ .

Then run markov chain with  $p_{x,x+1} = \omega_x$  and  $p_{x,x-1} = 1 - \omega_x$ 





First pick **Random Environment**: i.i.d. sequence  $\omega_X$ ,  $X \in \mathbb{Z}$ .

Then run markov chain with  $p_{x,x+1} = \omega_x$  and  $p_{x,x-1} = 1 - \omega_x$ 

**Question:** When is a RWRE transient to  $+\infty$ ?

- When 
$$P^0(X_1=1) > \frac{1}{2}$$
?

First pick **Random Environment**: i.i.d. sequence  $\omega_X$ ,  $X \in \mathbb{Z}$ .

Then run markov chain with  $p_{x,x+1} = \omega_x$  and  $p_{x,x-1} = 1 - \omega_x$ 

**Question:** When is a RWRE transient to  $+\infty$ ?

- When 
$$P^0(X_1=1) > \frac{1}{2}$$
?


### Electrical Network for RWRE Model

#### Given a random environment, define

$$\rho_{\mathsf{X}} := \frac{1 - \omega_{\mathsf{X}}}{\omega_{\mathsf{X}}}.$$

$$R(0 \leftrightarrow +\infty) = 1 + \rho_1 + \rho_1 \rho_2 + \rho_1 \rho_2 \rho_3 + \cdots$$
$$R(0 \leftrightarrow -\infty) = \rho_0^{-1} + (\rho_0 \rho_{-1})^{-1} + (\rho_0 \rho_{-1} \rho_{-2})^{-1} + \cdots$$

**Guess:** RWRE is transient to  $+\infty$  if  $E(\rho) < 1$ .



### Electrical Network for RWRE Model

#### Given a random environment, define

$$\rho_{\mathsf{X}} := \frac{1 - \omega_{\mathsf{X}}}{\omega_{\mathsf{X}}}.$$

$$R(0 \leftrightarrow +\infty) = 1 + \rho_1 + \rho_1 \rho_2 + \rho_1 \rho_2 \rho_3 + \cdots$$

$$R(0 \leftrightarrow -\infty) = \rho_0^{-1} + (\rho_0 \rho_{-1})^{-1} + (\rho_0 \rho_{-1} \rho_{-2})^{-1} + \cdots$$

**Guess:** RWRE is transient to  $+\infty$  if  $E(\rho) < 1$ 



#### Electrical Network for RWRE Model

#### Given a random environment, define

$$\rho_X := \frac{1 - \omega_X}{\omega_X}.$$

$$R(0 \leftrightarrow +\infty) = 1 + \rho_1 + \rho_1 \rho_2 + \rho_1 \rho_2 \rho_3 + \cdots$$
$$R(0 \leftrightarrow -\infty) = \rho_0^{-1} + (\rho_0 \rho_{-1})^{-1} + (\rho_0 \rho_{-1} \rho_{-2})^{-1} + \cdots$$

**Guess:** RWRE is transient to  $+\infty$  if  $E(\rho) < 1$ .



### Transience/Recurrence Criteria for RWRE

Want 
$$R(0 \leftrightarrow +\infty) = 1 + \rho_1 + \rho_1 \rho_2 + \rho_1 \rho_2 \rho_3 + \cdots < \infty$$
.

$$\rho_1 \rho_2 \cdots \rho_n = e^{\log(\rho_1 \rho_2 \cdots \rho_n)}$$

$$= e^{\sum_{i=1}^n \log \rho_i}$$

$$= e^{\left(\frac{1}{n} \sum_{i=1}^n \log \rho_i\right) n}$$

$$\approx e^{E(\log \rho_0) n} \qquad \text{(Law of Large Numbers)}$$

#### Theorem (Solomon '75)

- (a)  $E_P(\log \rho_0) < 0 \Rightarrow \lim_{n \to \infty} X_n = +\infty$
- (b)  $E_P(\log \rho_0) > 0 \Rightarrow \lim_{n \to \infty} X_n = -\infty$
- (c)  $E_P(\log \rho_0) = 0 \Rightarrow X_p$  is recurrent

### Transience/Recurrence Criteria for RWRE

Want 
$$R(0 \leftrightarrow +\infty) = 1 + \rho_1 + \rho_1 \rho_2 + \rho_1 \rho_2 \rho_3 + \cdots < \infty$$
.

$$\rho_1 \rho_2 \cdots \rho_n = e^{\log(\rho_1 \rho_2 \cdots \rho_n)} 
= e^{\sum_{i=1}^n \log \rho_i} 
= e^{\left(\frac{1}{n} \sum_{i=1}^n \log \rho_i\right) n} 
\approx e^{E(\log \rho_0) n}$$

(Law of Large Numbers)

#### Theorem (Solomon '75)

- (a)  $E_P(\log \rho_0) < 0 \Rightarrow \lim_{n \to \infty} X_n = +\infty$
- (b)  $E_P(\log \rho_0) > 0 \Rightarrow \lim_{n \to \infty} X_n = -\infty$
- (c)  $E_P(\log \rho_0) = 0 \Rightarrow X_n$  is recurrent

### Example:

#### Suppose the distribution on environments is:

$$P\left(\omega_0 = \frac{3}{4}\right) = .39$$
 and  $P\left(\omega_0 = \frac{1}{3}\right) = .61$ 

$$P(X_1 = 1) = .39\frac{3}{4} + .61\frac{1}{3} = \frac{119}{240} < \frac{1}{2}$$

$$E\rho_0 = .39\left(\frac{1-3/4}{3/4}\right) + .61\left(\frac{1-1/3}{1/3}\right) = \frac{27}{20} > 1$$

$$E_P(\log \rho_0) = -0.00563901 < 0$$



### Example:

Suppose the distribution on environments is:

$$P\left(\omega_0 = \frac{3}{4}\right) = .39$$
 and  $P\left(\omega_0 = \frac{1}{3}\right) = .61$ 


Then

$$P(X_1 = 1) = .39\frac{3}{4} + .61\frac{1}{3} = \frac{119}{240} < \frac{1}{2},$$

and

$$E\rho_0 = .39\left(\frac{1-3/4}{3/4}\right) + .61\left(\frac{1-1/3}{1/3}\right) = \frac{27}{20} > 1.$$

$$E_P(\log \rho_0) = -0.00563901 < 0$$



### Example:

Suppose the distribution on environments is:

$$P\left(\omega_0 = \frac{3}{4}\right) = .39$$
 and  $P\left(\omega_0 = \frac{1}{3}\right) = .61$ 

Then

$$P(X_1 = 1) = .39\frac{3}{4} + .61\frac{1}{3} = \frac{119}{240} < \frac{1}{2},$$

and

$$E\rho_0 = .39\left(\frac{1-3/4}{3/4}\right) + .61\left(\frac{1-1/3}{1/3}\right) = \frac{27}{20} > 1.$$

However,

$$E_P(\log \rho_0) = -0.00563901 < 0$$

and so the RWRE is transient to  $+\infty$ .



# Other Strange Behavior of RWRE

#### Transience with zero speed:

Can have 
$$\lim_{n\to\infty} X_n = +\infty$$
 but  $\lim_{n\to\infty} \frac{X_n}{n} = 0$ .

Non-Gaussian Limiting Distributions:


For simple random walk, always have

$$\lim_{n\to\infty} P\left(\frac{X_n - nv}{\sigma\sqrt{n}} \le X\right) = \Phi(X) = \int_{-\infty}^X \frac{1}{\sqrt{2\pi}} e^{-t^2/2} dt$$

For RWRE, can have examples where

$$\lim_{n\to\infty} P\left(\frac{X_n - nv}{n^{1/s}} \le x\right) = F_s(x).$$

where  $F_s$  is a totally asymmetric stable distribution of index  $s \in (1,2)$ .



## Other Strange Behavior of RWRE

#### Transience with zero speed:

Can have  $\lim_{n\to\infty} X_n = +\infty$  but  $\lim_{n\to\infty} \frac{X_n}{n} = 0$ .

#### Non-Gaussian Limiting Distributions:

For simple random walk, always have

$$\lim_{n\to\infty} P\left(\frac{X_n - nv}{\sigma\sqrt{n}} \le x\right) = \Phi(x) = \int_{-\infty}^x \frac{1}{\sqrt{2\pi}} e^{-t^2/2} dt$$

For RWRE, can have examples where

$$\lim_{n\to\infty}P\left(\frac{X_n-nv}{n^{1/s}}\leq x\right)=F_s(x),$$

where  $F_s$  is a totally asymmetric stable distribution of index  $s \in (1,2)$ .



### References

1. Peter G. Doyle and J. Laurie Snell, *Random walks and electric networks*. Carus Mathematical Monographs, 22. Mathematical Association of America, Washington DC, 1984

Free download available at http://arxiv.org/abs/math/0001057

**2.** O. Zeitouni, Random walks in random environment in *Lecture Notes in Mathematics* **1837**, Springer, Berlin (2004).