

703308 VO High-Performance Computing WS2021/2022 Measuring and Reporting Data

Philipp Gschwandtner

Overview

- what and how to measure
 - time
 - time-dependent (speedup, efficiency, ...)
 - **FLOPS**
- use measurements to drive optimizations
 - Amdahl's law

how to report measurements

Motivation: Optimization

- difficult to optimize without measuring
 - measurements are crucial for everything in computer science
 - How do you know whether program performance improved or not?
- difficult to measure without knowing what is measured and how
 - know your metrics!
 - performance, time, efficiency, memory footprint, energy, FLOPs, cache misses, ...
- tons of research on this topic...

Time-Related Metrics


Time

wall time

- time measured by looking at the wall clock
- disregards degree of parallelism
- the default when talking "time"

cpu time

- wall time for each rank
- cumulative over all ranks, varies with degree of parallelism
- the default when talking "costs"



Time is Parallel too

- synchronizing clocks over a large-scale system is very difficult
 - e.g. TSC: in-core **T**ime**S**tamp **C**ounter, 1 clock cycle tick rate (< 1 ns)
 - compare to network latency: 100–1000 ns, best case
 - note: CPU clock frequency scaling (DVFS) today no longer an issue
- hard to compare time measurements between processes
 - no issue if moderate accuracy and granularity requirements
 - otherwise check synchronization first (e.g. MPI_WTIME_IS_GLOBAL)
- also: mind the timer granularity in general
 - e.g. don't measure time intervals of 1-2 milliseconds with a 1 millisecond granularity
 - good practice: at least 10x higher granularity than shortest interval to be measured

Speedup

speed increase of a parallel program over the sequential version

• speedup_p =
$$\frac{t_s}{t_p}$$

- ideal: $t_p = \frac{t_s}{p}$, hence speedup $_p = \frac{t_s}{\frac{t_s}{p}} = p$ (linear)
- super-linear speedup also possible
 - e.g. problem partitioning reduces memory footprint per processor
 - enables more efficient use of memory hierarchy (caches)


Absolute and Relative Speedup

- two kinds of speedup
 - \triangleright absolute: reference t_s is the fastest sequential version
 - \blacktriangleright relative: reference t_s is the fastest parallel version run sequentially
 - bad third option: reference is t_p , with p' < p (e.g. p' = 16 and p = 128)
 - always specify your reference!
- non-trivial problem: parallelism might entail algorithmic changes and/or overheads (e.g. communication)

Efficiency

- measure of parallelization overhead
 - value range given between 0 and 1 or as a percentage
- efficiency_p = $\frac{\text{speedup}_p}{p}$
- ideal: efficiency $_p = 1$ (= linear speedup)
- worst case: $\lim_{p\to\infty} \text{efficiency}_p = 0$

Example Data for Speedup and Efficiency




Amdahl's Law

- > one of the oldest (1967) and still most important laws in parallel programming
- defines (upper limit on) speedup when dividing a parallel program into a sequential part (r_s) and a parallel part (r_p) , with $r_s + r_p = 1$
- ightharpoonup idea: r_s cannot be improved through parallelism
 - hence it must somehow pose a limiting factor for any potential speedup
 - lacktriangleright all parallelism improvement must originate solely from improving r_p
- ▶ note: idealized perspective, does not include e.g. hardware bottlenecks

Amdahl's Law cont'd


- law: speedup_n = $\frac{1}{r_s + \frac{r_p}{n}} = \frac{1}{\alpha + \frac{1-\alpha}{n}}$
- severely limits potential speedup,
 even for infinite parallelism
- example: $\alpha = 0.2$ (=20 % sequential)
 - ideal speedup on 8 processors is 3.33
 - ideal speedup on ∞ processors is 5



Amdahl's Law: Efficiency

the same principle applies to parallel efficiency

- \blacktriangleright example: $\alpha = 0.2$ (=20 % sequential)
 - max. efficiency on 8 processors is 0.42
 - ▶ max. efficiency on ∞ processors?



Amdahl's Law: Implications


- first order of business: minimize $\alpha!$
 - change algorithm to reduce amount of sequential code
 - careful, changes reference for relative speedup
 - optimize sequential code as much as possible
- don't spend excessive effort on optimizing parallel portion
- consider a sensible maximum degree of parallelism
 - don't allocate 1024 processors when using 128 is equally fast
 - also consider other users, power consumption, cpu time budgets, ...!

Amdahl's Law: Shortcomings

- Noticed, that it assumes the amount of work to be fixed?
 - not realistic for many use cases, problem size often scales with machine size
 - some problems are solved in real-time (e.g. rendering) but at the highest problem size (e.g. image quality) possible
 - more resources (=processors) can indeed help here
- John Gustafson reevaluated this issue in 1988
 - → Gustafson's Law

Gustafson's Law cont'd

- Assume a sequential portion α and a parallel portion (1α)
- Assume that α is fixed or scales very slowly with the number of processors
- speedup_p = $\alpha + (1 \alpha) \times P$



Strong vs. Weak Scalability

- scalability is (sort-of) a description for speedup and efficiency
 - "program scales (linearly)" = program achieves linear speedup
 - "program does not scale" = program doesn't get any faster (maybe even slower)
- strong scalability
 - how the program scales with a fixed problem size
- weak scalability
 - how the program scales when keeping the problem size proportional
 - important: how to scale the problem in proportion?

Weak Scalability

- consider an application with a two-dimensional domain of size n x m (e.g. 2D heat stencil)
 - scale n, or m, or both?
 - scale timesteps?
- consider a 3D/4D/5D/... problem?
- consider a blackbox problem?

Additional Metrics

FLOPS

- floating point operations (FLOP/s: per second)
 - only operations with floating point semantics
 - does not count load/store/bitwise/...
- main measure for useful performance of software and hardware (work processed per time)
 - time not necessarily useful: can be wasted in waiting states...
- not applicable to every problem
 - consider integer-heavy problems (e.g. combinational logic, dynamic programming, ...)
 - also: memory-heavy, I/O-heavy, etc...

FLOPS cont'd

- ▶ What's the number of floating point instructions in x86 on the right?
 - 2 operations: mul, add
 - 1 instruction: fused multiply-add (FMA)
- Don't confuse operations and instructions
 - number of instructions is hardware- and compiler-dependent
 - know your hardware, compiler, and environment (e.g. compiler flags)
 - do not blindly trust hardware peak FLOPS

```
x86: vfmadd132sd xmm0, xmm2, xmm1
```

Common way of Counting FLOPS: Multiply + Add

```
D = A * B + C; // 2 Ops, 1 Ins
D = A + C; // 1 Op, 1 Ins
D = A * B ; // 1 Op, 1 Ins
D = A * A * B + C; // 3 Ops, 2 Ins
D = A * B + C * A + B // 4 Ops, 2 Ins
```

Measuring FLOPS

instrumentation and profiling

- perf, PAPI, etc.
- requires detailed knowledge of the source code, hardware, and compiler

modeling

- know your algorithm and implementation
- there are also tools to automatically build models, of varying quality...

```
FP_ARITH_INST_RETIRED.SCALAR_DOUBLE
FP_ARITH_INST_RETIRED.128B_PACKED_DOUBLE
FP_ARITH_INST_RETIRED.128B_PACKED_SINGLE
FP_ARITH_INST_RETIRED.256B_PACKED_DOUBLE
FP_ARITH_INST_RETIRED.256B_PACKED_SINGLE
FP_ARITH_INST_RETIRED.512B_PACKED_DOUBLE
FP_ARITH_INST_RETIRED.512B_PACKED_DOUBLE
FP_ARITH_INST_RETIRED.512B_PACKED_SINGLE
UOPS_EXECUTED.X87
```

(a few floating point counters available on Intel Ice Lake CPUs)

FLOPS: Rmax vs. Rpeak

- Rmax: achieved by software
 - high performance linpack (HPL) benchmark
 - linear algebra stress-testing
- Rpeak: achievable by hardware
 - product of: number of FP units per CPU, their FP instructions per cycle, clock frequency, and number of CPUs

Rank	System	Cores	Rmax (TFlop/s)	Rpeak (TFlop/s)	Power (kW)
1	Supercomputer Fugaku - Supercomputer Fugaku, A64FX 48C 2.2GHz, Tofu interconnect D, Fujitsu RIKEN Center for Computational Science Japan	7,630,848	442,010.0	537,212.0	29,899
2	Summit - IBM Power System AC922, IBM POWER9 22C 3.07GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM DOE/SC/Oak Ridge National Laboratory United States	2,414,592	148,600.0	200,794.9	10,096
3	Sierra - IBM Power System AC922, IBM POWER9 22C 3.1GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM / NVIDIA / Mellanox DOE/NNSA/LLNL United States	1,572,480	94,640.0	125,712.0	7,438
4	Sunway TaihuLight - Sunway MPP, Sunway SW26010 260C 1.45GHz, Sunway, NRCPC National Supercomputing Center in Wuxi China	10,649,600	93,014.6	125,435.9	15,371

Application Throughput

- FLOPS are not everything
- consider what the application does
 - lagrangian simulation (no grid, move particles around): particles/s
 - eulerian simulation (no particles, compute properties at grid points): cells/s
 - chemistry applications: molecules/s
 - business applications: stock prices/s
 - unknown application: elements/s, updates/s, queries/s, ...
- domain-specific metrics are often much more useful to users than highly technical metrics

Compute Bound vs. Memory Bound (vs. Communication Bound)

- what is the bottleneck of your code X on hardware Y
 - memory accesses
 - computational throughput
 - data transfer
 - ...

compute bound

no benefit in speeding up memory accesses, execution units are 100% busy


memory bound

no benefit in speeding up computation, memory link is 100% busy

"Roofline" Model

- visual performance model for intra-node optimization
 - illustrates performance potential of a given hardware architecture
 - illustrates how much of this potential is used by an application
 - indicates which optimizations to apply
- indicates whether one is compute bound or memory bound

"Roofline" Model cont'd



Driving Optimizations

- Roofline model says "memory bound"
 - check cache optimality of algorithm
 - check NUMA mapping/bindings
 - check software prefetching
- Roofline model says "compute bound"
 - check vectorization (SIMD)
 - check compiler optimizations
 - check software caching ("memoization")

Performance Counters

- originally added to CPUs for post-silicon functional debugging
 - nowadays re-purposed for performance debugging
- can be read with tools
 - command line: perf
 - library: PAPI
 - tons of additional performance tools out there...
- can be extremely useful if you know your hardware well
 - Intel: https://perfmon-events.intel.com/
 - ▶ AMD: https://developer.amd.com/resources/developer-guides-manuals/ ("PPR")

Performance Counters Example

```
[c703429@login.lcc2 ~]$ perf stat ./heat_stencil_1D_seq
28,826,239,136 cycles:u
                       # 2.471 GHz
35,220,856,783 instructions:u # 1.22 insn per cycle
6,711,849,029 branches:u # 575.356 M/sec
    1,295,209 branch-misses:u # 0.02% of all branches
        1,044 LLC-load-misses:u
           26 LLC-store-misses:u
   15,312,122 L1-dcache-load-misses:u
  476,440,489 L1-dcache-store-misses:u
```

Properly Reporting Data

How to Report Metrics? (Non-Exhaustive)

- How many repetitions of an experiment do I need to run?
 - A single run is enough, right?
 - Three runs is enough for averaging, right?
- Should I run on multiple systems?
 - Should their architecture differ?
- Should my experiments be reproducible?
 - What information is required to enable reproducibility?

- Do I show all collected data?
 - Do I select data, and if so, how?
 - Do I aggregate data, and if so, how?
 - Do I report absolute or relative values?
- Do I quantify the reliability of my data?
 - If so, how?
- ...

Experiment Repetitions

Report whether your problem is deterministic!

if deterministic

- single run sufficient (should be ideally exactly reproducible)
- Are performance measurements deterministic?

if non-deterministic

- multiple runs are required
- report statistical measures
 - arithmetic/geometric/harmonic means
 - confidence intervals
 - **...**

How Many Repetitions are Required?

use confidence interval (CI)

- interval around sample mean, e.g. $\bar{x} = 80$ [75; 85]
- e.g. a 95 % CI means there's a 95 % probability it contains the true mean

for normally distributed data

b directly compute the number of measurements required to satisfy error e

$$n = \left(\frac{s \times t\left(n - 1, \frac{\alpha}{2}\right)}{e\bar{x}}\right)^2$$

check https://en.wikipedia.org/wiki/Confidence interval#Basic steps for details on computing CI

for non-normally distributed data

- \triangleright re-compute CI every k experiments (choose k depending on experiment effort), stop when happy
- at least e.g. 5 runs to compute meaningful CI

Running on Multiple Systems

- depends on how high you aim
 - "I have shown in a proof-of-concept that this might work in some selected cases"
 vs.
 - "I have shown that this generally works in all cases"
- more hardware (or software!) coverage is always better
 - but trade-off between porting effort and benefits

Data Collection and Selection

- document your efforts and backup your data and documentation
- if reporting only a subset of data, clearly specify the reason and motivation
 - e.g. only 8 to 16 nodes; only 4, 9, 16, 25, and 36 nodes
 - e.g. only using half the cores per node
 - e.g. applications 1, 2, and 3 on hardware A and B, but data for 3 on B is missing
 - e.g. only measuring parts of an application

Data Aggregation

costs

- usually atomic units, linear relationship
- can directly aggregate using arithmetic mean
- e.g. execution time (seconds), memory footprint (megabytes), energy consumption (joule)

rates

- if able, aggregate costs first and then compute rate; otherwise use harmonic mean
- e.g. FLOP/s, MB/s, etc.

ratios

- if able, don't aggregate at all; if required, aggregate base data instead
- e.g. "A is 50 % higher than B"

Reproducibility

- publish all required information, but not more than that
 - source code
 - compiler, version, flags, libraries
 - hardware architecture (detail depends on use case)
 - external factors (e.g. other users, load of the system, room temperature, ...)
 - reference data to compare against
 - aggregation methods, if used
- note: doesn't mean you need to provide a VM or container...
 - But often you can!

Four Steps to Creating an Optimized Parallel Program

▶ 1. devise and implement the simplest, most straight-forward parallel solution that you can think of

▶ 2. measure the performance (or whatever metric you are interested in) to obtain a point of reference

▶ <u>3.</u> improve your program based on your measurements

▶ 4. while(!☺) { step2(); step3(); }

Sequential Equivalence

strong sequential equivalence

- bitwise identical results
- requires preserving the order of computations compared to sequential version
- potentially big impact on performance (associativity, collective communication patterns, ...)

weak sequential equivalence

- mathematically equivalent but not bitwise identical (IEEE 754 float arithmetic is neither associative, nor commutative)
- does not require preserving the order of computations

Always check your requirements!

If your algorithm doesn't require a specific order, why should its implementation?

Portability

functional portability

- program runs on different hardware and produces correct results
- hardware architecture, compiler, libraries, etc.
- usually not hard to achieve (mostly x86/ARM + GPUs)
- performance (also "non-functional") portability
 - program runs efficiently on different hardware and is considered "fast"
 - no exact definition, topic of ongoing research

Summary

- lots of metrics to choose from
 - classics are speedup and efficiency
- always consider Amdahl's law for everything you do
- measure before you optimize
 - > and when you optimize, do it data-driven and not based on hunches

Image Sources

Rmax/Rpeak: https://www.top500.org/lists/2021/06/