MASKINHALLEN · USER MANUAL · VERSION 2.0

TURBIN

WAVETABLE + PHASE-MOD SYNTH · RPM · CHORD MACHINE

The power plant of the hall: two wavetable chambers, a phase-mod hub, two filters that can scream, and around 320 sounds.



VST3 · AU · LV2 · STANDALONE
MACOS · WINDOWS · LINUX

MASKINHALLEN

CONTENTS

01 Your first minute

02 Install

03 Unlock with your key

04 MOTOR

05 RÖRELSE

06 EFFEKTER

07 TURBINEN: RPM and the chord machine

08 Presets, macros and SNURRA

09 Troubleshooting

01 YOUR FIRST MINUTE

1. Pick a category and a sound at the top, play, and turn the eight macros. Press **SNURRA** for a fresh sound.

THE WINDOW



02 INSTALL

Unzip the file for your system. You get a folder called **TURBIN**. Then run the installer for your system and restart your DAW (or rescan plug-ins). TURBIN shows up as an instrument.

MACOS

1. Double-click `TURBIN-macOS.zip` in Downloads.
2. Open Terminal and run:
   `bash ~/Downloads/TURBIN/installera.command`
3. Quit your DAW completely and start it again.

VST3, AU and a standalone app. macOS 11 or newer, Intel or Apple Silicon. The installer copies the plug-ins and removes macOS's block on downloaded plug-ins.

WINDOWS

1. Right-click `TURBIN-Windows.zip` and choose **Extract all**.
2. Open the `TURBIN` folder and right-click `installera.bat` → **Run as administrator**.
3. If Windows says "Windows protected your PC": **More info** → **Run anyway**.

VST3 (in C:\Program Files\Common Files\VST3) and a standalone .exe. 64-bit Windows 10 or 11.

LINUX

1. Unzip `TURBIN-Linux.zip`.
2. Run `bash ~/Downloads/TURBIN/installera-linux.sh`. It copies the plug-ins to `~/.vst3` and `~/.lv2`.
3. Rescan plug-ins in your DAW (Bitwig, Reaper, Ardour and others).

VST3 and LV2, 64-bit x86 Linux (built on Ubuntu 22.04).

> SWEDISH OR ENGLISH
>
> The machines have Swedish names on the panel. One click on `SV | EN` in the header switches labels, menus and tooltips to English. Your choice is remembered for every MASKINHALLEN machine.

03 UNLOCK WITH YOUR KEY

Your purchase comes with a licence key: four groups of four characters, like `XXXX-XXXX-XXXX-XXXX`. You find it in the Payhip email and on your receipt.

1. Open TURBIN. Until it is unlocked, the window shows **UNLOCK TURBIN**.
2. Paste the whole key in the field and press `UNLOCK`.

3 Done. You only need to do this once per computer: every MASKINHALLEN machine on the computer finds the key. A bundle key unlocks every machine.

The key is not case sensitive, and I/L and O/0 are treated as the same character, so a typo there does not matter. If it says the key does not work, check that the whole key was pasted. You can use your key on your own computers.

THE FREE DEMO

Every machine has a free demo with the same sound engine. Some presets and functions are locked, and the demo has its own name (TURBIN DEMO), so it can sit next to the full version. Buying the full version is what unlocks everything; install it and paste your key.

UPDATES

Updates are free for life. Download the new zip from your Payhip receipt link and run the installer again. Your projects and your key are kept.

04 MOTOR

- **KAMMARE A and B** (chambers): 24 built-in wavetables, each with 64 frames that blend into each other. POSITION scans the frames. VRID warps the phase: BÖJ (bend), SPEGEL (mirror), SYNK (hard sync) or KVANT (quantise). OKTAV, HALVTON and FIN tune; UNISON gives up to seven voices with DETUNE and STEREO spread.
- **NAV** (hub): a sine modulator at a ratio (KVOT) of the note, phase-modulating A and B. **B → A** lets chamber B phase-modulate chamber A.
- **BRUS**: noise with colour. **DRIV**: RÖR (tube), VIK (fold), KROSS (crush), LIKRIKT (rectify), per voice after the filters.
- **FILTER 1 and 2**: LP 12, LP 24, BP, HP, NOTCH, STEGE (four-pole ladder with saturated feedback), KAM (comb tuned to the cutoff) and FORMANT (the cutoff sweeps the vowels a-e-i-o-u). ENV 2 sets how much envelope 2 opens the filter; TANGENT is key tracking. Run them in SERIE or PARALLELL.
- **RÖSTER** (voices): POLY, MONO or LEGATO, GLID (glide), BÖJNING (pitch-bend range), POLY (voice count), NIVÅ and ANSLAG (velocity sensitivity). **AMP** is the volume envelope.

05 RÖRELSE

- **ENV 2 and ENV 3**: envelopes for the cords. ENV 3 can LOOP and becomes a shapeable slow modulator.
- **LFO 1 and 2**: seven shapes, free rate or in time with the song. With OMSTART each voice starts its own LFO at note-on; without it the LFO follows the song position and can also drive the effects.

- **STEGVERK** (step machine): 16 steps in time with the song. Drag to draw, right-click to zero. LÄNGD sets the length (odd lengths make polymeter), GLID smooths between steps.
- **SLADDAR** (cords): 16 slots, each a source, a destination and an amount from −100 to +100. Sources: ENV 2, ENV 3, LFO 1, LFO 2, STEGVERK, ANSLAG (velocity), TANGENT (key), MODHJUL, TRYCK (aftertouch), SLUMP (random per note), AMP-ENV and the eight MAKRO knobs.

06 EFFEKTER

CHORUS (two voices in quadrature), **DELAY** (in time, ping-pong, with filtering and tape saturation in the feedback), **REVERB** (eight-line room), **BREDD** (stereo width) and **MASTER**. A limiter keeps the output below −0.3 dBFS.

07 TURBINEN: RPM AND THE CHORD MACHINE

New in TURBIN 2. Both stay put when you pick another sound, so you can browse sounds with chords on.

- **VARVTAL** (RPM) spins up the whole synth with one knob: wavetable position, filter, hub FM, unison width, drive and a little noise rise together, while the level is held in check. It also sits at the far right of the macro row, so it is always within reach, and it is a source in the cords. At 0 the sound is exactly as before.
- **TRÖGHET** (inertia) is how long the turbine takes to spin up and down, from instant to about 8 seconds. The fan shows the real speed right now.
- **ACKORD** turns one key into a chord: MOLL 7, MOLL 9, DUB (the open minor chord of dub techno), MOLL 11, SUS 2, SUS 4, KVINT and DUR 7. AV is a normal synth.
- **RYTM**: HÅLL keeps the chord while you hold the key. STAB, DUB, PULS, EUKLID and TAKT hit the chord in time while the song plays.
- **VANDRA** (wander) moves the chord through a dark progression, one step every 1, 2, 4 or 8 bars.
- **SPRIDNING** opens the voicing and adds the root an octave below. **LIV** varies velocity and inversion. **SJÄLV** plays on by itself while the song runs, using the last note you played.

Try: pick a sound in the new **DUB** category, set ACKORD to DUB, RYTM to STAB and VANDRA to 4 TAKTER, and hold one key.

08 PRESETS, MACROS AND SNURRA

Around 320 sounds in 14 categories: BAS, SUB, SYRA (acid), LEAD, STAB, PAD, PLOCK (pluck), KLANG (bells and keys), ATMO, SEKVENS (step-driven), PERK (percussion), FX, RÖST (voice) and DUB (chord stabs and pads made for the chord machine). Every preset wires and names its eight macros. **SNURRA** (spin) starts from a random factory sound and turns what changes its character, within limits that always sound good. **SPARA** stores your sound in Music/Phunkshunz/TURBIN Presets; **EGNA** lists them.

09 TROUBLESHOOTING

TURBIN does not show up	Quit the DAW completely and start it again, or rescan plug-ins. On Mac, run the installer again: it removes macOS's quarantine on the plug-in. On Windows, check that `TURBIN.vst3` is in C:\Program Files\Common Files\VST3.
macOS says the plug-in is damaged	That is macOS's block on downloaded files. Run `bash ~/Downloads/TURBIN/installera.command` again.
Windows protected your PC	Click **More info** → **Run anyway**. The plug-ins are not signed with a paid certificate.
The key does not work	Paste the whole key, including the dashes. A key for one machine only unlocks that machine; a bundle key unlocks all.
No sound	Press play in the DAW: the machines follow the transport. Instruments go on an instrument track, effects on an audio track or bus.

Anything else? Ask through the store, and the person who built the machine answers.

MASKINHALLEN