Auto-Completion Support

Description	Keystroke	Function	Note			
Auto Completion			t for completing what you type in the buffer: this is called auto-completion.			
Help @ Customization Built-in completion	Emacs comes with a basic completion system, accessible via the (completion-at-point) command bound to C-M-i. Emacs 30 provides the completion-preview-mode which provides an easy-to-use in-buffer completion help.					
Show completion mode status	PEL supports the following external packages which provide pop-up menu completion:					
completion-at-pointtoggle completion-preview-	The <u>auto-complete</u> package activated when the <u>pel-use-auto-complete</u> customization variable is set to t.					
modePEL controlled completion	 The company-mode package activated when the pel-use-company customization variable is set to t. PEL supports both and prevents activation of both of them in the same buffer. 					
auto-completecompany-mode	You can activate both modes and dynamically select one over the other, globally or buffer by buffer.					
O Auto-completion Reference	More on abbreviation completion is available in the <u>Abbreviations</u> table. Both abbreviation completion and one auto-completion mechanism can be used at the same time (using different keys if any), in some case the abbreviation choices can also be available via auto-completion.					
Automatic activation of	More dynamic completion modes based on Eglot or LSP are supported by Emacs but not yet documented in PEL.					
completion modes in specified	To automatically activate one of these completion modes on PEL supported major-modes, add the completion mode function name to the list of minor modes user-option for that major mode:					
major modes with PEL:	 PEL identifies a user option named pel-MODE-activates-minor-modes where MODE is the name of the major mode. For example, add completion-preview-mode to pel-elisp-activates-minor-modes to automatically activate it in all Emacs Lisp buffers. 					
	• For these PEL supported modes, you can access the customization buffer quickly with the <f11><f2> key sequence.</f2></f11>					
Last updated on:						
Open this PDF file. See also: <u>ℤ Help/Info</u>	<f11> , <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the ∑ <u>Auto-Completion</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg useroption is set it's the other way around.			
Customize PEL auto-completion support. See also: <u>∑ Customize</u>	<f11> , <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Open the PEL customize group(s) for the current context: auto-completion support. Use this to open to change PEL user option variables the activate and control the various Apple script features such as the name of the narrator voice.			
Customize Emacs built-in auto-	Z£11\ Z£2\	(pel-customize-library	When a prefix argument (like C-u) opens the buffer inside another window. Customize Emacs auto completion group which includes: auto complete company hippid			
completion support See also: <u>▼ Customize</u>	<f11> , <f3></f3></f11>	&optional OTHER-WINDOW)	Customize Emacs auto-completion group which includes: auto-complete, company, hippie-expand. When prefix arg. (like C-u) opens the buffer inside another window.			
	Group belonging to files that have not yet been loaded are normally not accessible in Emacs and via the customize-group command. PEL, however, attempts to locate the file that defines a non-loaded customization group and will prompt you for loading the file if it finds it.					
Display Auto-completion status	<f11> , ?</f11>	(pel-completion-info &optional APPEND)	Print information about available auto-completion info in a *pel-autocomplete-info* help-mode buffer. Clear previous buffer content unless a prefix arg (like C-u) is used.			
od Du 11	Prints current state and	,	as buttons you can use to get more info and change their customized values.			
Provides quick access buttons to change customizable	Shows which one is enabled via customization and their current activation state.					
user-options.		Underlines links are buttons that open the customization buffer where you can change the customized value. Emacs built-in completion is provided by the completion-at-point command, described below.				
Emacs Built-in Completion Symbol Completion at point	'	(completion-at-point)	Perform completion on the text around point.			
See also: Xref	• C-M-i • <esc> <tab> • M-<tab></tab></tab></esc>	(completion-at-point)	The completion method is determined by 'completion-at-point-functions'. The tags-completion-at-point-function is used for Emacs Lisp code by default. It provides a list of possible values in the *Completions* buffer.			
⊌	C-M-i is also used for F	lyspell, which can be used to sp	ell check only moments and strings.			
Symbol Completion at point	<f6> ,</f6>	(complete-symbol ARG)	Perform completion of the text around point, using the method identified by the variable			
and language specific completion			 completion-at-point-functions, acting as the completion-at-point command above. With prefix argument, such as C-u, this does completion within the collection of symbols listed in the index of the manual for the language you are using. 			
Complete language specific symbol at point	<f6> .</f6>	(info-complete-symbol &optional MODE)	Perform completion of symbol at point using mode-specific language items. • For example, inside a Emacs-Lisp buffer it finds the Emacs-Lisp functions, variables names.			
Toggle Completion Preview mode Emacs >= 30	<f11> , p</f11>	(completion-preview-mode & optional ARG)	Toggle completion-preview-mode in current buffer. • Activate it with positive prefix argument, disable it with negative prefix argument.			
A minor mode that shows possible completion in a light face. Can be available while another completion	<f11> , P</f11>	(global-completion-preview- mode &optional ARG)	Toggle Completion-Preview mode in all buffers. • Activate it with positive prefix argument, disable it with negative prefix argument.			
major-mode is used.	<tab></tab>	Expand suggested completion in buffer. Type more characters to further refine the search.				
	M-i Open a *Completion* buffer listing all possible completion candidates.					
		Select others with M- <up> and M-<down>. Then chose with M-RET.</down></up>				
	M-n	Selects and show next completion candidate.				
DEL . II I	M-p	Selects and show previous con	<u> </u>			
PEL controlled completion activation	PEL dynamically activate either auto-complete-mode or company-mode for one or all buffers through commands accessible via the <f11> , prefix. •</f11>					
Explicitly List Completion Candidates with the currently	• <f11> , , • M-1</f11>	(pel-complete)	List completion candidates. There must be at least 1 character preceding point. • Force auto-completion of text at point, don't wait for timeout, using the currently active			
Use auto-complete or company-	auto-completion system (either auto-complete-mode or company-mode).					
mode, whichever that is currently active globally or in the buffer.	 If no auto completion system is active in the current buffer, the command issues an error. M-1 default binding is to downcase-word. PEL rebinds this key company-mode is activated via customization and company-mode is active. 					
	• d With PEL, the M-1 key is close to the M-/ key, bound to the command used for abbreviation expansions. It becomes easy to use either.					
Completion Menu keys	When an completion pop-up menu generated either by auto-complete or company-mode is shown, you can use the following keys for operating on that menu:					
Auto-completion Menu Operations						
Company-Mode Menu	M-n : next candidate (or <down> cursor) M-p : previous candidate (or <up> cursor)</up></down>					
Operations	M-1, M-2, M-3, etc: select candidate by line number <tab>: complete using 1 candidate (if 1 choice), using the prefix part among many candidates, or cycle through all candidates.</tab>					
See also: ∑ Scrolling						
	• C-? : Show candidate help in separate buffer					
	Show candidate help in separate buffer.					
		Esc <pgdown> : Scroll help buffer forward C-M-S-v : Scroll help buffer backward</pgdown>				
	• Esc <pg-up> : Scr</pg-up>	oll help buffer backward p completion				
	· c-y : 510	p compiedon				

<u>Description</u>	<u>Keystroke</u>	Function		Note		
auto-complete	Auto-Complete is one of the auto completion package for Emacs supported by PEL. Requires the auto-complete package that PEL supports if the pel-use-auto-complete customization variable is set to t. Once activated by customization with PEL you can then activate it globally and/or control whether it is available for the current buffer, using the following commands. The pel-init function will install Auto-Complete from the MELPA archive if it is not already present. You may want to use another version (such as the one from MELPA stable). Just install it before customizing to use it and executing pel-init. This is an early version of PEL. Future versions of PEL will integrate logic to support use of Auto-Complete for more programming languages and systems (like templating package). For now PEL only incorporates the basic configuration of Auto-Complete provided by its ac-config-default function. Auto-complete provides the following customizable variables (and several others): ac-use-quick-help: set to t to activate a quick pop-up help display that shows right beside the menu choice. ac-quick-help-delay: delay before the quick help pops up. Default is 1.5 seconds.					
	PEL provides access to the auto-complete commands via the commands below. When invoked through the <511> or M. 1, key (def.)					
	When invoked through the <f11> , , or M-1 key bindings in a buffer that is set for it, auto-complete pops a drop-down menu similar to the one shown here.</f11>			defun defvar defined tter: default rentl defsubst defmacro he lo defconst n sta defvar-local default-value DEFAULT-VALUE. al Va ;;		
Toggle Auto-Complete mode for current buffer	<f11> , a</f11>	(pel-auto-complete-mode &optional ARG)	Toggle Auto-Complete mode in current buffer. • With prefix ARG, enable buffers' Auto-Complete mode if ARG is positive, otherwise deactivate it. • Solves not allow activation if company-mode is active. • If Global Auto-Complete is on, you can turn it off for one buffer using this command. This command calls auto-complete-mode when appropriate.			
Toggle Global Auto-Complete mode	<f11> , A</f11>	(pel-global-auto-complete- mode &optional ARG)	Toggle Global Auto-Complete mode. • With prefix ARG, enable Global Auto-Complete mode if ARG is positive, otherwise deactivate it. • ⊌ Does not allow activation if company-mode is active. • ⊌ ☑ The global-auto-complete-mode variable is customizable. If you set its customized value to t, then pel-init will automatically activate it. You will still be able to turn it off later in an Emacs session using this command and without having to change the customization value. ■ This command calls global-auto-complete-mode when appropriate.			
company-mode	Company-Mode is the other auto completion package supported by PEL.					
	When invoked through the <f11> , , or M-1 key bindings in a buffer that is set for it, <pre>company-mode</pre> pops a drop-down menu similar to the one shown here. The menu identifies the type of target.</f11>		;	defuse-company customization variable is set to t. defused defused defused defused defused defadvice defadvice default-boundp default-file-modes default-font-height default-indent-new-line default-line-height		
Toggle Company mode for current buffer	<f11> , c</f11>	(pel-company-mode &optional ARG)	Toggle Company Mode m • With prefix ARG, enable it.	node in current buffer. e buffers' Company Mode if ARG is positive, otherwise de-activate		
This command calls companymode when appropriate.	 Does not allow activation if auto-complete-mode is active. If Global Company Mode is on, you can turn it off for one buffer using this command. "complete anything"; is an in-buffer completion framework. Completion starts automatically, depending on the values 'company-idle-delay' and 'company-minimum-prefix-length'. Completion can be controlled with the commands: 'company-complete-common', 'company-complete-selection', 'company-complete', 'company-select-next', 'company-select-previous'. If these commands are called before 'company-idle-delay', completion will also start. Completions can be searched with 'company-search-candidates' or 'company-filter-candidates'. These can be used while completion is inactive, as well. The completion data is retrieved using 'company-backends' and displayed using 'company-frontends'. If you want to start a specific backend, call it interactively or use 'company-begin-backend'. 					
Toggle Global Company mode This command calls global-company-mode when appropriate.	<f11> , C</f11>	(pel-global-company-mode &optional ARG)	 Toggle Global Company mode. With prefix ARG, enable Global Company mode if ARG is positive, otherwise de-activate it. ✓ Does not allow activation if auto-complete-mode is active. ✓ Ithe global-company-mode variable is customizable. If you set its customized value to t, then pel-init will automatically activate it. You will still be able to turn it off later in an Emacs session using this command and without having to change the customization value. 			

Auto-completion — References

Document	Note		
Basic Auto Completion	GNU Emacs Manual - Completion for Symbol Names		
Auto Completion with Auto-Complete			
Auto Complete @ MELPA	You can get auto-complete from MELPA. An interesting point of this page lists the other packages that need auto-complete. There's over 45 packages that use it for various programming languages and environments.		
Auto Complete @ GitHub	Auto complete source code		
Auto Complete Manual @ Github	Covers installation, check, features, concepts, configuration, advanced usage. Reading required for users.		
Using Emacs: 8 - Auto-complete @ Youtube	Mike Zamansky video that covers abbreviation and auto-complete. Duration: 5 minutes.		
Using Emacs: 45- Company or Autocomplete @ Youtube	Another video from Mike Zamansky that covers both auto-complete and company-mode. Duration: 13 minutes.		
Auto Completion with Company-mode			
company-mode ; Modular in-buffer completion framework for Emacs	Text completion framework for emacs		
Using digits to select company-mode candidates @ (or emacs irrelevant)			