PEL Environment Variables

Environment variable	Description	Context		Used by
PEL Startup				
PEL_SHELL	Recommended environment variable name used by PEL early-init logic to detect that Emacs was launched from within a shell (as opposed to an Operating System GUI menu or icon). When used it must be identified in the pel-shell-detection-envvar user option. Use <f11> M-S <f2> to open the PEL fast startup customization group; it holds this user option.</f2></f11>	∑P Fast Startup		PEL fast startup initialization code.
PEL_EMACS_IN_GRAPHICS	Set by PEL Emacs launcher scripts to indicate whether Emacs was launched in graphics mode or not. Set to 1 to indicate it is launched in graphics mode. The PEL ge script sets it to 1.	Run Emacs daemon & clients		PEL initialization code.
PEL C/C++ File Open Helper				,
PEL_CC_FIND_TOOLCHAIN	Holds the name of a tool chain used when the pel-c-file-finder-method is set to pel-ini-file . In that case it effectively select a new set of tool-chain specific directories to search by pel-open-at-point .	<u> ұр і - С</u>	• M- <f6></f6>	(pel-open-at-point &optional N)
		₽ ί - С++	• <f11> f . • <u>6y</u></f11>	
PEL Erlang Support Helper	See Setting PEL Erlang Environment			
PEL_ERLANG_VERSION	Recommended name of the environment variable PEL can use to identify the version of Erlang, if that is the identification method selected by the pel-erlang-version-detection-method user option.	β ℓ - Erlang ⓒ♠A	<f11> SPC e ?</f11>	(pel-show-erlang-version)
			<f12> ?</f12>	
PEL_ERLANG_EXECPATH	Recommended name of the environment variable PEL can use to identify the directory path where the Erlang executable files are located, when this method of identification is selected by the pelerlang-exec-path user option.	<u>nι - Erlang</u> ⓒ∱A		
PEL_ERLANG_ROOT_DIR	Recommended name of the environment variable PEL can use to identify the root Erlang directory, when this method is selected by the pel-erlang-path-detection-method user option.	PI - Erlang ©(F)A		
PEL_ERLANG_MAN_PARENT_DIR	Recommended name of the environment variable PEL can use to identify the root directory holding OTP/Erlang man files, when this method is selected by the pel-erlang-man-parent-rootdir useroption.	PI - Erlang ©(f)A	• <f11> ? m • M-<f8> • %-M</f8></f11>	(man MAN-ARGS)