## **Undo/Redo/Repeat/Command Prefix Arguments**

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
<u>Undo</u>	Emacs standard need to think at people this quice Fortunately for people The external It provides 2 be shown vis The external	d undo command allows undo bout wether it wants to undo kkly becomes difficult to man le that find it difficult to handl undo-tree package helps, but different command for undo sually with the extra ability to undo-propose package is no	ut unusual for users of other editors because: oing an undo operation, providing redo capability. This comes with a complexity cost because the user or redo and may need to type something just to change from undo to redo or vice-versa. For a lot of age. le Emacs default undo, there are external packages that help for Emacs prior to 28. ut unfortunately it might lead to corrupted or lost data during complex undo/redo sequences. and redo. The undo only undoes. And the commands maintain a tree of undo/redo operations that car select undo/redo history branches. ot as powerful but also helps showing the history of complex undo/redo sessions. vs using a simpler undo/redo similar to other systems.	
∑ Customize with: <f11> u <f2></f2></f11>	Restrict undo to a result of the undo operation warked region are not seen as the undo operation warked region are not seen as the undo operation warked region are not seen as the undo operation was the undo operation with the undo operation was the undo operation was the undo operation with the undo operation was the u	ropose: activate use of the exundo: activate use of undo- egion: ng aspect of the Emacs undo- while the region is active/visib ot lost; once the there is no mally bound to (undo) but the F	external <u>undo-tree</u> package  external <u>undo-propose</u> package. Use it only when using Classic Emacs undo. It can help learn it too!  conly and undo-redo instead of classic undo. Emacs >= 28 only.  consystem is that we can restrict it to an area of the buffer by first selecting a region and then performing only. Nothing outside the region will be affected by the undo commands. The undo actions outside of the marked region further undo actions will undo changes in the text.  PEL setup sets it to (negative-argument) to help editing motion flow. M—_ and C—_ are also bound to the undo or redo commands.	
<f11> u <f2></f2></f11>	<f11> u <f1></f1></f11>	( <b>pel-help-pdf</b> &optional OPEN-WEB-PAGE)	Open the <u>Nundo/Redo/Repeat/Arg</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.	
<u>&gt; Customize</u> PEL undo control	<f11> u <f2></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL undo support.  • If OTHER-WINDOW is non-nil (use C-u), display in other window.	
Customize Emacs undo control	<f11> u <f3></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs undo support: undo, undo-tree.	
Undoing Changes	The following commands are available to undo changes to a buffer.  • It's also possible to undo all changes to a buffer associated with a file by reverting the content of the buffer to the content of the file.  • See the File Management section: ∑ File-mngt  • PEL provides the powerful undo-tree external package instead of the default undo ☑ when the pel-use-undo-tree user option is set to t.  ⚠ Note, however, that undo-tree may break during intensive redo operations and could even corrupt your buffer. No longer recommended.  • For Emacs prior to 28, you may want to use • undo-propose instead. ☑ pel-use-undo-propose activates it.  With Emacs 28 better alternatives exist and will be incorporated by PEL soon. You may want to use simple-undo with Emacs 28. See below.			
Simple undo/redo		do-redo is available and comp le not already familiar with Er	plements the undo-only that was available since Emacs 22, allowing the use of undo/redo system more macs.	
Simple undo : pel-use-undo-tree = nil : pel-use-simple-undo = t : Emacs >= 28	• C-/ • C-x u • M-u • C-z • s-z • ℋ-z	(undo-only &optional ARG)	<ul> <li>Undo some previous changes.</li> <li>Repeat this command to undo more changes.</li> <li>A numeric ARG serves as a repeat count.</li> <li>Contrary to 'undo', this will not redo a previous undo.</li> </ul>	
Simple redo : pel-use-undo-tree = nil : pel-use-simple-undo = t !\text{\frac{1}{2}}\text{ For Emacs} >= 28	• C-? • C-M • M-U • <f11> u r</f11>	(undo-redo &optional ARG)	Undo the last ARG undos, i.e., redo the last ARG changes.  Interactively, ARG is the prefix numeric argument and defaults to 1.  It undoes previous undo commands, but doesn't record itself as an undoable command, as opposed to the original <b>undo</b> (shown above).	
Classic Emacs Undo/Redo	Original/standard Emacs undo/redo system. As explained in Emacs Manual Undo section: "Any command other than an undo command breaks the sequence of undo commands. Starting from that moment, the entire sequence of undo commands that you have just performed are themselves placed into the undo record."  • When <u>undo-tree</u> package is activated and used, it is possible to disable the undo-tree-mode globally or locally using the <b>global-undo-tree-mode</b> and <u>undo-tree-mode</u> commands.			
Undo : pel-use-undo-tree = nil : pel-use-simple-undo = nil	• C-/ • C-x u • M-u • C-z • s-z • %-z	(undo &optional ARG)	Undo last changes using standard Emacs undo. Also used to undo an undo, causing a redo!  • A numeric ARG serves as a repeat count.  ☑ PEL uses it when the pel-use-undo-tree user option is nil (the default).  ⑤ If you are not familiar with standard Emacs undo, please first read about it before using it.  • It might seems strange at first to use the same key to undo and redo.	
Undo  Percentage in the percentage is pel-use-undo-tree = t  pel-use-simple-undo = nil	• <f11> u u</f11>	<ul> <li>(pel-undo &amp;optional ARG)</li> <li>(undo-tree-undo &amp;optional ARG)</li> <li>(undo &amp;optional ARG)</li> </ul>	<ul> <li>Undo changes. Does not redo.</li> <li>A numeric ARG serves as a repeat count.</li> <li>In Transient Mark mode when the mark is active, only undo changes within the current region. Similarly, when not in Transient Mark mode, just C-u as an argument limits undo to changes within the current region.</li> <li>C-/ only works in graphics mode</li> <li>s-z and %-z only work in macOS graphic mode. Note: with PEL, %-z is s-z.</li> </ul>	
	You can, however	toggle the local or global une	is key is bound to pel-undo which uses undo-tree-undo by default.  do-tree-mode by issuing the M-x global-undo-tree-mode or M-x undo-tree-mode. If the II use the Emacs standard undo command until the undo-tree-mode is re-enabled.	
Redo  Percentage in the second of the second	• M-U • <f11> u r • s-Z • %-Z</f11>	(pel-redo &optional ARG)  • (undo-tree-redo &optional ARG)  • (undo &optional ARG)	Redo changes. A numeric ARG serves as a repeat count.  In Transient Mark mode when the mark is active, only redo changes within the current region. Similarly, when not in Transient Mark mode, just <b>C-u</b> as an argument limits redo to changes within the current region.  S-Z and #-Z only works in graphics mode  Note: with PEL, #-Z is s-Z.	
	You can, however	toggle the local or global und	is key is bound to pel-redo which uses undo-tree-redo by default.  do-tree-mode by issuing the M-x global-undo-tree-mode or M-x undo-tree-mode. If the II use the Emacs standard undo command until the undo-tree-mode is re-enabled.	

<u>Operation</u>	<u>Keystroke</u>	Function	Note		
Show undo tree	<f11> u v</f11>	(undo-tree-visualize)	Show undo tree of current buffer.		
: pel-use-undo-tree = t			The *undo tree* keys are:  • <up>/<down> • <right>/<left> : move up/down the undo tree nodes  • <right>/<left> : changes branch when at a branch root  • s  : toggle selection mode: normally moving restores right away, this other mode allows you to move in the tree without changing the controlled buffer until RET is typed.  • d  • shows diff between buffer and currently selected undo node!!</left></right></left></right></down></up>		
			• t : toggles showing relative timestamp on undo nodes		
	With PEL, this is available when <b>pel-use-undo-tree</b> is <b>t</b> but also while the global or local undo-tree-mode is active, which it should be unless you explicitly disabled one of these via the global-undo-tree-mode or undo-tree-mode commands. If that is the case, re-enable the undo-tree-mode and you will be able to use the command.				
Switch branch of undo tree	<f11> u x</f11>	(undo-tree-switch- branch BRANCH)	Switch to a different BRANCH of the undo tree.  • This will affect which branch to descend when *redoing* changes using 'undo-tree-redo'.		
pel-use-undo-tree = t	With PEL, this is available when <b>pel-use-undo-tree</b> is <b>t</b> but also while the global or local undo-tree-mode is active, which it should be unless you explicitly disabled one of these via the global-undo-tree-mode or undo-tree-mode commands. If that is the case, re-enable the undo-tree-mode and you will be able to use the command.				
Goto last change	• <f11> u \ • C-x C-\ • <f6> \</f6></f11>	(goto-last-change &optional MARK-POINT MINIMAL-LINE- DISTANCE)	Set point to the position of the last change in the current buffer.  • Consecutive calls set point to the position of the previous change.  • With a prefix arg (optional arg MARK-POINT non-nil), set mark so C-x C-x will return point to the current position.  • This requires the goto-last-change.el package.  • Under PEL set the pel-use-goto-last-change user option to activate this.		
Enable undo in buffer		(buffer-enable-undo &optional BUFFER)	Enable undo recording in the current buffer. No effect if the undo was already recorded as its the case for all buffers except some (like the buffers that have a name that starts with a space).  • Interactively it's not possible to pass an argument.		
Disable undo in buffer		(buffer-disable-undo &optional BUFFER)	Disable undo in current buffer. Deletes all previous undo information for that buffer if it previously existed.  No effect if undo was previously disabled. Interactively it's not possible to pass an argument.		
undo-propose	windo-propose creates an undo history buffer where only undo key bindings to undo/redo are allowed. Use it to replay your undo and restore the buffer to a state that holds the text want to retrieve. You can then copy it back to the original (or another) buffer.				
Open a undo-propose temporary buffer - undo if inside Undo-	C-c u	(undo-propose)	Open a temporary *Undo Propose* buffer copy of the current buffer to navigate its undo history.  • Copies 'current-buffer' and 'buffer-undo-list' to a new temporary buffer, which is read-only except for undo commands. After finished undoing, type:  • C-c C-c to accept the chain of undos, or		
Propose buffer			<ul> <li>C-c C-s to copy the buffer but squash the undo's into a single edit event event.</li> <li>To cancel, type C-c C-k</li> <li>To view an ediff type C-c C-d</li> </ul>		
Repeat	The following comma	ands can repeat the last com	If already inside an 'undo-propose' buffer, this will simply call 'undo'.		
Repeat last operation		(repeat REPEAT-ARG)	Repeat most recently executed command.		
nepeat last operation	• C-x z • <f5></f5>	(repeat ner existand)	<ul> <li>With a prefix argument, supply a prefix argument to that command. Otherwise, give the command the same prefix argument it was given before, if any.</li> <li>When using C-x z to perform repeat, once one C-x z has been typed for the first repeat, type z again to again repeat. Typing z continuously continue to repeat last command (any command, even undo).</li> <li>PEL provides the <f5> key to perform repeat.</f5></li> </ul>		
Redo/edit last complex command executed	• C-x Esc Esc • C-x M-Esc • C-x M-:	(repeat-complex-command ARG)	<ul> <li>Edit and re-evaluate last complex command, or ARGth from last.</li> <li>A complex command is one which used the minibuffer. The command is placed in the minibuffer as a Lisp form for editing. The result is executed, repeating the command as changed.</li> <li>If the command has been changed or is not the most recent previous command it is added to the front of the command history.</li> <li>You can use the minibuffer history commands M-n and M-p to get different commands to edit and resubmit.</li> </ul>		
List command history See also: ∑ Help	<f11> ? d H</f11>	(list-command-history)	List history of commands that used the minibuffer.  • Show list of commands in the *Command History* buffer as a list of Emacs Lisp forms.		
Command Arguments		All Emacs keystrokes are bindings to an Emacs command, a function that supports interactive use. A lot of these commands have arguments. The user can provide these arguments by using the following key strokes <b>before</b> typing the needed command using the keys listed below.			
Prefix repeat N time	M- <number> Keystroke</number>		Meta N, where N is a typed number, tells Emacs to repeat the next <i>Keystroke</i> operation N times.  • N may be larger than 9: to pass a numeric prefix of 23 Hold the Meta key then type 2 followed by 3.		
Repeat prefix	C-u <number> Keystroke</number>	(universal-argument)	<ul> <li>C-u N, where N is a typed number, tells emacs to repeat the next operation N times.</li> <li>Pressing C-u before executing a command is a way to pass extra information to that command.</li> <li>For example, C-u 5 C-b means move the cursor left 5 characters. Sometimes the extra information is just the fact that C-u was pressed.</li> </ul>		
Prefix repeat 4 times	C-u	(universal-argument)	C-u alone stands for a flag, or a repeat factor of 4.		
Prefix repeat 16 times	C-u C-u	(universal-argument)	<b>C-u C-u</b> means 4 * 4 = 16		
Prefix repeat 64 times	C-u C-u C-u	(universal-argument)	<b>C-u C-u</b> means 4*4*4 = 64 repeat.		
Negative argument	• C • M • C-M • C • M	(negative-argument)	<ul> <li>Begin a negative numeric argument for the next command.</li> <li>If needed, C-u following digits or minus sign ends the argument.</li> <li>The PEL package also binds the Control and Meta underscore keys to the negative-argument function to help improve typing speed when entering negative arguments.</li> </ul>		

## Undo - Reference

GNU EMacs Lisp Manual — Command Overview	Describes that prior to executing a command Emacs runs undo-boundary to create undo boundary.
GNU Emacs Lisp Manual — Maintaining Undo Lists	Describes the standard Emacs undo mechanism.
Emacs undo-tree package	Author's we site, describes undo-tree.