## Emacs support for Erlang

Enting Language    Comparison of Principle Comparison	Description	Keystroke	Function	Note
Procuramination Language  Procuramination Proc	Support for the	Emacs provides support for	or Erlang and Erlang Tools via	a the <u>erlang.el</u> external package (see <u>erlang.el source</u> ) and some other packages.
P.C. Leucementation for Disting use the command below pelvely page-relang, and lettary conform.	<b>Erlang</b>	PEL activates Erlang supp	port via the customize user op	ption variable <b>pel-use-erlang</b> . It must be set to t to activate support for Erlang.
P. E. Landonizato for Friend y use the command tabloop planting phage-arting personnel production of the production of	<u>Programming</u>	Further customization is a	available via several user option	ons.
put string states cannot be carried to 1 to present the cities of the form actioning steep constraints.  put string efficients of this present in a country where his exempting colors are common the country of the cou	<u>Language</u>			
Pall calling debte prevented action can be 1 to grower the Pilling poals from according every command.  Pall calling before according and calling occles along a pall and according according to the pall calling occles and according according according to the pall calling occles and according according according to the pall calling occles and according according according according to the pall calling occles according to the pall calling to the pall calling occles according to the pall calling occles according to the pall calling to the p				
PET PLANS SOURCE COSE Sys. pall-enting-code-sylve  - pol-enting-disculants—cut in vite in terminating code interest before the entire through code in the street before the entire through the entire thro			nt-echo: set to t to prevent t	the Friang shell from echoing every command
pulsarising fill-column / column where from exceptions are used in Diray out on profit Selection 10 (20)   pol-etting-skell-insert fill-climinating visitation and profit of the profit Selection (1) (2)     pol-etting-skell-insert fill-climinating visitation about 11 per 12 per 1				
Part   Indicate   Indicate   Part   Indicate   Part   Indicate   Part   Indicate		pel-erlang-fill-colun	nn : column where line-wrapp	oing occurs: maximum line length (defaults to 100).
picketang-skel-invascrible-investations, switcher automatically updated time sturrings are invascred in fibring outsine order for teacher blocks.  **Per process has belowing and more account in the process of the special process.  **Per process has belowing and more accounts from the process of the special process.  **CELLOWING MAN whether the control of the special process.  **CELLOWING MAN whet				
File provision the following part of mixed expends (as provision (£11) and C = £12 and \$4.12 a				
Content with the content of the content of the state   a feet seep / content of the state				
Customize PEL Etting  Service 2 (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11) < (11)		The first one is always av	vailable. The other two prefixe	es are only available when the current buffer is in erlang-mode. The <m-f12> prefix helps the</m-f12>
Customic PEL Enting Support Signorit Si		typing flow when the nex	t key is a Meta key. For simp	olification, the <f11> SPC e prefix is normally omitted in the table.</f11>
Support   Supp	Erlang Mode version	<f12> ?</f12>	(erlang-version)	Display the current version of erlang.el in the mini-buffer.
Castomization groups as well, each one sole is sow window.   All Emails a sublice scene also in the count strate is to so reall, several windows may not be visible, however the buffers will be opered.	Customize PEL Erlang	• <f11> <f1> SPC e</f1></f11>		Customize PEL Erlang support.
Syntax Highlighting	Support	• <f12> <f1></f1></f12>		
Syntax Highlighting   Start code syntax nightlighting   Edit Erlang Code	(See also:   Customize)		WINDOW)	
The \$1,20 < \$1,20				
Syntax Highlighting				· ·
Edit Erlang Code  Create additional clause  C-c C-j  (erlang-generate-new-clause)  Clane clause arguments  C-c C-y  (erlang-clone-arguments)  C-c C-y  (erlang-clone-arguments)  C-c C-y  (erlang-slipn-arrows START END)  START END)  START END  START END  (erlang-slipn-arrows START END)  START END				
Create additional clause C-C C-j (erlang-generate-new-clause) Create additional Erlang clause header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce for five name of the current Erlang function. Create the header Pares the gounce of the precision of the gounce header. Copy the function argument is give previous clause. Copy the function argument is give parent as the proceeding. The marks for a size of the precision of the current function. With a prefix anyment, aligns all arrows in the region (or from beginning of buffer up to point not plant move in function clauses. Example: Electric Comma  Create additional Erlang clause between the function name and the first parent and the previous clause. Copy the function argument as the proceeding. The name of the precision of the current function. With a prefix anyment, aligns all arrows in the region (or from beginning of buffer up to point not plant move in function clauses. Electric Comma  Create and the name of the market and processing all arrows in the region (or from beginning of buffer up to point not plant move in the current function.  In the processing of the precision and prefix and precision in the current function.  In the processing of the precision and precision	Syntax Highlighting		ng has 4 levels and can be tu	irned off. Use the Erlang menu: <f10> to access the menu, then select Erlang and then Syntax</f10>
Create additional clause  C-c C-j  (offang-generate-new classes)  Characteristics and control Entire place the second in the sec	Edit Erlang Code	The following commands hel	p edit Erlang code.	
Clause   Pares the source life for the name of the current Erinag function. Create the header containing the name, pain of presentheses, and an own. The space between the function name and the first paretification by personal provided in the process of the pr		C-c C-i	(erlang-generate-new-	Create additional Erlang clause header.
Conclusive arguments   Color   Color   (orlang-clone-arguments)   (orlang-align-arrovs)   (orlang-align			,	Parses the source file for the name of the current Erlang function. Create the header
Cor C - y   (erlang-clone-arguments)   Cor C - y   (erlang-clone-arguments)   (erlang-clone-arguments)   (erlang-align-arrows   Corpt be function arguments of the providing clause. This command is useful when defining a new clause with almost the same argument as the proceding.  The mark is seat at the beginning of the inserted text, the point at the end.  Align arrows inside   Cor C - a   (erlang-align-arrows   START (END)   (erlang-align-arrows				
Copy the function arguments of the preceding Erlang clause. This command is useful when defining a rev clause with afmost the same argument as the proceding. The mark is set at the beginning of the inserted text, the point at the end.    Aligna arrows   Fig.   Aligna arrows   Aligna arrows   Proceedings   Aligna arrows   Procedure   Procedure   Aligna arrows   Procedure   Proce				
defining a new clause with almost the same drayment as the proceeding.  The mark is set at the beginning of the inserted text, the point at the end.  Align arrows inside region  Comment/un-comment  Align arrows (">1) in function clauses inside marked region or in the current function.  With a prefex argument, aligns all arrows in the region (or from beginning of buffer up to point) not just those in function clauses.  Example:  Example:  Electric Keys  The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code.  Ferfang-electric-comma  Acptional ARG   Insert a comment comma when supplied with a manerical arg, point is inside string or comment, or when there is no inserted. Normally the prototype consists of ">. Strong the semicolon when fulfilled a newline is inserted and prototype for the next line.  Belactric semicolon  (erlang-electric-semicolon character and possibly a prototype for the next line.  (erlang-electric-semicolon character and possibly a prototype for the next line.  (erlang-electric-semicolon character and possibly a prototype for the next line.  (erlang-electric-semicolon character and possibly a prototype for the next line.  Insert a semicolon character and possibly a prototype for the next line.  (erlang-electric-semicolon-crierial states a criterion, when fulfilled a newline is inserted. Hence the control the current line.  Electrics (for the end of arrow)  Electrics (for the end of arrow)  Erlang Comments  Erlang Comments  First prototype consists of ">. Should the semicolon end the feature are recommended and prototype for the next line is inserted. Normally the prototype consists of ">. The variable 'erlang-electric-semicolon-criterial states a criterion, when fulfilled a newline is inserted. Hence the course is indeed and prototype contents and prototype for the next line.  Extrang Comments  Extrang Comments  Extrang Comments  Extrang Comments  Extrang Comments  Extrang Comments  Extranged Comments are associated to the end of a line o	Clone clause arguments	С-с С-у	(erlang-clone-arguments)	
The mark is set at the beginning of the inserted text, the point at the eight needed region or in the current function.				
START END    With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point not just those in function clauses.   Example:				
START END    With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point not just those in function clauses.   Example:	Align arrows inside	C-c C-a	(erlang-align-arrows	Align arrows ("->") in function clauses inside marked region or in the current function.
Example: sus(£) > sus(£, 0), sus([1]], sus) > sum(T, sun + 11); sus([1]], sus) > sum(T, sun + 11); sus([1]], sus) > sum(T, sun + 11); sus([1]], sus) > sun(T, sun + 11); sus([1]], sus([1]], sus([1]]) =	region		,	With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point).
Electric Keys  The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code.  (erlang-electric-comma Soptional ARG)  (erlang-electric-comma soptional array soptional ARG)  (erlang-electric-comma soptional array soptional ar				
Security				
Bectric Keys   The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code.				
Electric Keys  The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code.  (**riang-electric-comma & optional ARG)  **riang Comment**  **processes to the special Erlang source code.  (**riang-electric-comma & optional ARG)  **processes to the special Erlang source code.  (**riang-electric-comma & optional ARG)  **processes to the special Erlang source code.  (**riang-electric-comma & optional ARG)  **processes to the special Erlang source code.  (**riang-electric-comma & optional ARG)  **processes to the special Erlang source code.  (**riang-electric-semicolon area to the special Erlang source code.  (**erlang-electric-semicolon Argonic ARG)  **processes to the special Erlang source code.  (**erlang-electric-semicolon Argonic ARG)  **processes to the special Erlang source code.  (**erlang-electric-semicolon Argonic ARG)  **processes to the special Erlang source code.  **processes to the special Erlang source code.  **processes to the special Erlang source and possibly a prototype for the next line is inserted. He next line is inserted. Normally the prototype consists of ">**processes to the special Erlang source code.  **Processes to the special Erlang source code are a decided to the special Erlang source code are a decided and special erlang source code and special erlang source code are a decided and special erlang source code and special erlang source code and special erlanges are special erlanges. The special erlanges are special erlanges and prototype for the next line is inserted. Normally the prototype consists of ">**processes to the special erlanges are a decided and special erlanges. The special erlanges are a decided and special e				
Electric Keys  The following keys have "electric" behaviour and perform special editing tasks to help edit Eriang source code.  (eriang-electric-comma & optional ARG)  (eriang-electric-semicolon comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.  (eriang-electric-semicolon & optional ARG)  (eriang-electric-semicolon & optional ARG)  (eriang-electric-semicolon & optional ARG)  (eriang-electric-semicolon & optional ARG)  (eriang-electric-get & optional & opt				
Electric Keys  The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code.  Insert a comma character and possibly a new indented line.  The variable erlang-electric-comma-criterial states a criterion, when fulfilled a newline is inserted and the next line is indented.  The variable erlang-electric-comma-criterial states a criterion, when fulfilled a newline is inserted and the next line is indented.  The variable erlang-electric-semicolon-criterial states a criterion, when fulfilled a newline is inserted. Normally the point on the current line comment.  The variable erlang-electric-semicolon-criterial states a criterion, when fulfilled a newline is inserted. Normally the prototype consists of ">"." Should the semicolon end a prototype for the next line is inserted. Normally the prototype consists of ">"." Should the semicolon ender the end of a semicolon ender.  The variable erlang-electric-semicolon-criterial states a criterion, when fulfilled a newline is inserted. Normally the prototype consists of ">"." Should the semicolon ender the end of a semicolon ender thank-lines' controls the number of blank lines inserted between the current line and new function header.  Electric > ffor the end of arrow)  Erlang Gomments  Erlang uses the % character to identify line comments. It uses the following conventions:  *% - Single percent characters are used for comments starting at indentation level.  *%% - Two percent characters are used for comments starting at indentation level.  **Why is a semicolon ender the end of a line of code  **Symbol Type percent characters are used to describe modules and are always placed in the first column  Comment under the ender of an end-of-line comment than C-c C-c and C-c  C-u C-c C-c C-c and C-c  C-u C-c C-c C-c and C-c  C-				
Insert a comma character and possibly a new indented line.   The variable 'erfang-electric-comma-richira' states a criterion, when fulfilled a newline is inserted and the next line is indented.   Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.   Insert a semicolon & provided in the next line is indented.   Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.	Electric Kevs	The following keys have "elec	ctric" behaviour and perform	
Electric semicolon   February		_	(erlang-electric-comma	Insert a comma character and possibly a new indented line
Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.    Insert a semicolon character and possibly a prototype for the next line is inserted. Normally the prototype consists of ">" The variable 'erlang-electric-semicolon-or-triceria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next line is inserted. Normally the prototype consists of ">" Should the semicolon end the clause a new clause a hew clause a new clause and new function header.    Electric > (for the end of a new clause a new clause and new function header.		'		
certaing-electric-semicolon   certaing-electric-semicolon & prototype for the next line.   Insert a semicolon character and possibly a prototype for the next line is inserted, the next line is inserted. Normally the prototype consists of "->". Should the semicolon end the clause a new clause header is generated.   The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.    Erlang uses the % character to identify line comments. It uses the following conventions:  * % - Single percent characters for comments located toward the end of a line of code  * %% - Three percent characters are used for comments starting at indentation level.  * * When no marked region and no comments date at the proper indentation level.  * When no marked region and no comments. I with % or %% style comments depending on the location in the buffer.  * When no marked region and no comments. I with % or %% style comments tarter at the proper indentation level.  * When no marked region and no comments.  * On ine with code: insert %% comment starter at the proper indentation level.  * On line with code: insert %% comment starter at the proper indentation level.  * On line with code: insert %% comment starter at the proper indentation level.  * On line with code: insert \$% comment starter at the proper indentation level.  * On line with code: insert \$% comment starter at the proper indentation level.  * On line with code: insert \$% comment starter at the proper indentation level.  * On line with code: insert \$% comment starter at the proper indentation level.  * On line with code: insert \$% comment starter at the proper				
line.   line   semicolon & potional ARG   semicolon & potional ARG   semicolon & potional ARG   semicolon catterial states a criterion, when fulfilled a newline is inserted. It he next line is inderted and a prototype for the next line is inserted. Normally the prototype consists of "->". Should the semicolon end the clause a new clause inserted. It have a prototype consists of "->". Should the semicolon end the clause a new clause inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' control state and end with a numerical arg, point is inside string or comment.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' control state and end with a numerical arg, point is inside string or comment.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' control string in end the line of code string or comment.   Perivariable 'erlang-electric-semicolon-insert-blank-lines' control string in end the line or 'erlang-electric-semicolon-insert-bl				
Semicolon & Optional ARG    The variable 'erlang-electric-semicolon-criteral' states a criterion, when fulfilled a newline is inserted. However, the inserted of the next line is inserted. Normally the prototype consists of ".>". Should the semicolon end the clause a new clause header is generated."   The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.   Semicolon & Comments				
Semicolon & Optional ARG    The variable 'erlang-electric-semicolon-criteral' states a criterion, when fulfilled a newline is inserted. However, the inserted of the next line is inserted. Normally the prototype consists of ".>". Should the semicolon end the clause a new clause header is generated."   The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.   Semicolon & Comments	Electric semicolon		(erlang-electric-	Insert a semicolon character and possibly a prototype for the next line.
prototype consists of "->". Should the semicolon end the clause a new clause  • header is generated. • The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header. • Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.  Erlang uses the % character to identify line comments. It uses the following conventions: • % • Single percent characters for comments located toward the end of a line of code • %% • Two percent characters are used for comments starting at indentation level. • %%% • Three percent characters are used to describe modules and are always placed in the first column  Comment/un-comment  Note: M-; works much better than C-c C-c and C-c C-u  (comment-dwim ARG)  (comment-dwim ARG)  (comment-dwim ARG)  Comment insert %% comment starter at the proper indentation level. • When no marked region and no comment: • On line with scure comment starter at the proper indentation level. • With marked un-commented region: • Comment tiesor insert % comment starter at the proper indentation level. • With marked un-commented region: • Comment tiesor insert % comment starter at the proper indentation level. • With marked un-commented region: • Comment tiesor insert % comment starter at the proper indentation level. • With marked un-commented region: • Comment tiesor insert % comment starter at the proper indentation level. • With marked un-comment of the current of the current line in empty, call 'comment-indent'. • With marked un-comment and you want (Do What I Mean). • If the region can be comment starter at the proper indentation level. • Call the comment-indent. • To insert *% comment starter at the proper indentation level. • Call the comment of call in uncomment-region' (unless it only consists of comments in which case it calls 'uncomment-region') (sies, if the current line in empty,		'		
header is generated.   The variable trange-lectric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.   Behaves just like normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.   Insert a greater-than sign, and optionally insert a new line and indent.   Septiments				
The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted better the and new function header.   Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.   Erlang Comments				1 1 1
inserted between the current line and new function header.  Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.  Firlang Comments  Erlang uses the % character to identify line comments. It uses the following conventions:  * % - Single percent characters for comments located toward the end of a line of code  * % * * Two percent characters are used for comments starting at indentation level.  * % * Three percent characters are used to describe modules and are always placed in the first column  Comment/un-comment  Note:  M-;  (comment-dwim ARG)  Comment-line or region with % or %% style comments depending on the location in the buffer.  • When no marked region and no comment:  • On empty line: insert % comment starter at the proper indentation level.  • On line with code: insert % comment starter atter the code for an end-of-line comment the region (each line is commented region:  • removes the comment.  • To insert %% comment style: type M-3 M-;  • Call the comment command you want (Do What I Mean).  • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line in empty, call 'comments, in which case it calls 'uncomment-region'). Else, if the current line in empty, call 'comments, in which case it calls 'uncomment-region'). Else, if the current line indent'.  **The erlang.el.code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing something else. The M-; binding to comment-dim works just as indent-for-comment if nothing				
string or comment, or when there are non-whitespace characters following the point on the current line.    Insert a greater-than sign, and optionally insert a new line and indent.				
Current line.				,
Erlang Comments  Erlang uses the % character to identify line comments. It uses the following conventions:  * % - Single percent characters for comments located toward the end of a line of code  * % - Two percent characters are used for comments startly at indentation level.  * % * Two percent characters are used to describe modules and are always placed in the first column  **Comment/un-comment**  Note:  * M-;  * When no marked region and no comments that at the proper indentation level.  * On line with code: insert % comment starter at the proper indentation level.  * On line with code: insert % commented:  * With marked un-commented region:  * Call the comment type M-3 M-;  * Call the comment type M-3 M-;  * Call the comment type is and 'case' it calls 'uncomment-region'). Else, if the current line in empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-insert-comment.  **The erlang el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the m-; binding to comment-dim works just as indent-for-comment if nothing is a comment of the manual properties of the manu				
Erlang uses the % character to identify line comments. It uses the following conventions:  * * - Single percent characters for comments located toward the end of a line of code  * * * - Two percent characters are used to describe modules and are always placed in the first column  Comment/un-comment  Note:  M-;  (comment-dwim ARG)  Comment-line or region with % or %% style comments depending on the location in the buffer.  * When no marked region and no comment:  * On line with code: insert % comment starter at the proper indentation level.  * On line with code: insert % comment starter after the code for an end-of-line comment  * With marked un-commented region:  * Comment region (each line is commented)  * With marked comment style: type M-3 M-;  * Call the comment style: type M-3 M-;  * Call the comment command you want (Do What I Mean).  * If the region is active and 'transient-mark-mode' is on, call 'comment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  ** The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing	Flactric > Ifor the and of		(erlang cloatric et	
Erlang Comments  Erlang uses the % character to identify line comments. It uses the following conventions:  * % - Single percent characters are used for comments starting at indentation level.  * %% - Three percent characters are used to describe modules and are always placed in the first column  Comment/un-comment  Note:  M-;  * Works much better than C-c C-c and C-c C-u  * With marked un-comment tearter at the proper indentation level.  * On line with code: insert % comment starter at the proper indentation level.  * On line with code: insert % comment starter at the proper indentation level.  * On line with code: insert % comment tearter after the code for an end-of-line comment than C-c C-c and C-c C-	arrow)	_		insert a greater-than sign, and optionally insert a new line and indent.
*% - Single percent characters for comments located toward the end of a line of code *%% - Two percent characters are used for comments starting at indentation level.  *%%% - Three percent characters are used to describe modules and are always placed in the first column  **Comment/un-comment**  Note:  M-; works much better than C-c C-c and C-c C-u  **C-u  **C-c and C-c C-u  **C-c and C-c C-c and C-c	Erlang Comments	Erlang uses the % character	to identify line comments. It	uses the following conventions:
* %%% - Three percent characters are used to describe modules and are always placed in the first column  Comment/un-comment  Note:  M-; works much better than C-c C-c and C-c C-u  With marked un-commented region: • Comment starter at the proper indentation level. • On empty line: insert %% comment starter after the code for an end-of-line comment than C-c C-c and C-c C-u  With marked un-commented region: • Comment region (each line is commented) • With marked commented region: • To insert %%% comment starter after the code for an end-of-line comment than commented region: • Comment region (each line is commented) • With marked commented region: • To insert %%% comment style: type M-3 M-; • Call the comment command you want (Do What I Mean). • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  **The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing		Single percent cha	aracters for comments locate	d toward the end of a line of code
Comment/un-comment  Note:  M-;  Comment-dwim ARG)  Comment line or region with % or %% style comments depending on the location in the buffer.  When no marked region and no comment:  On empty line: insert %% comment starter at the proper indentation level.  On line with code: insert % comment starter after the code for an end-of-line comment with marked un-commented region:  Comment region (each line is commented)  With marked comment degion:  removes the comment.  To insert %% comment style: type M-3 M-;  Call the comment command you want (Do What I Mean).  If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line if empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  The erlangel code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing		-		
<ul> <li>When no marked region and no comment: <ul> <li>On empty line: insert %% comment starter at the proper indentation level.</li> <li>On line with code: insert % comment starter after the code for an end-of-line comment than C-c C-c and C-c</li> <li>With marked un-commented region: <ul> <li>Comment region (each line is commented)</li> <li>With marked commented region: <ul> <li>removes the comment.</li> </ul> </li> <li>To insert %%% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line i empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> </ul> </li> <li>*The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing.</li> </ul></li></ul>	Oammentte.			
<ul> <li>On empty line: insert %% comment starter at the proper indentation level.</li> <li>On line with code: insert % comment starter after the code for an end-of-line comment than C-c C-c and C-c</li> <li>Comment region (each line is commented)</li> <li>With marked commented region: <ul> <li>removes the comment.</li> <li>To insert %% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> </ul> </li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>	Comment/un-comment	M-;	(comment-dwim ARG)	
<ul> <li>On line with code: insert % comment starter after the code for an end-of-line comment than C-c C-c and C-c</li> <li>With marked un-commented region: <ul> <li>Comment region (each line is commented)</li> <li>With marked commented region:</li> <li>removes the comment.</li> <li>To insert %%% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line i empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> </ul> </li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>	Note:			
<ul> <li>Comment region (each line is commented)</li> <li>With marked commented region: <ul> <li>removes the comment.</li> <li>To insert %% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line i empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> </ul> </li> <li>★ The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>	M-; works much better			On line with code: insert % comment starter after the code for an end-of-line comment
<ul> <li>With marked commented region:</li> <li>removes the comment.</li> <li>To insert %%% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>	than C-c C-c and C-c			
<ul> <li>removes the comment.</li> <li>To insert %%% comment style: type M-3 M-;</li> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line if empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing.</li> </ul>	C-u			
<ul> <li>Call the comment command you want (Do What I Mean).</li> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>				
<ul> <li>If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.</li> <li>The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing</li> </ul>				• To insert %%% comment style: type M-3 M-;
consists of comments, in which case it calls 'uncomment-region'). Else, if the current line i empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  The erlang.el code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing				
empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a commen and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.     ★ The erlang.el code binds M−1 to indent-for-comment. However PEL uses M−1 for something else. The M−; binding to comment-dim works just as indent-for-comment if nothing				
and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.				empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment
★ The <u>erlang.el</u> code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing				and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-
something else. The M-; binding to comment-dim works just as indent-for-comment if nothing				
				something else. The M-; binding to comment-dim works just as indent-for-comment if nothing is marked.

Description	Keystroke	Function	Note
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just C-u prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.  • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'.  • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.
Un-comment region	С-с С-и	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.
Fill current paragraph	• M-q	(fill-paragraph &optional	Fill multi-line comment at or after point.
(See also: ∑ Filling/ Justification)	• <f11> t f p</f11>	JUSTIFY REGION)	<ul> <li>To justify as well: C-u M-q</li> <li>In refill mode this is done automatically. In auto fill mode the filling is done at the end of the line.</li> <li>See the ∑ Filling/Justification for all filling and justification commands.</li> </ul>
Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active then toggle in the region. Otherwise, in the whole buffer.  • This requires the hide-comnt.el package (see ) Comments).
(See: ∑ Comments)		,	pel-use-hide-comnt user option is t.
<u>Indentation</u>			CC-Mode logic and provided commands listed below.  d at the end of this list. They are also listed in the ∑ Indentation table.
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.  • Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/
(See also: ∑ Indentation)		acptional And region)	off with the <f12> M-i key):  With syntactic-indentation on (the default):  In Transient Mark mode, when the region is active, reindent the region.  Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.  Otherwise reindent just the current line.  This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.  With syntactic-indentation off:  <tab> always indent current line by one level   C-u - <tab> or M- <tab> always un-indent current line by one level   Indenting marked region is done without syntax knowledge and at the same level as previous line.   If you want to indent rigidly you can use: (pel-indent-rigidly &amp;optional N) (bound to C-x <tab> and to <f11> <tab> <tab <tab=""> <tab <ta<="" <tab="" td=""></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></tab></f11></tab></tab></tab></tab></tab></f12>
Indent Erlang function	C-c C-q	(erlang-indent-function)	to indent the line or region rigidly.  • (tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column.  Indent current Erlang function.
muent Enang function	C-c C-q	(enang-indent-idiotion)	This also works with a simple tab (see above).
Indent lines of list after point (See also: ∑ Indentation)	C-M-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. When interactively called with prefix, indent the enclosing defun instead.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	<ul> <li>Indent each nonblank line in the region.</li> <li>A numeric prefix argument specifies a column: indent each line to that column.</li> <li>With no prefix argument, the command chooses one of these methods and indents all the lines with it: <ol> <li>If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.</li> <li>If 'indent-region-function' is non-nil, call that function to indent the region.</li> <li>Indent each line via 'indent-according-to-mode'.</li> </ol> </li> <li>When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab></li> </ul>
Navigation in Erlang code (See also: ∑ Navigation)	The erlang-mode provides commands to navigate across Erlang source code. PEL complements these. And EDTS also Several commands are specialization of the normal navigation commands which are described in the table ∑ Navigation, but several are specific to Erlang:  • Notice the 3 sets of commands:  1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives.  2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives.  3. The <f12> <m-cursor> commands (also accessible via <m-f12> <m-cursor>, move across Erlang clauses (as opposed to functions).</m-cursor></m-f12></m-cursor></f12></f6></down></f12></up></f12>		
Go to beginning of statement	M-a	(backward-sentence &optional ARG)	See the others inside ∑ Navigation, like the navigation by blocks.  Go backward to the beginning of an Erlang clause.  • With a numerical argument repeat that many times.
Go to the end of statement	м-е	(forward-sentence &optional ARG)	Go forward to the end of an Erlang clause.  • With a numerical argument repeat that many times.
Go to beginning of current function or top- level function	С-М-а	( <b>c-beginning-of-defun</b> &optional ARG)	Move backward to the beginning of an Erlang function.  • Every top level declaration that contains a brace paren block is considered to be a defun.  • With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
Goto end of current function or top-level function	С-М-е	(c-end-of-defun &optional ARG)	Move forward to the end of an Erlang function.  • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
Move backward to beginning of previous function	• <f12> <up> • <f12> f p</f12></up></f12>	(pel-previous-erl-function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M−ˆ.
Move forward to beginning of next function	• <f12> <down> • <f12> f n</f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M−ˆ.   ⇒Shift marking is available.
Backward to beginning of function or compiler directive	• C-M-a • C-M- <home> • <f6> p • <f6> <up> • <f12> f P</f12></up></f6></f6></home>	(beginning-of-defun &optional ARG) (erlang-beginning-of- function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive.  • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.  ➡Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode. <hr/> ➡Erlang.el man page indicates an invalid mapping for this.</up></f6></f6></home>

Description	Keystroke	Function	Note
Forward to beginning of	• <f6> n</f6>	(pel-beginning-of-next-	Move forward to the beginning of the next function definition or compiler directive.
next function or compiler directive	• <f6> <down> • <f12> f N</f12></down></f6>	defun &optional SILENT DONT-PUSH_MARK)	Beeps if does not find beginning of next function unless SILENT is non-nil.  If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  Move back to previous position with M−`.  Shift marking is available for the <f6> bindings.  This command complements what end-of-defun does.  It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.  It handles nested functions or class methods in languages like Python and others.</f6>
Backward to end of previous function or compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to the end of the previous function definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M−ˆ.  ⇒ Shift marking is available for the <f6> bindings.  • This command complements this set of 4 commands.</f6>
Forward to end of function or compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to end of Erlang function.  With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  ➤ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <end>).  However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></end>
Backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause.  • With argument, do this that many times.
Forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause.  • Pushes mark; move back to previous position with M−ˆ.  ⇒Shift marking is available.
Backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause.  • Pushes mark; move back to previous position with M−ˆ.  ⇒Shift marking is available.
Forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause.  • With argument, do this that many times.
EDTS/Navigation	support shift marking. There	are other commands and ke	ove point across Erlang functions. These do not support repetition prefix argument nor they by bindings to move across Erlang functions, and PEL support functions that perform the same and listed in the navigation section above.
Move backward to beginning of previous function	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function skipping all compiler directives.  PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
Move forward to beginning of next function	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function skipping all compiler directives.  PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
Search Support	In Erlang mode, the superwor	rd mode can be useful since	snake_case is often used. Using superword-mode helps searching.
Toggle superword-mode  (See also: ∑ Text Modes, ∑ Search/Replace)	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In Erlang, '_' are treated as part of words.  • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.  • PEL provides the <f12> M-p key for the programming language modes where <u>snake_case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Marking			available. They complement what is already available and described in the \( \subseteq \) Marking table. san invalid mapping for this. Reported as \( \frac{ERL-1314}{2} \).
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark- function &optional ARG)	Put mark at end of this function, point at beginning.  The function marked is the one that contains point or follows point.  With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.  If the mark is active, it marks the next or previous function(s) after the one(s) already marked.
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, point at beginning.
Highlighting blocks	show-paren-mode, which I	highlights the parens that mat	e useful modes to highlight blocks of (), {}, and []. tches the one before or after point. s are highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9 • <f11> b h (</f11></m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
(see also: ∑ Highlight)	,	(matalana dali da	Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.    Use blight a catalog a continuous by select
Enable/Disable coloured highlight of nested blocks (),{},∏ (see also: ∑ Highlight)	• <f12> M-r • <m-f12> M-r • <f11> b h R</f11></m-f12></f12>	(rainbow-delimiters- mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.  • Customize the depth and colours with M-x customize-group rainbow-delimiters    Requires: rainbow-delimiters.el    PEL activates this when the pel-use-rainbow-delimiters customize variable is set to t.
Inserting code			
Insert Parentheses	M-(	(insert-parentheses &optional ARG)	<ul> <li>For Erlang: insert a parenthesis pair '()', leaving point after open-paren.</li> <li>A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.</li> <li>A negative ARG encloses the preceding ARG sexps instead.</li> <li>No argument is equivalent to zero: just insert '()' and leave point between.</li> <li>PEL makes 'parens-require-spaces' buffer local and set it to nili in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.</li> <li>If region is active, insert enclosing characters at region boundaries.</li> <li>This command assumes point is not in a string or comment.</li> </ul>

Description	Keystroke	Function	Note	
Insert Erlang Code			tons using the standard tempo skeleton package.	
Templates	PEL provides the following	<ul> <li>The erlang package make these skeletons available on the Erlang/Skeletons menu (via <f10>).</f10></li> <li>PEL provides the following additional functionality:</li> </ul>		
(See also: ∑ Inserting Text	+		d under the pel:erlang-skel key prefix: <f12> <f12>.  h a +. These are also added to the menu.</f12></f12>	
for more info and information about tempo	Several aspects of to	he PEL Erlang Source Code S	Style is controlled by the user options inside the <b>pel-erlang-code-style</b> group. The controlled	
skeleton and yasnippet template-based text		marked with a C. The relevant include the following options	t user options are part of the <b>pel-erlang-code-style</b> group accessible with <f12> <f1> from an:</f1></f12>	
insertion).	<ul><li>pel-erlang-skel-inse</li><li>pel-erlang-skel-pro</li></ul>		: set whether an automatically updated timestamp is inserted in the file header block. : set whether file and function skeletons blocks prompt for purpose and insert it.	
	pel-erlang-skel-pro	mpt-for-function-name	: set whether function skeletons prompt for function name and then inserts that name. s : set whether function skeletons prompt for function arguments and then insert them.	
	pel-erlang-use-sep	arators	: set whether blocks use horizontal separator lines (these are the first of potentially 2 separators).	
	pel-erlang-use-sec     pel-erlang-skel-with		: set whether blocks use a second block horizontal separator line. : set whether generated code comments use EDoc markup.	
	• pel-erlang-skel-with		: set whether file header blocks use open source software license text controlled by 2 lice.	
	· ·	•	But by using file and directory variables ( see $\Sigma$ File/Directory Variables) they can also be used to tree. So by default, the user options that control the PEL tempo template take effect globally. If	
			ite the user option control block at the end of that file. If you want to control the behaviour of the e create a .dir-locals file and store the values of the relevant options variables inside that file. This	
			rmat of the tempo templates precisely and does not affect what you actually type.  ng the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-	
	marks) with the standar	d tempo-mode keys C-c M-	f and C-c M-b or some other keys like C-c . and C-c ,.	
	supports listing all com	pletions into a separate tempo	n also type the template name and then hit C-c C-M-i or <f12><f12><f12>. This orary buffer. This is mainly useful for templates which short names such as "if", "case", etc</f12></f12></f12>	
	Some of the template na	mes in the title column are als	to links to the relevant Erlang language construct reference page.	
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.	
case	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.	
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.	
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.	
<u>try</u> +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.	
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.	
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.	
<u>after</u>	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.	
loop	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.	
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.	
<u>function</u> C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition.     This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.	
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.	
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.	
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.	
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date.	
large-header C	<f12> <f12> C-h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • The formatting, use of Edoc, use of separator lines, insertion of automatic timestamp and license of this header and the large header used inside all OTP behaviour skeletons below are controlled by the user options described above.  • This command distinguish Erlang module files (files with the .erl extension.) from the Erlang	
			header files (.hrl files) and inserts the appropriate file header block.	
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.	
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.	
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.	
supervisor-bridge C	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.	
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.	
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.	
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.	
gen-statem-StateName	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.	
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.	
wx-object C	<f12> <f12> M-W</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.	
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.	
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a <b>CORBA</b> callback module.	
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite	
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite	
ts-test-suite	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite	

Description	Keystroke	Function	Note
Tempo Template Tag	• C-c C-M-i	(tempo-complete-tag	Look for a tag and expand it.
Insertion	• <f12> <f12> <f12></f12></f12></f12>	&optional SILENT)	<ul> <li>Instead of using the <f12><f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i. (or <f12><f12><f12>) A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.</f12></f12></f12></f12></f12></li> <li>All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all.</li> <li>If a single match is found, the corresponding template is expanded in place of the matching string.</li> <li>If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal.</li> <li>If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.</li> </ul>
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.
Using Flymake to	Flymake performs these chec	The second se	
perform dynamic syntax checking	Flymake has several customer the following customization of flymake-start-on-flymake flymake-no-changes-time flymake-start-syntax-che	omizable variables, which sor variables determine the exact s-mode: to start checking eout: time to wait after last cck-on-newline: to check a navigation to next or previous	circumstances whereupon Flymake decides to initiate a check of the buffer: when flymake-mode is started. nil to prevent check. change to start checking. Default = 0.5 seconds. after insertion or removal of newline char from buffer. nil to prevent check.
			of properties of Flymake diagnostic types. See Emacs documentation for more info.  s only when flymake-mode is turned on.
Toggle Flymake mode	<f12> F</f12>	(flymake-mode &optional	Toggle Flymake mode on or off.
on/off		ARG)	<ul> <li>With a prefix argument ARG, enable Flymake mode if ARG is positive, and disable it otherwise.</li> <li>Flymake is an Emacs minor mode for on-the-fly syntax checking.</li> <li>Flymake collects diagnostic information from multiple sources, called backends, and visually annotates the buffer with the results.</li> </ul>
Go to next flymake diagnostic	M-n	(flymake-goto-next-error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev-error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.
Compiling Erlang Code		ened to compile the files. The	ce code files to .beam files located in the same directory as the source code. Detected errors are buffer shows the location of error and the error description. The following commands are used
Compile code	C-e C-k	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting <ret> on the error file/line move point to that line in the Erlang file buffer. The <ret> key is bound to (compile-goto-error &amp;optional EVENT)  It's also possible to use the next-error and previous error.</ret></ret>
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.     Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	( <b>previous-error</b> &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Erlang Shell	The following commands are	used to explicitly launch an E	Erlang shell inside Emacs.
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start Erlang Shell	<f11> x r</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.
			<ul> <li>The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.</li> <li>C-c C-z starts the Erlang Shell from the Erlang Mode.</li> <li><f11> x r starts it anytime, as long as it was installed.</f11></li> <li>Under PEL this command is available only when the pel-use-erlang customize variable is set to t.</li> </ul>

Description	Keystroke	Function	Note		
Inside the Erlang Shell	Redundant command echo     On some systems the Erl     Set the pel-erlan     Cannot type the Erlang Ctr     To pass the Ctrl-G to the	2: ang shell annoyingly echoes of g-shell-prevent-echo user of l-G escape to access Erlang Erlang shell running inside Er	n into some issues. They are listed here along with work-arounds.  each typed command. If this is the case for your system, PEL provides a fix:  option to t. After doing that execute pel-init or restart Emacs.  JCL Command Menu:  rlang, type: C-q C-g RET  ork for the Erlang shell invoked via url inside a vterm shell (see ) Shells) launched inside Emacs.		
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt.  The Frlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: therefore commands from previously opened Erlang shells are also available. You can also use the Erlang shell commands to access the local shell history.				
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.		
Previous shell command	м-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.		
Using Man inside Emacs and support Erlang Man pages		ore powerful than the usual me system man utility, while were man is not available.	riside buffers. Ian reader available on the shell allowing navigation across man pages and opening hyperlinks. It has some formatting limitations compared to man but it's		
(See also: ∑ Help/Info)	On most systems the Ma There are several ways the One is to set the MANP/ Emacs to access Erlang MANPATH=`many export MANPAT  Another way is to custor of Emacs man to fin the as the above example w "-M'manpath':/us	In pages for Erlang are not avais can be remedied: ATH environment variable to in its man pages. For example to bath '.' usr/local/Cella: TH mize the Emacs Man-switch. Erlang's man pages without over need to set the Man-switch str/local/Cellar/erlang/22.3.4/lii	ailable to the man utility and therefore not available for man inside Emacs.  Include the directory where these files are located. Then man can be used outside and inside the following lines can be stored inside a shell script to do this:  Include the directory where these files are located. Then man can be used outside and inside the following lines can be stored inside a shell script to do this:  Includes the same directory. This will add the capability modifying the capabilities of the parent shell. For example, if we want to use the same directory nes which is normally set to nil to the following value:  Include the directory where these files are located. Then man can be used outside and inside the following value want to use the capability modifying the capability and the capability modifying the capability set to nil to the following value:  Include the directory where these files are located. Then man can be used outside and inside the following value was used outside and inside the following value.		
	shells that have their owr access to the man pages MANPATH and therefore MANPATH and buses ma	n value of MANPATH. That mit of different versions of Erlang providing the man pages fron un's ability to view several pag	ight be very useful for someone that uses different versions of Erlang in a system and needs g. It becomes possible to run different shells inside Emacs with each having its own value of n different locations. It is also possible to place all of these directories inside the Man-switches or		
	When learning Erlang it madirectory only. You must a	To only see Erlang topics in Man completion:  When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang man directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not work. See my description on how to create whatis file for local man directory.			
	EDTS (see below) suppor	rts the ability to download and ccess sections inside the man	Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's ne pages, allowing EDTS driven man page access to co-exist with manual man command		
Open a man page inside an Emacs buffer  (See also: ∑ Help/Info)	• <f11> ? m • ૠ-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:  • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing <ret> over the link.  • You can navigate easily between sections (n/p will move to the next/previous section)  • You can use any of the searches.  • You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.  • See all keys available in mode, with <f1> m or <f11> ? k m.  • The man command prompts, using the word at point as the default.  • PEL key sequence to customize man: <f11> <f1> M-g m</f1></f11></f11></f1></ret>		
Open a man page without external man process: woman  (See also: ∑ Help/Info)	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f1> M-g w  text width, use word at point, etc</f1></f11>		
EDTS	EDTS - Erlang Development Tool Suite  The commands in the following rows require the EDTS external package. PEL activates it when the pel-use-edts user option is set to t.  EDTS is customizable through it edts customization group. With PEL you can open it, with other Erlang specific groups with C-u <f12> <f1>.  If you want EDTS to start automatically when you open an Erlang file, set pel-activate-edts-automatically to t.  If EDTS has not been activated yet, the only EDTS specific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12></f1></f12>				
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional ARG)	Turn EDTS mode on or off. EDTS is an easy to set up Development-environment for Erlang. EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.		
EDTS/Cross References	EDTS provides the following	cross-reference commands.	It supports navigating in Erlang source code running in the current and remote nodes.		
Find definition of identifier at point	м	(edts-find-source-under- point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.		
Go back to where M was last issued	М-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.		
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.		
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.		
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local-function SET-MARK)	Find a function in the current module.  • List local functions in the mini-buffer. Support completion. Move point to selected one.  • With <b>C-u</b> prefix, push mark before moving point.		
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global- function)	Find a module in the current project.  List project modules in the mini-buffer. Support completion. Open the file of selected one.		

Description	Keystroke	Function	Note
EDTS/AHS Editing	in all of the buffer. The autom ahs-idle-interval which defa	natic symbol highlighting modults to 1.0 second.	S). and provides commands to modify the name of the highlighted name in the current function or de starts when the cursors stays on a symbol for a period longer than the value identified by the nove point away from the highlighted area.
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)
EDTS/Man	pages per project, so it is pos	ssible to have several Erlang	tition using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages. man commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
<b>EDTS Code Analysis</b>			
Compile current buffer 0	<f12> a c</f12>	(edts-code-compile-and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION- RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.
EDTS/Debug			
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node			
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node-name)	Print the node sname of the erlang node connected to current buffer.  The node is either:  The module's project node, if current buffer is an erlang module, or  The buffer's erlang node if buffer is an edts-shell buffer.  The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.		
Preview UML diagram from plantUML source in current plantUML region of commented source code  (See also: MPlantUML)	<f12> u</f12>	(pel-render-commented- plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment.  • Use region if identified otherwise use PlantUML block at point.  • Uses prefix (as PREFIX) to choose where to display it:  • 4 (when prefixing the command with C-u) -> new window  • 16 (when prefixing the command with C-u C-u) -> new frame.  • else -> new buffer  • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.  • Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  • Requires the plantuml-mode external package, 2 activated by pel-use-plantuml user option being non-nil.

Description	Keystroke	Function	Note
Preview diagram created from Graphviz DOT markup embedded	<f12> G</f12>	(pel-render-commented- graphviz-dot &optional POS)	Render the Graphviz-Dot markup embedded in current mode comment. Search at POS if specified, otherwise search around point. Use region if identified otherwise use Graphviz-Dot block.
in comments (See also: MGraphviz Dot)			<ul> <li>The graphviz DOT code must be located within a block delimited by the following special keywords (that are also in comments):</li> <li>@start-gdot</li> <li>@end-gdot</li> </ul>
			⚠ The current implementation leaves the created image file in a temporary directory. You will probably want to move that file or delete it, otherwise the size of this directory will increase with each of these created files. The file names use the pel-gdot- prefix.
			Pacquires the graphviz-dot-mode package external package, dativated by pel-use-graphviz-dot user option set to t.
<b>Development Tool</b>	The following commands are	used when adding Emacs Li	sp support for Erlang.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line.  • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
## TODO			Create a PEL command to create/update the TAGS file for the current Erlang project
			Inside the Emacs erlang shell, MFA expansion with the Meta key does not work the way it works in a pure Erlang shell. Why?

## Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.
Erlang Code Guidelines	
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.
EDoc User's Guide	Describes how to document code.
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create aa missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide)     Erlang mode for Emacs (man page)	On the <u>erlang.org</u> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  • I found bugs in the <u>erlang man</u> page in the <b>Edit- Moving the marker</b> section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <u>ERL-1314</u> .  • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.
<b>Emacs tools for Erlang</b>	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  : name "my-project"  : otp-path "path/to/otp"  : node-name "project-node-name"  : lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?

Document	Notes
company-mode; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.