## **Emacs support for the Erlang Programming Language**

<u>Description</u>	<u>Keystroke</u>	Function	Note				
Erlang Support	Emacs supports Erlang via the						
See also: • Erlang Reference	The <u>erlang.el</u> external package (see <u>erlang.el</u> source), part of <u>OTP</u> 2 PEL activates it with <u>pel-use-erlang</u> .						
about-erlang	The <u>EDTS</u> external package 2 PEL activates it with <u>pel-use-edts</u> (set to t or <u>start-automatically</u> ).  The <u>Isp-mode</u> external package 2 PEL activates it with <u>pel-use-erlang-is</u> . Uses the <u>erlang_is</u> Erlang LSP server. Integrates with:						
<ul> <li>Developing Erlang</li> <li>Code with PEL</li> </ul>	• Whelm by using helm-lsp  We per activates with per-use-helm-lsp.  PEL activates with per-use-helm-lsp.  PEL activates with per-use-helm-lsp.  PEL activates with per-use-helm-lsp.						
set PEL Erlang environment	• 📦 treemacs by using Isp-treemacs 2 PEL activates with pel-use-treemacs and pel-use-Isp-treemacs.						
	• 🃦 origami by using Isp-origami 🛂 PEL activates with pel-use-Isp-origami.						
• <u>» Finde/Show</u> • <u>» Text Modes</u>	The <u>Distel</u> external package also exists, but seems to have mainly been replaced by EDTS and needs maintenance. PEL does not support it.  The <u>hide-comnt.el</u> external package.  PEL activates it with <u>pel-use-hide-comnt</u>						
• <u>National Highlight</u>	The <u>iedit</u> external package	· ~	s it with pel-use-iedit.				
• <u>∑ Inserting Text</u>	The smart-dash external p	oackage. 🛂 PEL activate	es it with <b>pel-use-smart-dash</b> .				
	-		es it with pel-use-smartparens.				
			omatically in erlang-mode buffers by adding their mode to pel-erlang-activates-minor-modes. electric-pair-local-mode: add electric-pair-local-mode to pel-erlang-activates-minor-modes.				
	• Use <f12> <f3> electricity RET to access the customization group and select pairs.</f3></f12>						
• <u>∑ Speedbar</u>	<ul> <li>➡Useful global minor-modes to activate features in Erlang via pel-activates-global-minor-mode: show-paren-mode</li> <li>➡ PEL adds <u>∑ Speedbar</u> for .erl, .hrl and .escript Erlang files to show the list of functions.</li> </ul>						
<b>.</b>		PEL Erlang support implemented in: pel-erlang.el, pel-erlang-skels.el, sections of pelkey-macros.el and pel keys.el and PEL files they require.					
• <u>» Customize</u>	Customization:	wed by the group name an	nd RET to open the specific customization group or one of the following key sequences.				
	pel-pkg-for-erlang: to	o activate pel-use-erlang:	use <f11> SPC e <f2>, or <f12> <f2> from an Erlang buffer. This has sub-group: see</f2></f12></f2></f11>				
		to activate EDTS and LSP. when <b>pel-use-erlang</b> is on,	use <f11> SPC e <f3> 1</f3></f11>				
	• edts: v	when <b>pel-use-edts</b> is on,	use <f11> SPC e <f3> 3</f3></f11>				
	• Isp-mode: v	when <b>pel-use-erlang-Is</b> is o	on, use <f11> SPC e L <f3> 1 on, use <f11> SPC e L <f3> 2</f3></f11></f3></f11>				
			to control Erlang editing. Only some of them are described here. Use Emacs for the complete list.				
€ >>	pel-erlang-activates-mi	nor-modes: Schedules ac	ctivation of local minor modes in erlang-mode buffers, eg. smart-dash-mode.				
Identify minor modes to activate automatically	<ul> <li>pel-erlang-environment group:</li> <li>pel-erlang-man-parent-rootdir: Identifies the parent directory of Erlang man directory. The man directory should hold the man1, man3, man4 and man6 which contain Erlang man files. If this is set PEL sets (override) the erlang-el erlang-root-dir user-option value with it which activates the appropriate Erlang man files. Without PEL or if pel-erlang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option yourself.</li> </ul>						
in erlang-mode buffers							
	<ul> <li>pel-erlang-exec-path: Identifies the directory where Erlang binaries are stored.</li> <li>pel-erlang-version-detection-method: identifies a mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.</li> </ul>						
P / B /			Theorianism to detect Enang/OTT Version. By default it uses an Enang soript provided with TEE.				
Erlang Style	<ul> <li>pel-erlang-code-style group:</li> <li>pel-erlang-fill-column: column where line-wrapping occurs: maximum <i>line length</i> (defaults to 100). You can change the value or set it nil.</li> </ul>						
Control 🖛	<ul> <li>When pel-erlang-fill-column user option is nil, erlang-mode buffers use the global Emacs fill-column value.</li> <li>pel-erlang-skel-use-separators: whether line separators are used in Erlang code templates (see the Insert Erlang Code Template section below),</li> <li>pel-erlang-skel-use-secondary-separators: whether secondary separator lines are inserted by some Erlang code templates,</li> <li>pel-erlang-skel-insert-file-timestamp: whether automatically updated time stamps are inserted in Erlang source code file header blocks.</li> </ul>						
Ericsson AB     Guideline							
Inaka Guideline	<ul> <li>pel-erlang-skel-insert-file-timestamp: whether automatically updated time stamps are inserted in Erlang source code file header blocks.</li> <li>pel-erlang-space-after-comma-in-blocks: when turned on, a space is automatically inserted after a comma typed inside a parens block.</li> </ul>						
Open this PDF file.	• <f11> SPC e <f1></f1></f11>	(pel-help-pdf &optional	, in the second				
See also: <u><b>∑ Help/Info</b></u>	• <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11>	OPEN-WEB-PAGE)	the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.				
	• <f12> <f1></f1></f12>		Key sequences that start with <f11> SPC e are available from any major modes.</f11>				
	• <f12> w <f1> • <f12> L <f1></f1></f12></f1></f12>		Key sequences that start with <f12> are only available in erlang-mode buffers.  The <f12> keys sequences are mirrored by the <m-f12> key sequence for convenience.</m-f12></f12></f12>				
T Customize DEL Erland	<f11> SPC e <f2></f2></f11>	(pel-customize-pel	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages.				
∑ Customize PEL Erlang support	<f12> <f2></f2></f12>	&optional OTHER-	<ul> <li>If OTHER-WINDOW is non-nil (use <b>C-u</b>), display in another window.</li> </ul>				
		WINDOW)	Outside France Education and advantage and a substitute to control of the first state of the substitute of the substitut				
∑ Customize Emacs Erlang support	<f11> SPC e <f3></f3></f11>	&optional OTHER-	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol, electricity, smartparens, smart-dash.				
	<f12> <f3></f3></f12>	WINDOW)	• If OTHER-WINDOW is non-nil (use <b>c-u</b> ), display in another window.				
∑ Customize PEL LSP for Erlang support	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel &optional OTHER-	Customize PEL LSP Erlang support  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.				
0,	<f12> L <f2></f2></f12>	WINDOW)	This is available when <b>pel-use-erlang-is</b> is turned on.				
<u>▼ Customize</u> Emacs	<f11> SPC e L <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: lsp-erlang, lsp-mode, lsp-ui, helm-lsp, lsp-ivy, lsp-				
LSP for Erlang support	<f12> L <f3></f3></f12>	&optional OTHER- WINDOW)	origami, lsp-treemacs.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.				
			This is available when <b>pel-use-erlang-is</b> is turned on.				
<u>▼ Customize</u> PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support				
Window for Erlang support	<f12> w <f2></f2></f12>	&optional OTHER- WINDOW)	<ul> <li>If OTHER-WINDOW is non-nil (use C-u), display in another window.</li> <li>This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.</li> </ul>				
<b>∑ Customize</b> Emacs	<f11> SPC e w <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: Isp-treemacs, treemacs				
LSP Window for Erlang	<f12> w <f3></f3></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.				
support		,	This is available when <b>pel-use-treemacs</b> and/or <b>pel-use-lsp-treemacs</b> is turned on.				
<b>Environment Help</b>	Use the following command to	verify your Erlang environ	ment.				
Erlang Mode version	<f11> SPC e ?</f11>	(pel-show-erlang- version)	Display the following information in the minibuffer.				
	<f12> ?</f12>	,	of available Erlang system, of erlang.el, of erlang ls (if available), values of erlang-root-dir and pel-				
		erlang-man-parent-rootdi	ir. ACheck that erlang-root-dir matches the version of Erlang you use. If not check the setting of				
			rootdir. For more information see set PEL Erlang environment.				
Syntax Highlighting	The <u>erlang.el</u> external packag  Off, Level 1: comments only		f Erlang code syntax highlighting: maximum variety.				
	There is not key binding for thi	s. You must use the Synta	ax Highlighting section of the Erlang menu: nen select Erlang, Syntax Highlighting and the level you want.				
	- in terminar mode type <11	to access the menu, th	ion select chang, symax migninghting and the level you want.				

<u>Description</u>	<u>Keystroke</u>	Function	Note			
Electric Keys for Erlang	1. the <u>erlang.el</u> external 2. the <u>smartparens</u> exter • Use <f11> ( ( to the</f11>	an impact on the "electric" behaviour of some keys in erlang-mode buffers: al package, which controls the behaviour of the RET, ,,; and > keys as controlled by erlang-electric-commands variable. ernal package, which modifies the behaviour of the DEL and <deletechar> behaviour when smartparens-mode is active. toggle smartparens-mode on and off. and dynamic control of erlang.el electric key behaviour and provides electric behaviour of some extra keys.</deletechar>				
<u> ∑ Customize</u>	The pel-erlang-electric-     The pel-erlang-space-are	keys user-option set which of the RET, ,, ; and > keys have electric behaviour. By default they are all activated.  fter-comma-in-block user-option activates automatic insertion of space after comma inside a block. Disabled by default.  uffer, use the <f12> ~ prefix key followed by one of these keys to toggle the electric behaviour of the key.</f12>				
Toggle , electricity	<m-f12> M-` ,</m-f12>	(pel-erlang-comma &optional GLOBALLY)	Toggle electric behaviour of the comma key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M <m-f12> M-`,</m-f12>			
Toggle automatic insertion of space after comma in block	<m-f12> M-` M-,</m-f12>	(pel-erlang-toggle- space-after-comma &optional GLOBALLY)	Toggle automatic insertion of space after comma inside blocks. Show its new state.  • To modify the behaviour in all Erlang buffers type: M <m-f12> M-` M-,</m-f12>			
Toggle > electricity	<m-f12> M-` &gt;</m-f12>	(pel-erlang-gt &optional GLOBALLY)	Toggle electric behaviour of the greater-than key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M <m-f12> M-` &gt;</m-f12>			
Toggle RET electricity	<m-f12> M-` RET</m-f12>	(pel-erlang-newline &optional GLOBALLY)	Toggle electric behaviour of the newline key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M <m-f12> M-` RET</m-f12>			
Toggle ; electricity	<m-f12> M-`;</m-f12>	(pel-erlang-semicolon &optional GLOBALLY)	Toggle electric behaviour of the semicolon key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M <m-f12> M-`;</m-f12>			
Toggle . electricity	<m-f12> M-` .</m-f12>	(pel-erlang-period & Toggle Erlang electric behaviour of the semicolon key. Show message describing its ne • To modify the behaviour in all Erlang buffers type: M <m-f12> M-` .</m-f12>				
Matching Pairs	With smartparens-mode act     This requires smartpa     Add smartparens-mode	ivated typing the opening of the opening of the opening of the open of the open of the open open open open open open open ope	pairs made of ( ), [ ], { }, " " and ' '. PEL adds the << >> pair. haracter(s) automatically inserts the closing character(s) activated by pel-use-smartparens.  minor-modes to activate smartparens-mode automatically for erlang-mode buffers.  lectric-pair-local-mode: add electric-pair-local-mode to pel-activates-minor-modes list.			
Matching pairs	[	be part of a pair. The pairs	ternal package is used and the smartparens-mode is active, the characters on the left are taken to sare: ( ), [ ], { }, " ", ' ', and << >> (added by PEL).			
∑X Smartparens	{	To enclose a piece of tex	aracter of a pair, the rest of the pair is inserted and point is left inside.  xt inside one of those pairs, mark the text area then type the first character of the pair.  can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-			
	и		ey sequence to toggle the smartparens-mode on and off.			
	<<	PEL adds support for <-	There's also the smartparens-strict-mode that imposes balanced pairs but that does not help much in Erlang. PEL adds support for << >> including navigation across balanced pairs, something the default erlang.el does not do replacing forward-sexp and backward-sexp by specialized functions.			
Insert Parentheses	M- (	(insert-parentheses &optional ARG)	For Erlang: insert a parenthesis pair '()', leaving point after open-paren. Use this when smartparens is not used.			
	No argument is equivalent to PEL makes 'parens-require-	o zero: just insert '()' and lea spaces' buffer local and set	renthesis if they are balanced. A negative ARG encloses the preceding ARG sexps instead.  Ive point between. If region is active, insert enclosing characters at region boundaries.  It to nil in Erlang mode buffers, allowing the use of this command to insert the argument space between the function name and the opening parenthesis.			
New Line	RET	(erlang-electric-newline &optional ARG)	Break line at point. If electric behaviour is activated: indent, continuing comment if within one.  Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted.  Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing.			
Electric behaviour: • indent next line		The electric behaviour of this key is controlled by 2 variables:  • erlang-electric-commands must include the erlang-electric-newline symbol to activate the key electric behaviour.  • erlang-electric-newline-criteria identifies how to check whether newline should behave electric. By default, the validity makes it behave electric as soon as the erlang-electric-commands list includes erlang-electric-newline.				
Electric <  • ∑X Smartparens	<	(erlang-electric-lt &optional ARG)	Insert a less-than sign, and optionally mark it as an open paren.  • When smartparens-mode is active << automatically inserts the closing pair.			
Electric > Electric behaviour: • new line & indent	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.  • Electric behaviour: -> force new line and indent.  • With PEL, you can also type -> without electric behaviour by typing See below.			
	M-1 >		Disable electric behaviour for this character: Just insert > by typing M-1 >			
Insert -> by typing		(pel-erlang-electric- period &optional arg)	Insert -> when typing if the following conditions are met:  • period is included in the pel-erlang-electric-keys user-option value  • point is inside code and dash does not follow \$, as in \$-  • In all other cases, typing produces			
Electric comma Electric behaviour: • new line & indent • space after comma in	M-1 ,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly:  • a new indented line when the comma is at the end of an <u>Erlang expression</u> .  • a space if inside a block and <u>pel-erlang-space-after-comma-in-block</u> user-option is on.  Disable electric behaviour for this character: Just insert , by typing M-1 ,			
block Electric semicolon	;	(erlang-electric-	Insert a semicolon character and possibly a <u>function clause head</u> prototype on the next line.			
Electric behaviour: • insert clause function header		semicolon &optional ARG)	<ul> <li>Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.</li> <li>Inserts a function clause head prototype when the selection criteria identified by erlangelectric-comma-criteria indicates that it should be done.</li> </ul>			
		-	olon-insert-blank-lines sets # of lines inserted between the current line & new function header.			
See: National See: Inserting Text	• - • <kp-subtract></kp-subtract>	(smart-dash-insert)	Insert underscore following [A-Za-z0-9_], dash otherwise. See: <u>Note Inserting Text</u> Requires the <u>smart-dash</u> external package. PEL activates it with <u>pel-use-smart-dash</u> , or when smart-dash-mode is in <u>pel-erlang-activates-minor-modes</u> .			
Standard delete forward character	• <deletechar> • ☒</deletechar>	(delete-forward-char N &optional KILLFLAG)	Delete the following N characters (previous if N is negative).  If Transient Mark mode is enabled, the mark is active, and N is 1, delete the text in the region and deactivate the mark instead.  To disable this, set variable 'delete-active-region' to nil.  Interactively, N is the prefix arg, and KILLFLAG is set if N was explicitly specified.  When killing, the killed text is filtered by 'filter-buffer-substring' before it is saved in the kill ring, so the actual saved text might be different from what was killed.			
Delete forward, jump over block pair until block is empty then delete block  • <u>X</u> Smartparens with smartparens-	• <deletechar> • ☒</deletechar>	( <b>sp-delete-char</b> &optional ARG)				
mode active			closing delimiter whose deletion would break the proper pairing is hit.			

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Standard delete backward character	• DEL • 🗵	(backward-delete-char- untabify ARG &optional KILLP)	Delete characters backward, changing tabs into spaces.  Delete ARG chars, and kill (save in kill ring) if KILLP is non-nil.  Interactively, ARG is the prefix arg (default 1) and KILLP is t if a prefix arg was specified.  The exact behavior depends on 'backward-delete-char-untabify-method'.	
Delete backward, jump over block pair until block is empty then delete block  • <u>S</u> * Smartparens with smartparensmode active	• DEL • ⟨⊠	(sp-backward-delete- char &optional ARG)	Same as above with the additional behaviour:  If on a closing delimiter, move backward into balanced expression.  If on an opening delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression.  If the delimiter does not form a balanced expression, it will be deleted normally.  With a numeric prefix argument N = 0, simply delete a character backward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, delete characters backward until an opening delimiter whose deletion would break the proper pairing is hit.	
Erlang Comments  • Erlang Programming Rules & Conventions See also: Comments				
Comment/un-comment • PEL extension of comment-dwim specialized for Erlang.	M-;	(comment-dwim ARG) (pel-erlang-comment-dwim &optional ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.  Does the same but adds ability to insert %%% comments. It does that on the very first line in the buffer and lines that follow a line that starts with %%%.	
Automatically uses the %%% comment when appropriate.  **  Note:  M-; works much	With marked un-commented     With marked commented re	On first em On line wit d region: Comment region gion: Un-comments the		
better than C-c C-c and C-c C-u • PEL maps M-; to	➤ The erlang.el code binds M	-1 to indent-for-comment.	However PEL uses M-1 for something else. s indent-for-comment if nothing is marked.	
pel-erlang-comment- dwim which works even better.	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just <b>C-u</b> prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.	
See also: <u><b>∑</b> Comments</u>	<ul> <li>The comment start is identified by 'comment-start' and 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'.</li> <li>By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.</li> </ul>			
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.	
Toggle display of comments in buffer or active region See also: Comments	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer.  • Requires the <a href="https://hide-comnt.el">hide-comnt.el</a> package <a href="https://package">PEL activates it with pel-use-hide-comnt</a>	
Filling Text See also:  Filling/Justification	<ul> <li>Filling Erlang code does r</li> <li>The fill-column variable cor</li> </ul>	not work as it treats code as atrols where text wraps.	buffer: code and comment. The auto-fill command will automatically wraps code and comments. s normal text. But filling comment paragraphs is useful.  ue. Use set-fill-column (C-x f) to set it. Toggle a vertical line that shows it with <f11> 8.</f11>	
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point.  • To justify as well: C-u M-q  • In auto fill mode the text filling is done at the end of the line.	
Indentation	All syntactic indentation control for Erlang is controlled by the CC-Mode logic and provided commands listed below.  • Rigid indentation commands are also available and listed at the end of this list. They are also listed in the ∑ Indentation table.			
Indent current line or region	<tab></tab>	(indent-for-tab- command &optional ARG)	Indent active region, current line, or block starting on this line.	
See also: Indentation  Erlang Guidelines: Ericsson AB: try to limit most code to 2 levels of indentation. Inaka: indentation level = 2 space chars.	<ul> <li>The indentation level is controlled by the erlang-indent-level user-option. Its default is 4.</li> <li>Access its custom group buffer using <f12> <f3> 1 or <f11> SPC e <f3> 1. Or use <f11> <f2> g erlang RET.</f2></f11></f3></f11></f3></f12></li> <li><tab> performs syntactic indentation.</tab></li> <li>In Transient Mark mode, when the region is active, reindent the region.</li> <li>Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.</li> <li>Otherwise reindent just the current line.</li> <li>You can type <tab> anywhere in the line to indent the current line or everything in the marked area if a block is marked.</tab></li> <li>Note that the erlang.el logic doubles the indentation label inside funs. See this S.O. discussion on that.</li> <li>To indent rigidly you can use:</li> <li>(pel-indent-rigidly &amp;optional N) (bound to C-x <tab> and to <f11> <tab> <tab> <tab> tab&gt; <tab> to indent the line or region rigidly.</tab></tab></tab></tab></f11></tab></li> </ul>			
Indent complete buffer	• (tab-to-tab-stop), bour	nd to <b>M-i</b> to insert spaces (erlang-indent-current-	to the next tab stop column.  Indent current buffer as Erlang code.	
Indent Erlang function	C-c C-q <f12> f <tab></tab></f12>	buffer) (erlang-indent-function)	Works on the entire buffer, even if it is narrowed.  Indent current Erlang function. Point can be located anywhere inside the function.	
Indent function clause	<f12> f <tab></tab></f12>	(erlang-indent-clause)	Indent current Erlang clause. Point can be located anywhere in the Erlang clause.	
Indent lines of list after point See also: ∑ Indentation	C-M-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point.  When interactively called with prefix, indent the enclosing function instead.	
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.  • A numeric prefix argument specifies a column: indent each line to that column.  • With no prefix argument, the command chooses one of these methods and indents all the lines with it:  1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.  2. If 'indent-region-function' is non-nil, call that function to indent the region.  3. Indent each line via 'indent-according-to-mode'.  When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>	
Outline Erlang Code See <u>▼ Outline</u>	Once the minor mode is active This is very useful to quick	you can collapse and expa y see an outline of the code	the Erlang buffer into an outline of function definitions.  — outline-regex & outline-level and code as outlines and navigate using the outline commands. See the key bindings in <u>Outline</u> in a large file. Using the outline-hide-other is particularly effective.  > key prefix when the outline-minor-mode is active.	
Toggle outline minor mode	<f11> M-1</f11>	(outline-minor-mode &optional ARG)	Toggle Outline minor mode.  • Enable with a prefix positive argument ARG, disable with negative argument.	

See also:  ■ Notice the 3 sets of commands:  ■ Navigation  ■ Moving by Defuns  ■ Moving by Defuns  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparis	<u>N</u>	Function	<u>Keystroke</u>	Description
• to start of function  • Go backward to beginning of the previous function of previous function as the property of previous function  • Go forward to beginning of next function  • Go forward to beginning of next function  • Ce C -G C -F	Several commands are specialization of the normal navigation commands which are described in the table <u>Navigation</u> , but several are specific to Erlar  Notice the 3 sets of commands:  1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives.  2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives.  3. The <f12> <m-cursor> commands (also accessible via <m-f12> <m-cursor>, move across Erlang clauses (as opposed to functions).  The list below describe the specialized commands only. See the others inside <u>Navigation</u>, like the navigation by blocks.  Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity.</f11></f12></m-cursor></m-f12></m-cursor></f12></f6></down></f12></up></f12>			
Continued to beginning of the previous function supplied functions	npiler directives. Skips clauses.	on beginning/end at/skippir	Move to next/previous funct	• By <u>Function</u> • Mo
Seginaring of previous function	Move to beginning of function			
C-c C-d C-b (feri-goto-previous-function)  • Go forward to beginning of next function  • C+212> <a href="cellpass">document of the previous function." Sixps all compiler directives.  • C+212&gt; fin.  • C+212&gt; <a href="cellpass">cellpass all compiler directives.</a>  • C+212&gt; fin.  • C-2 c</a>	oves point to the first character of the function that the function prefix argument N repeat N times.		• <f12> f p</f12>	beginning of e <f< td=""></f<>
• Go forward to beginning of next function  • <pre> • Go forward to beginning of next function beginning of next function  • <fi> &lt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; f</fi></pre>	ift marking is available for the key sequence		• <f11> SPC e f p</f11>	• <f< td=""></f<>
Soptional N	ips all compiler directives.		C-c C-d C-b	С-с
• f11> SPC e f n	oves point to the first character of the function the prefix argument N repeat N times.	u	• <f12> f n</f12>	beginning of next function
* Lo start of function/directive     ** Move to beginning of function or compiler directive     ** C-N-a				
## Go backward to beginning of previous:  * Go backward to beginning of previous:  * C-N-a  * C-N-a  * C-N-chome>  * C-N-chome>  * C-R-chome>	ips all compiler directives.	(ferl-goto-next-function)	C-c C-d C-f	С-с
beginning of previous:	Move to beginning of function or compiler directive			
• C-M-a • tunction • tunction • compiler directive • <pre></pre>	0 0		<f12> f P</f12>	
defun &optional SILENT   Lunction   compiler directive   - (f11) SPC of N   - (f5) < down>   - (f5) < down>   - (f5) < down>   - (f11) SPC of N	ginning of defun. ift marking is available in graphics mode, r ome>). However <f6> p and <f6> &lt;</f6></f6>	(erlang-beginning- of-function	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	previous:     function     compiler     directive
• function • compiler directive • *f6> a			<f12> f N</f12>	
Backward to end of previous:	he beginning of next function is found, pus DNT-PUSH_MARK is non-nil. Move back to previous position with M-`.		• <f6> <down></down></f6>	• function • <f< td=""></f<>
of previous:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function definition.  - Shift marking is available for the <f6> bindings.  - With a numerical argument of to the that many times.  - Forward to line after end of Erlang function.  With a numerical argument repeat that many times.  - Forward to line after end of defun.      • Forward to line after end of defun.      • Flang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang function.  - Shift marking is available in graphics mode, not in terminal mode erlang function.  - Forward to line after end of Erlang function.  - Forward to line after en</f6>	Move to end of function or compiler directive			
next:     • function     • compiler directive      • By Expression     • functions, etc      • Go to beginning of statement      • Go to end of statement      • Go to end of statement      • Go to end of statement      • Cf12> s e      • Cf6> <right>      • Cf6&gt; <right>      • Cf6&gt; <right>      • ARG)     (erlang-end-of-function &amp; optional ARG)      • With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.      • Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-i     // End&gt;      • With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.      • Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-i     // End&gt;      • Note that in Erlang every single expression or expression sequence ends with a period. Expressions in expression sequences are separated by comparison or expressions in a sequence of expressions.      • Go to beginning of statement      • Go to beginning of statement      • Go to end of statement      • Go to end of statement      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.</right></right></right>	eps if does not find end of previous function he end of previous function is found, push ISH_MARK is non-nil. Move back to previous position with M-`.	defun &optional SILENT	<f6> <left></left></f6>	of previous:     • function     • compiler
<ul> <li>functions, etc</li> <li>The following commands move to the beginning/end of single expression or expression sequence.</li> <li>They do not move across expressions in a sequence of expressions.</li> <li>Since Erlang function definition is also an Erlang expression, these commands move across function definitions.</li> <li>Go to beginning of statement</li> <li>M-a</li> <li>(backward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	argument, do it that many times. Negative eding end of defun. nift marking is available in graphics mode,	ARG) (erlang-end-of- function & optional	• C-M- <end></end>	next: • function • compiler
<ul> <li>statement</li> <li><f12> s a</f12></li> <li>Go to end of statement</li> <li>M-e</li> <li>(forward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	xpression or expression sequence.	e to the beginning/end of sin pressions in a sequence of	The following commands move  • They do not move across ex	• functions, etc The f
statement <pre>statement</pre> <pre></pre>				statement
By <u>Function Clause</u> Move by clauses of a function. A function definition (statement) may have multiple clauses, each separated by a semicolon.		,		statement
	may have multiple clauses, each separate	A function definition (stater	Move by clauses of a function.	By Function Clause Move
• Go backward to beginning of clause • <pre></pre>	th argument, do this that many times.		• <f12> c a</f12>	beginning of clause • <f< td=""></f<>
• Go forward to beginning of next clause  • <f12> c n • <m-f12> <m-down> clause  • <f12> c n • <m-f12> <m-down> clause  • Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M-`.  ⇒Shift marking is available.</m-down></m-f12></f12></m-down></m-f12></f12>	shes mark; move back to previous position			beginning of next • <n< td=""></n<>
• Go backward to end of previous clause  • <f12> c p • <m-f12> <m-left>  (pel-end-of-previous-clause)  Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−`.  Shift marking is available.</m-left></m-f12></f12>	shes mark; move back to previous position		<del>-</del>	
• Go forward to end of current clause • <f12> c e • <m-right>  (erlang-end-of-clause &amp; optional ARG)  Move to the end of the current clause. • With argument, do this that many times.  Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.</m-right></f12>	th argument, do this that many times.	,	• <f12> c e</f12>	current clause • <f< td=""></f<>

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Block Navigation	<ul> <li>( ) for function p</li> <li>{ } for tuples, re</li> <li>[ ] for lists</li> <li>" " for strings</li> <li>&lt;&lt; &gt;&gt; for binaries a</li> </ul>	erameters, expression groue ecords, maps and bitstrings			
See also:  • <u>XX Smartparens</u>	• Use the <f11> ( key so Standard Erlang support provi</f11>	equence to toggle the smar de some commands to navi	for Erlang by adding erlang-mode to the <b>pel-erlang-activates-minor-modes</b> user-option. tparens-mode on and off. gate across and into these balanced blocks. Their name is shown in <b>black</b> in the following rows. en smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code.		
To Block start/end	The following commands mov	e to the beginning or end of	a block, skipping over Erlang terms inside these blocks.		
Go backward to beginning of previous block     Skips terms.	• С-м-р	(backward-list &optional ARG)	Move backward to beginning of previous block.  • Supports blocks of (), [] and {}.  • With ARG, do it that many times.  • A negative argument N means forward-list N.  • This command assumes point is not in a string or comment.		
			<pre>-spec ejabberd_started 6() -&gt; ok. ejabberd_started 5() -&gt;     gen_server:call 4(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -spec config_reloaded 3() -&gt; ok. config_reloaded 2() -&gt;     gen_server:call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT).0</pre>		
Go backward to end of previous block     Skips terms.     ∑x Smartparens with smartparensmode active	<m-f7> p</m-f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block.  • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp').  • A negative argument N means move to the end of N-th following balanced expression.  -spec ejabberd_started()		
Go forward to end of next block     Skips terms.	• С-М-п	(forward-list &optional ARG)	Move forward to end of next block.  Supports blocks of (), [] and {}.  With ARG, do it that many times.  A negative argument N means forward-list N.  This command assumes point is not in a string or comment.		
Go forward to beginning of next block     Skips terms.     ∑X Smartparens with smartparensmode active	<m-f7> n</m-f7>	(pel-sp-next-sexp &optional ARG)	Move forward to <b>beginning</b> of next block (and term if 'sp-navigate-consider-symbols' is set).  • With ARG, do it that many times.  • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp').  O-spec ejabberd_started1() -> ok.  ejabberd_started2() ->  gen_server:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -spec config_reloaded4() -> ok.  config_reloaded5() ->  gen_server:call6(?MODULE, config_reloaded, ?CALL_TIMEOUT).		
By Blocks and Terms	Several Linux distros map change Linux key binding in S	<pre><left> and Esc C-<righ c-m-<left=""> and C-M-<r: ystems-="">settings-&gt;keyboard</r:></righ></left></pre>	b stops at terms.  **E> bindings below, set pel-windmove-on-esc-cursor user-option is set to nil.  **ight> to desktop workspace operation. In that case you can either use another key binding or d->shortcuts to prevent it from using that key sequence.  **e ability to move across Erlang's << >> bit syntax statement blocks.		
Go backward to beginning of previous term/block	• C-M- <left> • C-[ C-b • Esc C-b • Esc C-<left>   • C-M-b</left></left>	(pel-erlang-backward- sexp &optional ARG)	Move backward backward to beginning of previous term or block.  • With ARG, do it that many times.  • A negative arg N means move forward to end of N terms/blocks.  • At beginning of block, jump out of the current one.  • This command assumes point is not in a string or comment.  • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.  • C-M-b : ► Shift marking is available in graphics mode, not in terminal mode.  • C-M- <left> : ► Shift marking works with this command.  • C-M-<left> does not work on Windows, but H-<left> works.</left></left></left>		
The street of the street	• C-M-b • <m-f7> b</m-f7>	(sp-backward-sexp &optional ARG)	Same as above with the additional behaviour:  • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.  • When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms.  -spec ejabberd_started() -> ok. ejabberd_started() -> gen_server:call 9 (?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -8 spec 7 config_reloaded 6() -> 5 ok. 5 config_reloaded 4() -> 3 gen_server: 2 call 1 (?MODULE, config_reloaded, ?CALL_TIMEOUT).0 Inside a block:		
			gen_server:call(?3MODULE, 2ejabberd_started, ?1CALL_TIMEOUT0).		

Description	<u>Keystroke</u>	Function	<u>Note</u>
Go forward to end of next term/block	• C-M- <right> • C-[ C-f • Esc C-f • Esc C-<right></right></right>	(pel-erlang-forward- sexp &optional ARG)	Move forward to end of term or block.  • With ARG, do it that many times.  • A negative argument N means move backward to beginning of previous term or block.  • At end of block, jump out of the current one.  • C-M-n : Shift marking is available in graphics mode, not in terminal mode.  • C-M-f : Shift marking is available in graphics mode, not in terminal mode.  • C-M- <right> : Shift marking works with this command.  • C-M-<right> does not work on Windows, but H-<right> does.</right></right></right>
Sx Smartparens     with smartparens- mode active:     C-M-f and <m- f7=""> f use sp- forward-sexp,     others are using forward-sexp</m->	• C-M-f • <m-f7> f</m-f7>	(sp-forward-sexp &optional ARG)	Same as above with the additional behaviour:  • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.  • When it is nil, point only stops at 3, 6 and 9 it jumps over terms.  O-spec1 ejabberd_started2()3 -> ok4.  ejabberd_started5()6 ->  gen_server7:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT)9.  -spec10 config_reloaded() -> ok.  config_reloaded() -> gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
Into block	Navigate inside nested blocks	of elements with the follow	ing commands.
Into block forward	C-M-d	(down-list &optional	Move forward to the beginning of inner element of a block.
Sx Smartparens     with smartparens- mode active	• C-M-d • <m-f7> d</m-f7>	(sp-down-sexp &optional ARG)	<ul> <li>With ARG, do this that many times.</li> <li>A negative argument N means move backward but still go down a level.</li> <li>If ARG is raw prefix argument C-u, descend forward as much as possible.</li> <li>If the RAG is raw prefix argument C-u C-u, jump to the beginning of current list.</li> <li>If the point is inside block and there is no down expression to descend to, jump to the beginning of current one. If moving backwards, jump to end of current one.</li> <li>music_info() -&gt;  [a] {2error, {anoreply, State}},</li></ul>
Into block backward  • <u>SX Smartparens</u> with smartparens- mode active	• <m-f7> z • C-M-z</m-f7>	(sp-backward-down- sexp &optional ARG)	<pre>frating, excellent}}}.  Move backward down one level to end of block element.  • With ARG, do this that many times.  • A negative argument N means move forward but still go down a level.  • If ARG is raw prefix argument C-u, descend backward as much as possible.  • If ARG is raw prefix argument C-u C-u, jump to the end of current list.  • If the point is inside sexp and there is no down expression to descend to, jump to the end of current one. If moving forward, jump to beginning of current one.  music_info(1) -&gt;  ②{{error, {noreply, State}},</pre>
to edge of block			·
To beginning of block  • <u>∑</u> * Smartparens with smartparens- mode active	• <m-f7> a</m-f7>	(sp-beginning-of-sexp &optional ARG)	Jump to beginning of the block the point is in.  The beginning is the point after the opening delimiter.  With no argument, this is the same as C-u C-u 'sp-down-sexp'  With ARG positive N > 1, move forward out of the current expression, move N-2 expressions forward and move down one level into next expression.  With ARG negative N < 1, move backward out of the current expression, move N-1 expressions backward and move down one level into next expression.  With ARG raw prefix argument C-u move out of the current expressions and then to the beginning of enclosing expression.  music_info() -> {{error, {noreply, State}}, {good, {{1year, 19074},
To end of current block  • forward  • ∑x Smartparens with smartparens- mode active	<m-f7> e</m-f7>	(sp-end-of-sexp &optional ARG)	Jump to end of the current block.  • With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'.  • With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression, move N-2 expressions backward and move down backward one level into previous expression.  • With ARG negative N < 1, move backward one level into previous expression.  • With ARG raw prefix argument C-u move out of the current expressions and then to the end of enclosing expression.  music_info() ->  {

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Out of block			
Out block forward • forward	C-M-]  • C-M-]  • <m-f7> ]</m-f7>	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING) (sp-up-sexp &optional ARG INTERACTIVE)	Move forward out of one level of block parens.  With ARG, do this that many times.  A negative argument means move backward but still to a less deep spot.  If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between end of the expression and the last "thing" inside the
<u>XX Smartparens</u> with smartparens-     mode active		,	expression.  This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-after-up-in-string' to nil.  If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions automatically.
			<pre>music_info() -&gt;     {{er Oror, {noreply, State}}1,</pre>
Out block backward  • backward	• <m-f7> u • C-M-u</m-f7>	(sp-backward-up-sexp &optional ARG INTERACTIVE)	Move backward out of one level of block parens.  With ARG, do this that many times.  A negative argument means move forward but still to a less deep spot.  If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the
X Smartparens with smartparens- mode active			<pre>expression.  music_info() -&gt;</pre>
Move over space	Current implementation of	sp-forward-symbol and sp- tegrated PEL implement wo	rage and required smartparens-mode minor-mode to be active.  -backward-symbol stop inside comments. I consider this a bug so I reported and submitted a brikaround commands that do not stop inside comments: pel-sp-forward-symbol and pel-speuntil the fix is integrated.
To beginning of next symbol/block	<m-f7> SPC n</m-f7>	(sp-skip-forward-to- symbol &optional STOP- AT-STRING STOP-	Skip whitespace and comments moving forward.  • If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string).  • If STOP-AFTER-STRING is non-nil, stop after exiting a string.  • If STOP-INSIDE-STRING is non-nil, stop before exiting a string.
<u>XX Smartparens</u> with smartparens-     mode active		AFTER-STRING STOP-INSIDE-STRING)	<pre>start_app(App) -&gt; 0</pre>
To end of next symbol or block  • <u>**** Smartparens</u> with smartparens-mode active	<m-f7> SPC m</m-f7>	(pel-sp-forward-symbol &optional ARG)	Move point to the next position that is the end of a symbol.  With ARG being positive number N, repeat that many times.  With ARG being negative number -N, repeat that many times in backward direction.  A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes.
See <b>**** ***</b> note above.			<pre>start_app(App) -&gt; % first clause     start_app(AppO, temporary1).  start_app(AppO, Type1) -&gt; % second clause     StartFlag2 = not3 is_loaded4(),     start_app5(App6, Type7, StartFlag8).</pre>
To beginning of previous  • <u>**** Smartparens</u> with smartparens-	<m-f7> SPC p</m-f7>	(pel-sp-backward- symbol &optional ARG)	Move point to the next position that is the beginning of a symbol.  With ARG being positive number N, repeat that many times.  With ARG being negative number -N, repeat that many times in forward direction.  A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
mode active  See im in note above.			<pre>classes. 8start_app(7App) -&gt; % first clause 6start_app(5App, 4temporary).</pre>
			<pre>3start_app(2App, 1Type) -&gt; % second clause  0StartFlag = not is_loaded(),     start_app(App, Type, StartFlag).</pre> <pre>     ** example</pre>
Skip forward past whitespace	<m-f7> SPC .</m-f7>	(sp-forward-whitespace &optional ARG)	Skip forward past the whitespace characters.  • With non-nil ARG return number of characters skipped.
<u>XX Smartparens</u> with smartparens-     mode active			<pre>start_app(App) -&gt; 0</pre>
Skip backward past whitespace	<m-f7> SPC ,</m-f7>	(sp-backward- whitespace &optional ARG)	Skip backward past the whitespace characters.  • With non-nil ARG return number of characters skipped.
<u>X</u> Smartparens     with smartparens- mode active			<pre>start_app(App) -&gt; 1</pre>
			<pre>OStartFlag = not is_loaded(), start_app(App, Type, StartFlag).</pre>
			7

Marking         See also: ∑ Marking       These commands complement what is already available and described in the ∑ Marking table.         • The first 2 command listed below are Erlang-mode specific marking functions.       • For those 2 commands the ☑ Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.         • The useful er/expand-region benefits from PEL enhancement to erlang syntax table supporting the < > pair therefore it is also mentioned here.         Mark Erlang function       • C-M-h       (mark-defun & optional ARG)       Put mark at end of this function, point at beginning.         • The function marked is the one that contains point or follows point.       • With positive ARG, mark this and that many next functions; with negative ARG, of direction of marking.         • Vith positive ARG mark this and that many next functions; with negative ARG, of direction of marking.       • If the mark is active, it marks the next or previous function(s) after the one(s) alreaded by elementary and the part of clause, point at beginning.         Mark region by semantic unit, increase marked region on each warked region and each warked region package, ☑ activated by pel-use-expand-region	nange the dy marked.
For those 2 commands the Friang.el man page indicates an invalid mapping for this. Reported as ERL-1314.      The useful er/expand-region benefits from PEL enhancement to erlang syntax table supporting the < > pair therefore it is also mentioned here.    Mark Erlang function	nange the dy marked.
Mark Erlang function  • C-M-h  (mark-defun & optional ARG)  • <f12> f m  (erlang-mark-function &amp; optional ARG)  Mark Erlang Clause  • C-c M-h  • <f12> c m  (erlang-mark-clause)  Mark region by semantic unit, increase</f12></f12>	nange the dy marked.
ARG)  • <f12> f m  (erlang-mark-function &amp; optional ARG)  • C-c M-h • <f12> c m  (erlang-mark-clause)  • Mark Erlang Clause  • Mark region by semantic unit, increase</f12></f12>	dy marked.
• <f12> f m  (erlang-mark-function &amp; optional ARG)  • With positive ARG, mark this and that many next functions; with negative ARG, clairection of marking. • If the mark is active, it marks the next or previous function(s) after the one(s) alreaded the mark at end of clause, point at beginning.  • Mark region by semantic unit, increase  • M—=  (er/expand-region ARG)  • With positive ARG, mark this and that many next functions; with negative ARG, clairection of marking. • Unit mark at end of clause, point at beginning.  • M—=  (er/expand-region ARG)  • Min positive ARG, mark this and that many next functions; with negative ARG, clairection of marking. • Unit mark at end of clause, point at beginning. • Mark region by semantic unit, increase</f12>	dy marked.
Mark Erlang Clause  • C-c M-h • <f12> c m  Mark region by semantic unit, increase  * M-=  **Requires the expand-region package.**  **Requires the expand-region package.**  **Requires the expand-region package.**  **Activated by nel-user-expand-region package.**  **Requires the expand-region package.**  **Activated by nel-user-expand-region.**</f12>	
• <f12> c m  Mark region by semantic unit, increase  • M-=  (er/expand-region ARG)    Increase selected region by semantic units.   Requires the expand-region package   Activated by nel-use-expand-region    </f12>	<b>n</b> user
Mark region by semantic unit, increase selected region by semantic units.  (er/expand-region ARG) Increase selected region by semantic units.	<b>n</b> user
semantic unit, increase	<b>n</b> user
marked region on each • <f11> . =</f11>	
invocation. option.	
<ul> <li>With prefix argument expands the region that many times.</li> <li>If prefix argument is negative calls 'er/contract-region'.</li> </ul>	
• If prefix argument is 0 it resets point and mark to their state before calling 'er/expand-region' for the first time.  This command is very powerful: the first time it's typed it selects a word, if you type it again it will expand the selection, and again, and again.	Гће
expansions follow the semantics of the current major mode: it is aware of the semantics of several programming languages.  The Once M-= is typed, you can quickly type the following single keys in sequence:	
• = to expand the region,	
<ul> <li>to contract the region,</li> <li>to reset the operation.</li> </ul>	
If you wait too long, then you have to use <b>M</b> -= again to continue the expansion, otherwise the region is de-activated.  Note that you can also use the following key chords to control the contraction of the selected text without having to worry about time:	
• M— M—= to contract the region • M—0 M—= to reset the operation.	
• Also you can use the cursor keys to expand or contract the region and C-x C-x to exchange mark and point to expand the other side of the	e region with
cursors.	
The following commands provides specialized copy and cloning operations. They are provided by <u>∑x Smartparens</u> • <u>∑x Smartparens</u> • With PEL the commands that are marked with  display the copied string when pel-show-copy-cut-text is t. Toggle this display with <f.< th=""><th>11&gt; M-=</th></f.<>	11> M-=
Copy current & forward <m-f7> = (sp-copy-sexp &amp; optional Copy the following ARG expressions to the kill-ring.</m-f7>	
block(s)  ARG)  This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefi work the same way.	x arguments
Copy previous block(s)  (sp-backward-copy-sexp & optional ARG)  (sp-backward-copy-sexp & optional ARG)  Copy the previous ARG expressions to the kill-ring.  This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the sarguments work the same way.	pecial prefix
clone current block (sp-clone-sexp)  Clone sexp after or around point.  If the form immediately after point is a sexp, clone it below the current one and pu	ut the point in
front of it.  Otherwise get the enclosing sexp and clone it below the current enclosing sexp.	
Transform code  The following commands can be used to help transform code. Some need external packages.	
iEdit mode  iEdit Mode - Edit multiple instances of variable/symbols simultaneously.   This mode is very useful to rename symbols or variable during	refactoring.
See also: Thighlight Requires the iedit external package. PEL activates it with pel-use-iedit.	
Toggle iedit mode See also:  C−;  (iedit-mode &optional See also:  ARG)  Toggle iEdit mode: edit all symbols in scope or region simultaneously.  ARG)  Toggle iEdit mode: edit all symbols in scope or region simultaneously.  ARG)	
• <fi1> e • ∑ Cursor • ∑ Search/Replace • <fi1> m i • ARG)  ARG  ARG  Both iEdit and Flyspell use the C-; key as their default binding. • PEL detects and reports that situation: modify the binding of one of them if yo • See ∑ Search/Replace where all the iedit-mode commands are described.</fi1></fi1>	u see it.
Align arrows inside c-c c-a (erlang-align-arrows START END)  Align arrows ("->") in function clauses inside marked region or in the current function clauses inside marked region or in the current function of the region (" -> ") in function clauses inside marked region or in the current function of the region or in the region or in the region or in the region or in the current function clauses inside marked region or in the current function of the region or in the region or in the region or in the current function of the region or in the current function of the region or in the region or in the current function of the region or in the region	
point), not just those in function clauses.	or up to
Before: After C-c C-a: sum(L) -> sum(L, 0). sum(L) -> sum(L, 0).	
<pre>sum([H T], Sum) -&gt; sum(T, Sum + H);</pre>	
To align something else Before: After C-u C-c C-a:	
than clauses, select the check(P, [H T]) -> check(P, [H T]) -> code and type: case P(H) of case P(H) of	
C-u C-c C-a true -> 1; true -> 1; false -> 0 false -> 0	
end; end;	
Transpose block elements (sp-transpose-sexp & optional ARG)  (sp-transpose-sexp & optional ARG)  (sp-transpose-sexp & optional ARG)  Transpose the expressions around point.  • The operation will move the point after the transposed block, so the next transpose optional ARG.	se will "drag"
it forward.  • With arg positive N, apply that many times, dragging the expression forward.	
• With arg negative -N, apply N times backward, pushing the word before cursor backward, pushing the word backward, pushing the	
Before (for all following examples):	
AList = [1, 2, 3, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].  After <m-f7> t:</m-f7>	
AList = [1, 2, [10,11,12,[22,33,44]], 3 , 5, 6, 7, 8,[]].  After M-2 < M-f7> t:	
AList = [1, 2, [10,11,12,[22,33,44]], 5, 3 , 6, 7, 8,[]].	
Before (for all following examples): AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8	,[]].
After <m-f7> t: AList = [[10,11,12,[22,33,44]], {first,[1, 2, 3]} , 5, 6, 7, 8</m-f7>	,[]].
After M-2 <m-f7> t: AList = [[10,11,12,[22,33,44]], 5, {first,[1, 2, 3]} , 6, 7, 8</m-f7>	,[]].
Before (for all following examples):	
AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8 After M <m-f7> t:</m-f7>	
AList = [{first,[1, 3 , 2]}, [10,11,12,[22,33,44]], 5, 6, 7, 8	,[]].
Push current block after next (sp-push-hybrid-sexp)   Push the hybrid sexp after point over the following one.    Before: After <m-f7> s:</m-f7>	
* ** ** ** ** ** ** ** ** ** ** ** ** *	
mode active [10,11,12,[22,33,44]], [3, 6, 7, 8,[], 5, 6, 7, 8,[]].	,44]]].

<u>Description</u>	<u>Keystroke</u>	Function	No	ote
Transform - slurp	The following commands perf	orm slurping operations, hor	wever support for Erlang could be improved as the	e commands do not always work properly.
Enclose next outside element into current block  • <u>Sx Smartparens</u>	nent into current ck		Add sexp following the current list in it by movin.  If the current list is the last in a parent list, exter we can extend a list or end of file).  If ARG is N, apply this function that many time.  If ARG is negative -N, extend the opening pair.  If ARG is raw prefix C-u, extend all the way to lif both the current expression and the express together.  This command does not always work well for use the next command for Erlang in those	end that list and possibly apply recursively until es. r instead (that is, backward). the end of the parent list. sion to be slurped are strings, they are joined r Erlang as shown in the first example.
		smartparens by itself fails to process these examples properly.  PEL fixes the behaviour by using ability to post-process code to ensure correct syntax.	<pre>Before: Names = [ ]Joe.  Before: AList = [[1, 2, 3  ], 4, 5].  Before: AList = [1, 2, 3,</pre>	After <m-f7> &gt;: Names = [ Joe].  After <m-f7> &gt;: AList = [[1, 2,  3, 4], 5].  After M <m-f7> &gt;: AList = [1, 2, [3,</m-f7></m-f7></m-f7>
Enclose previous outside element(s) into next block	<m-f7> &lt;</m-f7>	(sp-backward-slurp- sexp &optional ARG)  The position of point inside the list does not	Add the sexp preceding the current list in it by m  If the current list is the first in a parent list, ext we can extend a list or beginning of file).  If arg is N, apply this function that many times  If arg is negative -N, extend the closing pair in  If ARG is raw prefix C-u, extend all the way to  If both the current expression and the express together.  Before:  AList = [0, 1, [2, 3], 4], 5].	end that list (and possibly apply recursively until
		matter. The point does not move.  Before: AList = [-2, -1, 0,	Before: AList = [0, 1, [2, 3 , 4], 5].  After C-u <m- alist="[[-2,&lt;/td"><td>After M-2 <m-f7> &lt;: AList = [[0, 1, 2, 3 , 4], 5].  -f7&gt; &lt;: -1, 0, 1, 2, 3, 4 ], 5].</m-f7></td></m->	After M-2 <m-f7> &lt;: AList = [[0, 1, 2, 3 , 4], 5].  -f7&gt; &lt;: -1, 0, 1, 2, 3, 4 ], 5].</m-f7>
Enclose next element(s) into previous block  •	<m-f7> }</m-f7>	(pel-sp-add-to-previous-sexp & optional ARG)  smartparens by itself fails to process these examples properly.  PEL fixes the issues with post processing and wrapping function.	Add the expression around point to the first list p  With ARG positive N add that many expressio  If ARG is raw prefix argument C-u add all expressio is list.  If ARG is raw prefix argument C-u C-u add the sefore:  AList = [0, 1, [2, 3],  4, 5].  Before:  AList = [0, 1, [2, 3],  4, 5].	ns to the preceding list. ressions until the end of enclosing list to the
Enclose previous outside element(s) into next block  •  \( \sum \pi \times \text{Smartparens} \) with smartparensmode active	<m-f7> {</m-f7>	(sp-add-to-next-sexp &optional ARG)  This command works fine in Erlang for the following code examples:	Add the expressions around point to the first list  • With ARG positive N add that many expressio  • If ARG is raw prefix argument C-u add all expression  • If ARG is raw prefix argument C-u C-u add the self-argument	Inst to the following list.  ressions until the beginning of enclosing list to  recurrent list into the following list.  After <m-f7> {:     AList = [1,  [2, 3, 4]].  After C-u <m-f7> {:     AList = [[1,  2, 3, 4]].  After C-u <m-f7> {:     After C-u C-u <m-f7> {:</m-f7></m-f7></m-f7></m-f7>
Transform - harf	The following commands extra	act members from block		AList = [[[1,  2], 3, 4]].
Eject next element(s) out of current block  • <u>S</u> * Smartparens with smartparens- mode active	out of current block  • \( \sum_{x} \) Smartparens  with smartparens-	(sp-forward-barf-sexp &optional ARG)	Remove the last sexp in the current list by movin  If ARG is positive number N, barf that many ex  If ARG is negative number -N, contract the op  If ARG is raw prefix C-u, barf all expressions for and place the point before the closing delimiter  If the current list is empty, do nothing.	xpressions. ening pair instead. rom the one after point to the end of current list
		smartparens by itself fails to process these examples properly.  PEL fixes the issues with post processing.	Before: AList = [[1,  2, 3, 4]].  Before: AList = [[1,  2, 3, 4]].  Before: AList = [[1,  2, 3, 4]].	After <m-f7> /: AList = [[1,  2, 3], 4].  After M-2 <m-f7> /: AList = [[1,  2], 3, 4].  After M <m-f7> /: AList = [1,  [2, 3, 4]].</m-f7></m-f7></m-f7>
Eject previous element(s) out of current block • <u>SX Smartparens</u> with smartparens	<m-f7> M-/</m-f7>	(sp-backward-barf-sexp &optional ARG)  This command works fine		sing pair, the opening pair is contracted. For sp-forward-barf-sexp'.  After <m-f7> M-/:</m-f7>
with smartparens- mode active		in Erlang for the following code examples:	AList = [[1,  2, 3, 4]].  Before: AList = [[1,  2, 3, 4]].	AList = [1,  [2, 3, 4]].  After M-3 < M-f7> /:  AList = [1,  2, 3, [4]].

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Re-wrap block	Use the following commands t	o change the wrapping cha	g character pair surrounding a block		
Re-wrap current block  • <u>§ £ Smartparens</u> with smartparens- mode active	<m-f7> r</m-f7>	(sp-rewrap-sexp PAIR &optional KEEP-OLD) This command works fine in Erlang for the following code examples:	With C-u, keep old delimiter	r and wrap with PA	cter. Prompt for the pair beginning character.  IR on the outside of the current expression.  After <m-f7> r {:  AList = [{1,  2, 3, 4}]</m-f7>
		, sour enance,	Before: AList = [[1,  2, 3, 4]]		After C-u <m-f7> r {: AList = [{[1,  2, 3, 4]}]</m-f7>
Swap current block and parent block wrapping	<m-f7> w</m-f7>	(sp-swap-enclosing- sexp &optional ARG)	Swap the enclosing delimiters • With N > 0 numeric argumer		ent expression.
characters  • <u>SX Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	AList = ({[1,  2, 3, 4]	}).	After <m-f7> w: AList = ([{1,  2, 3, 4}]).</m-f7>
mode delive			<pre>Before: AList = ({[1,  2, 3, 4]}</pre>	}).	After <m-f7> w: AList = [{(1,  2, 3, 4)}].</m-f7>
Un-wrap block					
Extract all elements from current/next block	<m-f7> U</m-f7>	(sp-unwrap-sexp &optional ARG)	Un-wrap current or next block.  With ARG N, unwrap Nth ext  If ARG is negative -N, unwrap	pression as returne	ed by 'sp-forward-sexp'. backwards as returned by 'sp-backward-sexp'
<u>X Smartparens</u> with smartparens-     mode active		This command works fine in Erlang for the following code examples:	AList =  ({[1, 2, 3, 4]	}).	After <m-f7> U: AList =  [{1, 2, 3, 4}].</m-f7>
		Before:	Before: AList = ({[1,  2, 3, 4]	<pre>}). After <m-f7></m-f7></pre>	After <m-f7> U: AList = ({1,  2, 3, 4}).</m-f7>
		AList = [1,  2, [3,	4], 5, [6, 7], 8].	AList = [1,	2, 3, 4, 5, [6, 7], 8].
		Before: AList = [1, 2, [3,	4], 5, [6, 7], 8].	After M-2 <m- AList = [1,</m- 	-1/> U:  2, [3, 4], 5, 6, 7, 8].
Extract all elements from previous block	<m-f7> W</m-f7>	(sp-backward-unwrap- sexp &optional ARG)	Unwrap the previous block. Unwrap the previous expression	n.	
<u>X Smartparens</u> with smartparens- mode active	with smartparens-		With ARG N, unwrap Nth expression as returned by 'sp-backward-sexp'. If ARG is negative -N, unwrap Nth expression forward as returned by 'sp-forward-sexp'.		
		This command works fine in Erlang for the following	Before: AList = ({[1,  2, 3, 4]	}).	After <m-f7> W: AList = ({1,  2, 3, 4}).</m-f7>
		code examples:			Again After <m-f7> W: AList = (1,  2, 3, 4).</m-f7>
					Again <b>After <m-f7></m-f7></b> W: AList = 1,  2, 3, 4.
			<pre>Before: AList = [0, 1, [2,  3,</pre>	4], 5].	After <m-f7> W: List = [0, 1, 2, 3, 4, 5].</m-f7>
		Before: AList = [1, 2, [3, 4			2, [3, 4], 5, 6, 7, 8].
		Before: AList = [1, 2, [3, 4		After M-2 <m- AList = [1,</m- 	-f7> W: 2, 3, 4, 5, [6, 7],  8].
Split & Join Split block	OV 575	(sp-split-sexp ARG)	Split the list or string the point	is an into two	
<u>SX Smartparens</u> with smartparens-	<m-f7>  </m-f7>	(Sp-Spiit-Sexp And)		olit all the sexps in	current expression in separate lists enclosed
mode active	smartparens by itself fails to process the first of these examples properly.	<pre>Before: AList = [1, 2, [3, 4]</pre>		After <m-f7> AList = [1, 2</m-f7>	: , [3, 4],
	PEL fixes the issues with post processing.	<pre>Before: Name = "Joe   Armstro</pre>		After <m-f7> Name = "Joe</m-f7>	: " "Armstrong".
		Before: AList = [1, 2, [3, 4		After $C-u < M-AList = [1, 2]$	-f7>  : , [3], [4],  [5], [6], [7], 8].
Join blocks  • ∑X Smartparens  with smartparens- mode active	<m-f7> J</m-f7>	(sp-join-sexp &optional ARG)	If ARG is negative -N, join N	xpressions after the expressions before in all the terms up	e point with the one before the point. e the point with the one after the point. until the end of current expression.
		Before: AList = [0, 1, [2, 3		<pre>After <m-f7> AList = [0,</m-f7></pre>	J: 1, [2, 3, 4 <mark> </mark> , 5, 6], 7].
		Before: AList = [[0, 1] , [2		After M-2 <m- AList = [[0,</m- 	-f7> J: 1 , 2, 3, 4, 5, 6], 7].
Search Support			snake case is often used. Usin mode. To change this use the		
Toggle superword- mode  • ∑ Text Modes	<f12> M-p  • <f11> t m p</f11></f12>	(superword-mode &optional ARG)	treated as part of words.		s snake case as one word. In Erlang, '_' are node if ARG is positive, disable it otherwise.
• <u>∑ Search/Replace</u> Highlighting blocks			e useful modes to highlight bloc tches the one before or after po		
Toggle show-paren			s are highlighted with the same  Toggle visualization of matchin	colour.	aren mode).
mode on/off  See also: <u>N Highlight</u>	• <m-f12> M-9  • <f11> h (</f11></m-f12>	&optional ARG)	<ul> <li>With a prefix argument ARG otherwise.</li> </ul>	, enable Show Pare	en mode if ARG is positive, and disable it
Toggle colouring of	• <f11> SPC e M-9 • <f12> M-r</f12></f11>	(rainbow-delimiters-	highlighted in 'show-paren-s	style' after 'show-p	aren-delay' seconds of Emacs idle time. es with colours according to their depth.
nested blocks See also: <u>Neighlight</u>	• <m-f12> M-r</m-f12>	mode &optional ARG)	Customize the depth and co	lours with M-x cus	stomize-group rainbow-delimiters by pel-use-rainbow-delimiters.
	• <f11> h R</f11>		- III Januari Idanbow dominic	aonvaiou	

Description		<u>Keystroke</u>	Function	<u>Note</u>		
Edit Erlang Code		The following commands help	edit Erlang code.			
Create additional clause		C-c C-j	(erlang-generate-new-clause)	Create additional Erlang clause header.  Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.		
Clone clause arguments		С-с С-ұ	(erlang-clone- arguments)	Insert, at the point, the argument list of the previous clause.  Copy the function arguments of the preceding Erlang clause. This command is useful wher defining a new clause with almost the same argument as the preceding.  The mark is set at the beginning of the inserted text, the point at the end.		
Insert Erlang Coo with Specialized Tempo Skeletons		PEL provides the following a     Quick access keys to ins	additional functionality: ert the templates, all mappe	tons, available on the Erlang/Skeletons menu (via <f10>)  d under the pel:erlang-skel key prefix: <f12> <f12>.</f12></f12></f10>		
	-			h a +. These are also added to the menu.		
Erlang Style Control 🖝		templates affected are m	arked with a <b>C</b> . The relevant notude the following options	Style is controlled by the user options inside the <b>pel-erlang-code-style</b> group. The controlled t user options are part of the <b>pel-erlang-code-style</b> group accessible with <f12> <f2> from an : : : set whether an automatically updated timestamp is inserted in the file header block.</f2></f12>		
San alaas		pel-erlang-skel-prom     pel-erlang-skel-prom	pt-for-purpose pt-for-function-name	: set whether file and function skeletons blocks prompt for purpose and insert it. : set whether function skeletons prompt for function name and then inserts that name.		
See also:  • <u>∑ Inserting Text</u> f	or	pel-erlang-skel-prom	pt-for-function-arguments	s: set whether function skeletons prompt for function arguments and then insert them.		
more info and information about		<ul><li>pel-erlang-use-separ</li><li>pel-erlang-use-secor</li></ul>	ndary-separators	: set whether blocks use horizontal separator lines (these are the first of potentially 2 separators) : set whether blocks use a second block horizontal separator line.		
tempo skeleton and	b	<ul><li>pel-erlang-skel-with-</li><li>pel-erlang-skel-with-</li></ul>		: set whether generated code comments use EDoc markup. : set whether file header blocks use open source software license text controlled by <u>lice</u> .		
different yasnippet				But by using file and directory variables (see File/Directory Variables) they can also be used		
template-based terrinsertion).  + : additional template: C : templates with customization control	tes	to take effect on a single f If you want to change the the PEL tempo templates This allows you to control Once a skeleton was just marks) with the standard Instead of using the <f1 all="" compl="" listing="" nam<="" of="" some="" supports="" td="" template="" the=""><td>ile or all files inside a director behaviour for only one file, of for all files inside a directory the user options affecting the entered (or later by activatif tempo-mode keys C-c M-2&gt; <f12> bindings, you cetions into a separate tempes in the title column are also</f12></td><td>recovery tree. So by default, the user options that control the PEL tempo template take effect globally, write the user option control block at the end of that file. If you want to control the behaviour of tree create a .dir-locals file and store the values of the relevant options variables inside that file, here format of the tempo templates precisely and does not affect what you actually type, and the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-fand C-c M-b or some other keys like C-c and C-c, and C-c, and C-c. This is mainly useful for templates which short names such as "if", "case", etc to links to the relevant Erlang language construct reference page.</td></f1>	ile or all files inside a director behaviour for only one file, of for all files inside a directory the user options affecting the entered (or later by activatif tempo-mode keys C-c M-2> <f12> bindings, you cetions into a separate tempes in the title column are also</f12>	recovery tree. So by default, the user options that control the PEL tempo template take effect globally, write the user option control block at the end of that file. If you want to control the behaviour of tree create a .dir-locals file and store the values of the relevant options variables inside that file, here format of the tempo templates precisely and does not affect what you actually type, and the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-fand C-c M-b or some other keys like C-c and C-c, and C-c, and C-c. This is mainly useful for templates which short names such as "if", "case", etc to links to the relevant Erlang language construct reference page.		
<b>∑ Customize</b> PEL Er Skeletons layout	lang	Note that all <f12> prefixe <f12> <f12> <f2></f2></f12></f12></f12>	(pel-customize-pel &optional OTHER- WINDOW)	e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.  Customize PEL Erlang skeleton layout.  If OTHER-WINDOW is non-nil (use C-u), display in another window.</f11>		
<u>if</u>		<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.		
<u>case</u>		<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.		
export	+	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.		
import	+	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.		
try	+	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.		
try-of	+	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.		
<u>receive</u>		<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.		
after .		<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.		
loop		<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.		
<u>module</u>		<f12> <f12> m</f12></f12>	m (pel-erl-module) Insert the module attribute.			
<u>function</u>	С	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.		
author		<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.		
<u>spec</u>		<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.		
small-header	С	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.		
normal-header	С	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date		
large-header	С	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	<ul> <li>Insert a large header block that includes all normal header fields plus separators.</li> <li>All formatting is controlled by user-options described above.</li> <li>Distinguish Erlang .erl module files from the .hrl header files.</li> </ul>		
small-server	С	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.		
application	С	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.		
supervisor supervisor-bridge	С	<f12> <f12> M-u <f12> <f12> M-b</f12></f12></f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a <u>supervisor behaviour</u> .  Insert a large file header and template logic for a <u>supervisor bridge behaviour</u> .		
super visor-bridge		1127 \1127 M-D	bridge)	moore a raige me neader and template logic for a <u>supervisor britinge benaviour</u> .		
generic-server	С	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.		
gen-event	С	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a <b>gen-event behaviour</b> .		
gen-fsm	С	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.		
gen-statem-StateNa	C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.		
gen-statem-handle- event	С	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.		
wx-object	С	<f12> <f12> M-W</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.		
gen-lib	С	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.		
gen-corba-cb	С	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a <b>CORBA</b> callback module.		
ct-test-suite-s		<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite		
ct-test-suite-l		<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite		

Insertion  Insertion	<f11> SPC e <f12> <f11> All the tags in the tag lists in determined by the variable 't if a single match is found, the if a partial completion or no r if a partial completion is found:  12&gt; <f12> SPC <f11> SPC e <f12> SPC <f6> SPC</f6></f12></f11></f12></f11></f12></f11>	&optional SILENT)  'tempo-local-tags' (includin empo-match-finder'. If 'tem e corresponding template is match at all is found, and SI	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i. (or <f12> <f12> <f12> A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.  In the template name and hit RET. Emacs expands the template.  In the string matching is mpo-match-finder' returns nil, then the results are the same as no match at all.  In the string matching is mpo-match-finder' returns nil, then the results are the same as no match at all.  In the string matching is expanded in place of the matching string.  ILENT is non-nil, the function will give a signal.  Itelion-buffer' is non-nil, a buffer containing possible completions is displayed.  Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-</f12></f12></f12></f12></f12>		
Toggle pel-tempo-mode See also:	determined by the variable 't If a single match is found, the If a partial completion or no r If a partial completion is foun 12> <f12> SPC  <f11> SPC e <f12> SPC  <f6> SPC</f6></f12></f11></f12>	empo-match-finder <sup>3</sup> . If 'tem e corresponding template is match at all is found, and SI and and 'tempo-show-comple (pel-tempo-mode	npo-match-finder' returns nil, then the results are the same as no match at all. s expanded in place of the matching string.  ILENT is non-nil, the function will give a signal. etion-buffer' is non-nil, a buffer containing possible completions is displayed.  Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-		
See also:  • <u>∑ Inserting Text</u>	<f11> SPC e <f12> SPC <f6> SPC</f6></f12></f11>				
Jump to next tempo			Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second se are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.		
	C-c M-f C-c . C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key key bindings are only available when pel-tempo-mode is active.		
tempo mark		(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.		
See also:	Activate smartparens mode of This table uses the 🖾 and 🌣  := "forward delete" :=  := "backward delete" :=	manually with <f11> ( (  symbols to represent thes  deletechar&gt; := Fn  </f11>			
• kill block elements	e following commands kill th	e element(s) of a block.			
	<m-f7> ⊠ <m-f7> - n</m-f7></m-f7>		Change the content of current or next block. Point can be anywhere in block or element before block.  Before:  After:		
<u>∑X Smartparens</u>			{'EXIT',Reason} -> {'EXIT',Reason} -> { error,{asn1,Reason}}; {error,{ }};		
Delete content of current block  • <u>S</u> x Smartparens	i-f7>		Delete content of the enclosing block. Point can be anywhere inside the current block. <b>Before:</b> {'EXIT',Reason} -> {error,{ asn1,Reason}};  {error,{ }};		
Kill block elements forward   M-  M-  M-  M-  M-  M-  M-  M-  M-	(-f7> - ]		<pre>Kill block elements after point.  Before: case Tlv9 of   [] -&gt; true; -&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After:</pre>		
Kill block elements backward  • ∑X Smartparens	•	(sp-backward-kill-sexp &optional ARG DONT- KILL)	<pre>case Tlv9 of   [] -&gt; true;&gt; exit({error, })  Kill block elements before point.  Before:     case Tlv9 of       [] -&gt; true;&gt; exit({error, {asn1, {unexpected, Tlv9}}})  After:     case Tlv9 of</pre>		
Kill element after current   **M-current*  **  **X Smartparens*		· With ARG numeric prefix			
<u>Za Ginariparene</u>		• Tou can customize the bi	ehaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.		
Kill Whole line	I-f7> - 1	(sp-kill-whole-line)	Currently this deletes the whole line. Requires Erlang specific implementation.		
Kill/splice  Un-wrap current block, splicing its elements in enclosing block <u>XX Smartparens</u>	I-f7> 1 1	&optional ARG)	Un-wrap current block, splicing its content in enclosing block (if any).  Before: { EncBytes,EncLen} = 'enc'(Cdx, []),  EncBytes,EncLen = 'enc'(Cdx, []),  Before: -asn1_info(		
			[{vsn,'2.0.1'},     {module,'ELDAPv3'},     {options,[{i,"src"},{ outdir,"src"},noobj,{i,"."},{i,"asn1"}]}]).  After: -asn1_info(     [{vsn,'2.0.1'},     {module,'ELDAPv3'},     {options,[{i,"src"},  outdir,"src",noobj,{i,"."},{i,"asn1"}]}]).		
Kill block element(s) before point and splice remaining into outer block  • <u>S</u> X Smartparens		backward &optional ARG)	Kill elements before point in block and splice remaining elements into outer block.  Before: case Tlv9 of [] -> true; -> exit({error, {asn1, {unexpected,  Tlv9}}})  After: case Tlv9 of [] -> true; -> exit({error, {asn1,  Tlv0}})		
	I-f7> 1 ]	forward &optional ARG)	<pre>[] -&gt; true; -&gt; exit({error,{asn1,  Tlv9}})  Kill elements after point in block and splice remaining elements into outer block.  Before: case Tlv9 of    [] -&gt; true; -&gt; exit({error,{asn1, {unexpected,  Tlv9}}})  After: case Tlv9 of    [] -&gt; true; -&gt; exit({error,{asn1, unexpected }})</pre>		

```
Function
       Description
                                        Keystroke
                                                                                                                                                Note
Kill around element
                              <M-f7> 1 o
                                                                (sp-splice-sexp-killing-
                                                                                              Kill content around current element/block
                                                                around &optional ARG)
asit_inition
[{vsn,'2.0.1'},
   {module, 'ELDAPv3'},
   {options,[{i,"src"},|{outdir,"src"},noobj,{i,"."},{i,"asn1"}]}]).
                                                                                                      info(
                                                                                                 (vsn, '2.0.1'),
{module,'ELDAPv3'},
{options,|{outdir,"src"},}]).
                                                                                               [{vsn.

    Delete/Kill

                              m
   region
                                                               (sp-delete-region BEG END)
Delete region
                              <M-f7> DEL -
                                                                                              Delete the text between point and mark, like 'delete-region'.
                                                                                                BEG and END are the bounds of region to be deleted.
                                                                                                If that text is unbalanced, signal an error instead.
                                                                                                With a prefix argument, skip the balance check
Kill region
                                                                (sp-kill-region BEG END)
                                                                                             Kill the text between point and mark, like 'kill-region'
                              <M-f7> - -
                                                                                              · BEG and END are the bounds of region to be killed.
                                                                                                If that text is unbalanced, signal an error instead.
                                                                                              · With a prefix argument, skip the balance check
                              <M-f7> - r
                                                                (sp--kill-or-copy-region
                                                                                              Kill or copy region between BEG and END according to DONT-KILL.
                                                                BEG END &optional
                                                                                                   'evil-mode' is active, copying a region will also add it to the 0 register.
                                                                                              · Additionally, if command was prefixed with a register, copy the region to that register
                                                                DONT-KILL)
                                                                (sp-delete-char
Delete char forward
                              <M-f7> DEL n
                                                                &optional ARG)
                                                                                               (quu|x "zot") -> (quu| "zot")
                                                                                               (auux |"zot") -> (auux "|zot") -> (auux "|ot")
                                                                                               (foo (|) bar) -> (foo | bar)
                                                                                               [(foo bar) -> ([foo bar)
                              <M-f7> DEL p
Delete char backward
                                                                (sp-backward-delete-
                                                                char &optional ARG)
                                                                                               ("zot" q|uux) -> ("zot" |uux)
                                                                                               ("zot" | auux) -> ("zot | auux) -> ("zol auux)
                                                                                               (foo (|) bar) -> (foo | bar)
                                                                                               (foo bar) | -> (foo bar])

    Delete/Kill word

Delete word backward
                                                                                              (sp-backward-delete-word &optional ARG)
                              <M-f7> DEL v
                                                                (sp-backward-delete-
                                                                                                Delete a word backward, skipping over intervening delimiters.
                                                                word &optional ARG)

    Deleted word does not go to the clipboard or kill ring.
    With ARG being positive number N, repeat that many times.

                                                                                              · With ARG being Negative number -N, repeat that many times in backward direction.
                                                               (sp-delete-word & optional ARG)
Delete word forward
                                                                                              Delete a word forward, skipping over intervening delimiters
                              <M-f7> DEL w
                                                                                                Deleted word does not go to the clipboard or kill ring.
                                                                                                With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.
Kill word backward
                                                                                              Kill a word backward, skipping over intervening delimiters.
                                                                (sp-backward-kill-word
                              < M-f7 > - v
                                                                &optional ARG)

    With ARG being positive number N, repeat that many times.

                                                                                              • With ARG being Negative number -N, repeat that many times in backward direction.

Kill a word forward, skipping over intervening delimiters.
With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.

Kill word forward
                              < M-f7 > - w
                                                                (sp-kill-word &optional

    Delete/Kill

                              See 'sp-backward-symbol' and 'sp-forward-symbol' for what constitutes a symbol for the backward and forward commands respectively.
   symbol
                                                                (sp-backward-delete-
                                                                                             Delete a symbol backward, skipping over any intervening delimiters.

• Deleted symbol does not go to the clipboard or kill ring.
Delete symbol
                              <M-f7> DEL a
backward
                                                                symbol &optional ARG

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in forward direction.

                                                                WORD)
Delete symbol forward
                                                                (sp-delete-symbol
                                                                                              Delete a symbol forward, skipping over any intervening delimiters.
                              < M-f7 > DEL s

    Deleted symbol does not go to the clipboard or kill ring.
    With ARG being positive number N, repeat that many times.
                                                                &optional ARG WORD)
                                                                                              • With ARG being Negative number -N, repeat that many times in backward direction.
Kill symbol backward
                                                                (sp-backward-kill-
                                                                                              Kill a symbol backward, skipping over any intervening delimiters.

• With ARG being positive number N, repeat that many times.
                              < M-f7 > - a
                                                                symbol &optional ARG
                                                                WORD)
                                                                                              • With ARG being Negative number -N, repeat that many times in forward direction.
                                                               (sp-kill-symbol &optional ARG WORD)
                                                                                             Kill a symbol forward, skipping over any intervening delimiters.

• With ARG being positive number N, repeat that many times.
Kill symbol forward
                              < M-f7 > - s
                                                                                              • With ARG being Negative number -N, repeat that many times in backward direction.
                              💲 Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the 📭 external package flycheck.
Erlang syntax
checking
                                   To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake.
                                   By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened,
                                   add 'erlang-mode to the pel-modes-activating-syntax-check user-option.
Using either:
   <u>flycheck</u> or <u>flymake</u>
                                flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang.
                                 PEL automatically installs and activates flycheck when pel-use-goflymake user option is set to 'use-flycheck.
                              Flymake has several customizable variables, which some listed here:
                              The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer:

• flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check.

∑ SyntaxCheck

                                flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds
                                flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check.
                              The following variable control navigation to next or previous error:
                                flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries.
flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info.
                              The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.
                                                                                              Toggle the selected Erlang syntax checker mode on/off.
Activate/deactivate
                              <f12> !
                                                                (pel-erlang-toggle-
 elected syntax
                                                                syntax-checker)
                                                                                                   The syntax checker activated or deactivated is either flycheck or flymake, as selected by the
                              <f11> SPC e !
checker
                                                                                                  user-option variable 'pel-use-erlang-syntax-check'
                                                                                              See the required settings above to activate this command and select the syntax checker.
```

<u>Description</u>	<u>Keystroke</u>	Function	Note	
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	
Go to previous flymake diagnostic	М-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	
Compiling Erlang Code	The following commands are used to compile Erlang source code files to .beam files located in the same directory as the source code. Detected errors are listed in the *erlang* shell opened to compile the files. The buffer shows the location of error and the error description. The following commands are used to navigate to the next or previous detected error.			
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.	
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.	
Move to next compile error	• C-x • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move;  • negative means move back to previous error messages.  • Just C-u as a prefix means reparse the error message buffer and start at the first error.  • This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
Move to previous compilation or Flycheck detected error	C-c C-p	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
<b>Development Tool</b>	The following commands are u	ised when adding Emacs Li	sp support for Erlang.	
Show syntactic information	C-c C-s	(erlang-show-syntactic-information) Show syntactic information for current line. Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.		
Erlang Shell	Commands to explicitly launch comint.el library running in erla		that runs under an Emacs inferior-erlang process controlled by the comint mode from the	
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.	
Start new Erlang Shell	<f11> z r e</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.	
	<f12> z</f12>		C-c C-z starts the Erlang Shell from the Erlang Mode.  (f11> z r is available globally and will work as long as the erl executable is accessible.  Under PEL this command is available only when the pel-use-erlang user option is set to t.	
Work around to issues in the Erlang Shell	When running the Erlang Shell inside Emacs, you may run into some issues. They are listed here along with work-arounds.  • Redundant command echo: On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix: Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs.  • Typing Ctrl-G does not open the Erlang JCL Command Menu: work-around: type the following instead: C-q C-g RET  • Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see ∑ Shells).			
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt.  Erlang shell command history file:  The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available.  Within an Emacs inferior-erlang the You can also use the Erlang shell commands to access the local shell history.			
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.	
Previous shell command	м-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.	

<u>Description</u>	<u>Keystroke</u>	Function	Note		
Using Man inside	Emacs provide 2 main commands to display man pages inside buffers.				
Emacs and	Both of these are much more powerful than the usual man reader available on the shell allowing navigation across man pages and opening hyperlinks.  They are:				
support Erlang Man pages	The man command uses     WoMan: Browse Unix Ma		Man" a complete implementation. It has some formatting limitations compared to man but it's a Windows.		
See also: <u><b>∑</b> Help/Info</u>	To see Erlang man pages using the man command:  On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs.  There are several ways this can be remedied:  One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside				
	Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this:  MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man: manpath export MANPATH  • Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the can be stored in the same directory.				
	<ul> <li>Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the cap of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same dire as the above example we need to set the Man-switches which is normally set to nil to the following value:         <ul> <li>"-M'manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"</li> </ul> </li> </ul>				
	The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and new access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-sw MANPATH and buses man's ability to view several pages for the same topic.				
	To only see Erlang topics in Man completion:  When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not see my description on how to create whatis file for local man directory.				
	EDTS (see below) support	s the ability to download and cess sections inside the mar	f Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's ne pages, allowing EDTS driven man page access to co-exist with manual man command		
About Erlang	PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing				
	<ul> <li>Creating whatis files</li> <li>Using the Erlang Mar</li> <li>Using Specialized OS</li> </ul>	n files within Emacs			
See also: <u><b>∑ Menus</b></u>	Use the following commands to You can also use the toolba		e inside Emacs. th < <b>f10&gt;</b> ) in the Erlang section.		
Open a man page inside an Emacs buffer	• <f11> ? m • ₩-M</f11>				
See also:  • <u>S Help/Info</u> • <u>S Customize</u>	<ul> <li>You can navigate easily between sections (n/p will move to the next/end) you can use any of the searches.</li> <li>You can use any of the options to the man command at the prompt, access all man pages of the same name. Then use M-n and M-p to other page, inside the same buffer.</li> <li>See all keys available in mode, with <f1> m or <f11>? k m.</f11></f1></li> <li>The man command prompts, using the word at point as the default.</li> </ul>		<ul> <li>You can use any of the searches.</li> <li>You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.</li> </ul>		
Open a man page	<f11> ? w</f11>	(woman &optional TOPIC			
without external man process: woman See also:  •   Help/Info  •  Customize	CIII2 ? W	RE-CACHE)	(and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>		
EDTS	EDTS - Erlang Developr	nent Tool Suite			
	The commands in the following rows require the EDTS external package. PEL activates it when the pel-use-edts user option is set to t. If you want EDTS to start automatically when you open an Erlang file, set pel-use-edts to start-automatically instead of t.				
Erlang Project settings	EDTS is customizable through it <b>edts</b> customization group. With PEL you can open it, with other Erlang specific groups with <b><f12> <f3></f3></f12></b> .  EDTS also uses an external <b>.edts</b> configuration file to store Erlang project specific settings. See <b>EDTS: Configure your projects.</b> This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-whitelist, xref-file-whitelist				
See also: <u>Sessions</u>	<ul> <li>▶ Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler.</li> <li>▶ PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.</li> <li>▶ If EDTS has not been activated yet, the only EDTS specific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12></li> </ul>				
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional	Turn EDTS mode on or off.		
	<f11> SPC e M-SPC</f11>	ARG)	<ul> <li>EDTS is an easy to set up Development-environment for Erlang.</li> <li>EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.</li> </ul>		
EDTS/Navigation	EDTS (see below) provides 2 commands to move point across Erlang functions: ferl-goto-previous-function and ferl-goto-next-function. They are listed above in the navigation section. The EDTS navigation functions do not support repetition prefix argument nor they support shift marking. There are other commands and key bindings to move across Erlang functions, and PEL support functions that perform the same and support repetition and shift marking. See the commands listed in the navigation section above.				
EDTS/Cross References			It supports navigating in Erlang source code running in the current and remote nodes. e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>		
Find definition of identifier at point	M	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Go back to where M was last issued	М-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.	
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.	
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.	
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local- function SET-MARK)	Find a function in the current module.  • List local functions in the mini-buffer. Support completion. Move point to selected one.  • With C-u prefix, push mark before moving point.	
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global- function)	Find a module in the current project.  List project modules in the mini-buffer. Support completion. Open the file of selected one.	
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS). and provides commands to modify the name of the highlighted name in the current function all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by ahs-idle-interval which defaults to 1.0 second.		de starts when the cursors stays on a symbol for a period longer than the value identified by the	
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current- function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.	
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.	
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.	
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.	
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.	
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)	
EDTS/Man	pages per project, so it is poss	sible to have several Erlang	projects each one with a different version of Erlang and their corresponding man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages.	
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.	
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.	
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.	
EDTS Code Analysis				
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.	
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.	
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.	
EDTS/Debug				
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.	
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.	
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
EDTS/Erlang Node				
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer.  • The node is either:  • The module's project node, if current buffer is an erlang module, or  • The buffer's erlang node if buffer is an edts-shell buffer.  • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).	
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.	
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).	

LSP support:  • lsp-mode  • erlang ls	LSP (language Server Protocol) support for Erlang is provided via:  • The Isp-mode Emacs Lisp external package PEL activates it when the pel-use-erlang-Is user-option is turned on (set to t).  • The erlang Is Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site.  • The erlang Is can be configured using a YAML file erlang Is.config file that must be placed at the root of the Erlang project.  • It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features			
erlang Is required environment	The following executable must be accessible from PATH:  • <u>erl, escript</u> and other Erlang executables. See <u>Installing Erlang</u> if you need to learn how to install Erlang and its tools.  • erlang_ls. To install erlang_ls follow the instruction on the <u>erlang_ls GitHub page</u> : git clone it, then run make and make install.  • and the various <u>Tools for Erlang</u> .			
• <u>S Customize</u> Isp-mode	Several Isp-mode settings are customizable in the Isp-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings are probably what you may want to customize:  Isp-log-io  Isp-ui-sideline-enable  Isp-ui-doc-enable  Isp-ui-doc-</f3></f12>			
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. The initial state is set by the 'Isp-ui-doc-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	<ul> <li>Toggle the logging of LSP I/O.</li> <li>The initial state is set by the 'Isp-log-io' user-option.</li> <li>By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.</li> </ul>	
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line.  The initial state is set by the 'lsp-ui-sideline-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Erlang LS Features	Overview of the features provided to the features provided to the features provided to the features of the features of the feature of the fea	Edoc support     Navigation to Included Files     Find/Peek References	<ul> <li>LSP Lenses: lsp-avy-lens</li> <li>LSP sideline:         <ul> <li>enable with: (setq lsp-ui-sideline-enable t)</li> <li>Use M-x lsp-execute-copde-action to trigger quick-fix actions</li> </ul> </li> <li>Erlang Project-Specific LS Configuration:</li> <li>Erlang LS is customizable by using a YAML syntax file called erlang ls.config that should be placed in the root directory of the project.</li> </ul>	
lsp-mode features	<ul> <li>Completion at point         <ul> <li>traditional popup with company-mode</li> <li>Code navigation, with</li> <li>lsp-find-definition</li> <li>lsp-find-references</li> <li>Symbol highlights</li> </ul> </li> <li>Code navigation, with isp-find-definition</li> <li>lsp-find-references</li> <li>Symbol highlights</li> <li>Server-info: display a run button next to a Common Test testcase.</li> <li>server-info: display some Erlang LS server info on top of each module. For debug only.</li> <li>show-behaviour-usages: show the number of modules implementing a behaviour.</li> </ul>			
	Isp-find-references	<ul> <li>ct-run-test: display a</li> <li>server-info: display s</li> </ul>	a <i>run</i> button next to a Common Test testcase. some Erlang LS server info on top of each module. For debug only.	
Isp-mode integrations see also:  • ∑ Completion/Input  • ∑ Treemacs  • ∑ Hide/Show	Isp-find-references	• ct-run-test: display a • server-info: display s • show-behaviour-usa with:	a <i>run</i> button next to a Common Test testcase. some Erlang LS server info on top of each module. For debug only.	
see also:  • ∑ Completion/Input  • ∑ Treemacs	Isp-find-references Symbol highlights  Isp-mode supports integration Helm by using helm-Isp Ivy by using Isp-ivy Treemacs by using Isp-ori Worigami by using Isp-ori Key bindings: The Isp-mode is Since the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key bindings shown in the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key binding	• ct-run-test: display a • server-info: display s • show-behaviour-usa with:	a run button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  andidates: <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.</m-f9></f9></f9></f2>	
see also:  • © Completion/Input  • © Treemacs  • © Hide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace	Isp-find-references Symbol highlights  Isp-mode supports integration Helm by using helm-Isp Ivy by using Isp-ivy Treemacs by using Isp-ori Worigami by using Isp-ori Key bindings: The Isp-mode is Since the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key bindings shown in the super modifier key with M-x customize-op With PEL, the following key The key bindings shown in the super modifier key binding	• ct-run-test: display a • server-info: display s • show-behaviour-usa with:  When the pell activates Pell acti	a run button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  aff11> <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  1 key prefix.</m-f9></f9></f9></f2>	
see also:  • © Completion/Input  • © Treemacs  • © Hide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     Iveemacs by using Isp-ori     Worigami by using Isp-ori Key bindings: The Isp-mode is     Since the super modifier key with M-x customize-ori     With PEL, the following k     The key bindings shown l     If you change Isp-keyi	• ct-run-test: display a • server-info: display s • show-behaviour-usa with:  ## PEL activates ## PEL activates gami ## PEL activates a minor mode and provides by is not always available, in ption or with PEL via the eys are good replacement of the property of the prope	a run button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  l key prefix.  eplaced with your selected prefix key.</m-f9></f9></f9></f2>	
see also:  • © Completion/Input  • © Treemacs  • © Hide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace log buffer  Validate LSP	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     Iveremacs by using Isp-ori     Worigami by using Isp-ori  Key bindings: The Isp-mode is     Since the super modifier key with M-x customize-op     With PEL, the following k     The key bindings shown l     If you change Isp-keyt  s-1 L	• ct-run-test: display a • server-info: display s • show-behaviour-usa with:  When the pell activates Pell activates Pell activates Pell activates Pell activates Pell activates a minor mode and provides a minor mode and provides a minor mode and provides below is not always available, in tion or with Pell via the composition or with Pell via the color whow the standard is map-prefix that would be refused.  (Isp-workspace-show-log WORKSPACE)	a run button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  sf11> <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  1 key prefix.  splaced with your selected prefix key.  Display the log buffer of WORKSPACE.</m-f9></f9></f9></f2>	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     treemacs by using Isp-ori     Worigami by using Isp-ori Key bindings: The Isp-mode is     Since the super modifier key with M−x customize-ori     With PEL, the following key in the key bindings shown ley if you change Isp-keys  - It  s-1 d	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL activates PEL activates PEL activates PEL activates a minor mode and provide ey is not always available, intion or with PEL via the seys are good replacement of below show the standard s map-prefix that would be recorded workspace-show-log WORKSPACE)  (Isp-doctor)	a run button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  -1 key prefix.  -2 lkey prefix.  -2 lkey prefix.  -3 lkey prefix.  -4 lkey prefix.  -4 lkey prefix.  -5 lkey prefix.  -6 lkey prefix.  -7 lkey prefix.  -7 lkey prefix.  -8 lkey prefix.  -8 lkey prefix.  -9 ladded with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.</f2>	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     treemacs by using Isp-ori  Key bindings: The Isp-mode is     Since the super modifier key with M−x customize-op     With PEL, the following key the key bindings shown ley lf you change Isp-keytes  - It	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL a	arun button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  andidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  l key prefix.  eplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders.</m-f9></f9></f9></f2>	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     Ive treemacs by using Isp-ori     Worigami by using Isp-ori     Key bindings: The Isp-mode is     Since the super modifier key with M−x customize-ory     With PEL, the following k     The key bindings shown l     If you change Isp-keys  - It	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL a	arun button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  andidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  1 key prefix.  eplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders.  • Prompts for the directory.</m-f9></f9></f9></f2>	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     Ivy by using Isp-ivy     Ive-macs by using Isp-ori     Worigami by using Isp-ori     Key bindings: The Isp-mode is     Since the super modifier key with M−x customize-ory     With PEL, the following k     The key bindings shown l     If you change Isp-keys      S-1 L      S-1 d      S-1 = S-1 F a      S-1 F b	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL a	arun button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  1 key prefix.  caplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a "Isp-performance" buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders.  • Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.</m-f9></f9></f9></f2>	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     Ivy by using Isp-ivy     Ive-macs by using Isp-ori     Key bindings: The Isp-mode is     Since the super modifier ky with M−x customize-ory     With PEL, the following k     The key bindings shown l     If you change Isp-keys  - It	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL a	arun button next to a Common Test testcase.  some Erlang LS server info on top of each module. For debug only.  arges: show the number of modules implementing a behaviour.  sowhen pel-use-helm-lsp is turned on.  sowhen pel-use-lsp-ivy is turned on.  sowhen pel-use-lsp-treemacs is turned on.  sowhen pel-use-lsp-origami is turned on.  sowhen pel-use-lsp-ivy is turned on.  sowhen	
see also:	<ul> <li>Isp-find-references</li> <li>Symbol highlights</li> <li>Isp-mode supports integration</li> <li>Image: Image: Im</li></ul>	ct-run-test: display a server-info: display s server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL activa	arun button next to a Common Test testcase.  It is come Erlang LS server info on top of each module. For debug only, ages: show the number of modules implementing a behaviour.  It is when pel-use-helm-lsp is turned on.  It is when pel-use-lsp-ivy is turned on.  It is when pel-use-lsp-treemacs is turned on.  It is when pel-use-lsp-origami is turned on.  It is customizable prefix key for its key bindings. The default key prefix is s=1.  It can be modified through customization: change the lsp-keymap-prefix value. This can be done certified through customization: change the lsp-keymap-prefix value. This can be done certified through customization: change the lsp-keymap-prefix value. This can be done certified through customization: change the lsp-keymap-prefix value. This can be done certified through customization: change the lsp-keymap-prefix value. This can be done certified through customization: change the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified to see the lsp-keymap-prefix value. This can be done certified t	
see also:	Isp-find-references     Symbol highlights  Isp-mode supports integration     Helm by using helm-Isp     Ivy by using Isp-ivy     treemacs by using Isp-ori     Since the super modifier ke with M−x customize-op     With PEL, the following ke     The key bindings shown level bin	ct-run-test: display a server-info: display s server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL activates PEL activates PEL activates PEL activates a minor mode and provide ay is not always available, intion or with PEL via the server good replacement of below show the standard smap-prefix that would be reflected by the period of the peri	arun button next to a Common Test testcase.  Some Erlang LS server info on top of each module. For debug only.  agges: show the number of modules implementing a behaviour.  Sowhen pel-use-helm-lsp is turned on.  Sowhen pel-use-lsp-ivy is turned on.  Sowhen pel-use-lsp-treemacs is turned on.  Sowhen pel-use-lsp-treemacs is turned on.  Sowhen pel-use-lsp-origami is turned on.  Sowhen pel-use-lsp-ivy is turned on.  Sowhen pel-use-lsp-origami is turned on.  Sowhen pel-use-lsp-origami is turned on.  Sowhen pel-u	
see also:	Isp-find-references Symbol highlights  Isp-mode supports integration Helm by using helm-Isp Wive by using Isp-ivy Treemacs by using Isp-ori Worigami by using Isp-ori Key bindings: The Isp-mode is Since the super modifier key with M-x customize-op With PEL, the following key The key bindings shown the liftyou change Isp-key  s-1 L  s-1 d  s-1 =  s-1 F a  s-1 F f  s-1 G g  s-1 G f  s-1 G r	ct-run-test: display a server-info: display s server-info: display s show-behaviour-usa with:  PEL activates PEL a	a fun button next to a Common Test testcase.  Some Erlang LS server info on top of each module. For debug only, signes: show the number of modules implementing a behaviour.  Is when pel-use-helm-lsp is turned on.  Is when pel-use-lsp-treemacs is turned on.  Is when pel-use-lsp-treemacs is turned on.  Is when pel-use-lsp-treemacs is turned on.  Is customizable prefix key for its key bindings. The default key prefix is s-1.  It can be modified through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded through customization: change the lsp-keymap-prefix value. This can be done concluded to an experimentation be done concluded to an experimentation consider using customization is customization.  Add PROJECT-ROOT to the list of workspace folders.  Prompts for the directory.  Remove PROJECT-ROOT from the list of workspace folders.  Find definitions to the IDENTIFIER at point.  Find references to the IDENTIFIER at point.	

Description

<u>Keystroke</u>

Function

<u>Note</u>

Description	<u>Keystroke</u>	Function	Note	
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line.  • Displays code status such as definition errors, etc	
Toggle code action on modelling	s-1 T a	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.	
Toggle headline breadcrumbs	s-1 T b	(Isp-headerline- breadcrumb-mode &optional ARG)	<ul> <li>Toggle breadcrumb on headerline.</li> <li>When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.</li> </ul>	
Toggle hover information	s-1 T d	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame.  When active, information about symbol at point is shown in a pop-up overlay area. In graphic mode the information has links that can be used to open web-located information.  For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.	
Toggle symbol highlighting	s-1 T h	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.	
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays.  • Code-lens show information like # times a specific function is referenced.	
Execute code action	s-l a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION.     If ACTION is not set it will be selected from 'lsp-code-actions-at-point'.     Request codeAction/resolve for more info if server supports.	
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.	
Click LSP lens via avy	s-1 a 1	(Isp-avy-lens)	Click lsp lens using 'avy' package.  • The code lens must be active. Use s-1 T 1 to activate it if it's not active.	
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN.  Can be used to search symbol outside project.  The argument has the same meaning as in 'apropos'.  The result is shown in a *xref* buffer.	
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.	
Find implementations of symbol at point	s-l g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.	
Find references of symbol at point	s-1 g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point.  • The result is shown in a *xref* buffer.	
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.	
Display documentation of symbol at point in *lsp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point.  • Display help about symbol at point inside a *lsp-help* buffer.  • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.	
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.	
Rename symbol at point See also:  Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>	
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.	
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'.  • Show available tools and the available capabilities  • Shows the information inside a LspBrowser buffer.	
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it	
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it	
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup.  When ARG is t the lsp mode will start new language server even if there is language server which can handle current language.  When ARG is nil current file will be opened in multi folder language server if there is such.  When 'lsp' is called with prefix argument ask the user to select which language server to start.	
Treemacs support  • ∑x Treemacs	provide extra features that help	p Erlang development. Whe	respectively activated by PEL user-options <b>pel-use-treemacs</b> and <b>pel-use-lsp-treemacs</b> , en these are activated PEL provides bindings for the <a href="mailto:lsp-treemacs">lsp-treemacs</a> features.  s customization group. With PEL use <a href="mailto:sp-treemacs">sf12&gt; w<a href="mailto:wdf12">w<a href="mailto:sp-treemacs">sf12&gt; w<a href="mailto:sp-treemacs">sf12&gt; w</a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a>	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type-hierarchy DIRECTION)  Show the type hierarchy for the symbol at point.  With prefix 0 show sub-types.  With prefix 1 show super-types.  With prefix 2 show both.  This is not implemented for Erlang.		
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.			
	You can also use Graphviz, see M Graphviz Dot			
Preview UML diagram from plantUML source	<f12> u</f12>	(pel-render-	Render the PlantUML markup embedded in current mode comment.	
in current plantUML region of commented source code See also: M PlantUML	<f11> SCP e u</f11>	Use region if identified otherwise use PlantUML block at point.     Uses prefix (as PREFIX) to choose where to display it:		
	PlantUML block and issuing th	is command.	cture with PlantUML markup, then generate the UML rendering by moving point inside the	

## Emacs & Erlang — References

Document	Notes			
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.			
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal			
Erlang/OTP @ Github	Erlang source code			
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.			
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.			
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.			
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling GOTO 2018			
Erlang References				
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.			
A Concise Guide to Erlang	A very nice quick reference. From David Matuszek, University of Pennsylvania			
Erlang Code Guidelines				
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.			
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.			
EDoc User's Guide	Describes how to document code. Comments should conform to the Edoc comment style and format.			
2600Hz Erlang Documentation Guideline	An example of a corporate Erlang Documentation Guideline.			
Erlang Books	There are several printed and online Erlang books. <u>Erlang's FAQ</u> lists several of them. The following lists some extra ones.			
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.			
Erlang Information Sites				
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.			
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • about-erlang provides general information about Erlang, including:  • Learning Erlang, a table with links to resources to learn Erlang.  • Installing Erlang, describes various ways to install Erlang on macOS.  • Tools for Erlang, describes tools you can use for Erlang development.			
Emacs and Erlang Man files				
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.			
The Erlang mode for Emacs (user guide)     Erlang mode for Emacs (man page)	On the <u>erlang.org</u> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  • If found bugs in the <u>erlang man</u> page in the <b>Edit- Moving the marker</b> section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <u>ERL-1314</u> .  • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.			

<b>Emacs</b>	tools	for	Erlang
--------------	-------	-----	--------

Document	Notes			
<u>EDTS</u>	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  :name "my-project"  :otp-path "path/to/otp"  :node-name "project-node-name"  :lib-dirs '("lib" "deps")			
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  After installing EDTS, I got several compile errors, and had to install the following other modules:  - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?			
Language Server Protocol	Language Server Protocol @ Wikipedia     Language Server Protocol Specifications web site     Language Server Protocol @ Github			
LSP for Erlang	LSP support for Erlang is done using the following:  The lsp-mode Emacs Lisp package  The erlang ls Erlang server			
company-mode ; Modular in-buffer completion framework for Emacs				
Using Tags with Erlang				
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.			
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.			
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.			