## Emacs Support for Gerbil Scheme

Description	<u>Keystroke</u>	Function	<u>Note</u>
Gerbil Scheme Programming Language Support See also:  • ¾I - Scheme • ∑ File/ Directory Variables	PEL activates Gerbil Scheme support when the pel-use-scheme user-option is turned on (t).  PEL provide extra support for the Scheme programming language and its various implementations by providing access to the following external packages:  The gerbil-mode external package.  PEL activates it when the pel-use-gerbil user-option is turned on (t). Used only for Gerbil Scheme.  The Gerbil programming language is a specialized Scheme. The Gerbil files use the same extension as Scheme: .ss.  To activate the gerbil-mode automatically for Gerbil files, it is customary to use Emacs file variable to identify the mode: the first line of the file should have the following text: ;; -*- Gerbil -*-  The gerbil-mode package can also be installed by installing Gerbil.  PEL provides Lispy support for Gerbil Scheme when the gerbil-mode is added to the list specified by pel-modes-activating-lispy user-option.  See \$\Pi\$I-Lispy		
Open this PDF file. See also: <u>∑ Help/</u> Info	<f11> SPC C-s C-i <f1> <f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN- WEB-PAGE)	Open the <u>\$\mathbb{N}\cent{\text{ - Gerbil Scheme}}\) local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b>) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.</u>
∑ Customize PEL     Gerbil Scheme     support	<f11> SPC C-s C-i <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Gerbil Scheme support.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
© Customize Emacs Gerbil Scheme support	<f11> SPC C-s C-i <f3> <f12> <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs Scheme support: gerbil-mode, scheme, geiser, quack, lispy.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
	Use the following commands to interact with the gxi Scheme Gerbil REPL		
Compile current buffer	C-c C-f	(gerbil-compile-current-buffer)	Compile the current buffer
Import current buffer	• C-c C-i • C-c <tab></tab>	(gerbil-import-current-buffer)	Import current buffer
Reload current buffer	C-c C-r	(gerbil-reload-current-buffer)	Reload current buffer
Build	C-c C-b	(gerbil-build)	Build
Evaluate current definition	C-c C-e	(scheme-send-definition)	Send the current definition to the inferior Gerbil Scheme process.
Evaluate marked region	C-c C-c	(scheme-send-region START END)	Send the current region to the inferior Gerbil Scheme process.
Restart inferior scheme process	С-х 9	(restart-scheme)	Restart the inferior Gerbil Scheme Process
Open the Gerbil REPL	<f12> z</f12>	(pel-gerbil-repl &optional N)	Run the Gerbil REPL in window specified by N.  • By default use the other window. If a numeric argument is specified, its value correspond to the direction of a numeric keypad:  8 4 6 2 That is: • 8: up • 4: left • 6: right • 2: down • 0 and 5 identify the current window.
Erase the content of REPL	<f12> C-1</f12>	(pel-clear-scheme-repl-buffer)	Erase content of the Gerbil Scheme REPL running under Emacs.