Navigation

Move Operation	<u>Keystroke</u>	Function	<u>Note</u>
Navigation Commands	external packages or by P • PEL provides access and The avy external p The ace-link extern	EL itself. This table list the mair dactivation of the following extended ackage ackage activated when the land package activated when	point (Emacs name for cursor) inside a buffer. Several are built in Emacs. Others are provided by a generic commands for navigation. Pernal packages that provide extra navigation commands and modes: pel-use-avy user option is set to t. In the pel-use-ace-link user option is set to t. more information on specialized navigation provided by these modes and the tools they support.
<u>▼ Customize</u> PEL navigation control	<f11> <f2> P n 1</f2></f11>	(pel-cfg-pkg-navigation &optional OTHER-WINDOW)	Customize PEL navigation tools support: customize pel-pkg-for-navigation group which provides access to the following PEL user-options: • pel-use-ace-link • pel-use-avy • If OTHER-WINDOW is non-nil (use C-u), display in another window.
∑ Customize Emacs navigation control	<f11> <f2> P n 2</f2></f11>	(pel-cfg-pkg-navigation &optional OTHER-WINDOW)	Customize Emacs navigation tools support: <u>avy</u> . • If OTHER-WINDOW is non-nil (use C - u), display in another window.
<u>S</u> Customize PEL <u>S</u> Completion/Input	• <f11> M-c <f2> • M-g <f4> <f2></f2></f4></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL input completion support: access the customization buffer that holds the PEL user options that activate the input completion packages and the pel-goto-symbol command. • If OTHER-WINDOW is non-nil (use C-u), display in other window.
<u>▼ Customize</u> PEL imenu support See: <u>▼ Menus</u>	<f11> <f10> <f2></f2></f10></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL imenu support. Provides access to: • pel-imenu-follows-order-p • pel-use-filmenu • pel-use-imenu-anywhere • pel-use-imenu-extra • pel-use-popup-imenu
			 pel-use-popup-switcher If OTHER-WINDOW is non-nil (use C-u), display in another window.
Shift-Selection	If you press and hold the shift key while typing a movement command, that sets the mark before moving point (Emacs name for cursor) so that the region extends from the original point to its new position. This Shift-Selection is called "Shift-Marking" in this document. It is available for only some commands. When running Emacs in Terminal mode, less commands support it. Ability to perform "Shift-Marking" is identified in the description of the commands below.		
Move Point			est context; when editing right to left text these commands may mayo in the reverse direction
by <u>character</u> right/next char			nal context: when editing right to left text these commands may move in the reverse direction. Move point N characters forward (backward if N is negative).
rignunext char	C-f	(forward-char &optional N)	 On reaching end or beginning of buffer, stop and signal error. Interactively, N is the numeric prefix argument. If N is omitted or nil, move point 1 character forward. Support bidirectional context. Shift marking is available in graphics mode, not in terminal mode.
right/next char	<right></right>	(right-char &optional N)	Move point N characters to the right (to the left if N is negative). On reaching beginning or end of buffer, stop and signal error. Shift marking works with this command.
left/previous char	С-Б	(backward-char &optional N)	Move point N characters backward (forward if N is negative). • On attempt to pass beginning or end of buffer, stop and signal error. • Interactively, N is the numeric prefix argument. • If N is omitted or nil, move point 1 character backward. ■ Support bidirectional context. ■ Shift marking is available in graphics mode, not in terminal mode.
left/previous char	<left></left>	(left-char &optional N)	Move point N characters to the left (to the right if N is negative). On reaching beginning or end of buffer, stop and signal error. ➤ Shift marking works with this command.
Go to a specific char position	м-д с	(goto-char POSITION)	Enter a character position, a decimal value identifying the index into the continuous set of characters in the buffer. Shift marking does not work with this command.
by character using <u>avy</u>	move to the location. The last Shift selection is not sup. Move back to original location.	ocation can be inside any windo sported but you can mark (see <u>»</u> cation with M-	you want to move; avy highlights the target locations with another character: type that character to ow. This provides a very efficient way of moving the point. Marking) before moving to create a marked region. activated when the pel-use-avy user option is set to t.
Jump to visible char using avy	• C-: • M-G • M-g M-c	(avy-goto-char CHAR &optional ARG)	Jump to the currently visible CHAR. • The window scope is determined by 'avy-all-windows' (ARG negates it).
Jump to visible 2 chars using avy	• C-' • M-H • M-g M-j	(avy-goto-char-2 CHAR &optional ARG)	Jump to the currently visible CHAR1 followed by CHAR2. • The window scope is determined by 'avy-all-windows'. • When ARG is non-nil, do the opposite of 'avy-all-windows'. • BEG and END narrow the scope where candidates are searched.
• by <u>line</u>	When moving up or dow		ction with Shift for marking. The <up> and <down> cursor can be used with Shift for marking. target line exactly over the current column, the cursor is positioned after the character in that line not long enough.</down></up>
Previous line	• C-p • <up></up>	(previous-line &optional ARG TRY-VSCROLL)	Move cursor vertically up ARG lines. • C−p : Shift marking is available in graphics mode, not in terminal mode. • <up>: Shift marking works with this command.</up>
Next line	• C-n • <down></down>	(next-line &optional ARG TRY-VSCROLL)	Move cursor vertically down ARG lines. • C-n : → Shift marking is available in graphics mode, not in terminal mode. • <down> : → Shift marking works with this command.</down>
Go to a specific line in current buffer	• M-g g • M-g M-g • %-1	(goto-line LINE &optional BUFFER)	Go to LINE, counting from line 1 at beginning of buffer. If called interactively, a numeric prefix argument specifies LINE; without a numeric prefix argument, read LINE from the minibuffer. If optional argument BUFFER is non-nil, switch to that buffer and move to line LINE there. If called interactively with C-u as argument, BUFFER is the most recently selected other buffer. Prior to moving point, this function sets the mark (without activating it), unless Transient Mark mode is enabled and the mark is already active. Move back to original location with M-` Shift marking does not work with this command.
Goto line using avy • potentially in other window	• M-g f • M-g l	(avy-goto-line &optional ARG)	Jump to line start in current (or all visible if 'avy-all-windows' is t) window. Type highlighted key to move point. More control available with prefix argument: • ARG=1: you can also type a number to cancel and use 'goto-line' for this typed number. • ARG=4: negate the window scope determined by 'avy-all-windows'. • ARG=any other number: use 'goto-line' to move point to this line number. • Shift marking does not work with this command. • Move back to original location with M- • Requires the avy external package activated when pel-use-avy user option is set to t.

Move Operation	<u>Keystroke</u>	Function	<u>Note</u>
To column	The following command mo	ove point to a specified column.	It does not provide Shift-marking.
Go to a specific column	M-g <tab></tab>	(move-to-column COLUMN &optional FORCE)	Prompts for a column number (or it can be entered as a command prefix). • Move point to column COLUMN in the current line.
	 The column of a character is calculated by adding together the widths as displayed of the previous characters in the line. This function ignores line-continuation; there is no upper limit on the column number a character can have and horizontal scrolling has no effect. If specified column is within a character, point goes after that character. If it's past end of line, point goes to end of line. If a region is marked and point is at one end, modifies the region. 		
Set Goal Column	The goal column identifies a	a target for point when moving t	o a line. The goal column is stored in the variable 'goal-column'. This is a buffer-local setting.
Set/reset Goal Column	C-x C-n	(set-goal-column ARG)	Set the current horizontal position as a goal for C-n and C-p . Those commands will move to this position in the line moved to rather than trying to keep the same horizontal position. • Without argument: activate the goal column and set it to the current column. • With non nil argument (example: C-u): disable the goal column. • When the goal column is active, it is shown as G on the ruler (when the ruler-mode is active.) Execute ruler-mode (<f11> b -) to activate the ruler to see if the goal column is active. • This command might be disabled at first, so in that case the first time you use it Emacs might prompt for activating this command. See enable-command in the Emacs Lisp table.</f11>
• into line	The following commands m	nove point within the current line).
Beginning of line	C-a	Text: (pel-beginning-of-	Move point to beginning of current line as displayed. If point is already at the beginning of the
★ PEL Enhanced Key ★		line ARG) 2. Org-Mode: (org-beginning-of-line &optional N)	 line, move to the fist non-whitespace character (using back-to-indentation). (If there's an image in the line, this disregards newlines which are part of the text that the image rests on.) With argument ARG not nil or 1, move forward ARG - 1 lines first. If point reaches the beginning or end of buffer, it stops there. (But if the buffer doesn't end in a newline, it stops at the beginning of the last line.) Shift marking is available in graphics mode, not in terminal mode. In Org-mode: Go to the beginning of the current visible line. If this is a headline, and 'org-special-ctrl-a/e' is set, ignore tags on the first attempt, and only move to after the tags when the cursor is already beyond the end of the headline.
End of line	С-е	1. Text: (pel-end-of-line	Move point to end of current line as displayed. If point is already at the end of the line, move point
★ PEL Enhanced Key ★		ARG) 2. Org-Mode: (org-end-of-line &optional N)	to the first trailing space character if there is any. With argument ARG not nil or 1, move forward ARG - 1 lines first. If point reaches the beginning or end of buffer, it stops there. Shift marking is available in graphics mode, not in terminal mode. In Org-mode: Go to the end of the line, but before ellipsis, if any. If this is a headline, and 'org-special-ctrl-a/e' is set, ignore tags on the first attempt, and only move to after the tags when the cursor is already beyond the end of the headline.
First non-whitespace	M-m	(back-to-indentation)	Move point to the first non-whitespace character on this line. ➡ Shift marking works with this command.
• by word	A "word" is a syntactic unit which is identified by a set of variables that can be modified and is controlled by Emacs syntax table. See the subword-mode and superword-mode to change that.		
word forward	• M-f • M- <right></right>	(forward-word &optional ARG)	Move point forward ARG words (backward if ARG is negative). If ARG is omitted or nil, move point forward one word. • Supports superword-mode and subword-mode. ⇒Shift marking works with this command (both keys). □ This moves point right after the end of the word. If you want to move to the first letter of next word use M-n.
Beginning of next word	M-n	(pel-forward-word-start)	Move point forward to beginning of next word. • Supports superword-mode but not the subword-mode. ⇒Shift marking works with this command. □ On Qwerty, Qwerztz and Azerty keyboards the 'b' and 'n' letters are side by side. ↑ This key binding differs in other buffers. • In Info buffers, M-n is mapped to clone-buffer. • Inside shell buffers M-n is mapped to comint-next-input. • For the moment PEL does not change this but might (via a PEL user option in the future) since it's such a useful key.
word backward	• M-b • M- <left></left>	(backward-word &optional N)	Move backward until encountering the beginning of a word. With argument ARG, do this that many times. • Supports superword-mode and subword-mode. • Shift marking works with this command (both keys).
beginning of next token	C- <right></right>	(pel-forward-token-start &optional N)	Move to the beginning of next word/symbol. It handles characters that may be part of symbol in the current major mode (like '_' in C), and jumps over them but stops at whitespace and operators. Supports numerical argument for repetition. Negative argument reverses the movement direction. Shift marking works with this command. Useful when the superword-mode is not activated: allows jumping to next symbol while the word commands stop at each word separator character.
beginning of previous token	C- <left></left>	(pel-backward-token-start &optional N)	Move to the beginning of previous word/symbol. • It handles characters that may be part of symbol in the current major mode (like '_' in C), and jumps over them but stops at whitespace and operators. • Supports numerical argument for repetition. • Negative argument reverses the movement direction. ■ Shift marking works with this command. ■ Useful when the superword-mode is not activated: allows jumping to previous symbol while the word commands stop at each word separator character.
Goto word using 1 letter with avy • potentially in other window	M-g w	(avy-goto-word-1 CHAR &optional ARG BEG END SYMBOL)	Jump to the currently visible CHAR at a word start. Type first letter of target word, then highlighted key(s). • The window scope is determined by 'avy-all-windows'. • When ARG is non-nil, do the opposite of 'avy-all-windows'. • ► Shift marking does not work with this command. • Requires the avy external package 2 activated when pel-use-avy user option is set to t.
Goto word with avy • potentially in other window	М-g е	(avy-goto-word-0 ARG &optional BEG END)	 Jump to a word start. Highlights each word with letters to select to jump. The window scope is determined by 'avy-all-windows'. When ARG is non-nil, do the opposite of 'avy-all-windows' Shift marking does not work with this command. Requires the avy external package activated when pel-use-avy user option is set to t.

Move Operation	<u>Keystroke</u>	Function	<u>Note</u>	
by syntactic	Moving by syntactic elemen	its, regardless of the word mode	е.	
elements	These are marginally useful	except for investigating the syn	atax handling of various Emacs major modes.	
Move point forward to next syntactic change	• <f11> M-<right> • <f11> M-f</f11></right></f11>	(pel-forward- syntaxchange-start)	Move point forward: stop at beginning of character syntax change.	
Move point backward to previous syntactic change	• <f11> M-<left> • <f11> M-b</f11></left></f11>	(pel-backward- syntaxchange-start)	Move point backward: stop at beginning of character syntax change.	
• by blocks	Blocks can be: pairs of brackets: (),[],{},<>,"", ''. Blocks using parentheses correspond to Lisp S-Expressions (sexp). This works in Lisp-like programming languages and programming languages that support block syntax.			
block backward	• C-M-b • C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-b : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ► Shift marking works with this command.</left>	
	❖ C-M- <left> does not v ⑤ Several Linux distros ma</left>	work on Windows, but H-<left< b=""> ap C-M-<left></left> to desktop w</left<>	ing you must ensure that pel-windmove-on-esc-cursor user option is set to nil. is works. vorkspace operation. In that case you can either use another key binding or change Linux key went it from using that key sequence.	
block forward	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : ➡ Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : ➡ Shift marking works with this command.</right>	
	 ⚠ With PEL: if you want to use Esc C-<right> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil.</right> ❖ C-M-<right> does not work on Windows, but H-<right> does.</right></right> ④ Several Linux distros map C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</right> 			
<u>Up/inside sexp</u> <u>hierarchy</u>	• C-M-u • C-M- <up> • C-[C-u • Esc C-u • Esc C-<up></up></up>	(backward-up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move backward out of one level of parentheses. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. With PEL: if you want to use Esc C- <up> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. C-M-u: Shift marking is available in graphics mode, not in terminal mode. C-M-<up> im Shift marking works with this command. C-M-<up> does not work on Windows, but H-<up> does.</up></up></up></up>	
Down/inside sexp/block	• C-M-d • C-M- <down> • C-[C-d • Esc C-d • Esc C-<down></down></down>	(down-list &optional ARG)	Move forward down one level of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do this that many times. A negative argument means move backward but still go down a level. • This command assumes point is not in a string or comment. • ⚠ With PEL: if you want to use Esc C- <down> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. • C-M-d: ► Shift marking is available in graphics mode, not in terminal mode. • C-M-<down> : ➡ Shift marking works with this command.</down></down>	
Up/right sexp/block	C-M-]	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move forward out of one level of parentheses. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot. If ESCAPE-STRINGS is non-nil (as it is interactively), move out of enclosing strings as well. If NO-SYNTAX-CROSSING is non-nil (as it is interactively), prefer to break out of any enclosing string instead of moving to the start of a list broken across multiple strings. On error, location of point is unspecified.	
Backward block/list	• C-M-p • C-[C-p • Esc C-p	(backward-list &optional ARG)	Move backward across one balanced group of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do it that many times. • Negative arg -N means move forward across N groups of parentheses. • This command assumes point is not in a string or comment. • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.	
Forward block/list	• C-M-n • C-[C-n • Esc C-n	(forward-list &optional ARG)	Move forward across one balanced group of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do it that many times. • Negative arg -N means move backward across N groups of parentheses. • This command assumes point is not in a string or comment. • C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.	

Move Operation Kevstroke Function Note The following command can be used to move point to any quickly selected a symbol definition, in any major mode supported by **Emacs imenu.**A Most major mode for programming and markup languages support image. PEL adds out a support for programming and markup languages support image. to symbol definition PEL provides 2 commands: pel-goto-symbol lists target symbols in the current buffer, allowing you to select one and jump to it.
 pel-goto-symbol-any-buffer does the same but for all buffers currently opened.
 For each of these commands PEL provides a selectable user interface. The user interface used for each command when Emacs starts is selected by a customization user-option variable. During an editing session PEL provides a UI selection command. In both cases the available user interfaces depend in current buffer In all opened **buffers** on what you activate Customize pel-goto-symbol user interface with M-g <f4> <f2> to access the customization buffer: • the pel-initial-goto-symbol-UI user option. Select one of: See also: ∑ Completion/Input • 0 = Use Emacs default: imenu **∑** Menus 1 = Use Ido.
 Requires Ido ubiquitous mode.
 pel-use-ido and pel-use-ido-ubiquitous must both be turned on. **∑** Speedbar • 2 = Use Ivy. Requires Ivy mode and Ivy mode completion with Counsel mode Ivy mode pel-use-counsel must both be on. • 3 = Use helm. PRequires Helm mode pel-use-helm must be turned on. • 4 = Use popup-imenu. PRequires popup-imenu pel-use-popup-imenu to be turned on (in pel-pkg-for-imenu group). • 5 = Use popup-switcher. Paquires popup-switcher pel-use-popup-switcher to be turned on (in pel-pkg-for-imenu group). • Modify the pel-goto-symbol UI for the current editing session with the pel-select-goto-symbol-UI command, bound to M-g <f4> h $\bullet \ \, \text{Customize pel-goto-symbol-any-buffer} \ \, \text{user interface with with } \ \, \underline{\text{M-g}} \ \, <\underline{\text{f2>}} \ \, \text{to access the customization buffer} .$ • 🔡 📦 Requires imenu-anywhere 🗹 pel-use-imenu-anywhere user option must be set to one of the following values: fault: basic Emacs completion. Use tab to see possible matches • Use Ido. 🗾 pel-use-ido must be turned on. Requires Ivy mode Del-use-ivy must be on. • Use helm. Pequires Helm mode Del-use-helm must be turned on. • Modify pel-goto-symbol-any-buffer UI for the current editing session with the pel-select-goto-symbol-any-buffer-UI command, bound to M-g <f4> • Use pel-show-goto-symbol-settings, bound to M-g? to show the current settings for both commands.

When using Ido, for you have more options: you can select a different Ido prompt geometry and whether it uses 'flx' fuzzy matching. Ido prompt geometries: The Emacs default: Ido linear selection Grid initially collapsed or expanded. Requires ido-grid-mode Activate it with pel-use-ido-grid-mode user-option turned on. Requires ido-vertical-mode Activate it with pel-use-ido-vertical-mode user-option turned on. Vertical list • Select the initial geometry with the pel-initial-ido-geometry. Change it in the editing session with pel-select-ido-geometry (M-g <f4> M-g). Ido 'flx' fuzzy matching prequires flx-ido. Activate it with pel-use-flx user-option turned on. • Also use <f11> <f10> <f2> to customize the PEL iMenu user-options which have an impact on the way the iMenu entries are displayed. 圈 Note that it is also possible to use the <u>Speedbar</u> (which also uses the symbols detected by <u>imenu</u>). See <u>y Speedbar</u> Move to imenu detected symbol definition in • M-g h Prompt using for imenu symbol of the current buffer and move point to it. · Refresh imenu and jump to a place in the buffer using the completion method selected. • M-g M-h • Modify user interface currently used with M-g <f4> h. current buffer * • The command sets a ref-marker before moving. Return to previous location by typing M-, 1 There seems to be an intermittent bug in the use of imenu when changing to popup-switcher for some files under some conditions. When this problem occurs imenu—make-index-alist does not return an plist with the proper markers. Setting imenu-auto-rescan to t fixes the problem for imenu but not for popup-switcher. This condition is unstable. I am trying to identify the condition that cause this issue. I noticed the following: The issue does not seem to show up when Ivy or Helm is used as the backend for this command. • When the issue manifests itself, turning the semantic-mode one seems to solve the issue. But then turning it back off breaks pel-goto-symbol when it is using popup-switcher because imenu tries to continue using semantics.

Overall this will require analysis of popup-switcher (which has sticky persistent overlay problems) and interaction various minor modes, which I am will be doing. Move to imenu detected • M-g y (pel-goto-symbol-any-Prompt using for imenu symbol of all loaded menu supported buffers and move point to the buffer) symbol definition of all • M-g M-y opened buffers * · Provide input completion using the currently selected method (emacs-default, ido, ivy or helm). Select the default completion method by customization setting pel-use-imenu-anywhere. Modify user interface currently used with M-g < f4 > y. • The command sets a ref-marker before moving. Return to previous location by typing M-, Display current setting (pel-show-goto-symbol-Display current settings used by the goto symbol commands in the echo area. Something like M-g ? .. settings) goto-symbol UI is: popup-switcher goto-any-buffer UI is: Ido pel-goto-symbol pel-goto-symbol-anybuffer - iMenu lists are not flatten. Ido uses: - Ido prompt geometry: grid mode, starts collapsed: expand with tab - Ido Ubiquitous mode: off - flx-ido mode: off Select the input completion method used by the **pel-goto-symbol** command for the duration of **Select Input Completion** (pel-select-goto-symbol-UI) M-q < f4 > hthe current editing session. used by pel-goto When Emacs starts the method used is determined by the value of the pel-initial-gotosvmbol **symbol-UI** user-option. You can use this command to change what is used in the current editing session without affecting the customized default. See also the commands to control input completion (see <u>No Completion/Input</u>) • pel-select-ido-geometry: M-g <f4> M-g • pel-ido-ubiquitous : M-g <f4> M-u : M-g <f4> M-f pel-flx-ido Select the input completion method used by the **pel-imenu-anywhere** command for the duration (pel-select-goto-symbol-Select Input Completion M-q < f4 > yMethod used by pel-imenu-anywhere of the current editing session and used by the **pel-goto-symbol-any-buffer** command.

• When Emacs starts the method used is determined by the value of the PEL **pel-use-imenu**any-buffer-UI) anywhere user-option. You can use this command to change what is used in the current editing session without affecting the customized default. The commands move point by function definitions. In elisp code that's defun, defvar, etc... but it also works in other modes, as the same keys are bounded • by defun to different command The <f6> cursor key mappings use <up> and <down> to move to the beginning of the defun, and <left> and <right> to the end of the defun. 🤘 In this context the word *defun* corresponds to the concept of function, method, procedure, section, used for the current buffer. 🔥 These commands work well when editing Lisp-like programming languages. The first two commands will skip nested functions at a level nested relative to the current level (and that can be considered a nice feature) The extra commands provided by PEL are based on the first 2 commands and inherit these The pel-beginning-of-next-defun works well in most cases but has problems handling some C++ template code.
The pel-end-of-previous-defun is even more affected by the limitations when used to move inside some nested code. Obviously need a better sequential navigation mechanism for nested functions definitions in source code.

Move Operation	<u>Keystroke</u>	Function	<u>Note</u>
Backward to beginning of defun	• C-M-a • C-M- <home> • <f6> p • <f6> <up> • C-[C-a • Esc C-a</up></f6></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of a defun. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ► Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode. This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions and methods that are more deeply nested.</up></f6></f6></home>
Forward to end of defun	• C-M-e • C-M- <end> • <f6> <right> • C-[C-e • Esc C-e</right></f6></end>	(end-of-defun &optional ARG)	Move forward to next end of defun. • With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-e, C-[C-e and Esc C-e keys). However <f6> <right> handle Shift-marking fine in terminal mode. ⚠ This command moves to the end of the next top-level function or class. It skips the nested functions and methods.</right></f6>
Forward to start of next defun	• <f6> n • <f6> <down></down></f6></f6>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ. ⇒ Shift marking is available. • This command complements what end-of-defun does. • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect. • It handles nested functions or class methods in languages like Python and others.
Backward to end of previous define	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ. ➡Shift marking is available.
• by URL		goto-address-mode to act on	oss the buffer to the next and previous URL. the URL. PEL adds command to download a web page to a local temporary file and visit it.
Move to end of next URL in buffer See also: <u>▼ File-mngt</u>	C-c C-n <f6> C-n</f6>	(pel-goto-next-url)	Move point forward to the end of the next URL located in the current buffer. • The C-c C-n binding is only available when point is over the URL and the goto-address-mode minor mode is active. Use <f11> f u or <f11> f U to activate this mode. • The global <f6> C-n key binding activates the goto-address-mode if it is not already active.</f6></f11></f11>
Move to beginning of previous URL in buffer See also: File-mngt	C-c C-p <f11> C-p</f11>	(pel-goto-previous-url)	Move point backward to the beginning of the previous URL located in the current buffer. • The C-c C-p binding is only available when point is over the URL and the goto-address-mode minor mode is active. Use <f11> f u or <f11> f U to activate this mode. • The global <f6> C-p key binding activates the goto-address-mode if it is not already active.</f6></f11></f11>
• by <u>sentences</u>	The variable 'sentence-end' is a regular expression that matches ends of sentences. Also, every paragraph boundary terminates sentences as well. The definition of what is a sentence depends on the major mode. For example, in C++//l mode the end of sentence means end of C++ statement. More information on navigation is available on each mode.		
To beginning of sentence	м-а	(backward-sentence &optional ARG)	Move backward to start of sentence. With arg, do it arg times. ➡ Shift marking works with this command.
To end of sentence	М-е	(forward-sentence &optional ARG)	Move forward to next end of sentence. With argument, repeat. With negative argument, move backward repeatedly to start of sentence. Shift marking works with this command.
• by paragraphs	A paragraph start is the beginning of a line which is a 'paragraph-start' or which is ordinary text and follows a 'paragraph-separate'ing line; except: if the first real line of a paragraph is preceded by a blank line, the paragraph starts at that blank line. Note: It is not possible to Shift mark with these bindings. Use C-SPC to mark first then use the keys to move and extend the region.		
Backward paragraph	• C- <up> • M-{</up>	(backward-paragraph &optional ARG)	Move backward to start of paragraph. • With argument ARG, do it ARG times; • a negative argument ARG = -N means move forward N paragraphs. • C- <up> : ► Shift marking works with this key. • M-{ : ► Shift marking does not work with this key.</up>
Forward paragraph	• C- <down> • M-}</down>	(forward-paragraph &optional ARG)	Move forward to end of paragraph. • With argument ARG, do it ARG times; • a negative argument ARG = -N means move backward N paragraphs. • C- <down> : ► Shift marking works with this key. • M-} : ► Shift marking does not work with this key.</down>
• by <u>pages</u>	A page boundary is any line	whose beginning matches the	regexp 'page-delimiter'. By default, that is a ^L (form feed) at the beginning of a line.
Forward 1 page	С-ж]	(forward-page &optional COUNT)	Move forward to page boundary. With arg, repeat, or go back if negative. Shift marking does not work with this key.
Backward 1 page	C-x [(backward-page &optional COUNT)	Move backward to page boundary. With arg, repeat, or go fwd if negative. Shift marking does not work with this key.
• to buffer & window top/end	PEL provides the <home< th=""><th>> and <end> keys. They beh</end></th><th>entre of the current buffer or window. ave like the Brief/CRiSP equivalent keys with the additional handling of Emacs fields. d of buffer, and M-r to move top top, centre and end of the visible portion of the current buffer.</th></home<>	> and <end> keys. They beh</end>	entre of the current buffer or window. ave like the Brief/CRiSP equivalent keys with the additional handling of Emacs fields. d of buffer, and M-r to move top top, centre and end of the visible portion of the current buffer.
To beginning of: line, window, buffer	<home></home>	(pel-home)	The behaviour of this command depends on the current point location: → beginning of field (if any) → beginning of line → beginning of window → beginning of buffer
★ PEL Enhanced Key ★ See also: Secolling	So to go to beginning of buffer, type <home> 3 times if point is not at the beginning of line or window, 4 times if the line has a field (like prompt in interactive buffers like IELM) and point is not at the beginning of field. • Push mark at previous position, unless either a C-u prefix is supplied, or Transient Mark mode is enabled and the mark is active. • Scrolls other window when PEL window scroll mode is active. See Scrolling. • Shift marking is available in graphics mode, not in terminal mode. • On macOS laptops, the <home> key is not available; use Fn <left> instead. • Because the behaviour of the key depends on the original position avoid using this key inside keyboard macros when you cannot guarantee the position when the keyboard macro is invoked. Use C-a instead inside keyboard macros when you want to move point to the beginning of a line.</left></home></home>		
To end of line, window, buffer	<end></end>	(pel-end)	The behaviour of this command depends on the current point location: → end of field (if any) → end of line → end of window → end of buffer

Move Operation	<u>Keystroke</u>	Function	<u>Note</u>
★ PEL Enhanced Key ★	So to go to end of buffer, type <end> 3 times if point is not at the end last window line, or 4 times if there is a field in the line after the point's position. REPL like <u>IELM</u> use fields on prompt lines. • If the buffer is narrowed, this command uses the end of the accessible part of the buffer. • Push mark at previous position, unless either a C-u prefix is supplied, or Transient Mark mode is enabled and the mark is active. • Scrolls other window when PEL window scroll mode is active. See <u>Scrolling</u>. Shift marking is available in graphics mode, not in terminal mode. • On macOS laptops, the <end> key is not available; use Fn <right> instead. Because the behaviour of the key depends on the original position avoid using this key inside keyboard macros when you cannot guarantee the position when the keyboard macro is invoked. Use C-e instead inside keyboard macros when you want to move point to the end of a line.</right></end></end>		
To beginning of buffer	M-<	(beginning-of-buffer &optional ARG)	 Move point to the beginning of the buffer. With numeric arg N, put point N/10 of the way from the beginning. If the buffer is narrowed, this command uses the beginning of the accessible part of the buffer. Push mark at previous position, unless either a C-u prefix is supplied, or Transient Mark mode is enabled and the mark is active. Shift marking does not work with this key.
To end of buffer	M->	(end-of-buffer &optional ARG)	Move point to the end of the buffer. • With numeric arg N, put point N/10 of the way from the end. • If the buffer is narrowed, this command uses the end of the accessible part of the buffer. — Shift marking does not work with this key.
To left line center, top, bottom of window	M-r	(move-to-window-line-top- bottom &optional ARG)	Position point relative to window. • By default moves to beginning of line at: center, top, bottom of window in successive calls. • The recenter-positions user-option can be modified to change that default. • Arguments: • A negative argument reverses the order. • A numeric argument identifies a line number. • Number 0 identifies the first line in window: M−0 M−r : move to top of window • Negative 0 identifies the last line in window: M−0 M−r : move to end of window ■ Shift marking does not work with this key.
• in buffer of other windows	The following 2 commands do not move point in the current buffer, they move it in the buffer showing in the other window.		
To beginning of buffer in other window	• Esc <home> • <m-home></m-home></home>	(beginning-of-buffer-other- window ARG)	Move point to the beginning of the buffer in the other window. • Leave mark at previous position. • With arg N, put point N/10 of the way from the true beginning.
To end of buffer in other window	• Esc <end> • <m-end></m-end></end>	(end-of-buffer-other- window ARG)	Move point to the end of the buffer in the other window. • Leave mark at previous position. • With arg N, put point N/10 of the way from the true end.
Goto match/ Compilation Error	A match is the result of a previous operation like: grep search result, compilation errors, etc		
Jump to next match	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; negative means move back to previous error messages. Just C-u as a prefix means reparse the error message buffer and start at the first error.
Jump to previous match	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).
recentering in current window	The following 2 command of the current window.	do not move point, but repositio	n the text in the current window. These are quite useful as they can be used to refresh the view in
Position current line to window's Center / Bottom / Top . Refresh screen.	C-1	(recenter-top-bottom &optional ARG)	Without argument: moves the current line to window: center -> top -> bottom. • With arg: centre first: • C-u C-l C-l C-l C-l • → center → bottom → center → top • With negative arg: bottom first: • C C-l C-l C-l • → bottom → center → top • With arg 0: top first: • M-0 C-l C-l C-l • → top → bottom → center • With numeric positive: move current line to window top position N • With negative numeric: move current line to bottom window position: -1 := last line
Reposition comment/ definition in full view	• C-M-1 • C-[C-1 • Esc C-1	(reposition-window &optional ARG)	Attempts to make the current comment or current definition fully visible by scrolling the lines without changing the point. • Further invocations move it to the top of the window or toggle the visibility of comments that precede it (by scrolling the lines).