## Comments

Action	Key binding	Command	Notes
<b>Comment Commands</b>	This is an early vers	ion of this page. More information is required on the	nis topic.
Insert, realign, comment/ uncomment region	M-;	(comment-dwim ARG)	Insert or realign comment on current line.  • If the region is active, comment or uncomment the region instead.  • C-u M-; executes comment-kill
Comment/uncomment current line	• C-x C-; • <f11> ; 1</f11>	(comment-line N)	Comment/uncomment current line (the comment is at the beginning of the line).
			Since C-; is not an ASCII Control character, C-x C-; does not work in Terminal. Use the alternate keystroke.
Comment the region as a box	<f11> ; B</f11>	(comment-box BEG END &optional ARG)	Comment the marked region in a comment box.
Kill comment on current line	<f11> ; k</f11>	(comment-kill ARG)	Kill the complete comment text on the line (whether it is at the beginning of the line or after some code) and remember in kill ring.  With numeric argument, kill comment on as many lines staring with the current one.  For one line this can also be executed with C-u M-;
Delete all comments in buffer or marked region	<f11> ; 🖾</f11>	(pel-delete-all-comments)	Delete all comments in current (possibly narrowed) buffer or marked region.
(See also: ∑ Cut & Paste)			To delete all comments inside a region mark the region first. You can also narrow a region and then use this command to remove all comments from that narrowed region, without affecting anything else. See the ∑ Narrowing table for information on narrowing.
Kill all comments in buffer or marked region (& retain them in kill ring)  (See also: ∑ Cut & Paste)	<f11> - ;</f11>	(pel-kill-all-comments)	Kill all comments in current (possibly narrowed) buffer or marked region and retain them in kill ring.  To kill all comments inside a region mark the region first. You can also narrow a region and then use this command to remove all comments from that narrowed region, without affecting anything else. See the ∑ Narrowing table for information on narrowing.
Set comment column to current column	С-х ;	(comment-set-column ARG)	Set the comment-column variable (shown in the ruler as '#').
Set comment column to previous comment and adjust/ insert a comment	С-и С-х ;	(comment-set-column 1)	<ul> <li>With no argument: set to the current column.</li> <li>With any positive argument set comment-column to the same column as the previous comment and align/create a comment on this line at that column.</li> <li>With - as arg, kill any comment on current line.</li> </ul>
New line & aligned comment	• M-j • C-M-j	Mapped to:     C, C++ modes: (c-indent-new-comment-line & optional SOFT ALLOW-AUTO-FILL)     Buffer Menu, text mode, python mode: (comment-dwim ARG)	When M-j is typed, on a line that contains a comment, a new line is entered and a comment is placed in the same column, with point placed after the same number of spaces.
Set comment start string	<f11> ; b</f11>	(pel-comment-start)	Show and set comment start string for current mode.  • Controlled by variable: comment-start
Set comment end string	<f11> ; e</f11>	(pel-comment-end)	Show and set comment end string for current mode.  • Controlled by variable: comment-end  • By default it's "". It must be "" if the comment ends at the end of the line.
Set comment continue (middle) string	<f11> ; m</f11>	(pel-comment-middle)	Show and set comment continue/middle string for current mode.  Controlled by variable: <i>comment-continue</i> By default it is <i>nil</i> . Can be set to any string.  This is used for multi-line comments
Set Fill Column	C-x f	(set-fill-column ARG)	When no prefix value: prompts for column.  If with C-u prefix: use current column.  If with prefix value: use that value.  Note: this command and other fill specific commands are described in the Fill/Justification table.
Toggle auto fill inside comments only	<f11> t f C</f11>	(pel-auto-fill-only-comments)	Toggle the <i>comment-auto-fill-only-comments</i> variable to control whether filling is done everywhere or only inside the comments.  Pote: this command and other fill specific commands are described in the Fill/Justification table.
See all comment control variables	• C-h v comment- • <f1> v comment</f1>		Lists all variables that have a name that starts with the word "comment-".  See the Help table for more information on getting help from within Emacs.

## Comments - References

GNU Emacs Manual - Manipulating Comments	
GNU Emacs Lisp — Tips on Writing Comments	Emacs Lisp comments conventions/guidelines.