Text Modes

Operation	Keystroke	Function	Note
Text Modes	Emacs has several of	other text modes that deal with	
See also: Whitespace	or when CamelCa	se is being used.	e quite useful when editing source code where underscores are used to separate words in symbols e is obsolete and has been replaced by the more general subword-mode.
Switch Insert/Overwrite mode	<pre>• <insert> • <f11> t o • <f11> `</f11></f11></insert></pre>	(overwrite-mode & optional ARG)	Toggles the overwrite mode on/off The <insert> key is not available in macOS keyboards. With a prefix argument ARG, enable Overwrite mode if ARG is positive, and disable it otherwise.</insert>
Binary file overwrite only mode	<f11> t 0</f11>	(nhexl-overwrite-only-mode &optional ARG)	Minor mode where text is only overwritten. Insertion/deletion is avoided where possible and replaced by overwriting existing text, if needed with 'nhexl-overwrite-clear-byte'. The nhexl mode must first be activated to edit the file in binary mode. Requires the nhexl-mode package. PEL activates this when the pel-use-nhexl customize variable is set to t.
Make Info control text visible/invisible (toggle visible mode)	<f11> t m v</f11>	(visible-mode &optional ARG)	Toggle making all invisible text temporarily visible (Visible mode). With a prefix argument ARG, enable Visible mode if ARG is positive, and disable it otherwise. Useful for developing info files, where some characters are not visible by default. Same in Orgmode (for example to show everything, or to show the syntax of links without expanding anything).
Toggle subword-mode See also: Search/Replace	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise. • PEL provides the <f12> M-b key for the programming language modes where <u>camelCase</u> and <u>PascalCase</u> are popular.</f12>
Toggle superword-mode	• <f11> t m p</f11>	(superword-mode &optional	Toggle superword-mode: a minor mode that treats snake case as one word. In Lisp, '-' and ' '
See also: Search/Replace	• <f12> M-p • <m-f12> M-p</m-f12></f12>	ARG)	 are treated part of words. With a prefix argument ARG, enable Superword mode if ARG is positive, and disable it otherwise. PEL provides the <f12> M-p key for the programming language modes where snake case is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Toggle sentence separators between 1 or 2 spaces	<f11> t m s</f11>	(pel-toggle-sentence-end)	Toggle definition of end of sentence between 2 and 1 space character (to help text filling). This has an impact on the commands that deal with sentences (navigation such as (backwardsentence) and (forward-sentence), kill such as (kill-sentence) and (backward-kill-sentence).
Toggle local electric quote mode	<f11> t m '</f11>	(electric-quote-local-mode &optional ARG)	Toggle 'electric-quote-mode' only in this buffer. Useful to insert nicer-looking quote characters.
Show state of text modes	<f11> t m ?</f11>	(pel-show-text-modes)	Display the state of the various text modes in the mini buffer.
Text Whitespace Modes	The following Emacs table.	command control how whites	pace is shown or hidden. The following commands are also described in the Text Whitespace
Toggle Whitespace Mode See also: <u>∑ Whitespace</u>	<f11> t w m</f11>	(whitespace-mode &optional ARG)	Toggle whitespace visualization (Whitespace mode). With a prefix argument ARG, enable Whitespace mode if ARG is positive, and disable it otherwise. The kind of whitespace visualized is determined by the list variable <i>whitespace-style</i> , <i>whitespace-newline</i> .
Hide/Show trailing whitespaces See also: Whitespace	<f11> t w T</f11>	(pel-toggle-show-trailing- whitespace)	Toggle highlight of the trailing whitespaces in current buffer. Toggles the value of the variable show-trailing-whitespace .
Hide/Show trailing empty	<f11> t w e</f11>	(pel-toggle-indicate-empty-	Toggle highlight of empty lines.
lines See also: <u>∑ Whitespace</u>		lines)	Toggles the value of the variable <i>indicate-empty-lines</i> .
Toggle individual elements of whitespace-style See also: Whitespace	<f11> t w o</f11>	(whitespace-toggle- options ARG)	 If local whitespace-mode is off, toggle the option given by ARG and turn on local whitespace-mode. If local whitespace-mode is on, toggle the option given by ARG and restart local whitespace-mode. The argument, which is a single character and must be typed following the <f11> t w o, can be:</f11>
Mark and Posion	With most editors w	han you type over a "calected"	 f toggle face visualization t toggle TAB visualization s toggle SPACE and HARD SPACE visualization r toggle trailing blanks visualization l toggle "long lines" visualization L toggle "long lines" tail visualization n toggle NEWLINE visualization e toggle empty line at bob and/or eob visualization c-i toggle indentation SPACEs visualization (via 'indent-tabs-mode') I toggle indentation SPACEs visualization i toggle indentation TABs visualization C-t toggle big indentation visualization c-a toggle SPACEs after TAB visualization (via 'indent-tabs-mode') A toggle SPACEs after TAB: SPACEs visualization a toggle SPACEs after TAB: TABs visualization c-b toggle SPACEs after TAB: TABs visualization b toggle SPACEs before TAB: SPACEs visualization b toggle SPACEs before TAB: TABs visualization c-b toggle SPACEs before TAB: TABs visualization b toggle SPACEs before TAB: TABs visualization c-ch toggle SPACEs before TAB: TABs visualization c-b toggle SPACEs before TAB: TABs visualization c-ch toggle SPACEs before TAB: TABs visualization
Mark and Region (See also: <u>▼ Marking</u>	not behave like this;	instead it allows typing text wh	ille there is an active a marked region. If you want Emacs behave like other editors and election-mode" with the following command.
Toggles delete selection mode See also: <u>∑ Cut & Paste</u> <u>∑ Marking</u>	<f11> t m d</f11>	(delete-selection-mode)	Toggles delete selection-mode on/off. In delete-selection-mode typing a character while a region is active replaces the entire region with what is typed. By default delete selection-mode is off.
Drawing ASCII in Emacs	Emacs provides the picture-mode and artist-mode to draw ASCII-based pictures. Both are available when Emacs runs in graphics and terminal mode. However, I have not been able to use artist-mode with the mouse, even with xterm-mouse-mode active: each click just prints an ANSI sequence code.		
Picture Mode	Emacs supports the picture mode that allow you to move your cursor freely anywhere inside the window, which greatly simplify creating rectangular shapes for tables or even <i>drawing</i> ASCII-art. This work well in both graphics and terminal mode.		
Enter picture mode	• <f11> D p • <f11> t p</f11></f11>	(picture-mode)	Switch to Picture mode, in which a quarter-plane screen model is used. Switch to Picture mode, in which a quarter-plane screen model is used. Switch to Picture mode, in which a quarter-plane screen model is used.
See also: <u>∑ Drawing</u>			• Type C-c C-c to exit picture-mode and return to the mode previously used in the buffer.
Artist Mode	Although you can ge	et some commands to work in to	erminal mode, it's best to use artist-mode when running Emacs in graphics mode.
Toggle artist mode See also: <u>∑ Drawing</u>	<f11> D a</f11>	(artist-mode &optional ARG)	Toggle Artist mode. With argument ARG, turn Artist mode on if ARG is positive. Artist lets you draw lines, squares, rectangles and poly-lines, ellipses and circles with your mouse and/or keyboard.

Text Modes — References

Topic & Link	Notes
GNU Emacs Manual: Text - Words	
GNU Emacs Manual: Text - Sentences	
GNU Emacs Manual: Text - Paragraphs	
GNU Emacs Manual: Text - Quotation Marks	
GNU Emacs Manual: Modes - Minor Modes	
GNU Emacs Manual: Programs - Other Features Useful for Editing Programs	
GNU Info Manual: Getting Started - Invisible text in Emacs Info	