## **Abbreviations/Expansions**

		ADDIEVIALIO115/	•	
<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
<u>Abbreviations</u>	There's manual and In the dynamic expands and The manual mode a special spell ch It's possible to use a	n various, configurable sources (for Hipp e is the Abbrev minor mode. In this mod ecking command. a dynamic expansion mode as well as a r	: expansions are determined automatically from the content of the current buffer (for	
Open this PDF file. See also: <u>∑ Help/Info</u>	<f11> a <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>Nabbreviations</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.	
Open PEL abbreviation customization group. See also: Customize	<f11> a <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Open the PEL customize group(s) for the current context.  Use this to open to change PEL user option variables the activate and control the various abbreviations features.  • When a prefix argument (like <b>C-u</b> ) opens the buffer inside another window.	
Customize Emacs built-in abbreviation support See also: <u></u> Customize	<f11> a <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs <b>abbrev</b> group which includes: abbrev-mode, dynamic-abbreviations, expand, hippie-expand, quickurl.  • When a prefix argument (like <b>C-u</b> ) opens the buffer inside another window.  • Group belonging to files that have not yet been loaded are normally not accessible in Emacs and via the customize-group command. PEL, however, attempts to locate the file that defines a non-loaded customization group and will prompt you for loading the file if it finds it.	
Show active abbrev mode	<f11> a ?</f11>	(pel-abbrev-info)	Print information about abbreviation/expansion control in a *pel-abbrev-info* buffer.  Prints current state and values of the relevant user-options as buttons you can use to get more info and change their customized values.	
Dynamic Text Expansion:  dabbrev-expand hippie-expand ★★	The <i>dynamic</i> expansion mode refers to the dynamic identification of the fully expanded text for partial text.  • Emacs supports two built-in dynamic expansion commands: <a href="dabbrev-expand">dabbrev-expand</a> and <a href="https://expand">https://expand</a> .  • The <a href="https://expand">https://expand</a> provides the same functionality as <a href="dabbrev-expand">dabbrev-expand</a> but it also includes more selectable sources of abbreviation/expansions.  The <a href="https://expand">M—//exp is bound to <a href="dabbrev-expand">dabbrev-expand</a> by default.</a>			
Expand Abbreviation	M-/	(dabbrev-expand ARG)	Expand previous word "dynamically". Used in DAbbrev mode.  PEL activates this when the pel-use-hippie-expand user option is set to nil	
	<ul> <li>Expands to the most recent, preceding word for which this is a prefix.</li> <li>If no suitable preceding word is found, words following point are considered. If still no suitable word is found, then look in the buffers accepted by the function pointed out by variable 'dabbrev-friend-buffer-function', if 'dabbrev-check-other-buffers' says so. Then, if 'dabbrev-check-all-buffers' is non-nil, look in all the other buffers, subject to constraints specified by 'dabbrev-ignored-buffer-names' and 'dabbrev-ignored-regexps'.</li> <li>A positive prefix argument, N, says to take the Nth backward *distinct* possibility. A negative argument says search forward.</li> <li>If the cursor has not moved from the end of the previous expansion and no argument is given, replace the previously-made expansion with the next possible expansion not yet tried.</li> <li>The variable 'dabbrev-backward-only' may be used to limit the direction of search to backward if set non-nil.</li> </ul>			
Hippie Expand Abbreviation				
See: Text Expansion with Hippie Expand @ Mastering Emacs		The expansion functions in 'hippie-expand-try-functions-list' are tried in order, until a possible expansion is found. Repeated application of 'hippie-expand' inserts successively possible expansions.  With a positive numeric argument, jumps directly to the ARG next function in this list. With a negative argument or just C-u, undoes the expansion. PEL activates this when the pel-use-hippie-expand user option is set to t.		
See also: <u><b>∑ Hide/Show</b></u>	M-/ M-/		When the origami-mode is active, hippie-expand is re-mapped to this key binding.  The origami-mode is a code folder mode. See Figure 1.2 Miles 1.2 Miles 1.2 Miles 2.2	
Find all possible expansions	C-M-/	(dabbrev-completion &optional ARG)	Completion on current word.	
	Like M-/ but finds all expansions in the current buffer and presents suggestions for completion.  • With a prefix argument ARG, it searches all buffers accepted by the function pointed out by 'dabbrev-friend-buffer-function' to find the completions.  • If the prefix argument is 16 (which comes from C-u C-u), then it searches *all* buffers.			
Manual Abbreviation: Abbrev Mode	Emacs abbreviation system performs abbreviation expansions when the abbrev minor mode is active in the current buffer.  • Association of abbreviation to fully expanded text must be defined explicitly with commands identified in the section "Creating Abbreviations" below.  The abbreviations are stored in a file identified by the abbrev-file-name user option, which is "~/.emacs.d/abbrev_defs" by default.  • When Emacs terminates, it will prompt for saving the new abbreviations.  • You can change that by setting the save-abbrevs user option to silently instead of t.  AEmacs load the abbreviation file at init time. As its size grows, the load time increases and that slows down Emacs startup time.  • PEL delays the loading of the abbreviation file by temporary changing the value of abbrev-file-name, loading it silently after initialization.			
<ul> <li>To expand abbreviation</li> <li>To prevent expansion</li> <li>To automatically activate</li> </ul>	<ul> <li>PEL installation instructions describe the required code; see the <u>PEL Manual</u> section <u>Delay Loading of Abbreviation Definition File</u>.</li> <li>When abbrev-mode is active, type the abbreviation then space or punctuation to expand the abbreviation.</li> <li>To prevent abbreviation expansion type C-q after the abbreviation before typing space or punctuation.</li> </ul>			
abbrev-mode in modes	To automatically activate abbrev-mode for some major modes, add the name of these major modes to the <b>pel-modes-activating-abbrev-mode</b> user-option. Access the appropriate customize buffer with the <b>fill a f2</b> > key sequence.			
Toggle Abbrev mode	<f11> a a (abbrev-mode &amp; optional ARG) Toggle the Abbrev mode in current buffer. <ul> <li>Once the Abbrev mode is activated in a buffer, you can type the abbreviation then a space or punctuation (comma, period, return, etc) will automatically expand the abbreviation to its complete expansion.</li> <li>To explicitly prevent the expansion, type C-q just after the abbreviation and before the next character.</li> </ul></f11>			
Creating Abbreviations	<ul> <li>To define an abbreviation, position point after the word(s) that define the target expansion and use: <ul> <li>C-x a g</li> <li>to define the abbreviation globally or</li> <li>C-x a 1</li> <li>to define the abbreviation for the current mode only.</li> <li>In both cases Emacs prompts for the corresponding abbreviation.</li> </ul> </li> <li>The inverse method is to position the cursor after the abbreviation text in the buffer and use: <ul> <li>C-x a i g</li> <li>to define the target expansion globally or</li> <li>C-x a i 1</li> <li>to define it for the current mode only (local).</li> </ul> </li> </ul>			
Abbreviations can be global or specific to a major mode.	The explicit commands listed below prompt for the abbreviation and its expansion. Abbreviations are either global or local to a specific major mode:  Command define-global-abbrev defines abbreviations that are accessible from all buffers.  Command define-mode-abbrev defines abbreviations that are only active in the buffer using the current major mode.			
Define an abbreviation	• C-x a g • <f11> a g</f11>	(add-global-abbrev ARG)	Define global (all modes) abbrev for last word(s) before point.  Prompts for the abbreviation that will be used when the abbrev-mode is used.  The prefix argument specifies the number of words before point that form the expansion; or zero means the region is the expansion.  A negative argument means to undefine the specified abbrev.  This command uses the minibuffer to read the abbreviation.	
Define an abbreviation for the current mode only	• C-x a 1 • C-x a + • C-x a C-a • <f11> a 1</f11>	(add-mode-abbrev ARG)	Define mode-specific abbrev for last word(s) before point.  Argument is how many words before point form the expansion; or zero means the region is the expansion.  A negative argument means to undefine the specified abbrev.  Reads the abbreviation in the minibuffer.	

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Define expansion	• C-x a i g • C-x a -	(inverse-add-global-abbrev N)	Define last word before point as a global (mode-independent) abbrev.  With prefix argument N, defines the Nth word before point.  This command uses the minibuffer to read the expansion.  Expands the abbreviation after defining it.	
Define expansion for the current mode only	С-жаі1	(inverse-add-mode-abbrev N)	Define last word before point as a mode-specific abbrev.  • With prefix argument N, defines the Nth word before point.  • This command uses the minibuffer to read the expansion.  • Expands the abbreviation after defining it.	
Explicitly define global abbreviation/expansion	<f11> a G</f11>	(define-global-abbrev ABBREV EXPANSION)	Define ABBREV as a global abbreviation for EXPANSION. Prompts for both.  • All characters in ABBREV must all be word constituents in the standard syntax table.	
Explicitly define local abbreviation/expansion	<f11> a L</f11>	(define-mode-abbrev ABBREV EXPANSION)	Define ABBREV as a mode-specific abbreviation for EXPANSION. Prompts for both.  • All characters in ABBREV must all be word-constituents in the current mode.	
Create abbreviations from spelling mistakes  See: autocorrection abbrevs	Take advantage of the spell check mechanism to identify abbreviations that really are spell checking fixes by using the command pel-ispell-word-then-abbrev when you detect a spelling error either manually, or through flyspell with flyspell-auto-correct-word. After fixing a typo once with the command below, similar typos will be automatically corrected by the abbreviation replacement mechanism.  To activate flyspell corrections inside the abbreviation table to automatically correct future typos, modify the following flyspell user-options:  flyspell-abbrev-p: set it to t to automatically store flyspell corrections in local abbrev table.  flyspell-use-global-abbrev-table-p: set it to t to have it store in the global abbrev table instead.  If you prefer to define the spell-check detected abbreviations manually, then use the pel-ispell-word-then-abbrev command on each one.			
Fix spelling mistake before point	• <f11> a \$ • <f11> M-\$</f11></f11>	(pel-ispell-word-then-abbrev &optional LOCALLY)	Fix spelling mistake in text before point.    See flyspell-auto-correct-word.	
Add old->new in the abbreviation table  See also: <u>▼ Spell Checking</u>	<ul> <li>Create an 'abbrev' abbreviation that match the typo to its correction.</li> <li>Store the abbreviation globally unless the LOCALLY argument is non-nil, in which case store it in the local abbreviation list.</li> </ul>			
	• If there's nothing wrong with the word at point, keep looking for a typo until the beginning of buffer. You can skip typos you don't want to fix with 'SPC', and you can abort completely with 'C-g'.			
Deleting Abbreviations	To remove all global ar	nd local abbreviations, type M-x kill-all-a	bbrevs	
Delete all abbreviations		(kill-all-abbrevs)	Undefine all defined abbrevs.  Deletes both globals and locals (current mode specific) ones.	
Manual Expansion of Abbreviations	The following commands expand the abbreviations created manually.			
Expand abbreviation with prefix	м-'	(abbrev-prefix-mark &optional ARG)	Mark current point as the beginning of an abbrev.  • Abbrev to be expanded starts here rather than at beginning of word.  See the EmacWiki Abbrev Prefixes for very nice example on how to use this.	
	<ul> <li>This way, you can expand an abbrev with a prefix: insert the prefix, use this command, then insert the abbrev. This command inserts a temporary hyphen after the prefix (until the intended abbrev expansion occurs).</li> <li>If the prefix is itself an abbrev, this command expands it, unless ARG is non-nil. Interactively, ARG is the prefix argument.</li> <li>If you just want to expand an abbreviation, type the abbreviation and then type M-′. The command will expand and append a '-' character that you can then delete if you don't need it.</li> <li>If you want expand a word with a prefix type the prefix, type M-′, then type the abbreviation and type M-′ again.</li> </ul>			
Expand abbreviation	• C-x a e • <f11> a e • <f11> /</f11></f11>	(expand-abbrev)	Expand the abbrev before point, if there is an abbrev there.  Solution This can be used to expand skeleton abbreviations.	
Expand abbreviations in region	<f11> a E</f11>	(expand-region-abbrevs START END & optional NOQUERY)	<ul> <li>For abbrev occurrence in the region, offer to expand it.</li> <li>The user is asked to type 'y' or 'n' for each occurrence.</li> <li>A prefix argument means don't query; expand all abbrevs.</li> </ul>	
Undo last expansion	<f11> a u</f11>	(unexpand-abbrev)	Undo the expansion of the last abbrev that expanded.  • This differs from ordinary undo in that other editing done since then is not undone.	
Editing Abbreviations	Use the following commands to list all existing abbreviations and modify them inside the *Abbrevs* buffer.  • The abbrevs editing buffer contains a header line for each abbrev table, which is the abbrev table name in parentheses.  • This is followed by one line per abbrev in that table:  NAME USECOUNT EXPANSION HOOK  where NAME and EXPANSION are strings with quotes, USECOUNT is an integer, and HOOK is any valid function or may be omitted  • (it is usually omitted).			
List & Edit all abbreviation definitions	<f11> a M-1</f11>	(list-abbrevs &optional LOCAL)	Display a list of defined abbreviations inside the *Abbrevs* buffer, that operates in editabbrevs-mode.  • If LOCAL is non-nil, interactively when invoked with a prefix arg ( <b>C</b> - <b>u</b> ), display only local, i.e. mode-specific, abbrevs. Otherwise display all abbrevs.  • Edit the text in the opened *Abbrev* buffer to modify the abbreviations.  • Complete by typing <b>C-c C-c</b> .	
Edit abbreviations in *Abbrev* buffer	• <f11> a M-e • ₩-E</f11>	(edit-abbrevs)	Alter abbrev definitions by editing the current mode list in the *Abbrevs* buffer, that operates in edit-abbrevs-mode.  • Selects a buffer containing a list of abbrev definitions with point located in the abbrev table for the current buffer, and turns on 'edit-abbrevs-mode' in that buffer.  • You can edit them and type C-c C-c to redefine abbrevs according to your editing.	
*Abbrevs* buffer commands	Inside the *Abbrevs* b	uffer the following commands can be use	ed:	
Use specified abbreviations Save abbreviations	C-c C-c C-x C-s	(edit-abbrevs-redefine) (abbrev-edit-save-buffer)	Redefine abbrevs according to current buffer contents.  Save all user-level abbrev definitions in current buffer.	
Save abbreviations to	C-x C-w	(abbrev-edit-save-to-file FILE)	The saved abbrevs are written to the file specified by 'abbrev-file-name'.  Save all user-level abbrev definitions in current buffer to FILE.	
specified file Saving Abbreviations	Use the following com	,	puffer, restore abbreviations from a file or a buffer.	
Write abbreviations in a file	<f11> a s</f11>	(write-abbrev-file &optional FILE VERBOSE)	<ul> <li>Write all user-level abbrev definitions to a file of Lisp code.</li> <li>This does not include system abbrevs; it includes only the abbrev tables listed in listed in 'abbrev-table-name-list'.</li> </ul>	
Read abbreviations from a file	<f11> a r</f11>	(read-abbrev-file &optional FILE QUIETLY)	Read abbrev definitions from file written with 'write-abbrev-file'.  • Optional argument FILE is the name of the file to read; it defaults to the value of 'abbrev-file-name'.	
Write abbreviations inside current buffer after point	<f11> a i</f11>	(insert-abbrevs)	Insert after point a description of all defined abbrevs.  • Mark is set after the inserted text.	
Define abbreviations by reading them from the current buffer	<f11> a X</f11>	(pel-extract-abbrev-definitions)	Read abbreviation/expansion data from the current abbrev definition buffer.  Prompt user before proceeding.  See documentation of 'edit-abbrevs' for info on the format of the text you must have in the buffer.  With argument, eliminate all abbrev definitions except the ones defined from the buffer now.  pel-define-abbrevs calls define-abbrevs after a positive response to the prompt.	