## Autosave / Backup

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>
File Auto-Saving	By default Emacs autosaves files into file that have a name that starts and ends with '#', unless there's code that changes that behaviour.  • PEL uses the default auto-save file names.  • Buffers not visiting files can also be autosaved if that is requested explicitly (by turning the auto-save-mode for that buffer).  • When a large portion of text is deleted from a buffer, its auto-save-mode is automatically disabled temporarily to help retain that deleted text in the auto-saved copy. It is re-activated when the buffer is saved in a file (with C-x C-s) or when activating auto-save-mode.		
Last updated on:	2025-04-30	PEL does not assign key bindings to commar	nds that toggle backup to prevent toggling them by mistake.
Open this PDF file (∑ Autosave/Backup) See also: ∑ Help/Info	• <f11> ? p • <f11> p</f11></f11>	(pel-help-pdf-select &optional OPEN-WEB-PAGE)	Prompt for a PEL PDF and open it. Prompt supports tab completion.  For this PDF type <b>backup</b> < <b>RET&gt;</b> at the prompt.  If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.
Toggle autosave of the current buffer	M-x auto-save- mode	(auto-save-mode &optional ARG)	Toggle auto-saving in the current buffer (Auto Save mode).  • With a prefix argument ARG, enable Auto Save mode if ARG is positive, and disable it otherwise.
Toggle auto-saving directly to the file (instead of the normal auto-save file)	M-x auto-save- visited-mode	(auto-save-visited-mode &optional ARG)	Toggle automatic saving to file-visiting buffers on or off.  With a prefix argument ARG, enable regular saving of all buffers visiting a file if ARG is positive, and disable it otherwise.  Unlike 'auto-save-mode', this mode will auto-save buffer contents to the visited files directly and will also run all save-related hooks.
Auto-save now all buffers that need it.	M-x do-auto-save	(do-auto-save &optional NO-MESSAGE CURRENT-ONLY)	Auto-save all buffers that need it.  This is all buffers that have auto-saving enabled and are changed since last auto-saved.  Auto-saving writes the buffer into a file so that your editing is not lost if the system crashes. This file is not the file you visited; that changes only when you save.
Recovering Data from auto- saves	The following commands allow recovering data from auto-saved files.		
Recover content of file from its auto- saved copy.	M-x recover-file	(recover-file FILE)	Visit file FILE, but get contents from its last auto-save file.
Recover a session after Emacs crash	M-x recover- session	(recover-session)	Recover auto save files from a previous Emacs session.  This command first displays a Dired buffer showing you the previous sessions that you could recover from.  To choose one, move point to the proper line and then type C-c C-c. Then you'll be asked about a number of files to recover.
Backup Files	<ul> <li>By default Emacs makes a single backup file for each file edited: a file with the name ending with '~'.</li> <li>It's also possible to use numbered backups with our without automatic deletion of old ones.</li> <li>All of this is controlled by <u>backup user options</u>: version-control, kept-new-versions, kept-odd-versions, deleted-old-versions and dired-kept-versions</li> <li>Emacs has a set of functions that deal with backups but no explicit commands.</li> </ul>		
Compare file with its backup			
Compare file with its backup See also: <u>▼ Diff &amp; Merge</u>	<f11> d e f k</f11>	(ediff-backup FILE)	Compare a file with its backup. If there are several numerical backups, use the latest.  • If the file is itself a backup, then compare it with its original.

## Autosave/Backup — References

Topic & Link	Description	
Emacs Manual - Auto-save		
Emacs Manual - Backup Files		
How do I reload a file in a buffer? @ StackExchange	Discussion that describes several aspect of reloading a file.	