## Emacs support for Python

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Python Support	PEL Python support is incomplete, not yet fully implemented nor fully documented. This is currently evolving.  Important aspects of Python source code management are customizable with PEL user option variables.  PEL customization for Python:  • Emacs customization group: pel-pkg-for-python (To edit change, use <f12> <f2> , see below).  • pel-python-tab-width: The width of a tab used for c-mode files. Defaults to 4.  • This concept differs from indentation: you can have an indentation of 3 and tab width of 8: M-i will move point to columns that are multiple of 8 <tab> will indent to a column that is a multiple of 3. PEL stores this value inside the tab-width variable for python-mode buffers.  • The values for those user option variables can also be stored inside directory local files and even as file local variables. You can also modify them for each buffer and view their current settings using the commands listed in the following set of rows. See ▼File/Directory Variables for more info.  • None of the commands below change PEL default; they change the value for the current buffer only.</tab></f2></f12>			
	PEL provides the following set of mode-specific key prefixes: <f11> SPC p, <f12> and M-<f12> The first one is always available. The other two prefixes are only available in c-mode buffers. The M-<f12> prefix helps the typing flow when the next ke key. For simplification, the <f11> SPC p prefix is normally omitted in the table.  Tree-Sitter Support : when the pel-use-tree-sitter user-option is set to t, PEL downloads, installs and provides tree-sitter support via:</f11></f12></f12></f12></f11>		ble in c-mode buffers. The M- <f12> prefix helps the typing flow when the next key is a Meta in the table.</f12>	
	Tree-sitter Support was: when the per-use-tree-sitter user-option is set to t, PEL downloads, installs and provides tree-sitter support via:    Tree-sitter and tree-sitter-langs external packages. These are installed automatically by PEL when pel-use-tree-sitter is on.			
Tree-Sitter (@GitHub)	Other Requirements:  • Emacs with dynamic module loading, and built with tree-sitter support. tree-sitter library must be installed separately.  • See: How to Get Started with Tree-Sitter  • Emacs must find the tree-sitter language dynamic library files that have a name similar to 'libtree-sitter-python.so' (for Linux) or .dylib (for macOS).			
Last updated on:	<ul> <li>Identify the relevant directory in the pel-treesit-load-path. See the docstring of that user-option for further instructions.</li> <li>2025-03-19</li> </ul>			
Open this PDF file. See also: <u>E Help/Info</u>	<f11> SPC p <f1><f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$\mathbb{N} \cdot - Python</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.	
© Customize PEL Python support	<f11> SPC p <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Python support: python, python-flymake.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
© Customize Emacs Python support	<f11> SPC p <f3> <f12> <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs Python support: python, python-flymake.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
Select python-mode for extension-less file	<f12></f12>	(pel-as &optional FORCE)	Inside a fundamental-mode buffer, interactively select major mode for the buffer. Re-do it with arg.	
The <f12> key is available only until a PEL controlled major mode is activated. Then it becomes a buffer prefix key.</f12>	This command is mostly used to set the major mode of a buffer in fundamental-mode', when the <f12> key binding is available for it.  After being used once in a buffer the major mode is selected and the PEL key binding will not be available when PEL supports the major mode.  For Python file, select python. It will insert a shebang line specified by pel-python-shebang-line user option.  PEL defines the (as &amp;optional FORCE) alias unless pel-has-alias-as user-option is set to nil. You can use M-x as to invoke it.</f12>			
Comments				
Toggle display of comments in buffer or active region See also: <u>S Comments</u>	<f11> ; ;</f11>	(hide/show-comments-toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active then toggle in the region. Otherwise, in the whole buffer.  • This requires the <a href="hide-commt.el">hide-commt.el</a> package (see <a href="Secomments">Secomments</a> ). <a href="#ide-commt">Ide-commt</a> PEL activates it when the <a href="pel-use-hide-commt">pel-use-hide-commt</a> user option is t.	
Navigation	The following navigation commands are specialized for Python and complement what is described in the <u><b>\bar{\textit{L}} Navigation</b></u> section.			
Find definitions using iMenu	• C-c C-j • <f11> <f10> i</f10></f11>	(imenu INDEX-ITEM)	Opens the imenu buffer in the minibuffer window with a list of all definitions.  • Provides the same list as the MenuBar Index: the list of important entry points in the file.  • Use TAB completion to select entry: on TAB, lists all top level function and classes. Type	
• by block		nove point through Python code blocks	the name of the class than a period and TAB lists all members of the class.	
Go backward to	M-a	(python-nav-backward-block &optional	Go backward to the beginning of the previous block of code (if there is one).	
beginning of the previous block of code		ÄRG)	Blocks are the following statements: if, else, for, while, def, class, With ARG, repeat. Shift marking is available	
Go forward to the beginning of the	М-е	(python-nav-forward-block &optional ARG)	Go forward to the next block of code. Shift marking is available Blocks are the following statements: if, else, for, while, def, class, With ARG, repeat. With negative argument, move ARG times backward to previous bloc	
Go up in the block hierarchy	• C-M-u • C-M- <up> • C-[ C-u • Esc C-u • Esc C-<up></up></up>	(python-nav-backward-up-list &optional ARG)	Go backward out of one level of parentheses (or blocks).  • With ARG, do this that many times.  • A negative argument means move forward but still to a less deep spot.  • This command assumes point is not in a string or comment.  • Muth PEL: if you want to use Esc C- <up> binding you must ensure that pel-</up>	
			windmove-on-esc-cursor user option is set to nil.  • C-M-u : ► Shift marking is available in graphics mode, not in terminal mode.  • C-M- <up> : ► Shift marking works with this command.  • C-M-<up> does not work on Windows, but H-<up> does.</up></up></up>	
<ul> <li>by class/ function definition</li> </ul>	The commands move point by function and class definitions.  The <ff> cursor key mappings use <up> and <down> to move to the beginning of the function/class definition, and <left> and <right> to the end of the function/class definition.  These work with function definitions and allow moving forward to the end of a class definition, but not backward to the beginning or end of a class definition.</right></left></down></up></ff>			
Backward to beginning	• C-M-a	(beginning-of-defun &optional ARG)	Move backward to the beginning of a defun.	
of function definition	• C-M- <home> • <f6> <up> • C-[ C-a • Esc C-a</up></f6></home>		<ul> <li>With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.</li> <li>Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M-<a href="https://www.home">home</a>). It's always available for <f6> <up>: hold Shift after typing <f6>.</f6></up></f6></li> <li>⚠ This command moves to the beginning go the next function or of the same nesting leve of the current location. It skips the functions and methods that are more deeply nested.</li> </ul>	
Forward to end of function and class definition	• C-M-e • C-M- <end> • <f6> <right> • C-[ C-e • Esc C-e</right></f6></end>	(end-of-defun &optional ARG)	Move forward to next end of defun. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  F Shift marking is available in graphics mode, not in terminal mode (both keys).  This command moves to the end of the next top-level function or class. It skips the nested functions and methods.	
Forward to start of next function definition	<f6> <down></down></f6>	(pel-beginning-of-next-defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition.  Beeps if does not find beginning of next function unless SILENT is non-nil.  If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  Move back to previous position with M-^ or <f6><f6>.  Shift marking is available: hold Shift after typing <f6>.  This command complements what end-of-defun does.  It moves forward but not to the end of the function definition (like end-of-defun) but to the</f6></f6></f6>	
			beginning of the function definition, which is often what users of other editors expect.  • It handles nested functions or class methods in languages like Python and others.	

Description	<u>Keystroke</u>	Function	Note
Backward to end of previous function definition	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT-PUSH_MARK)	Move backwards to the end of the previous function definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M−ˆ or <f6><f6>.  ▼ Shift marking is available.  ▼ This command complements this set of 4 commands.  • ⚠ It handles most nested functions or class methods in Python but not always. In some cases it does not move the point. Better logic is needed.   ★★★★</f6></f6>
Highlight blocks	The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and [].  • show-paren-mode, which highlights the parens that matches the one before or after point.  • <u>rainbow delimiters</u> mode, where matching nested parens are highlighted with the same colour.		
Toggle show-paren mode on/off	• <f12> M-9 • M-<f12> M-9</f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>I Highlight</u>	• <f11> h (</f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (),{},[] See also: ∑ Highlight	• <f12> M-r • M-<f12> M-r • <f11> h R</f11></f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.  • Customize the depth and colours with M-x customize-group rainbow-delimiters  • Requires: rainbow-delimiters.el
			PEL activates this when the <b>pel-use-rainbow-delimiters</b> user option is set to <b>t</b> .
Indentation			omplement what is available in the <u>S Indentation</u> section.
Mark current function or class definition	• C-M-h • C-[ C-h • Esc C-h	(python-mark-defun &optional ALLOW-EXTEND)	Put mark at end of this python function or class definition, point at beginning.  The function or class definition marked is the one that contains point or follows point.  Interactively (or with ALLOW-EXTEND non-nil), if this command is repeated or (in Transient Mark mode) if the mark is active, it marks the next function or class definition after the ones
Decent current line	DEL	(python-indent-dedent-line-backspace ARG)	already marked.  De-indent current line: dements the line when point is on the first non-blank character.  • Argument ARG is passed to 'backward-delete-char-untabify' when point is not in between the indentation.
	<backtab></backtab>	(python-indent-dedent-line)	De-indent current line: dements the line when point is on the first non-blank character.
	C-c <	(python-indent-shift-left START END & optional COUNT)	Shift lines contained in region START END by COUNT columns to the left. Point can be anywhere on the line. COUNT defaults to 'python-indent-offset'.  • If region isn't active, the current line is shifted. The shifted region includes the lines in which START and END lie. An error is signaled if any lines in the region are indented less than COUNT columns.
Indent current line	C-c >	(python-indent-shift-right START END & optional COUNT)	Shift lines contained in region START END by COUNT columns to the right. Point can be anywhere on the line. COUNT defaults to 'python-indent-offset'.  • If region isn't active, the current line is shifted. The shifted region includes the lines in which START and END lie.
Open the indent-tools hydra  See also:  Indentation	• <f11> <tab> <f7> • <f7> <tab> • C-c &gt;</tab></f7></f7></tab></f11>	(indent-tools-hydra/body)	Activate the body in the "indent-tools-hydra" hydra.  Requires indent-tools external package PEL activates it when the pel-use-indent-tools user-option is turned on (set to t).  With PEL, this key binding is only available when:  globally, when pel-indent-tools-key-bound is set to globally,  in python-mode only when pel-indent-tools-key-bound is set to python.  The actual key is selected by indent-tools indent-tools-keymap-prefix user-option, the default is C-c >
See also: Fide/Show  Indent region or line or complete symbol before point	c: 'indent-tools-or U: 'indent-tools-ui P: 'indent-tools-in 1: 'indent-tools-ki C: 'indent-tools-s s: 'indent-tools-s e: 'indent-tools-g u: 'indent-tools-g d: 'indent-tools-g n: 'indent-tools-g	dent', emote', ident-end-of-defun', omment', ident-paragraph', ident-end-of-level', ill-tree', opy-hydra/body', elect', oto-end-of-tree', oto-parent',	Indent   j v
point.			<ul> <li>If cursor is at end of a symbol, try to complete,</li> <li>otherwise indent the current line.</li> <li>Note: use 'C-q TAB' to insert a literally TAB-character</li> <li>In 'python-mode' 'py-complete-function' is called, in (I)Python shell-modes 'py-shell-complete'</li> </ul>
Search Support			often used. Using superword-mode helps searching.  this use the <f11> t <f2> to access the customize buffer.</f2></f11>
Toggle superword-mode See also:  • ∑ Text Modes  • ∑ Search/Replace	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In Python '_' are treated as part of words.  • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.  • PEL provides the <f12> M-p key for the programming language modes where <u>snake case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Generic code skeletons • tempo skeletons See also: • ∑ Inserting Text • T Templates	Several mechanisms have been developed to allow easy insertion of predefined text in Emacs. PEL does not yet define skeletons for Python. You can use the generic one.  • Emacs provides the built-in skeleton mechanism and the tempo skeletons.  • PEL supports both. They are used a little bit differently. PEL provides generic tempo skeletons you can use for Python until PEL adds Python-specific skeletons.  • PEL provides key bindings to the tempo skeletons: the generic code templates, accessible via the <f6> prefix key, and the language-specific code templates, accessible via the <f12> key prefix.</f12></f6>		
<u>© Customize</u> PEL Text Insertions control for Python code skeletons.	<f6> <f2> <f12> <f12> <f2></f2></f12></f12></f2></f6>	(pel-customize-pel &optional OTHER-WINDOW)  (pel-customize-generic-skels &optional OTHER-WINDOW)	Open the customization groups that control the format of the various skeletons including the generic skeleton used by the <f6> h key and the <f12><f12> h key (see below).  • If OTHER-WINDOW is non-nil (use C-u), display in other window.</f12></f12></f6>
Insert generic file module header block — Language agnostic	<f6> h</f6>	(pel-generic-file-header)	Insert a file header block at the top of the file. Works only for buffer visiting a file.  The command key binding <f6> h is available only 1 second after Emacs has started.  As mentioned above PEL does not yet define Python-specific skeletons, this uses the</f6>
After inserting the	1127 1127 11		generic one.

<u>Description</u> template, navigate though	<u>Keystroke</u>	Function	Note
areas that must be filled with:	_ · · · · ·		eric-code-style customization group accessible via <f6> <f2></f2></f6>
<ul> <li>tempo-forward-mark:</li> <li>C-c.</li> <li>tempo-backward-mark:</li> <li>C-c,</li> </ul>	S After inserting a temporare, use tempo-rorward-mark and tempo-backward-mark to move to the beginning of each section that must be fined.		
Toggle pel-tempo-mode	<f6> SPC</f6>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off.
	is active the pel-tempo-mod	de lighter (‡) is shown on the status bar. The sec	d C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode cond set of keys are only available in graphics mode.  leton: the PEL tempo mode is automatically activated by typing <f6> h.</f6>
Expand any tag in	<f6> <f12> (tempo-complete-tag &amp;optional SILENT) Look for a tag and expand it. All the tags in the tag lists in 'tempo-local-tags' (this in 'tempo-tags') are searched for a match for the text before the point. The way the strip.</f12></f6>		
template  Note: PEL default skeleton does not use tags.	<f12> <f12> <f12></f12></f12></f12>		<ul> <li>'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all.</li> <li>If a single match is found, the corresponding template is expanded in place of the matching string.</li> <li>If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal.</li> <li>If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.</li> </ul>
Python Skeleton			
Insert class	C-c C-t c	(python-skeleton-class &optional STR ARG)	Insert class statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert def	C-c C-t d	(python-skeleton-def &optional STR ARG)	Insert def statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert for	C-c C-t f	(python-skeleton-for &optional STR ARG)	Insert for statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert if	C-c C-t i	(python-skeleton-if &optional STR ARG)	Insert if statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert import	C-c C-t m	(python-skeleton-import &optional STR ARG)	Insert import statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert try	C-c C-t t	(python-skeleton-try &optional STR ARG)	Insert try statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Insert while	C-c C-t w	(python-skeleton-while &optional STR ARG)	Insert while statement.  This is a skeleton command (see 'skeleton-insert').  Normally the skeleton text is inserted at point, with nothing "inside".  If there is a highlighted region, the skeleton text is wrapped around the region text.  A prefix argument ARG says to wrap the skeleton around the next ARG words.  A prefix argument of -1 says to wrap around region, even if not highlighted.  A prefix argument of zero says to wrap around zero wordsthat is, nothing.  This is a way of overriding the use of a highlighted region.
Python shell	Interact with a Python proce	ess with the following commands.	
Start Python Shell in Emacs Window	• <f11> z r p</f11>	(run-python &optional CMD DEDICATED SHOW)	Run an inferior Python process.  Argument CMD defaults to 'python-shell-calculate-command' return value. When called interactively with 'prefix-arg', it allows the user to edit such value and choose whether the
See also: <u>Shells</u>	• C-c C-p • <f12> z</f12>		<ul> <li>interpreter should be DEDICATED for the current buffer. When numeric prefix arg is other than 0 or 4 do not SHOW.</li> <li>For a given buffer and same values of DEDICATED, if a process is already running for it, it will do nothing. This means that if the current buffer is using a global process, the user is still able to switch it to use a dedicated one.</li> <li>Runs the hook 'inferior-python-mode-hook' after 'comint-mode-hook' is run. (Type C-h m in the process buffer for a list of commands.)</li> </ul>
Switch to the buffer running the Python shell	C-c C-z	(python-shell-switch-to-shell &optional MSG)	Switch to inferior Python process buffer.  When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.
Send a string to Python interpreter process	C-c C-s	(python-shell-send-string STRING &optional PROCESS MSG)	Send STRING to inferior Python PROCESS. Prompt for the string.  When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.
Send region to Python interpreter	C-c C-r	(python-shell-send-region START END &optional SEND-MAIN MSG)	Send the region delimited by START and END to inferior Python process.  • When optional argument SEND-MAIN is non-nil, allow execution of code inside blocks delimited by "ifname== 'main':".  • When called interactively SEND-MAIN defaults to nil, unless it's called with prefix argument. When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.

Description	Keystroke	Function	Note
Send a function	C-M-x	(python-shell-send-defun &optional ARG	Note  Send the current defun to inferior Python process to ensure that this function is available in
definition to the Python interpreter	J-M-1	MSG)	different defunition interior symbol process to ensure that this function is available in the shell directly by its name. diffusion has a doctest.  When argument ARG is non-nil do not include decorators. When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.
Send the entire buffer to the Python interpreter	C-c C-c	( <b>python-shell-send-buffer</b> & optional SEND-MAIN MSG)	Send the entire buffer to inferior Python process.  • When optional argument SEND-MAIN is non-nil, allow execution of code inside blocks delimited by "ifname== 'main':".  • When called interactively SEND-MAIN defaults to nil, unless it's called with prefix argument.  • When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.
Send a file to the Python interpreter	C-c C-1	(python-shell-send-file FILE-NAME &optional PROCESS TEMP-FILE-NAME DELETE MSG	Send FILE-NAME to inferior Python PROCESS. Prompt for the file name.  If TEMP-FILE-NAME is passed then that file is used for processing instead, while internally the shell will continue to use FILE-NAME.  If TEMP-FILE-NAME and DELETE are non-nil, then TEMP-FILE-NAME is deleted after evaluation is performed.  When optional argument MSG is non-nil, forces display of a user-friendly message if there's no process running; defaults to t when called interactively.
Python Utilities			
Check Python code	C-c C-v	(python-check COMMAND)	Check a Python file (default current buffer's file).  Runs COMMAND, a shell command, as if by 'compile'.  The 'python-check-command' user option variable identifies the command to run. It is set to pyflakes or epylint. You can identify any program that checks python code.
Display help	C-c C-f	(python-eldoc-at-point SYMBOL)	<ul> <li>Get help on SYMBOL using 'help'.</li> <li>Interactively, prompt for symbol.</li> <li>Displays information on the echo area. This works mostly for function that have a simple docstring.</li> <li>This would benefit from some work to display longer strings inside a dedicated buffer as well as detecting single line help that could be shown in the echo area.</li> </ul>
Display help for symbol at point	C-c C-d	(python-describe-at-point SYMBOL PROCESS)	Same as above, except that it picks the word at point.  This would benefit from some work to display longer strings inside a dedicated buffer as well as detecting single line help that could be shown in the echo area.
Newline and indent	RET	(newline &optional ARG INTERACTIVE)	Insert a newline and indent.  • Two different implementations with the same effect.
	C-j :	(py-newline-and-indent)	
	DEL		
	backspace		
	C-backspace		
	C-c delete		
Go to beginning of statement	С-с С-р	(py-backward-statement &optional ORIG DONE LIMIT IGNORE-IN-STRING-P REPEAT MAXINDENT)	Go to the initial line of a simple statement.  • For beginning of compound statement use 'py-backward-block'.  • For beginning of clause 'py-backward-clause'.
Go to end of statement	C-c C-n	( <b>py-forward-statement</b> & optional ORIG DONE REPEAT)	Go to the last char of current statement.
Go to beginning of compound statement	C-c C-u	(py-backward-block)	Go to beginning of 'block'.  • If already at beginning, go one 'block' backward.
Go to end of compound statement	C-c C-q	(py-forward-block &optional ORIG BOL)	Go to end of block.
Go to beginning of function or class definition	С-м-а	(py-backward-def-or-class)	Go to beginning of 'def-or-class'.  • If already at beginning, go one 'def-or-class' backward.
Go to end of function or class definition	С-М-е	(py-end-of-def-or-class &optional ORIG BOL)	Go to end of def-or-class.  • Return end of 'def-or-class' if successful, nil otherwise
De-indent	s-backspace	(py-dedent &optional ARG)	Dedent line according to 'py-indent-offset'.  • With arg, do it that many times.  • If point is between indent levels, dedent to next level.
De-indent	• C-c C-1 • C-c <	(py-shift-left &optional COUNT START END)	Dedent region according to 'py-indent-offset' by COUNT times.  • If no region is active, current line is dedented.
Indent	• C-c C-r • C-c >	(py-shift-right &optional COUNT BEG END)	Indent region according to 'py-indent-offset' by COUNT times.  • If no region is active, current line is indented.
	C-c tab	(py-indent-region BEG END)	In case first line accepts an indent, keep the remaining lines relative.     Otherwise lines in region get outmost indent, same with optional argument     In order to shift a chunk of code, where the first line is okay, start with second line.
Rendering markun	C-c: The following commands as	re used to create images from specific markup of	code embedded inside Python source code comments. This can be useful when using these
Rendering markup embedded in comments	markup languages to descr	ibe UML diagrams or finite-state machines for e	
Preview UML diagram	You can also use Graphviz,		Render the PlantUML markup embedded in current mode comment.
Preview UML diagram from plantUML source in current plantUML region of commented source code  See also: M PlantUML	<f12> u</f12>	(pel-render-commented-plantumi PREFIX &optional POS)	Use region if identified otherwise use PlantUML block at point.  Uses prefix (as PREFIX) to choose where to display it:  4 (when prefixing the command with C-u) -> new window  16 (when prefixing the command with C-u C-u) -> new frame.  else -> new buffer  This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.  Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.
		Emacs & Python –	- References
Docu	ument	Not	
Installing Python  How to install Python o	n your System	The latest version of macOS has a macOS s Users cannot modify /usr/bin. Also, it's best to ensure that your develop which is normally an older version of Pyth Whatever other Python is installed, the Python is installed.	dier versions are no longer supported by Apple and therefore Python on macOS): system Python installed in /usr/bin by the macOS System development tools.  Dement Python installation does not modify what's available to the system's Python (on /usr/bin), then that can be updated on macOS system updates.  Sython packages should not be changing what's available to the system's Python.  Install Python using the Official Python Installer or homebrew:

Document	Notes		
Recommended for macOS ==>>	The Official Python Installer is more complete, therefore rea	commended.	
	It installs Python in: /usr/bin/local     Once done, you need to customize your shell startup sor	rint to setup the environment variable required for Python	
	The installer provides a script.	input to Setup the environment variable required for Fython.	
	USRHOME provides a set of scripts to activate     It also installs Python HTML documentation, the IDLE appli	cation, Python Launcher application, a script to update the shell profile.	
	Homebrew installs Python in a directory that depends on the macOS system type:  On older Intel-based macOS system: /usr/local/bin as a symbolic link to a  On latest Apple-silicon macOS systems: /opt/homebrew/bin/python3		
d It's possible, on a macOS system to have 3 base	⚠ However, they will most probably be different versions of Py	thon and the Python libraries of each one should be isolated from the	
installations of Python and they can co-exist.	<ul> <li>others, otherwise you risk cross-contamination and problems as time passes!</li> <li>Because of the above, if you develop your own Python source code, you will probably want to ensure that the byte-compiled files a stored in a location that corresponds to the version of Python that you use.</li> </ul>		
Installing Python on macOS:	Location of Python executable(s):	Location of Python Library (sys.path):	
Showing state at one point in time, with the 3 different types of installations each using a different version of Python:  • macOS system dev tools (3.9)  • Note: even though the /usr/bin/python3 is the system Python, if PATH has several other directories, to use it put / Applications/Xcode.app/Contents/ Developer/Library/Frameworks/ Python3.framework/Versions/3.9/bin at the beginning of PATH to prioritize Python.	/usr/bin/python3	/Applications/Xcode.app/Contents/Developer/Library/Frameworks.     Python3.framework/Versions/3.9/lib/python39.zip     /Applications/Xcode.app/Contents/Developer/Library/Frameworks/Python3.framework/Versions/3.9/lib/python3.9     /Applications/Xcode.app/Contents/Developer/Library/Frameworks/Python3.framework/Versions/3.9/lib/python3.9/lib-dynload     /Applications/Xcode.app/Contents/Developer/Library/Frameworks/Python3.framework/Versions/3.9/lib/python3.9/site-packages	
Official Python Installer. (3.13)     Note: even though symlinks to all executables are stored in /usr/local/bin, when installing this Python in PATH, put /Library/Frameworks/Python.framework/Versions/3.13 at the beginning of PATH to prioritize only Python.	All executables are in: /Library/Frameworks/ Python.framework/Versions/3.13     Symbolic links are stored in: /usr/local/bin:     python3	<ul> <li>/Library/Frameworks/Python.framework/Versions/3.13/lib/ python313.zip</li> <li>/Library/Frameworks/Python.framework/Versions/3.13/lib/python3.13</li> <li>/Library/Frameworks/Python.framework/Versions/3.13/lib/python3.13/ lib-dynload</li> <li>/Library/Frameworks/Python.framework/Versions/3.13/lib/python3.13/ site-packages</li> </ul>	
Note: even though homebrew Python is in /opt/homebew/bin/python3, if you want it's Python to be used over the other ones, put /opt/homebrew/Cellar/python@3.12/3.12.7/bin at the beginning of PATH to prioritize only its Python.  Python Topics	All executables are in: /opt/homebrew/Cellar/python@3.12/3.12.7/bin Symbolic links are stored in /opt/homebrew/bin: /opt/homebrew/bin/python3 /opt/homebrew/bin/python3.12 /opt/homebrew/bin/python3.12-config /opt/homebrew/bin/python3.12-config	<ul> <li>/opt/homebrew/Cellar/python@3.12/3.12.7/Frameworks/ Python.framework/Versions/3.12/lib/python312.zip</li> <li>/opt/homebrew/Cellar/python@3.12/3.12.7/Frameworks/ Python.framework/Versions/3.12/lib/python3.12</li> <li>/opt/homebrew/Cellar/python@3.12/3.12.7/Frameworks/ Python.framework/Versions/3.12/lib/python3.12/lib-dynload</li> <li>/opt/homebrew/lib/python3.12/site-packages</li> </ul>	
Python Environment Variables @ Python Doc	List of environment variables that influence Python's behaviour.	Like DYTHONDATH and DYTHONHOME	
_			
Emacs Python Support	The information below is old and needs to be updated as do	es PEL support of Python.	
Emacs - The Best Python Editor?			
emacs-for-python			
Duth an indontation			
Python indentation			
Python code Indentation			
Python code Indentation  Elpy - Emacs Python Development Environment	Windows-related problem description, and description of a fix	(which I have implemented in my init all. Fiving that does not solve	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor	mpletion does not work on Windows and that we should add "python" to the	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: describ	he following lines. mpletion does not work on Windows and that we should add "python" to the	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en	he following lines.  mpletion does not work on Windows and that we should add "python" to the nacs.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: describ warning (using the method described above).	he following lines.  mpletion does not work on Windows and that we should add "python" to the nacs.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: describ warning (using the method described above).  Windows-related problem description. Same problem.	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: descrit warning (using the method described above).  Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode; Modular in-buffer completion framework for Emacs	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: descrit warning (using the method described above).  Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode; Modular in-buffer completion	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: describ warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the nacs.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode; Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages	everything under Windows, and there is another issue, listed in t  Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en  Windows-related problem description: elpy-issue-887: descrit warning (using the method described above).  Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. Date of that package. Date of the pa	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode : Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode  Despite still being used by notable Python authors, this package needs a complete overhaul As it stand in early 2021 I recommend to stay away from it	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode  Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in early 2021 I recommend to stay away from it.	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode  Despite still being used by notable Python authors, this package needs a complete overhaul As it stand in early 2021 I recommend to stay away from it  elpy  jedi	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580  [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode  Despite still being used by notable Python authors, this package needs a complete overhaul As it stand in early 2021 I recommend to stay away from it  elpy  jedi  eval-in-repl-python	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode : Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in early 2021 I recommend to stay away from it. I elpy  jedi  eval-in-repl-python  auto-virtualenv  cerbere  cinspect  conda	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roc code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul. A as it stand in early 2021 I recommend to stay away from it. I elpy jedi  eval-in-repl-python  auto-virtualenv  cerbere cinspect  conda epaste	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode ; Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul.	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following:  you set it on in the past.  ateion of that package.  nacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode  Despite still being used by notable Python authors, this package needs a complete overhaul As it stand in early 2021 I recommend to stay away from it  elpy jedi  eval-in-repl-python  auto-virtualenv  cerbere  cinspect  conda  epaste  elpy  elpygen	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul.	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode ; Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in early 2021 I recommend to stay away from it. I elpy  jedi  eval-in-repl-python  auto-virtualenv  cerbere  cinspect  conda  epaste  elpy  elpygen  fabric  indent-tools	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following: you set it on in the past. ateion of that package. hacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in early 2021 I recommend to stay away from it. elpy  jedi  eval-in-repl-python  auto-virtualenv  cerbere  cinspect  conda  epaste  elpy  elpygen  fabric  indent-tools  jump-to-line	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Discreption support with font locking, basic navigation, comment, imenu and roce code files.  Want to get rid of it you must do the following:  you set it on in the past.  ateion of that package.  nacs.d/elpa directory.	
Python code Indentation  Elpy - Emacs Python Development Environment  Python shell prompts not detected @ Github  'python-shell-interpreter' doesn't seem to support readline  Elpy seems partially incompatible with Emacs 25's 'native completion' feature  GNU bug report logs - #28580 [w32] python.el: native completion setup failed  PTY - Pseudo terminal @ wikipedia  pyreadline-ais  company-mode : Modular in-buffer completion framework for Emacs  Python Supporting Emacs Lisp packages  python.el  python-mode !  Despite still being used by notable Python authors, this package needs a complete overhaul. As it stand in early 2021 I recommend to stay away from it. I elpy  jedi  eval-in-repl-python  auto-virtualenv  cerbere  cinspect  conda  epaste  elpy  elpygen  fabric  indent-tools	everything under Windows, and there is another issue, listed in t Windows-related problem description, stating that "native" cor list of python-shell-completion-native-disabled-interpreters in en Windows-related problem description: elpy-issue-887: descrit warning (using the method described above). Windows-related problem description. Same problem.  Description of the PTY/pseudoterminal concept.  Note that by installing pyreadline-ais, the problem remains in em  This file is distributed with Emacs to support Python. It has bas speedbar support. Enough for editing a small set of Python sou This is the original Emacs package that supported Python. If you have installed it via the Emacs package management and Set PEL pel-use-external-python-mode user-option to nil if This user-option is still present but no longer controls active Remove all version of python-mode directories from you ~/-er	he following lines.  Impletion does not work on Windows and that we should add "python" to the nacs.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that we should add "python" to the last emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that we should add "python" to the last emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that we should add "python" to the last emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the last emacs 26 will disable the lines.  Does that it cannot be fixed on Windows and that emacs 26 will disable the last emacs 26 will disab	

Document	Notes		
poetry	Interface to the poetry Python dependency management and packaging tool		
py-import-check	A small Emacs package that finds unused Python imports using importchecker.		
py-smart-operator	A package that inserts spaces around Python operators. Identified as deprecated by its author and now also hosted in Emacs Mirror		
py-test			
pydoc			
pyenv-mode-auto			
pygen			
pylon			
Extending EmacsLisp with Python	The following Emacs Lisp modules extend EmacsLisp to other programming languages: being able to call Python code from Emacs Lisp code for example.		
Pymacs	Pymacs allows calling Python code directly from EmacsLisp. It was first developed by <u>François Pinard</u> who very sadly died in April 2014 Pymacs is now maintained by Dennis Gentry (see <u>dgentry/Pymacs @ GitHub</u> ). It is not available through MELPA		
Python code supporting packages	Install the following Python packages with pip		
ropemacs	An emacs mode for using rope python refactoring library. Uses rope and Pymacs.		
<u>rope</u>	A python refactoring library		
ropemode	A helper for using repo refactoring library in IDEs		
Traad: a Python refactoring server	A python package that implements a Python refactoring server. On Emacs, the <u>emacs-traad</u> client interact with it. The Emacs package installs the Python server.		
traad: an Emacs client to Python refactoring ser	This is: the Emacs client to the Traad server.		