Autosave / Backup

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
File Auto-Saving	By default Emacs autosaves files. The autosaved files normally have a name that starts and ends with '#', unless there's code that changes that behaviour. • Buffers not visiting files can also be autosaved if that is requested explicitly (by turning the auto-save-mode for that buffer). • When a large portion of text is deleted from a buffer, its auto-save-mode is automatically disabled temporarily to help retain that deleted text in the auto-saved copy. It is re-activated when the buffer is saved in a file (with C-x C-s) or when activating auto-save-mode.			
Toggle autosave of the current buffer	M-x auto-save- mode	(auto-save-mode &optional ARG)	Toggle auto-saving in the current buffer (Auto Save mode). • With a prefix argument ARG, enable Auto Save mode if ARG is positive, and disable it otherwise.	
Toggle auto-saving directly to the file (instead of the normal auto-save file)	M-x auto-save- visited-mode	(auto-save-visited-mode &optional ARG)	Toggle automatic saving to file-visiting buffers on or off. With a prefix argument ARG, enable regular saving of all buffers visiting a file if ARG is positive, and disable it otherwise. Unlike 'auto-save-mode', this mode will auto-save buffer contents to the visited files directly and will also run all save-related hooks.	
Auto-save now all buffers that need it.	M-x do-auto-save	(do-auto-save &optional NO-MESSAGE CURRENT-ONLY)	Auto-save all buffers that need it. This is all buffers that have auto-saving enabled and are changed since last auto-saved. Auto-saving writes the buffer into a file so that your editing is not lost if the system crashes. This file is not the file you visited; that changes only when you save.	
Recovering Data from auto- saves	The following commands allow recovering data from auto-saved files.			
Recover content of file from its auto- saved copy.	M-x recover-file	(recover-file FILE)	Visit file FILE, but get contents from its last auto-save file.	
Recover a session after Emacs crash	M-x recover- session	(recover-session)	Recover auto save files from a previous Emacs session. This command first displays a Dired buffer showing you the previous sessions that you could recover from. To choose one, move point to the proper line and then type C-c C-c. Then you'll be asked about a number of files to recover.	
Backup Files	 By default Emacs makes a single backup file for each file edited: a file with the name ending with '~'. It's also possible to use numbered backups with our without automatic deletion of old ones. All of this is controlled by <u>backup user options</u>: version-control, kept-new-versions, kept-odd-versions, deleted-old-versions and dired-kept-versions Emacs has a set of functions that deal with backups but no explicit commands. 			
Compare file with backup				
Compare file with its backup See also: <u>∑ Diff & Merge</u>	<f11> d e f k</f11>	(ediff-backup FILE)	Compare a file with its backup. If there are several numerical backups, use the latest. • If the file is itself a backup, then compare it with its original.	

Autosave/Backup — References

Topic & Link	Description	
Emacs Manual - Auto-save		
Emacs Manual - Backup Files		
How do I reload a file in a buffer? @ StackExchange	Discussion that describes several aspect of reloading a file.	