## **Inserting Text**

		11136	Tung lext	
Description	Keystroke	Function	Note	
Inserting Text	The first sections of	cribed in this table insert specialized of the table show commands that in describe the flexible template sy		
Text Insertions	<f11> <f1> I</f1></f11>	(pel-cfg-insertions &optional OTHER-WINDOW)	Customize PEL text insertion support.  If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window and open insertion related and supported groups: <u>lice</u> , <u>smart-dash</u> , <u>yasnippe</u> t and <u>yasnippet-snippets</u> .	
Time-stamps				
Insert current date	<f11> i d</f11>	(pel-insert-current-date &optional UTC)	Insert current date (only, no time) at point.  • Local by default, UTC if C-u prefix used.	
Insert current date & time	<f11> i D</f11>	(pel-insert-current-date-time & Optional UTC)	Insert current date and time at point.  • Local by default, UTC if C-u prefix used.	
Insert current filename	• <f11> i F • <f6> F</f6></f11>	( <b>pel-insert-filename</b> &optional N)	Insert the file name of the currently edited file at point.  • By default: insert filename of current buffer with complete absolute path.  • With a numeric argument you can select the file name of the current buffer or the buffers in the 4 surrounding windows. 8: up, 2: down, 4: left, 6: right. Any other number identifies the current window.  • When the numeric argument is positive the file with complete absolute path is inserted, if the numeric argument is negative the path is omitted.  ■ When creating keyboard macros that must insert text that includes a file name, you can open 2 windows and use this facility to enter the name of the file that is located in the other window, making the keyboard macro more general.	
Insert time stamp	<f11> i t</f11>	(pel-insert-iso8601- timestamp &optional UTC)	Insert ISO 8601 conforming abbreviated YYYY-MM-DD hh:mm:ss format timestamp.  • Local by default, UTC if C-u prefix is used.	
Insert software license text	• <f11> i L • <f6> L</f6></f11>	(lice NAME)	Insert license and headers at point.  Prompts for license NAME, which is a license template name like "mit", "gpl-3.0", etc The list is available with TAB completion: hit TAB on prompt to get the complete list of templates.  PEL activates it if pel-use-lice user option is t.	
Updating file time stamp				
Update file time stamp	<f11> f t</f11>	(time-stamp)	Force update the time stamp string(s) in the current buffer. The time stamp is updated if the one of the following strings is found in the first 8 lines of the file:	
(See Also: ∑ File mngt)			Time-stamp: <> Time-stamp: "  If you want time stamps updated automatically, write the following inside your init.el file:  (add-hook 'before-save-hook 'time-stamp)	
Toggle time stamp automatic update		(time-stamp-toggle-active &optional ARG)	Toggle 'time-stamp-active', setting whether <f11> f t updates a buffer.  • With ARG, turn time stamping on if and only if arg is positive.</f11>	
Inserting & Automatically Updating Copyrights	Emacs has built-in support for insertion and update of copyright notices inside files.  • Two commands, shown below, are provided to manually insert or update the file's copyright notice.  • The copyright notice can be automatically updated by adding the copyright-update function to the list of before-save-hook variable with the following code:  (add-hook 'before-save-hook 'copyright-update)  • To be automatically updated, the copyright notice must be placed within an area at the beginning of the file specified by the value of the copyright-limit variable, normally defined as the first 2000 characters. This variable is customizable.			
Insert copyright notice at point	<f11> i C</f11>	,	Insert a copyright by \$ORGANIZATION notice at cursor.  If the ORGANIZATION environment variable is not available, Emacs prompts for it.	
(See Also: ∑ File mngt)				
Update file's copyright notice		(copyright-update &optional ARG INTERACTIVEP)	Update copyright notice to indicate the current year.  • With prefix ARG, replace the years in the notice rather than adding the current year after them. If necessary, and 'copyright-current-gpl-version' is set, any copying permissions following the copyright are updated as well.  • If non-nil, INTERACTIVEP tells the function to behave as when it's called interactively.  ▲ Even when used interactively copyright-update does not warn if there is no copyright in the current buffer to update. It does not create a missing notice.  ■ If you want to be prompted automatically to update an existing but out-of-date copyright notice, write the following inside your init.el file:  (add-hook 'before-save-hook 'copyright-update)	
Insert Commented Lines	The following commands help insert commented lines or just underlines the current line of text using the character corresponding to one of the adornment level used for reStructuredText sections. The strings are commented according to the major mode of the current buffer. If the buffer has no identified comment strings, the command prompts for them the first time it is used in that type of buffer.  The following commands are also listed in the $\Sigma$ Comments table.			
Insert commented line (See also: ∑ Comments)	• <f11> i 1 • <f6> 1</f6></f11>	(pel-insert-line &optional LINELEN)	Insert a (commented) line before/at current line.  If point is at the beginning of the line insert it there.  If point is in the middle of a line, move point at beginning of line before inserting it.  The number of dash characters of the line is specified by LINELEN:  If LINELEN is not specified the buffer's fill-column value is used.  If ill-column is customizable and can be used as a file or directory variable.	
Comment-underline current line with level 1 adornment	<f11> _ 1</f11>	(pel-commented-adorn-1)	Insert a commented level-1 reST line adornment at point.	
Comment-underline current line with level 2 adornment	<f11> _ 2</f11>	(pel-commented-adorn-2)	Insert a commented level-2 reST line adornment at point.	
Comment-underline current line with level 3 adornment	<f11> _ 3</f11>	(pel-commented-adorn-3)	Insert a commented level-3 reST line adornment at point.	
Comment-underline current line with level 4 adornment	<f11> _ 4</f11>	(pel-commented-adorn-4)	Insert a commented level-4 reST line adornment at point.	
Comment-underline current line with level 5 adornment	<f11> _ 5</f11>	(pel-commented-adorn-5)	Insert a commented level-5 reST line adornment at point.	
Comment-underline current line with level 6 adornment	<f11> _ 6</f11>	(pel-commented-adorn-6)	Insert a commented level-6 reST line adornment at point.	
Comment-underline current	<f11> _ 7</f11>	(pel-commented-adorn-7)	Insert a commented level-7 reST line adornment at point.	
line with level 7 adornment				
line with level 7 adornment  Comment-underline current line with level 8 adornment	<f11> _ 8</f11>	(pel-commented-adorn-8)	Insert a commented level-8 reST line adornment at point.	

Description	Keystroke	Function	Note	
Comment-underline current line with level 10 adornment	<f11> _ 0</f11>	(pel-commented-adorn-10)	Insert a commented level-10 reST line adornment at point.	
Smart Dash Mode	This uses the <u>smart-dash</u> external package. PEL activates it when <b>pel-use-smart-dash</b> is set to <b>t</b> .  The <b>pel-modes-activating-smart-dash-mode</b> user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the smart-dash-mode user option identifies the major modes where PEL automatically activates the major modes where PEL autom			
	Anyone that has been writing Lisp code for a while knows that using dash as word separator instead of underscore is more natural and faster to type. Unfortunately most programming languages (all non-Lisp?) have restrictions on the characters available in identifiers and underscore is often used. Typing underscore requires hitting the Shift key and it annoys some people that enjoyed writing Lisp code. This is where the smart-dash-mode helps. You can insert underscore in text by typing the dash key without hitting the Shift key! A <b>very</b> useful mode.  More information is available in the <b>author's page</b> .			
Toggle smart dash mode	<f11> M</f11>	(smart-dash-mode &optional ARG)	Toggle the smart-dash-mode on/off.	
(See also: ∑ Numkeypad)			<ul> <li>When smart-dash-mode is active, it redefines the dash key to insert an underscore within C-style identifiers and a dash otherwise. This allows you to type all_lowercase_c_identifiers as comfortably as you would lisp-style-identifiers.</li> <li>While Smart-Dash mode is active, you can type C-q - or use the minus key on the numeric keypad to override it and insert a dash after a C-style identifier character. You might need to do this if you want to type a cramped-looking expression like x-5.</li> <li>If Smart-Dash mode is activated while in a C-like mode (c-mode, c++-mode, and objc-mode by default, customizable with 'smart-dash-c-modes') it will also activate Smart-Dash-C mode, which translates "_&gt;" into "-&gt;" and "" into "" automatically so that struct pointer member access and postfix-decrement aren't made more difficult by Smart-Dash mode's tendency to insert underscores at the tail ends of identifiers whether you want it to or not. Note that this will necessitate that you type literal underscores if you want more than one underscore in a row.</li> <li>With PEL, the keypad '-' key is assigned to the pel-keypad-subtract command which is</li> </ul>	
			controlled by the PEL controlled numlock state. The <f11> # key sequence is assigned to pel-toggle-mac-numlock which makes the keypad '-' key either insert a dash or cut the current line. See \( \subseteq \</f11>	
Text and code skeletons and snippets	Several mechanisms have been developed to allow easy insertion of predefined text in Emacs. Emacs provides the built-in skeleton mechanism, and the tempo skeletons. The popular yasnippet external library is more recent and provides a very flexible and powerful mechanism to create code templates and several people created so-called snippets for various programming and markup languages.			
	PEL supports both. They are used a little bit differently. PEL provides key bindings to the tempo skeletons, not for yasnippets. To use yasnippets must type the snippet abbreviation and then hit the TAB key to expand the text.			
Entering Templated Text with Tempo Skeletons	Emacs built-in support includes the tempo skeletons.  PEL implements extension to the tempo skeleton Emacs built-in package for some major modes.  The currently supported modes are:  • erlang-mode (see   • restructuredText).  PEL creates key bindings to invoke the skeletons in the supported major modes, using the same key prefix sequence for each mode:   • f12>   • rst-mode (see   • restructuredText).  PEL creates key bindings for equivalent concepts (such as file header block) as much as possible. The tempo skeletons provided by PEL can be quite complex and their formats are controlled by user options.  • Emacs user options can be stored inside a file and control the behaviour of Emacs when editing files inside the current directory (see   • File/Directory Variables). This allows you to control the user options affecting the format of the tempo snippets by directories and not affect what you actually type.			
Tempo Templates Prefix	<f12> <f12></f12></f12>		Key prefix sequence to the list of tempo skeleton commands. See the complete list of commands in the table describing the key binding of the supported major mode.	
Entering Templated Test with <u>Yasnippet</u>	PEL also supports the popular <a href="mailto:yasnippet">yasnippet</a> external package which provides another way to insert templated text, and <a href="yasnippets">yasnippet</a> external package which provides a large set of code snippets for a large set of major modes.  Requires <a href="mailto:yasnippet">yasnippet</a> activated when <a href="mailto:pet-snippets">pet</a> is set to			

## Inserting Text — References

Topic & link	Description
GNU Emacs Manual: Time Stamps	
Smart-Dash Mode homepage	A description of this extremely useful mode and why it was created.