## **Emacs support for C**

Linacs support for C				
Description	Keystroke	Function	Note	
Support for the C Programming Language	Emacs supports C natively via the built-in c-mode. This package extends the Emacs CC Mode built-in package which supports the curly-bracket programming languages like C.    Important aspects of C source code syntax controlled by the CC Mode are customizable with PEL user option variables.    PEL customization for C: Simplifies configuration for editing C source code. (To change, use pel-cfg-pkg-c , see below).    Emacs customization group: pel-pkg-for-c			
Customize PEL C Support (See also: ∑ Customize)	• <f11> <f1> SPC c • <f12> <f1></f1></f12></f1></f11>	(pel-cfg-pkg-c &optional OTHER-WINDOW)	Customize PEL C support.  If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window and open the C programming groups as well.  The <f12> <f1> binding is available when point is in a buffer visiting a C file.</f1></f12>	
CC Mode Style Management	Automatic indentation is done by the CC Mode according to its syntactic interpretation of the current line and the indentation mode in use. You can impose an indentation style by customization. But you may use source code written by others and want to continue using the same style. In those cases you can use CC Mode's ability to analyze the style and report it or start using it (installing it) with the following commands. Not all commands are documented here, see the CC Mode manual for more info.			
Guess the style used in the current buffer, do not install it	M-x c-guess-buffer- no-install	(c-guess-buffer-no-install &optional ACCUMULATE)	Guess the style on the whole current buffer; don't install it.  • If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of the code in the buffer	M-x c-guess-buffer	(c-guess-buffer &optional ACCUMULATE)	Guess the style on the whole current buffer, and install it.  The style is given a name based on the file's absolute file name.  If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess style in the region	M-x c-guess	(c-guess &optional ACCUMULATE)	Guess the style in the region up to 'c-guess-region-max', and install it.  The style is given a name based on the file's absolute file name.  If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
Guess the style of a region	M-x c-guess-region	(c-guess-region START END &optional ACCUMULATE)	Guess the style on the region and install it.  The style is given a name based on the file's absolute file name.  If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.	
View Guessed style	M-x c-guess-view	( <b>c-guess-view</b> &optional WITH-NAME)	Emit emacs lisp code which defines the last guessed style, so you can put the code into .emacs if you prefer the guessed code.  TSTYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is given, it is used instead. WITH-NAME is expected as a string but if this function called interactively with prefix argument, the value for WITH-NAME is asked to the user.	
Determine syntactic context of current line.	M-x c-guess-basic- syntax	(c-guess-basic-syntax)	Determine the syntactic context of the current line.	
Show/Modify syntactic context	C-c C-o	(c-set-offset SYMBOL OFFSET &optional IGNORED)	Change the value of a syntactic element symbol in 'c-offsets-alist'.  • SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that syntactic element. The optional argument is not used and exists only for compatibility reasons.	
Show syntactic information for current line	C-c C-s	(c-show-syntactic- information ARG)	Show syntactic information for current line.  • With universal argument, inserts the analysis as a comment on that line.	
CC Mode support	The following commands are CC Mode specific, available for each of the programming languages similar that have a mode derived from CC Mode like C.  The CC Mode controls the indentation and bracket style which controls what happens when electric characters are typed (when the electric mode is activated) and provide a better experience when editing C source code.			
Display current Mode settings	• <f12> M-? • <m-f12> M-? • <f11> SPC c M-?</f11></m-f12></f12>	(pel-cc-mode-info)	Display information about current CC mode derivative for the current c-mode buffer.  • Example of the information displayed (which reflects PEL's defaults):  -UU-:F1 hello.c All (1,0) (C/*la WK)	
Toggle Electric state	• C-c C-1 • <f12> M-e • <m-f12> M-e</m-f12></f12>	( <b>c-toggle-electric-state</b> &optional ARG)	<ul> <li>Toggle the electric indentation feature done with the electric character keys.</li> <li>Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off when negative, and just toggles it when zero or left out.</li> </ul>	
Toggle auto-newline insertion mode	• C-c C-a • <f12> M-RET • <m-f12> M-RET</m-f12></f12>	(c-toggle-auto-newline &optional ARG)	Toggle <u>auto-newline</u> feature.  Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out.  Turning on auto-newline automatically enables <i>electric indentation</i> .  When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.	
Set indentation style	• C-c . • <f12> M-s • <m-f12> M-s</m-f12></f12>	(c-set-style STYLENAME &optional DONT-OVERRIDE)	Set the <u>bracket/indentation style</u> for the current buffer.  Prompts for the name.  Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.	

Description	Keystroke	Function	Note
Toggle syntactic indentation	• <f12> M-i • <m-f12> M-i</m-f12></f12>	(c-toggle-syntactic- indentation &optional ARG)	Toggle syntactic indentation.  Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out.  When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable.  When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.
Electric Keys and Keywords	The following characters have	e special meaning when the elec	trical state is active in a buffer using c-mode.
	#	(c-electric-pound ARG)	Insert a "#".  • If 'c-electric-flag' is set, handle it specially according to the variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is supplied, or if point is inside a literal or a macro, nothing special happens.
	• (	(c-electric-paren ARG)	Insert a parenthesis.  If 'c-syntactic-indentation' and 'c-electric-flag' are both non-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside a literal.  Whitespace between a function name and the parenthesis may get added or removed; see the variable 'c-cleanup-list'.  Also, if 'c-electric-flag' and 'c-auto-newline' are both non-nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.
	• {	(c-electric-brace ARG)	Insert a brace.  • If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings in 'c-hanging-braces-alist'.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.
	:	(c-electric-colon ARG)	Insert a colon.  Insert a colon.  If 'c-electric-flag' is non-nil, the colon is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the colon based on the settings in 'c-hanging-colons-alist'.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, whitespace between two colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
	• ;	(c-electric-semi, ARG)	Insert a comma or semicolon.  If 'c-electric-flag' is non-nil, point isn't inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions:  a) When the auto-newline feature is turned on (indicated by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-semi&comma-criteria' for how newline insertion is determined.  b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil.  c) If auto-newline is turned on, a comma following a brace list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-cleanup-list'.
C Comments	2 more characters have electric behaviour: / and * to help support comments in C. C supports 2 types of comments: Block Comments: /* comment */ Line Comments (since C99): // comment to end of line		
	/	(c-electric-slash ARG)	Insert a slash character.  If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'.  Indent the line as a comment, if:  1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or  2. The slash is part of a "*/" token that closes a block oriented comment.  If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
	*	(c-electric-star ARG)	Insert a star character.  If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment.  If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited.  With this key it becomes easy to type the following two styles of multi-line block comment:  /* Two star  ** continuation  ** prefix for
			** multi-line  ** C comment.  */  /* Single star  * prefix for  * multi-line  * C comment.  */  When typing the '" at the beginning of the line, it indents automatically. If another '" is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.
Toggle Comment Style	• C-c C-k • <f12> M-; • <m-f12> M-;</m-f12></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block and line comments.  • Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out.  In this is part of CC Mode. Use <f12> M-? to display the current state.</f12>

Description	Keystroke	Function	Note
Comment/un-comment	M-;	(comment-region BEG END &optional ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer.  • When no marked region and no comment:  • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line.  • On line with code: insert comment starter after the code for an end-of-line comment  • With marked un-commented region:  • Comment region (each line is commented)  • With marked commented region:  • removes the comment  • Call the comment command you want (Do What I Mean).  • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'.  • You can configure 'comment-style' to change the way regions are commented: see <f12> M-; to toggle the comment style.  Comment or uncomment each line in the region.  • With just C-u prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.  • The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'.  • By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.  • If you try this when no region is marked and the /* * / style comments is active, the comment ends on the next space, which is probably not what you want. The command</f12>
Fill current paragraph (See also: ∑ Filling/ Justification)	• M-q • <f12> F • <m-f12> F</m-f12></f12>	( <b>c-fill-paragraph</b> &optional ARG)	comment-dwim works better.  Like <f11> t f p but handles // and /* */ style comments.  If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details).  If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following:  char description[] = "\ A very long description of something that you want to fill to make nicely formatted output.";  If point is in any other situation, i.e. in normal code, do nothing.  Optional prefix ARG means justify paragraph as well.</f11>
Toggle subword- mode (See also: ∑ Text Modes)	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words.  • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hungry Deletion of Whitespace	The CC mode provides two commands that can perform "hungry whitespace deletion" that can also be used in every mode.  PEL provides the convenient keys with the <f11> prefix keys for those 2 commands, available in all modes.  In modes compatible with the CC Mode (e.g. for C, C++, D, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour of the simple <del> and C-d, to perform hungry deletions. That's not currently supported in other modes.  When the Hungry Delete Mode is on, the mode-line displays a 'h' to the right of the '/l' indication of electric mode.  The Hungry Mode also activates the key prefixes below that start with C-c. They are listed but remember they are only available once the Hungry state mode is activated (and that can only be done in modes that are CC Mode compatible).  In modes derived from CC Mode you can also activate the hungry state to make standard delete commands delete hungrily, but that does not work for other modes. PEL provides the <f12> M-DEL key for those modes (like C).</f12></del></f11>		
Delete preceding char or all preceding whitespace.  (See also: ∑ Cut & Paste)	• C-c DEL • C-c ⟨∑ • C-c C-⟨∑  • C-c <c-backspace> • C-c C-DEL • <f11> ⟨∑ </f11></c-backspace>	(c-hungry-delete-backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character.  □ In terminal mode, even though C-⟨SI, ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.  □ With PEL, the ⟨f11⟩ ⟨SI binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.
Delete next char or all following whitespace.  (See also: ∑ Cut & Paste)	• C-c C-d • C-c ⊗ • C-c C-⊠ • C-c <c-delete> • <f11> ⊠</f11></c-delete>	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character.  In terminal mode, even though C-\overline{\text{S}} and <c-delete> are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.  With PEL, the <f11> \overline{\text{S}} binding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11></c-delete>
Toggle Hungry Delete mode	• <f12> M-DEL • <m-f12> M-DEL</m-f12></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affect <b><del></del></b> and <b>C−d</b> keys.  • Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out.  • When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop.  ■ This is part of CC Mode. Use <b>&lt;£12&gt;</b> M-? to display the current state.
Indentation	-		Mode logic and provided commands listed below. the end of this list. They are also listed in the ∑ Indentation table.

Description	Keystroke	Function	Note
Indent current line or	<tab></tab>	(c-indent-line-or-region	Indent active region, current line, or block starting on this line.
region (See also: ∑ Indentation)		&optional ARG REGION)	Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/ off with the <f12> M-i key):  • With syntactic-indentation on (the default):  • In Transient Mark mode, when the region is active, reindent the region.  • Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.  • Otherwise reindent just the current line.  • This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.  • With syntactic-indentation off:  • <tab> always indent current line by one level  • C-u - <tab> or M- <tab> always un-indent current line by one level  • Indenting marked region is done without syntax knowledge and at the same level as previous line.  • If you want to indent rigidly you can use:  • (pel-indent-rigidly &amp;optional N) (bound to C-x <tab> and to <f11> <tab><tab><tab><tab><tab><tab><tab><tab></tab></tab></tab></tab></tab></tab></tab></tab></f11></tab></tab></tab></tab></tab></f12>
Indent lines of list after point (See also: ∑ Indentation)	C-M-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it.  • A prefix argument (C-u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.  • A numeric prefix argument specifies a column: indent each line to that column.  • With no prefix argument, the command chooses one of these methods and indents all the lines with it:  1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.  2. If 'indent-region-function' is non-nil, call that function to indent the region.  3. Indent each line via 'indent-according-to-mode'.  When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	Emacs provides the following	command to indent without reg	ards to semantics. More information on indentation is available in the ∑ Indentation table.
Insert spaces or tabs to next defined tabstop column (See also: ∑ Indentation)	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column.  • The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer.
Indent/Unindent rigidly  (See also: ∑ Indentation)	• C-x <tab> • <f11> <tab> <tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	<ul> <li>Indent rigidly the marked region or current line N times.</li> <li>If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes.</li> <li>If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): <ul> <li>N = [-1, 0, 1] : operate on current line</li> <li>N &gt; 1 : operate on the current line and N-1 lines below.</li> <li>N &lt; -1 : operate on the current line and (abs N) -1 lines above.</li> </ul> </li> <li>PEL rebinds this key, but it extends the functionality: pel-indent-rigidly uses indent-rigidly, described below the dashed line. <ul> <li>Indent all lines starting in the region.</li> <li>If called interactively with no prefix argument, activate a transient mode in which the</li> </ul> </li> </ul>
		instead of the standard: (indent-rigidly START END ARG &optional INTERACTIVE)	indentation can be adjusted interactively by typing <left>, <ri>right&gt;,  <li>These commands activate a transient mode where Emacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. The capabilities are controlled by the variable indent-rigidly-map with by default provides: <ul> <li>S-<right> indent-rigidly-right-to-tab-stop</right></li> <li>S-<left> indent-rigidly-left-to-tab-stop</left></li> <li><right> indent-rigidly-right</right></li> <li><le><le>left&gt; indent-rigidly-left</le></le></li> </ul> </li> <li>Typing any other key deactivates the transient mode.</li> <li>Since cua-mode uses C-x, to invoke this command when cua-mode is active, type it really fast or type C-x C-x <tab> (or use the PEL binding <f11> <tab> <tab> <tab> <tab> <tab> <tab> </tab> </tab> </tab> </tab> </tab> </tab> </f11></tab></li></ri></left>
Indent rigidly C-mode style	• <f6> <tab> • <f11> <tab> c</tab></f11></tab></f6>	(pel-insert-c-indent &optional N)	Insert as many spaces as identified by <b>c-basic-offset</b> variable on the current line or all marked lines.  • If a region was marked before the command it remains marked, allow further use of the same or other command to control the region. Use <b>C-g</b> to de-activate the region.
Un-indent rigidly C-mode style	<pre>• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab></pre>	(pel-unindent &optional N)	Un-indent current line or marked lines by N times <b>c-basic-offset</b> spaces.  • Works for point is anywhere on the line.  • If a region was marked before the command it remains marked, allow further use of the same or other command to control the region. Use <b>C-g</b> to de-activate the region.  • Which is the same of the region of the region of the region.
Inserting New Lines	The behaviour of the RET key depends on whether the CC Mode electric mode is active or not. When it is not active it simply inserts a new line. When it is active the point also moves to the proper indentation according to the syntactic context. The following commands can also be used.		
Open Line in Context (See also: ∑ Whitespace)	• <f12> RET • <m-f12> RET</m-f12></f12>	(c-context-open-line)	Insert a line break suitable to the context and leave point before it.  • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details.
Insert an indented line below current line (See also:∑Indentation)	• M- <ret> • <f11> <tab> <ret></ret></tab></f11></ret>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point.  So if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation.
Marking	Emacs provides the following	command to quickly mark the w	whole content of the current function. More mark commands exists, see the ∑ Marking table.

Description	Keystroke	Function	Note
Mark the complete	C-M-h	(c-mark-function)	Mark complete function.
function body		(o man randion)	Put mark at end of the current top-level declaration or macro, point at beginning.
(See also: ∑ Marking)			<ul> <li>If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function.</li> </ul>
			A mark is left where the command started, unless the region is already active (in Transient Mark mode).
			As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a
0.411.	Lico the fellowing account	to ovtract ountactic informati	brace block.
Getting Syntactic Information	Use the following commands	to extract syntactic information	nom the source code.
Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it.  • With a prefix arg, push the name onto the kill ring too.
Highlighting blocks	show-paren-mode, which	highlights the parens that matche	eful modes to highlight blocks of (), {}, and []. es the one before or after point. e highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9</f12>	( <b>show-paren-mode</b> &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it
(see also: ∑ Highlight)	• <m-f12> M-9 • <f11> b h (</f11></m-f12>	, italy	otherwise.  • Show Paren mode is a global minor mode. When enabled, any matching parenthesis is
			highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.
nested blocks (),{},[]	• <f11> b h R</f11>		Customize the depth and colours with M-x customize-group rainbow-delimiters
(see also: ∑ Highlight)			Requires: rainbow-delimiters.el  PEL activates this when the pel-use-rainbow-delimiters customize variable is set to t.
Navigation in C	Emacs provides commands	to navigate across source of curb	/ bracket programming languages like C.
(See also: ∑ Navigation)	Most commands are speciali	zation of the normal navigation color describe the specialized con	ommands which are described in the table $\Sigma$ Navigation, along with the other commands that mmands only. See the others inside $\Sigma$ Navigation, like the navigation by blocks, very useful in C.
Go to beginning of statement	м-а	(c-beginning-of-statement &optional COUNT LIM	Go to the beginning of the innermost statement.  • With prefix arg, go back N - 1 statements.
		SENTENCE-FLAG)	<ul> <li>If already at the beginning of a statement then go to the beginning of the closest preceding one, moving into nested blocks if necessary (use C-M-b to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.</li> </ul>
Go to the end of	м-е	(c-end-of-statement	Go to the end of the innermost statement.
statement		&optional COUNT LIM SENTENCE-FLAG)	<ul> <li>With prefix arg, go forward N - 1 statements.</li> <li>Move forward to the end of the next statement if already at end, and move into nested blocks</li> </ul>
		,	(use C-M-f to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.
Backward to	С-М-а	(c-beginning-of-defun	Move backward to the beginning of a defun.
beginning of current top-level function or		&optional ARG)	Every top level declaration that contains a brace paren block is considered to be a defun.     With a positive argument, move backward that many defuns. A negative argument -N means
struct	a G V chamas	(beginning-of-defun	move forward to the Nth following beginning.  Move backward to the beginning of a defun.
	• C-M- <home> • <f6> p</f6></home>	&optional ARG)	With ARG, do it that many times. Negative ARG means move forward to the ARGth following
	• <f6> <up></up></f6>		beginning of defun.  Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M-
			<home>). However <f6> p handles Shift-marking fine in terminal mode.</f6></home>
			This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions and methods that are more deeply nested.
Forward to end of	С-М-е	( <b>c-end-of-defun</b> &optional	Move forward to the end of a top level declaration.
current top-level function or struct.	·	ARG)	With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to next end of defun.  With argument, do it that many times. Negative argument -N means move back to Nth
	• <16> <right></right>		preceding end of defun.
			Shift marking is available in graphics mode, not in terminal mode (both keys).  This command moves to the end of the next <b>top-level</b> function or class. It skips the nested
			functions and methods.
Forward to start of	• <f6> n</f6>	(pel-beginning-of-next-defun &optional SILENT DONT-	Move forward to the beginning of the next function definition.  • Reeps if does not find beginning of next function unless SII ENT is non-nil
next top level function or struct	• <f6> <down></down></f6>	PUSH_MARK)	<ul> <li>Beeps if does not find beginning of next function unless SILENT is non-nil.</li> <li>If the beginning of next function is found, push the start location to the mark ring unless</li> </ul>
			DONT-PUSH_MARK is non-nil.  • Move back to previous position with M
			Shift marking is available.
			<ul> <li>This command complements what end-of-defun does.</li> <li>It moves forward but not to the end of the function definition (like end-of-defun) but to the</li> </ul>
			beginning of the function definition, which is often what users of other editors expect.  • It handles nested functions or class methods in languages like Python and others.
Backward to end of	<f6> <left></left></f6>	(pel-end-of-previous-defun	Move backwards to the end of the previous function definition.
previous top level function or struct		&optional SILENT DONT- PUSH_MARK)	Beeps if does not find end of previous function unless SILENT is non-nil.     If the end of previous function is found, push the start location to the mark ring unless DONT-
idilotion of struct		I JOH_IVIANN	PUSH_MARK is non-nil.
			<ul> <li>Move back to previous position with M-\[\times\).</li> <li>\(\times\) Shift marking is available.</li> </ul>
			This command complements this set of 4 commands.
			⚠ In some cases it fails to detect the end of the previous block and fails. ♣
C Pre-Processor	By default, Emacs supports navigation through C pre-processor conditional statements, allow expansion of pre-processor macros, hiding pre-processor statements that would not be executed with the Hide-ifdef mode. There are also external packages that provide extra support. All commands provided by Emacs and external packages are listed below. They can be used for editing C and C++ source code.		
Navigate across pre- processor conditionals	The following commands move point across the <b>#if</b> , <b>#else</b> , <b>#elif</b> and <b>#endif</b> C pre-processor conditional statements.		
Move up in the pre-	C-c C-u	(c-up-conditional COUNT)	Move back to the containing preprocessor conditional, leaving mark behind.
processor conditional	u	(- ap considering coord)	A prefix argument acts as a repeat count. With a negative argument, move forward to the
block			end of the containing preprocessor conditional.  • "#elif" is treated like "#else" followed by "#if", so the function stops at them when going
			backward, but not when going forward.
Move to the previous pre-processor conditional block	С-с С-р	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move back across a preprocessor conditional, leaving mark behind.  • A prefix argument acts as a repeat count. With a negative argument, move forward across a preprocessor conditional.
- 2			FF. 200000 001141111111

Keystroke	Function	Note
C-c C-n	(c-forward-conditional	Move forward across a preprocessor conditional, leaving mark behind.
	COUNT &optional TARGET-	A prefix argument acts as a repeat count. With a negative argument, move backward across
	DEPTH WITH-ELSE)	a preprocessor conditional.  • If there aren't enough conditionals after (or before) point, an error is signaled.  • "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed
		when tracking subconditionals.
	(c-macro-expand START END SUBST)	Expand C macros in the region, using the C preprocessor.  • Normally display output in temp buffer, but prefix arg means replace the region with it.
• <m-12> # #</m-12>		Customizations:
		<ul> <li>'c-macro-preprocessor' specifies the preprocessor to use.</li> <li>If the user option 'c-macro-prompt-flag' is non-nil prompt for arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-cppflags'.</li> </ul>
The Hide-ifdef mode can hide	e portion of the C pre-processor I	
This feature hides blocks of the Hide-ifdef environment Note that with PEL, in the feature is the second s	of code that would not be include the <b>hide-ifdef-env</b> association	in the expanded file according to the state of pre-processor symbols that are maintained inside list Emacs variable (use <f1> v to see the content of these variables, see the \( \subseteq \) Help table). Help table is the <f12> prefix keys can also be reached via the <m-f12> and the <f11> SPC c</f11></m-f12></f12></f1>
	ption variables affect how the hid	ing is done (to change, execute: M-x customize-group hide-ifdef):
variable, which limits + source files opened • (SYMBOL) is used	hideif to parse only one C/C++ fit simultaneously in different buffet when the SYMBOL is defined (b	
An association list of set the current 'hide-	pre-defined symbol lists. Use 'hi	de-ifdef-set-define-alist' to save the current 'hide-ifdef-env' and 'hide-ifdef-use-define-alist' to 'hide-ifdef-define-alist'.
Set to non-nil to not s  • 'hide-ifdef-initially'		·
'hide-ifdef-read-only'		
After 'show-ifdefs', re	ead-only status is restored to pre-	
• <f12> M-#</f12>	(hide-ifdef-mode &optional	Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode).
• <m-f12> M-# • <f11> SPC C M-#</f11></m-f12>	ARG)	<ul> <li>With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise.</li> </ul>
		Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
• C-c @ h	(hide-ifdefs &optional	Hide the contents of some #ifdefs.
• <f12> # H</f12>	NOMSG)	<ul> <li>Assume that defined symbols have been added to 'hide-ifdef-env'.</li> <li>The text hidden is the text that would not be included by the C preprocessor if it were given</li> </ul>
• <f11> SPC c # H</f11>		the file with those symbols defined.
		<ul> <li>With prefix command presents it will also hide the #ifdefs themselves.</li> <li>Turn off hiding by calling 'show-ifdefs'.</li> </ul>
• C-c @ s • <f12> # S</f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
• C-c @ C-d • <f12> # h</f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor.  • With optional prefix argument ARG, also hide the #ifdefs themselves.
• C-c @ C-s • <f12> # s</f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
• C-c @ d • <f12> # d</f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'.  This allows #ifdef VAR to be hidden.
• C-c @ u • <f12> # u</f12>	(hide-ifdef-undef START END)	Undefine a VAR so that <b>#ifdef VAR</b> would not be included.
• C-c @ D • <f12> # D</f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable.  The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
• C-c @ U	(hide-ifdef-use-define-alist	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef-
• <f12> # U</f12>	NAME)	env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
• C-c @ C-q • <f12> # r</f12>	(nide-ifdef-toggle-read-only)	Toggle read-only: toggle 'hide-ifdef-read-only'.  Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
• C-c @ C-w • <f12> # w</f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing.  When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).
• C-c @ C • <f12> # C</f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'.  • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
• C-c @ e • <f12> # e</f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region.  If no region active, find the current #ifdefs and evaluate the result.
		Currently it supports only math calculations, strings or argumented macros can not be expanded.
	C-c C-n  C-c C-e  Cf12> # #  CM-12> # #  The Hide-ifdef mode can hide  This feature hides blocks of the Hide-ifdef environment  Note that with PEL, in the prefix keys.  Several customize user op  'hide-ifdef-env'  An association list of variable, which limits + source files opened  (SYMBOL). VALUE  'hide-ifdef-define-alist An association list of set the current 'hide-  'hide-ifdef-initially'  Indicates whether 'hide-ifdef-initially'  Set to non-nil to not so thide-ifdef-initially'  Set to non-nil if you we After 'show-ifdefs', refine we will be after the complex of the	C-c C-n  (c-forward-conditional COUNT &optional TARGET-DEPTH WITH-ELSE)  • C-c C-e • <f12> # # • <m-12> # #  SUBST)  The Hide-ifdef mode can hide portion of the C pre-processor • This feature hides blocks of code that would not be included the Hide-ifdef environment: the hide-ifdef-environment: the hide-ifdef</m-12></f12>

Description	Keystroke	Function	Note
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside C source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.		
Preview UML diagram from plantUML source in current plantUML region of commented source code  (See also: MPlantUML)	<f12> u</f12>	(pel-render-commented- plantum! PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment.  • Use region if identified otherwise use PlantUML block at point.  • Uses prefix (as PREFIX) to choose where to display it:  • 4 (when prefixing the command with C-u) -> new window  • 16 (when prefixing the command with C-u C-u) -> new frame.  • else -> new buffer  • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.  Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.
Preview diagram created from Graphviz DOT markup embedded in comments  (See also: MGraphviz Dot)	<f12> G</f12>	(pel-render-commented- graphviz-dot &optional POS)	Render the Graphviz-Dot markup embedded in current mode comment.  Search at POS if specified, otherwise search around point.  Use region if identified otherwise use Graphviz-Dot block.  The graphviz DOT code must be located within a block delimited by the following special keywords (that are also in comments):  Search at POS and the following special keywords (that are also in comments):  Search at POS and the following special keywords (that are also in comments):  Search at POS and the following special keywords (that are also in comments):  Search at POS if special

## Emacs & C - References

Document	Notes
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
company-mode ; Modular in-buffer completion framework for Emacs	