

Description	Keystroke	Function	Note
Text Justification See also: ⓘ Enriched Text	Text justification is normally used when enriched text support is activated via the enriched-mode. The standard Emacs key- sequences listed below are only available in enriched-mode. The PEL key-sequences are always available.		
Toggle Enriched Text Mode See also: ⓘ Text Modes	<f11> t e e <f11> t m e	(enriched-mode &optional ARG)	Minor mode for editing text/enriched files. These are files with embedded formatting information in the MIME standard text/enriched format.
Set justification - full (both)	M-j b	(set-justification-full B E)	Make paragraphs in the region fully justified. - This makes lines flush on both margins by inserting spaces between words. - If the mark is not active, this applies to the current paragraph.
	<f11> t j f		
Set justification - left	M-j l	(set-justification-left B E)	Make paragraphs in the region left-justified. - This means they are flush at the left margin and ragged on the right. - If the mark is not active, this applies to the current paragraph.
	<f11> t j l		
Set justification - center	- M-j c - M-S	(set-justification-center B E)	Make paragraphs in the region centered. If the mark is not active, this applies to the current paragraph.
	<f11> t j c		
Set justification - right	M-j r	(set-justification-right B E)	Make paragraphs in the region right-justified. - This means they are flush at the right margin and ragged on the left. - If the mark is not active, this applies to the current paragraph.
	<f11> t j r		
Set justification - none (un-justify)	M-j u	(set-justification-none B E)	Disable automatic filling for paragraphs in the region. If the mark is not active, this applies to the current paragraph.
	<f11> t j u		
Centering	The following commands center text horizontally.		
Center paragraph	M-o M-S	(center-paragraph)	Center each nonblank line in the paragraph at or after point.
Center line	M-o M-s	(center-line &optional NLINES)	Center the line point is on, within the width specified by ‘fill-column’. - It adjusts the indentation so that it equals the distance between the end of the text and ‘fill-column’. - With numeric prefix argument NLINES: centres that many lines.  The ⌘-- key is normally bound here in graphics mode. PEL re-assigns it.

Filling and Justification — References

Operation	Keystroke
Text Filling	
GNU Emacs Lisp - Text - Filling	
GNU Emacs Lisp - Text - Auto Filling	
GNU Emacs Lisp - Text - Adaptive Filling	
GNU Emacs Lisp - Text - Margins	
Emacs hard wrap lines	
Emacs wiki - Ruler Mode	
Emacs wiki - refilling mode	
Emacs wiki - Auto Fill Mode	
How to set multiline comments - StackOverflow	
Line Wraps	
Truncate Lines @ EmacsWiki	Describes how to set/disable line wrapping globally. Also explains how to control it for a given mode.
Line Wrap @ EmacsWiki	Describes various modes: AutoFillMode, LongLines, VisualLineMode
longlines-mode @ emacs horror	Discuss difference between longlines-mode and visual-line-mode
ErgoEmacs: Show Cursor Position	Xah Lee's ErgoEmacs web site has a picture of the ruler at the top of this page. I did not see one inside Emacs manuals (yet, let me know if you find one).