

Org-Mode

Description	Keystroke	Function	Note
Org Mode - Help & Customize - Shift-selection - Text markup / electric keys - Other markup (◦ more) - Clean View Narrow/widen - Visibility Cycling Motion - Edit Structure (+heading) ↔ t copy paste clone sort - TODO state & checkbox - Drawers, Notes Properties - HyperLinks - Date & Time +Timestamps - Clocking Work Time - Org Syntax Check - Org Commands - Archiving - References	Emacs Org-Mode is very powerful outline document lightweight markup with a lot of powerful features designed for notes, planning and authoring: Markup: *bold*, <i>/italic/</i>, <u>_underline_</u>, <code>~code~</code>, <code>=verbatim=</code>, +strike-through+ and <code>[[https://orgmode.org][Org links]]</code> Document structure: documents are outlines with headlines that have visibility cycling, support motion, - Has commands for document structure editing - Supports: Sparse Trees, Plain Lists, Drawers and Blocks - Headlines can be assigned properties - Org mode allow creating Agenda with date and time timestamps, time-ranges and deadlines. Time stamps can be active and inactive.  I am currently updating this table to include as much as possible or Org Mode feature descriptions. New version will be available soon.		
Last updated on:	2026-08-26	Also see: Org-Mode Reference Card and Org-Mode Command and Function Index	
Open this PDF file. See also: 📖 Help/Info	<f11> SPC M-o <f1> <f12> <f1>	(pel-help-pdf & optional OPEN-WEB-PAGE)	Open the M Org-Mode local PDF. If the prefix argument (like C-u or M--) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
🔧 Customize PEL Org Mode support	<f11> SPC M-o <f2> <f12> <f2>	(pel-customize-pel & optional OTHER)	Customize PEL Org Mode support: open pel-pkg-for-org-mode group. If OTHER is non-nil (use C-u), display in another window.
🔧 Customize Emacs Org Mode support	<f11> SPC M-o <f3>	(pel-customize-library & optional OTHER)	Customize Org Mode external packages support: If OTHER is non-nil (use C-u), display in another window.
Shift Select Control See: shift selection See: org-support-shift-select docstring (use <f1> > o)	In most major modes, Emacs supports text selection by holding the Shift key down while moving point; this feature is called shift selection. By default, shift selection is not available in org-mode; in org-mode the shift cursor keys are used to control the bullet state, titles and timestamps.  However, by you can customize org-support-shift-select to re-activate shift-selection completely (set it to always) or partially (set it to t) which activates shift-selection when the cursor is not in special context, and bullet cycling will only occur when point is exactly over the bullet.		
Text Emphasis Electric Keys org-mode emphasis Escape character Org Mode Markup Syntax	 With the pel-org-use-electric-markup user-option set, PEL provides a specialized electric-pair-mode to type the characters below in pair.  The pel-electric-pair-lighter user-option identifies the line-mode lighter displayed when the electric-pair-mode is active. Defaults to “$\varepsilon(1)$” in 🔧 Mode Line For the following keys: If an area is currently marked, the character typed is inserted before and after the marked area. If no area is marked, two characters are inserted and the point is left in between. Type following key to emphasize when electric keys are active. Disable them via <f11> M-e, then use the C-c C-x C-f key sequence to enter emphasis.		
Bold	*	To insert a single * character inside the text there are several methods: - Insert a zero-width space right after the asterisk: Type: C-x 8 RET zero width space RET - Insert *~ - Insert ==* or ~*- markup	
If you want to use it at the beginning of a line without creating a header, insert a comma right before it; org-mode will strip the comma upon export: insert: , *			
Italic	/	To insert a single / character inside the text there are several methods: - Insert a zero-width space right after the slash: Type: C-x 8 RET zero width space RET - Insert /= or ~/~ markup - Add surrounding spaces: if you put a space before and after the slash it will not trigger italics: example: this / that	
Underline	_	To insert a single _ character inside the text there are several methods: - Insert a zero-width space right after the underscore: Type: C-x 8 RET zero width space RET - Insert =_ or ~_~ markup - Use a backslash before the underscore if your only concern about is how the document exported to HTML or PDF looks: _	
You may also want to disable subscript for the current file by adding the following configuration line at the top of the Org file. That stops org-mode from turning underscores into subscripts unless you explicitly wrap text in curly braces like this: <code>_{subscript}</code> Add the following entry at the very top of the file and then refresh the buffer by typing C-c C-c on that line after typing it: #+OPTIONS: ^: { }			
Code	~	To insert a single ~ character inside the text there are several methods: - Insert a zero-width space right after the tilde: Type: C-x 8 RET zero width space RET - Insert ==~ markup - Add surrounding spaces: put a space before and after the tilde: example: value ~ 10 - Use a backslash before the tilde if your only concern about is how the document exported to HTML or PDF looks: \~	
Verbatim (literal)	=	To insert a single = character inside the text there are several methods: - Insert a zero-width space right after the equal: Type: C-x 8 RET zero width space RET - Insert ~== markup - Add surrounding spaces: put a space before and after the equal: example: value = 10	
To use it at the beginning of a line without org-mode interpreting it, insert a comma right before it; org-mode strips the comma upon export: insert: , =			
Strike-trough	+	To insert a single + character inside the text there are several methods: - Insert a zero-width space right after the plus: Type: C-x 8 RET zero width space RET - Insert =+= or -+- markup - Add surrounding spaces: if you put a space before and after the slash it will not trigger italics: example: this + that - Use a backslash before the plus if your only concern about is how the document exported to HTML or PDF looks: \+	
Insert, change or remove emphasis	C-c C-x C-f	(org-emphasize & optional CHAR)	Insert or change an emphasis, specifying the emphasis character or SPACE to remove emphasis. - If there is an active region, change that region to a new emphasis. - If there is no region, just insert the marker characters and position the cursor between them.
Toggle electric-pair-mode in current buffer 	<f11> M-e	(electric-pair-local-mode & optional ARG)	Toggle automatic parens pairing (Electric Pair mode) and org-mode special pair electric keys. With a prefix argument ARG, enable Electric Pair mode if ARG is positive, and disable it otherwise.
Lighter := $\varepsilon(1)$	Only affects the current buffer. Electric Pair mode is a global minor mode. When enabled, typing an open parenthesis automatically inserts the corresponding closing parenthesis, and vice versa. (Likewise for brackets, etc.). If the region is active, the parentheses (brackets, etc.) are inserted around the region instead.		
Other markup	The following sub-sections describe Org mode extensive markup capabilities. Hyperlink syntax is described in the HyperLinks section.		
Subscripts, Superscripts	‘^’ and ‘_’ are used to indicate super- and subscripts as in: ^superscript _subscript or with surrounding braces: ^{superscript} _{subscript}		
Toggle pretty display	C-c C-x \	(org-toggle-pretty-entities)	Toggle the composition display of entities as UTF8 characters, in a WYSIWYM way.  Works best with GUI based Emacs; terminal mode limits the capabilities and may hide markup.
Paragraphs & line breaks	Paragraphs are separated by empty line(s). Force line break with trailing <code>\\</code>		
Horizontal Rules.	A line consisting of only dashes, and at least 5 of them, is exported as a horizontal line.		
Captions	Assign a caption to a specific part of a document by inserting a ‘CAPTION’ keyword immediately before it: <pre>#+CAPTION: This is the caption for the next table (or link) ----- </pre> or use a short caption on one line: <pre>#+CAPTION[Short caption]: Longer caption.</pre>		

Description	Keystroke	Function	Note
Footnotes	Footnotes use the <code>[fn:⊕]</code> where ⊕ is either a number or a string. There must be 2 or more of the same set. - Text showing in footnote: follows the <code>[fn:⊕]</code> that starts at the beginning of a line. There must only be one for each ⊕. - Other(s) <code>[fn:⊕]</code> are inserted in the text and act as references to the footnote. Each of these footnotes is an org hyperlink. Footnotes are normally inserted inside a Footnotes heading. Control renumbering/sorting after each insertion/deletion with org-footnote-auto-adjust user-option.		
Create footnote, or move from reference to definition (or definition to reference)	C-c C-x f	(org-footnote-action &optional SPECIAL)	- If there is no footnote at point: create one. - If point is at a footnote reference: move to footnote definition. C-c C-o also jumps to it. - If point at a footnote definition: jump to the references if they exist, offer to create them otherwise. - With prefix, or when no footnote can be created, offer additional commands in a menu: Footnotes: [s]ort [r]enumber fn:N [S]=r+s [n]ormalize [d]elete s Sort the footnote definitions by reference sequence. r Renumber the simple ‘fn:N’ footnotes. S Short for first r, then s action. n Rename all footnotes into a ‘fn:1’ ... ‘fn:n’ sequence. d Delete the footnote at point, including definition and references.
Move to footnote definition or reference	C-c C-c	(org-ctrl-c-ctrl-c &optional ARG)	If point is on a footnote reference, jump to the definition. If it is at the definition, jump back to the reference. When called at a footnote location with a prefix argument, offer the same menu as C-c C-x f.
	C-c C-o mouse-1/2	(org-open-at-point &optional ARG)	Footnote labels are also links to the corresponding definition or reference, and you can use the usual commands to follow these links.
Special Symbols	org-mode provides LaTeX-like syntax to insert special symbols. Like <code>\alpha</code> for α or <code>\to</code> for →.		
Show all available special symbols	<f12> h e	(org-entities-help)	Create a Help buffer with all available entities (special symbols), with their corresponding Org entity markup, LaTeX code and HTML code inside a “Org Entity Help” buffer (which is an org-mode buffer).
Toggle pretty display of special symbol	C-c C-x \	(org-toggle-pretty-entities)	Toggle the composition display of entities as UTF8 characters, in a WYSIWYM way. Works in GUI and terminal based Emacs (based on terminal capabilities).
Embedded LaTeX	LaTeX fragments can be present in org mode files: org-mode recognizes LaTeX syntax (also see LaTeX syntax tutorial). LaTeX processing is configured by org-export-with-latex user-option. You can also set it in the file with the following lines: <pre>#+OPTIONS: tex:t Do the right thing automatically (MathJax) #+OPTIONS: tex:nil Do not process LaTeX fragments at all #+OPTIONS: tex:verbatim Verbatim export, for jsMath or so</pre> Previewing LaTeX fragments : use the command below or turn previewing directly in the file with: <pre>#+STARTUP: latexpreview To turn previewing on #+STARTUP: nolatexpreview To turn previewing off</pre>		
Toggle preview of LaTeX fragment at point	C-c C-x C-1	(org-latex-preview &optional ARG)	Toggle preview of the LaTeX fragment at point. - If the cursor is on a LaTeX fragment, create the image and overlay it over the source code, if there is none. Remove it otherwise. - If there is no fragment at point, display images for all fragments in the current section. With an active region, display images for all fragments in the region. - With ‘C-u’ prefix: clear images for all fragments in the current section. - With ‘C-u C-u’ prefix: display image for all fragments in the buffer. - With ‘C-u C-u C-u’ prefix: clear image for all fragments in the buffer.
Toggle pretty entities	C-c C-x \	(org-toggle-pretty-entities)	Toggle the composition display of entities as UTF8 characters: subscript, superscript, etc... Works in GUI and terminal based Emacs (based on terminal capabilities).
Using CDLaTeX 	Enter math with  CDLaTeX minor mode .  not yet supported by PEL).		
Literal Examples	To write long technical text without escaping any Org-mode markup characters listed above, wrap your text in an Example Block: Org-mode treats everything inside this block as literal, unformatted text. For example: <pre>#+begin_example Here is a long technical note where no markup applies: /* This is not a header or bold text. A comma MUST precede the * or a #+ at the beginning of a line. / This text will not be italicized. x = y + z_subscript; ~ This is just plain text. #+end_example</pre> For simple examples, you can use lines with a colon followed by spece(s), as in: <pre>Here is an example : Some example from a text file.</pre>		
Source code blocks See also: Org-mode code blocks Structure Templates See (ref:name) syntax and the -r switch to remove the labels from source.	To include source code for a specific programming language use the #+BEGIN_SRC followed by the language major mode name, as in: <pre>#+BEGIN_SRC emacs-lisp (defun org-xor (a b) "Exclusive or." (if a (not b) b)) #+END_SRC</pre> In the example at right: specify line number with -n and use +n to continue line numbers with an optional offset. <pre>#+BEGIN_SRC emacs-lisp -n 20 ;; This exports with line number 20. (message "This is line 21") #+END_SRC #+BEGIN_SRC emacs-lisp +n 10 ;; This is listed as line 31. (message "This is line 32") #+END_SRC</pre>		
Edit source code Terminate/save changes with C-c ' again	C-c '	(org-edit-special &optional ARG) → (org-edit-src-code &optional CODE EDIT-BUFFER-NAME)	Edit the source code at point in its native mode in a temporary buffer. The temporary buffer activates the org-src-mode minor mode which binds the C-c ' key to save the changes, close the temporary buffer and go back to the original org-mode buffer.
Insert Structure Templates	C-c C-, <f12> s	(org-insert-structure-template TYPE)	Insert a block structure of the type #+begin_foo/#+end_foo . With an active region, wrap the region in the block. Otherwise, insert an empty block.
	Select a block from ‘ org-structure-template-alist ’ (default shown below) or type either RET, TAB or SPC to write the block type explicitly. <pre> a ‘#+BEGIN_EXPORT ascii’ ... ‘#+END_EXPORT’ c ‘#+BEGIN_CENTER’ ... ‘#+END_CENTER’ C ‘#+BEGIN_COMMENT’ ... ‘#+END_COMMENT’ e ‘#+BEGIN_EXAMPLE’ ... ‘#+END_EXAMPLE’ E ‘#+BEGIN_EXPORT’ ... ‘#+END_EXPORT’ h ‘#+BEGIN_EXPORT html’ ... ‘#+END_EXPORT’ l ‘#+BEGIN_EXPORT latex’ ... ‘#+END_EXPORT’ q ‘#+BEGIN_QUOTE’ ... ‘#+END_QUOTE’ s ‘#+BEGIN_SRC’ ... ‘#+END_SRC’ v ‘#+BEGIN_VERSE’ ... ‘#+END_VERSE’</pre>		
Images and link previews.	 Note that Org-mode 9.7 (available in Emacs 31) which differs . PEL support will be updated soon 		
Toggle display of images	C-c C-x C-v <f12> v v	(org-toggle-inline-images &optional INCLUDE-LINKED BEG END)	Toggle the display of inline images. INCLUDE-LINKED is passed to ‘org-display-inline-images’.
Refresh inline images	C-c C-x C-M-v <f12> v V	(org-redisplay-inline-images)	Assure display of inline images and refresh them.
Preview image (for Org >= 9.8)	<f12> v r	(org-link-preview-region)	Create inline previews for external links in the active region, or the buffer. With a prefix argument, also preview links with a text description part.
Clear external link previews (for Org >= 9.8)	<f12> v c	(org-link-preview-clear)	Clear external link previews in the active region, or the buffer.

Description	Keystroke	Function	Note
Cleaner Outline View	Org documents are an outline tree. Org headlines (also called headings) start on the left margin with one or more stars followed by space.		
Toggle <u>clean view mode</u> . 	<f12> <tab>	(org-indent-mode &optional ARG)	Toggle the cleaner outline view, which hides headings leading stars (but still shows in Terminal frames (depending on colors)), automatically indent text to align with their headline and activate proper automatic line wrap. You can activate this minor mode for individual files with: #+STARTUP: indent
Narrowing tree/blocks	Limit area of buffer showed in the current window and restrict operations to that area. See ☞ Narrowing for more info.		
Narrow to subtree	C-x n s	(org-narrow-to-subtree &optional ELEMENT)	Narrow buffer to current subtree. With optional argument ELEMENT narrow to subtree around ELEMENT : for elisp code only.
Narrow to block	C-x n b	(org-narrow-to-block)	Narrow buffer to current block.
Widen	C-x n w	(widen)	Widen buffer to remove narrowing. This allows the buffer's full text to be seen and edited.
Set initial visibility	When opening an org file, all lines are shown by default unless the file has a #+STARTUP: line that identifies the startup folding state. The possible values are: #+STARTUP: overview #+STARTUP: content #+STARTUP: showall #+STARTUP: show2levels #+STARTUP: show3levels #+STARTUP: show4levels #+STARTUP: show5levels #+STARTUP: showeverything		
Visibility Cycling	Org documents are treated as outlines; the heading lines are section levels and can be hidden and shown with the following commands.		
Rotate current subtree between states	<tab>	(org-cycle)	Expand/compress the sub-tree title lines: folded → see children → see all subtree. <i>Works when:</i> - the line is empty (except for the star identifying it as a heading) - there are other headings of level 2 or more somewhere else in the document.
Global VisibilityCycling	C-u <tab> S-<tab>	(org-global-cycle)	<i>With point anywhere:</i> Rotate the entire buffer among the following states: 1) Overview, 2) Contents 3) Show all.
Restore property-dependent startup visibility	C-u C-u <tab>	(org-cycle-set-startup-visibility)	<i>With point anywhere:</i> Restore initial visibility : restores the default property-dependent and startup-configured folding view. Switch back to the startup visibility of the buffer, i.e., whatever is requested by startup options and "VISIBILITY" properties in individual entries.
Show the whole file, including drawings	C-u C-u C-u <tab>	(org-fold-show-all)	<i>With point anywhere:</i> show all lines, including drawers.
Cycle subtree always	C-<tab>	(org-cycle-force-archived)	Cycle subtree even if it is archived.
Reveal context around point	C-c C-r	(org-reveal &optional SIBLINGS)	Reveal context around point, showing the current entry, the following heading, and the hierarchy above. Useful for working near a location that has been exposed by a sparse tree command (see Sparse Trees) or an agenda command (see Commands in the Agenda Buffer). - With 'C-u' prefix: show, on each level, all sibling headings. - With 'C-u C-u' prefix: also show the entire subtree of the parent.
Show all sub-headings, hide their bodies	C-c C-k	(org-kill-note-or-show-branches)	Expose all the headings of the subtree (show all current subheadings), but not their bodies. Also: abort storing current note.
Show all <i>direct</i> sub-headings	C-c <tab>	(outline-show-children &optional LEVEL)	Expose all direct children of the subtree. If lines (or bodies) are already shown, nothing changes. Does not show the body (but does not hide them when already showing). By default show only 1 level of sub-headings, with numeric argument identify the number of levels to show: For example to show 3 sub-levels: C-u 3 C-c <tab>
Show current subtree in indirect buffer	C-c C-x b	(org-tree-to-indirect-buffer &optional ARG)	Show the current subtree in an indirect buffer: take current subtree and open in an indirect buffer, not affecting current buffer's visibility. - Any edit in the indirect buffer goes inside the same file. - Very useful to see the layout and be able to expand information inside a subtree. - With numeric argument N: go up to level N and then take that tree. If N is negative, then go up that many levels. - With 'C-u' prefix: do not remove the previously used indirect buffer.
Move through headings	See: Motion commands. ARG is 1 by default. Supply a different value via a numeric argument ; with negative value to move in opposite direction.		
Next heading	C-c C-n	(org-next-visible-heading ARG)	Move to the next visible heading. With numerical argument move that many.
Previous heading	C-c C-p	(org-previous-visible-heading ARG)	Move to the previous visible heading. With numerical argument move that many.
Next heading same level	C-c C-f	(org-forward-heading-same-level ARG &optional INVISIBLE-OK)	Move forward to the ARG'th subheading at same level as this one. Stop at the first and last subheadings of a superior heading.
Previous heading same level	C-c C-b	(org-backward-heading-same-level ARG &optional INVISIBLE-OK)	Move backward to the ARG'th subheading at same level as this one. Stop at the first and last subheadings of a superior heading.
Backward to higher level heading	C-c C-u	(outline-up-heading ARG &optional INVISIBLE-OK)	Move to the visible heading line of which the present line is a subheading. With argument, move up ARG levels.
Search/Jump to text	C-c C-j	(org-goto &optional ALTERNATIVE-INTERFACE)	Look-up and jump to a different place without changing the current outline visibility. - With 'C-u' prefix: use alternative 'org-goto-interface': 'outline' ⇔ 'outline-path-completion'. - When you want look-up or go to a different location in a document, the fastest way is often to fold the entire buffer and then dive into the tree. This method has the disadvantage, that the previous location will be folded, which may not be what you want. - This command works around this by showing a copy of the current buffer in an indirect buffer, in overview mode. You can dive into the tree in that copy, use 'org-occur' and incremental search to find a location. When pressing RET or 'Q', the command returns to the original buffer in which the visibility is still unchanged. After RET it will also jump to the location selected in the indirect buffer and expose the headline hierarchy above.
Edit Structure of document	Modify the <u>outline</u> structure of the Org document by issuing the following commands on heading lines .  With PEL, M-<up> and M-<down> are normally bound to <u>PEL scroll commands</u> , but not in org-mode because they are bound to org-mode commands. To scroll up/down in org-mode: use the number keypad key 3 and 9 of the <u>number keypad not num-locked</u>, or when using hydra external package use the <f7> prefix with <up> and <down> keys. For more info see: ☞ Scrolling.		
• Insert headings	Insert <u>outline</u> headings (also called headlines) in the Org document with the following commands. The org-blank-before-new-entry user-option controls whether a separator empty line is inserted before the new heading.		
Create heading at same level	Esc RET M-RET	(org-meta-return &optional ARG)	Insert new heading of same level as current. If cursor is at a plain list item, create new item. If used in the middle of a line, split the line and the rest become a new headline.
Create heading at same level - don't split line	C-RET	(org-insert-heading-respect-content &optional INVISIBLE-OK)	Insert the line as if cursor is at end of line (never split current line). This insert heading as if 'org-insert-heading-respect-content' is currently set to t.
• Insert TODO heading	TODO notes are Org headings that have the TODO state. They can have: priorities , time stamps (scheduling & deadlines) and time tracking.		
Insert a new heading at same level and TODO state	M-S-RET C-c C-x M	(org-insert-todo-heading ARG &optional FORCE-HEADING)	Insert a new heading with the same level and TODO state as current heading. - If the heading has no TODO state, or if the state is DONE, use the first state (TODO by default). Also with one prefix arg (C-u), force first state. - With two prefix args (C-u C-u), force inserting at the end of the parent subtree.
Insert a new heading at same level and TODO state	C-S-RET	(org-insert-todo-heading-respect-content &optional ARG)	When point on TODO heading: insert a new TODO heading, never split current line. This insert heading as if 'org-insert-heading-respect-content' is currently set to t.
Convert Line <-> Heading	C-c *	(org-ctrl-c-star)	- When point on normal line or plain list item: change line to a subheading at its location. - When point is on a heading: turn into anormal line by removing the stars. - If there is an active region, turn all lines in the region into headlines. If the first line in the region was an item, turn only the item lines into headlines. Finally, if the first line is a headline, remove the stars from all headlines in the region.

Description	Keystroke	Function	Note
Demote current heading (make it a sub-heading)	M-<right>	(org-metaright &optional ARG)	Demote heading, list item at point or move table column right. In front of a drawer or a block keyword, indent it correctly.
Promote current heading	M-<left>	(org-metaleft &optional ARG)	Promote heading, list item at point or move table column left.
Demote current sub-tree	M-S-<right>	(org-shiftmetaright)	Demote subtree or insert table column.
Promote current sub-tree	M-S-<left>	(org-shiftmetaleft)	Promote subtree or delete table column.
Move subtree/table row up (only inside its section)	M-<up>	(org-metaup &optional ARG)	When on heading or plain list item line : move subtree up or move table row up.
Move subtree/table row down (only inside its section)	M-<down>	(org-metadown &optional ARG)	When on heading or plain list item line : move subtree down or move table row down.
Move current line up (only inside its section)	M-S-<up>	(org-shiftmetaup &optional ARG)	When on heading or content line : drag the line at point up, only that line.
Move current line down (only inside its section)	M-S-<down>	(org-shiftmetadown &optional ARG)	When on heading or content line : drag the line at point down only that line.
Cut and paste			
Copy visible text	C-c C-x v	(org-copy-visible BEG END)	Copy the <i>visible</i> text in the region into the kill ring.
Mark subtree	C-c @	(org-mark-subtree &optional UP)	Mark the current subtree. Puts point at the start of the current subtree, and mark at the end. With a numeric prefix, move up into the hierarchy of headlines by UP levels before marking the subtree.
Cut current subtree or region in table	C-c C-x C-w	(org-cut-special)	Cut region in table or cut current subtree.
Paste past subtree or rectangular region into table	C-c C-x C-y	(org-paste-special ARG)	Paste rectangular region into table, or past subtree relative to level.
Yank (paste)	C-y	(pel-overwrite-yank &optional ARG)	In org-mode the PEL command invokes (org-yank ARG) to yank like in org-mode: If the kill is a subtree, treat it specially.
	Pastes subtrees folded using the same command as C-c C-x C-y. With the default settings, no level adjustment takes place, but the yanked tree is folded unless doing so would swallow text previously visible. Any prefix argument forces a normal yank: a good way to force a normal yank is C-u C-y. If you use yank-pop after a yank, it yanks previous kill items plainly, without adjustment and folding. Look at the current kill and check if is a single subtree, or a series of subtrees. If it passes the test, and if the cursor is at the beginning of a line or after the stars of a currently empty headline, then the yank is handled specially according to the value of the following user-option variables: org-yank-folded-subtrees: By default, this variable is non-nil, which results in subtree(s) being folded after insertion, except if doing so would swallow text after the yanked text. org-yank-adjusted-subtrees: When non-nil (the default value is nil), the subtree will be promoted or demoted in order to fit into the local outline tree structure, which means that the level will be adjusted so that it becomes the smaller one of the two "visible" surrounding headings.		
Clone sub-tree	C-c C-x c	(org-clone-subtree-with-time-shift N &optional SHIFT)	Clone a subtree by making a number of sibling copies of it. Prompts for the number of copies to make; you can also specify whether any timestamps in the entry should be shifted. This can be useful, for example, to create a number of tasks related to a series of lectures to prepare. For more details, see the docstring of the command org-clone-subtree-with-time-shift
Refile and Copy	C-c C-w	(org-refile &optional ARG DEFAULT-BUFFER RFLOC MSG)	Refile entry or region to a different location. See Refile and Copy .
Sort entries	C-c ^	(org-sort &optional WITH-CASE)	Sort same-level entries. With an active region, all entries in the region are sorted. Otherwise, the children of the current headline are sorted. With a C-u prefix, sorting is case-sensitive.
	Prompts for the sorting method, which can be alphabetically, numerically, by time—first timestamp with active preferred, creation time, scheduled time, deadline time—by priority, by TODO keyword—in the sequence the keywords have been defined in the setup—or by the value of a property. Reverse sorting is possible as well. You can also supply your own function to extract the sorting key.		
Change TODO items state and priority basic TODO functionality extended use of TODO Progress Logging	Change Org state of headline item with the following commands. The state of TODO items is controlled by the org-todo-keywords user-option. The default is ((sequence "TODO" "DONE")). More complex list are possible, see the variable docstring. When pel-use-org user option is set, PEL sets it to ((sequence "TODO" "IN-PROGRESS" "DONE")) which provides an extra state. 🐼 Several commands are mapped to S-<cursor>. These are only available on headline. In other lines the using the Shift key with cursor is used for shift selection when org-support-shift-select user option is set to t to always.		
Rotate heading state of current item	S-<right>	(org-shiftright &optional ARG)	With point on a headline , cycle switch to the next TODO keyword. empty → TODO → IN PROGRESS → DONE.
	S-<left>	(org-shiftleft &optional ARG)	With point on a headline , switch to the next TODO keyword. empty ← TODO ← IN PROGRESS ← DONE.
	C-c C-t		Changes state in order (as in org-todo-keywords) : unmarked, TODO, IN PROGRESS, DONE.
Update state, log progress	C-u C-c C-t	(org-todo)	Prompt for note, record the time of the TODO state change. The note is inserted as a list item below the headline, but can also be placed into a drawer, see Tracking TODO state changes .
Set task priority	C-c ,	(org-priority &optional ACTION SHOW)	Change the priority of an item. Prompts for priority level (A to C). Hit space to remove. Wth a C-u prefix, show the priority in the minibuffer instead of changing it.
Increase task priority	S-<up>	(org-priority-up)	Increase the priority of the current item.
Decrease task priority	S-<down>	(org-priority-down)	Decrease the priority of the current item.
Todo Checkboxes	- TODO items can have checkboxes, written like this: [☐], with a space between the brackets. There can be a top-level count: - written like this: [☐ /], it will show the number of items done over the total (like [24/46], or - written like this: [%], which shows the percentage of items done.		
Toggle checkbox status stop clock(s) in DONE item	C-c C-c	(org-ctrl-c-ctrl-c &optional ARG)	Toggle checkbox status. With C-u prefix: toggle checkbox presence at point: add/remove checkbox. With C-u C-u prefix, set it to '[-]', which is considered to be an intermediate state.
Toggle checkbox status	C-c C-x C-b	(org-toggle-checkbox &optional TOGGLE-PRESENCE)	Toggle the checkbox in the current line. With prefix argument TOGGLE-PRESENCE, add or remove checkboxes. With a double prefix argument, set the checkbox to "[-]".
	When there is an active region , toggle status or presence of the first checkbox there, and make every item inside have the same status or presence, respectively. If point on a headline, apply to all checkbox items in the text below heading, taking as reference the 1st item in subtree, ignoring planning line & any drawer after.		
Insert a new, empty, checkbox on the next line	M-S-RET	(org-insert-todo-heading ARG &optional FORCE-HEADING)	Insert a new heading with the same level and TODO state as current heading (inserts the checkbox on the current line). - If the heading has no TODO state, or if the state is DONE, use the first state (TODO by default). Also with one prefix arg, force first state. With two prefix args, force inserting at the end of the parent subtree. - When called at a plain list item, insert a new item with an unchecked check box.
Toggle the ‘ORDERED’ property	C-c C-x o	(org-toggle-ordered-property)	Toggle the ‘ORDERED’ property of the entry, to toggle if checkboxes must be checked off in sequence. A property is used for this behavior because this should be local to the current entry, not inherited like a tag. However, if you would like to track the value of this property with a tag for better visibility, customize org-track-ordered-property-with-tag.
Update the statistics cookie	C-c #	(org-update-statistics-cookies ALL)	With point on line with statistic cookie : update statistics cookie, either from TODO or from checkboxes. When called with a C-u prefix, update all statistics cookies in the buffer.

Description	Keystroke	Function	Note
Drawers and Notes	Org mode has drawers to keep information associated with an entry which is not normally shown. They can contain anything but a headline and another drawer.		
Insert drawer at point Ideally issue this at end of line.	C–c C–x d	(org-insert-drawer &optional ARG DRAWER)	Insert a drawer at point. Prompt for drawer name. Point is left between drawer’s boundaries. If a region is active, insert the drawer around that region instead. When optional argument ARG is non-nil, insert a property drawer.
Add note	C–c C–z	(org-add-note)	Add a note to the current entry. This is done in the same way as adding a state change note.
Properties	Org properties are key-value pairs associated with a heading and inserted inside a drawer . See Property Syntax . To insert a property: Type : at the beginning of a line or type C–c C–x p		
Select property key	M–TAB	(pcomplete-completions-at-point)	After an initial colon in a line , complete property keys. All keys used in the current file are offered as possible completions. - Provide standard completion using pcomplete’s completion tables. - Same as ‘pcomplete’ but using the standard completion UI.
Insert/set a property	:		When typed at the beginning of a line: insert a property.
	C–c C–x p	(org-set-property PROPERTY VALUE)	Prompt for a property name, offering completion on existing and default properties. And then prompt for a value, offering completion either on allowed values (via an inherited xxx_ALL property) or on existing values in other instances of this property in the current file. Insert markup for that property key-value pair.
Add/Set a property	C–c C–c s	(org-set-property PROPERTY VALUE)	When point is over a property: add/set PROPERTY to VALUE in the current entry. Prompt for property name (with completion) and value (with completion) on this property in current file.
Delete property from current entry	C–c C–c d	(org-delete-property PROPERTY)	When point is over a property: delete PROPERTY of the current entry. Prompts for the property.
Delete property globally	C–c C–c D	(org-delete-property-globally PROPERTY)	When point is over a property: remove PROPERTY globally, from all entries. Prompts for the property. This function ignores narrowing, if any.
Compute property at point	C–c C–c c	(org-compute-property-at-point)	When point is over a property: compute the property at point. - This looks for an enclosing column format, extracts the operator and then applies it to the property in the column format’s scope. - For example: given a tree of heading items with an ‘:Effort: property that identifies number of hours, issuing the command in the parent level heading would compute the sum of all ‘:Effort: values identified in the :effort: properties of child heading items and store it in the parent heading ‘:Effort: property value.
Switch to next allowed value	S–<right>	(org-property-next-allowed-value)	When point is over a property key tag: switch to the next allowed value for this property.
Switch to previous allowed value	S–<left>	(org-property-previous-allowed-value)	When point is over a property key tag: switch to the previous allowed value for this property.
Hyperlinks	Org mode supports links in the file to external files, web pages, emails and much more. Link format: [[LINK][DESCRIPTION]] or [[LINK]] It also supports internal links , links to other parts of the current file/buffer such as: [[#my-custom-id]] to entry with CUSTOM_ID property or [[*Some section]] to the headline with the name ‘Some Section’. <<My Target>> to any element that has an element name using the following format: #+NAME: My Target		
Store a link to the current location (define a link target)	C–c l <f12> l	(org-store-link ARG &optional INTERACTIVE?)	Store a link to the current location in ‘ org-stored-links ’ that can later be inserted into an Org buffer with ‘org-insert-link’ (C–c C–l). 🙌 Type these keys at the beginning of a line to get a proper link.
Video: linking files @ 🧑🏻💻	- A ‘C–u’ prefix: negates ‘org-link-context-for-files’ for file links or ‘org-gnus-prefer-web-links’ for links to Usenet articles. - A ‘C–u C–u’ prefix: forces skipping storing functions that are not part of Org core. - A ‘C–u C–u C–u’ prefix: forces storing a link for each line in the active region.		
Insert a hyperlink or Edit the visible LINK part of an already formatted link.	C–c C–l	(org-insert-link &optional COMPLETE-FILE LINK-LOCATION DEFAULT-DESCRIPTION)	Insert a link at point. Supports several types of links; select type with tab-completion, then complete it and hit <RET> . Then enter the description text and hit <RET> . Inside the Org-mode file, insert the link that was created with C–c l or <f12> l . Use the up arrow to retrieve the link, then type the documentation inside the mini buffer and hit return to insert inside the org mode file. With a ‘C–u’ prefix, prompts for a file to link to.
Open/follow the link item Example: open directory in Dired	C–c C–o	(org-open-at-point &optional ARG REFERENCE-BUFFER)	With point over a rendered hyperlink: open a buffer for the target at the location of the target. - Some links will open using external software. For example, if the link is a directory, the OS program will be used. - To force opening the link inside Emacs use the ‘C–u’ prefix. For example, to open a link to a directory with Dired, use: C-u C-c C-o
Go back	C–c &	(org-mark-ring-goto &optional N)	Jump to previous position in mark ring. With prefix arg N, jump back that many stored positions. When called several times in succession, walk through the entire ring. Org mode commands jumping to a different position in current file, or to another Org file, automatically push old position onto the ring.
Move to next hyperlink	C–c C–x C–n	(org-next-link &optional SEARCH-BACKWARD)	Move forward to the next link. If the link is in hidden text, expose it. When SEARCH-BACKWARD is non-nil, move backward.
Move to previous hyperlink	C–c C–x C–p	(org-previous-link)	Move backward to the previous link. If the link is in hidden text, expose it.
Dates and Times	To assist project planning, TODO items can be labeled with a date and/or a time: an org timestamp. Format: <2003–09–16 Tue 12:00–12:30>		
• Creating Timestamps	Time/Date range: 2 timestamps connected by ‘--’. Format: <2004–08–23 Mon 10:00–11:00>--<2004–08–26 Thu 10:00–11:00>		
Add/replace active time stamp • To insert a Time/Date range issue the command twice.	C–c .	(org-timestamp ARG &optional INACTIVE)	Insert/replace an active time stamp. Prompts. By default only the date is included. - With ‘C–u’ prefix: the time stamp contains date & time. - With ‘C–u C–u’ prefix: the time stamp contains date & time. No prompt.
	All parts of a date not specified by the user are filled in from the timestamp at point, if any, or the current date/time otherwise.		
Add/replace inactive time stamp	C–c !	(org-timestamp-inactive &optional ARG)	Insert an inactive time stamp. Prompts. By default only the date is included. An inactive time stamp is enclosed in square brackets instead of angle brackets. It is inactive in the sense that it does not trigger agenda entries. So these are more for recording a certain time/date. - With ‘C–u’ prefix: the time stamp contains date & time. - With ‘C–u C–u’ prefix: the time stamp contains date & time. No prompt. Replace existing timestamp if there was any.
Normalize timestamp	C–c C–c	(org-ctrl-c-ctrl-c &optional ARG)	When point on a timestamp: normalize timestamp, insert/fix day name if missing or wrong
Insert date timestamp from calendar current position	C–c <	(org-date-from-calendar)	Insert time stamp corresponding to cursor date in “Calendar” buffer. If there is already a time stamp at the cursor position, update it.
Change timestamp date	S–<right>	(org-shiftright &optional ARG)	With point on timestamp: increment date. Use numeric arg to increment by that number.
	S–<left>	(org-shiftright &optional ARG)	With point on timestamp: decrement date. Use numeric arg to decrement by that number.
Go to calendar at date specified by timestamp	C–c >	(org-goto-calendar &optional ARG)	Go to the Emacs calendar at the current date. - If there is a time stamp in the current line, go to that date, otherwise go to today’s date. - With ‘C–u’ prefix: force the current date.
Open agenda at date	C–c C–o	(org-open-at-point &optional ARG)	When point on a timestamp: open the agenda at the day specified.
Evaluate time range	C–c C–y	(org-evaluate-time-range &optional TO-BUFFER)	Evaluate a time range by computing the difference between start and end. - Print result in the echo area, but with prefix arg insert result after time stamp in buffer. - If the time range is in a table, insert result into the next column. ⚠️ A year is assumed to be exactly 365 days in order to avoid rounding problems.

Description	Keystroke	Function	Note
• Clocking Work Time	Org mode allows tracking time for each task item; add info in them with the following commands.		
Start clock on current item	C-c C-x C-i	(org-clock-in &optional SELECT START-TIME)	Start the clock on the current item. - If necessary, clock-out of the currently active clock. - With a universal prefix (C-u), offer a list of recently clocked tasks to clock into.
Stop clock on current item	C-c C-x C-o	(org-clock-out &optional SWITCH-TO-STATE FAIL-QUIETLY AT-TIME)	Stop the currently running clock. - Throw an error if there is no running clock and FAIL-QUIETLY is nil. - With a universal prefix (C-u), prompt for a state to switch the clocked out task to, overriding the existing value of 'org-clock-out-switch-to-state'.
Cancel the current clock (remove all its current time)	C-c C-x C-q	(org-clock-cancel)	Cancel the running clock by removing the start timestamp.
Restart clock: start clock on last closed clocked item	C-c C-x C-x	(org-clock-in-last &optional ARG)	Clock in the last closed clocked item. When already clocking in, send a warning. - With 'C-u' prefix: select the task you want to clock in from the last clocked in tasks. - With 'C-u C-u' prefix: start clocking using the last clock-out time, if any. - With 'C-u C-u C-u' prefix: prompt for a todo state to switch to, overriding the existing value 'org-clock-in-switch-to-state'.
Recompute time interval	C-c C-y	(org-evaluate-time-range &optional TO-BUFFER)	Evaluate a time range by computing the difference between start and end. - Normally the result is just printed in the echo area, but with prefix arg TO-BUFFER, the result is inserted just after the date stamp into the buffer. - If the time range is actually in a table, the result is inserted into the next column. - For time difference computation, a year is assumed to be exactly 365 days in order to avoid rounding problems.
Resolve any half-open clocks	C-c C-x C-z	(org-resolve-clocks &optional ONLY-DANGLING-P PROMPT-FN LAST-VALID)	Resolve all currently open Org clocks. If 'only-dangling-p' is non-nil, only ask to resolve dangling (i.e., not currently open and valid) clocks.
Set effort property See: Effort Estimates	C-c C-x e	(org-set-effort &optional INCREMENT VALUE)	When point over a heading line or any of its children text/plain list items: Set the effort property of the current entry. If INCREMENT is non-nil, set the property to the next allowed value. Otherwise, if optional argument VALUE is provided, use it. Eventually, prompt for the new value if none of the previous variables is set.
Modify/update effort estimate	C-c C-x C-e	(org-clock-modify-effort-estimate &optional VALUE)	Modify the effort estimate of the item currently being clocked: add to or set the effort estimate of the item currently being clocked. - VALUE can be a number of minutes, or a string with format hh:mm or mm. - When the string starts with a + or a - sign, the current value of the effort property will be changed by that amount. - If the effort value is expressed as an unit defined in 'org-duration-units' (e.g. "3h"), the modified value will be converted to a hh:mm duration. This command will update the "Effort" property of the currently clocked item, and the value displayed in the mode line.
Increment timestamp element	S-<up>	(org-timestamp-up &optional ARG)	With point over timestamp: increase/decrease the date item at the cursor by one. With point over the year, change the year, the month, the day or the time, change that.
Decrement timestamp element	S-<down>	(org-timestamp-down &optional ARG)	With point on the enclosing bracket, change the timestamp type. - With prefix ARG, change by that many units. - Call 'org-timestamp-up' or 'org-timestamp-down' .
Increment date	S-<right>	(org-shiftright &optional ARG)	With point over timestamp: increase/decrease the date (only the date).
Decrement date	S-<left>	(org-shiftright &optional ARG)	With prefix ARG, change by that many units.
Move point to specified TODO item	C-c C-x C-j	(org-clock-goto &optional SELECT)	Go to the currently clocked-in entry, or to the most recently clocked one. - With prefix arg SELECT (C-u), offer recently clocked tasks for selection. - Type identified character to move to specified item.
Display clock times for headlines in current file	C-c C-x C-d	(org-clock-display &optional ARG)	Show subtree times in the entire buffer. By default, show the total time for the range defined in ' org-clock-display-default-range '. - With 'C-u' prefix: show the total time for today instead. - With 'C-u C-u' prefix: use a custom range, entered at prompt. - With 'C-u C-u C-u' prefix: display the total time in the echo area.
Generate a report for clock activity	C-c C-x C-r	(org-toggle-radio-button &optional ARG)	Toggle off all checkboxes and toggle on the one at point.
Create sparse tree(s) from TODO items	C-c /	(org-sparse-tree &optional ARG TYPE)	Create a sparse tree, prompt for the details. This command can create sparse trees. You first need to select the type of match used to create the tree:
	t Show all TODO entries. T Show entries with a specific TODO keyword. m Show entries selected by a tags/property match. p Enter a property name and its value (both with completion on existing names/values) and show entries with that property. r Show entries matching a regular expression ('/' can be used as well). b Show deadlines and scheduled items before a date. a Show deadlines and scheduled items after a date. d Show deadlines due within 'org-deadline-warning-days'. D Show deadlines and scheduled items between a date range.		
• The clock table	Org mode can produce complex reports based on time clocking information. These reports are called <i>clock table</i>		
Create/Update clock report	<f12> c r	(org-clock-report &optional ARG)	Update or create a table containing a report about clocked time. - If point is inside an existing clocktable block, update it. Otherwise, insert a new one. - With 'C-u' prefix: move to the first clock table in the buffer and update it.
	The new table inherits its properties from the variable 'org-clock-clocktable-default-properties'. The scope of the clocktable, when not specified in the previous variable, is 'subtree' of the current heading when the function is called from inside heading, and 'file' elsewhere (before the first heading).		
Update dynamic block (update clock report)	C-c C-x C-u	(org-dblock-update &optional ARG)	User command for updating dynamic blocks. With 'C-u' prefix: update all dynamic blocks in the buffer.
	C-c C-c		Update the dynamic block at point.
Shift current :block: interval & update the table	S-<right> S-<left>	(org-clocktable-try-shift DIR N)	Shift the current ':block' interval and update the table. Point needs to be in the '#+BEGIN: clocktable' line for this command. If ':block' is 'today', it is shifted to 'today-1', etc.

Description	Keystroke	Function	Note																																								
Org Syntax Check	Tools to check the syntax of org files.																																										
Lint org file report warnings	<f12> c	(org-lint)	Check current Org buffer for syntax mistakes. By default, run all checkers. • With a ‘C–u’ prefix ARG, select one category of checkers only. With a ‘C–u C–u’ prefix, run one precise checker by its name. All lint warnings are shown in the “Org Lint” buffer. In that buffer the following commands are available: <table><tr><td>C–j, TAB</td><td>Display the offending line</td><td>h</td><td>Hide all reports from the same checker</td></tr><tr><td>RET</td><td>Move point to the offending line</td><td>i</td><td>Also remove them from all subsequent checks</td></tr><tr><td>g</td><td>Check the document again</td><td>s</td><td>Sort reports by the column at point</td></tr></table>	C–j, TAB	Display the offending line	h	Hide all reports from the same checker	RET	Move point to the offending line	i	Also remove them from all subsequent checks	g	Check the document again	s	Sort reports by the column at point																												
C–j, TAB	Display the offending line	h	Hide all reports from the same checker																																								
RET	Move point to the offending line	i	Also remove them from all subsequent checks																																								
g	Check the document again	s	Sort reports by the column at point																																								
Parse org file	(org-element-parse-buffer &optional GRANULARITY VISIBLE-ONLY KEEP-DEFERRED)		Recursively parse the buffer and return structure. If narrowing is in effect, only parse the visible part of the buffer. See output in the “Message” buffer.																																								
Org Commands	The following are powerful commands that perform useful operation that create Org files.																																										
• Org Agenda • Agenda Views • Agenda Commands	<f12> a	(org-agenda &optional ARG KEYS RESTRICTION)	Dispatch agenda commands to collect entries to the agenda buffer. • Prompts for a command to execute. • Any prefix arg will be passed on to the selected command. <table><tr><td>Type the following extra key to issue the command:</td><td>n</td><td>Agenda and all TODOs</td><td><</td><td>Buffer, subtree/region restriction</td></tr><tr><td></td><td>a</td><td>Agenda for current week or day</td><td>></td><td>Remove restriction</td></tr><tr><td></td><td>/</td><td>Multi-occur</td><td>e</td><td>Export agenda views</td></tr><tr><td></td><td>t</td><td>List of all TODO entries</td><td>T</td><td>Entries with special TODO kwd</td></tr><tr><td></td><td>m</td><td>Match a TAGS/PROP/TODO query</td><td>M</td><td>Like m, but only TODO entries</td></tr><tr><td></td><td>s</td><td>Search for keywords</td><td>S</td><td>Like s, but only TODO entries</td></tr><tr><td></td><td>? </td><td>Find :FLAGGED: entries</td><td>C</td><td>Configure custom agenda commands</td></tr><tr><td></td><td>*</td><td>Toggle sticky agenda views</td><td>#</td><td>List stuck projects (!=configure)</td></tr></table>	Type the following extra key to issue the command:	n	Agenda and all TODOs	<	Buffer, subtree/region restriction		a	Agenda for current week or day	>	Remove restriction		/	Multi-occur	e	Export agenda views		t	List of all TODO entries	T	Entries with special TODO kwd		m	Match a TAGS/PROP/TODO query	M	Like m, but only TODO entries		s	Search for keywords	S	Like s, but only TODO entries		?	Find :FLAGGED: entries	C	Configure custom agenda commands		*	Toggle sticky agenda views	#	List stuck projects (!=configure)
Type the following extra key to issue the command:	n	Agenda and all TODOs	<	Buffer, subtree/region restriction																																							
	a	Agenda for current week or day	>	Remove restriction																																							
	/	Multi-occur	e	Export agenda views																																							
	t	List of all TODO entries	T	Entries with special TODO kwd																																							
	m	Match a TAGS/PROP/TODO query	M	Like m, but only TODO entries																																							
	s	Search for keywords	S	Like s, but only TODO entries																																							
	?	Find :FLAGGED: entries	C	Configure custom agenda commands																																							
	*	Toggle sticky agenda views	#	List stuck projects (!=configure)																																							
Switch between Org buffers.	<f12> b	(org-switchb &optional ARG)	Switch between Org buffers. • With ‘C–u’ prefix, restrict available buffers to files. • With ‘C–u C–u’ prefix, restrict available buffers to agenda files.																																								
Capture something	<f12> C	(org-capture &optional GOTO KEYS)	Select a template from ‘org-capture-templates’, and then file the newly captured information. The text is immediately inserted at the target location, and an indirect buffer is shown where you can edit it. Pressing ‘C–c C–c’ brings you back to the previous state of Emacs, to continue your work. • When called interactively with a ‘C–u’ prefix argument GOTO, don’t capture anything, just go to the file/headline where the selected template stores its notes. • With a ‘C–u C–u’ prefix argument, go to the last note stored. When called with a ‘C–0’ (zero) prefix, insert a template at point. • When called with a ‘C–1’ (one) prefix, force prompting for a date when a datetree entry is made. • Instead of Control key for numerical prefixes you can also use the Meta key. If ‘org-capture-use-agenda-date’ is non-nil, capturing from the agenda will use the date at point as the default date. Then, a ‘C–1’ prefix will tell the capture process to use the HH:MM time of the day at point (if any) or the current HH:MM time.																																								
Archiving																																											
Archive current entry	C–c C–x C–a	(org-archive-subtree-default)	Move the current subtree inside an .org_archive file. The file has the same path and base name.																																								
Archiving Tree	☞ Move tree to archive file																																										
Move current subtree to the archive	C–c C–x C–s	(org-archive-subtree &optional FIND-DONE)	Move the current subtree to the archive. • The archive can be a certain top-level heading in the current file, or in a different file. The tree will be moved to that location, the subtree heading be marked DONE, and the current time will be added. • C-u C-c C-x C-s : When called with a single prefix argument FIND-DONE, find whole trees without any open TODO items and archive them (after getting confirmation from the user). • C-u C-u C-c C-x C-s : When called with a double prefix argument, find whole trees with timestamps before today and archive them (after getting confirmation from the user). If the cursor is not at a headline when these commands are called, try all level 1 trees. If the cursor is on a headline, only try the direct children of this heading.																																								
Archiving - internal	☞ Internal archiving																																										
Toggle archive tag for current headline	C–c C–x a	(org-toggle-archive-tag &optional FIND-DONE)	Toggle the archive tag for the current headline. • C-u C-c C-x a : With prefix ARG, check all children of current headline and offer tagging the children that do not contain any open TODO items.																																								
Move the current entry to the Archive Sibling	C–c C–x A	(org-archive-to-archive-sibling)	Archive the current heading by moving it under the archive sibling. • The archive sibling is a sibling of the heading with the heading name ‘org-archive-sibling-heading’ and an ‘org-archive-tag’ tag. If this sibling does not exist, it will be created at the end of the subtree. • Archiving time is retained in the ARCHIVE_TIME node property.																																								
More information needed 🚧🚧🚧	The following rows do not contain valuable information. They are left over for future work. They will be removed soon and integrated with more information.🚧🚧🚧🚧🚧																																										
	S–<right>	(org-shiftright &optional ARG)	Act on the current element according to context. This does one of the following: • switch a timestamp at point one day into the future • on a headline, switch to the next TODO keyword • on an item, switch entire list to the next bullet type • on a property line, switch to the next allowed value • on a clocktable definition line, move time block into the future • in a table, move a single cell right																																								
	S–<left>	(org-shiftleft &optional ARG)	Act on the current element according to context. This does one of the following: • switch a timestamp at point one day into the past • on a headline, switch to the previous TODO keyword. • on an item, switch entire list to the previous bullet type • on a property line, switch to the previous allowed value • on a clocktable definition line, move time block into the past • in a table, move a single cell left																																								
	S–<up>	(org-shiftup &optional ARG)	Act on current element according to context. Call ‘org-timestamp-up’ or ‘org-priority-up’, or ‘org-previous-item’, or ‘org-table-move-cell-up’. See the individual commands belowfor more information.																																								
	S–<up>	(org-previous-item)	Move to the beginning of the previous item.																																								
	S–<up>	(org-table-move-cell-up)	Move a single cell up in a table. Swap with anything in target cell.																																								
	S–<down>	(org-shiftdown &optional ARG)	Act on current element according to context. Call ‘org-timestamp-down’ or ‘org-priority-down’, or ‘org-next-item’, or ‘org-table-move-cell-down’. See the individual commands below for more information.																																								
	S–<down>	(org-next-item)	Move to the beginning of the next item.																																								
	S–<down>	(org-table-move-cell-down)	Move a single cell down in a table. Swap with anything in target cell.																																								
Move current line up (only inside its section)	M–S–<up>	(org-shiftmetaup &optional ARG)	Drag the line at point up. Any line and just that line: a heading line or a content line. • In a table, kill the current row. • On a clock timestamp, update the value of the timestamp like ‘S–<up>’ but also adjust the previous clocked item in the clock history. • Everywhere else, drag the line at point up.																																								
Move current line down (only inside its section)	M–S–<down>	(org-shiftmetadown &optional ARG)	Drag the line at point down. Any line and just that line: a heading line or a content line. • In a table, insert an empty row at the current line. • On a clock timestamp, update the value of the timestamp like ‘S–<down>’ but also adjust the previous clocked item in the clock history. • Everywhere else, drag the line at point down.																																								

Org-Mode - Reference

Topic & link	Description
Org Mode @ Wikipedia	A good introduction to Org Mode concepts
🔗 Org mode home and 🔗 The Org Manual	Org mode is actively developed. The Org Mode home page contains links to all you need.
Quick Reference for emacs Org-Mode key binds	
How to move a subtree to another subtree in org-mode emacs	Stack Overflow Q&A. Just to move the sub-tree itself (not its top level headline).
Command to copy and delete subtree in org-mode	Stack Overflow Q&A. Answer: C-C C-x C-w and C-c C-x C-y
Getting started with Org-Mode @ Youtube	
Literate DevOps with Emacs - youtube video	
David 'Otool Org Tutorial	
Hello Worg, the Org-Mode Community!	
Org Mode Tools	
Org-Mode Exporters - The New Org-mode Exporter Framework	
* ox.el @ github	
Pandoc support	
Pandoc-mode - An Emacs mode for interacting with Pandoc	
Org mode and Pandoc	
Keeping a lab notebook with org-mode, git, Papers, and Pandoc (Part II)	
Confluence Wiki Support for Org Mode	
https://www.emacswiki.org/emacs/ConfluenceMode	
confluence-el (10 years old)	
confluence-el : seems newer.	
ox-confluence - 2012-2014 : export org files to confluence using the ox.el	
sdelafond /org-confluence	That was integrated inside org-mode.
In org-mode, how do I export to JIRA wiki markup? @ StackExchange	
Clocking Work Time - The Org Manual	
Time Tracking in Emacs with org-clock	Short article written by David Charle, on November 2017.
Clocking time with Org-mode	Good description of the clocking time mechanism supported by org-mode. Written in April 2017 by Lee Hinman
Org Mode Time and Task Tools – Straightforward Emacs @YouTube	
Emacs Org id will change how you see things @YouTube	From Chris Maiorama
Org Mode Citation and Footnote Features — Straightforward Emacs	Jake B YouTube video presenting Emacs org-mode citation and footnote features.