

Description	Keystroke	Function	Note
Org Mode ○ Shift-selection • Text markup / electric keys • Toggle clean view mode ○ Move through headings • Edit Structure +headings • ±TODO, yank, clone, sort ○ Change TODO state • Todo checkboxes • Hyper Links Narrow/widen • Control Outline Visibility ○ Date & Time +Timestamps • Clocking Work Time ○ Org Syntax Check • Org Commands • Archiving ○ References Last updated on: 2026-08-20	Emacs Org-Mode is very powerful outline document lightweight markup with a lot of powerful features designed for notes, planning and authoring: • Markup: *bold*, <i>/italic/</i>, <u>_underline_</u>, ~code~, =verbatim=, +strike-through+ and [[https://orgmode.org][Org links]] • Document structure: documents are outlines with headlines that have visibility cycling, support motion, • Has commands for document structure editing • Also supports: Sparse Trees, Plain Lists, Drawers and Blocks 🚧🚧🚧 I am currently updating this table to include as much as possible or Org Mode feature descriptions. New version will be available soon.		
Open this PDF file. See also: 🔗 Help/Info	<f11> SPC M-o <f1> <f12> <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the M Org-Mode local PDF. If the prefix argument (like C-u or M--) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
🔗 Customize PEL Org Mode support	<f11> SPC M-o <f2> <f12> <f2>	(pel-customize-pel &optional OTHER)	Customize PEL Org Mode support: open pel-pkg-for-org-mode group. • If OTHER is non-nil (use C-u), display in another window.
🔗 Customize Emacs Org Mode support	<f11> SPC M-o <f3>	(pel-customize-library &optional OTHER)	Customize Org Mode external packages support: • If OTHER is non-nil (use C-u), display in another window.
Shift Select Control and other conflicts See also: shift selection	In most major modes, Emacs supports text selection by holding the Shift key down while moving point; this feature is called shift selection. • By default, shift selection is not available in org-mode because in org-mode the shift cursor keys are used to control the state of the bullets and have other meaning in titles and time stamps. 👤👤👤 However, you can customize org-support-shift-select user-option to re-activate partially or completely re-activate shift-selection. • Setting it to t: activates shift-selection when the cursor is not in special context: the bullet cycling will no longer happen anywhere in an item line, but only if the cursor is exactly on the bullet. • Setting it to always: activates shift-selection in org-mode. then the keys will not be special in headlines, property lines, item lines, and table cells, to make shift selection work there as well. Read its docstring for more information with <f1> o		
Text Emphasis Electric Keys See also: 🔗 Mode Line	👤👤 With the pel-org-use-electric-markup user-option set, PEL provides a specialized electric-pair-mode to type the characters below in pair. 👤👤 The pel-electric-pair-lighter user-option identifies the line-mode lighter displayed when the electric-pair-mode is active. Defaults to “ε{I}” For the following keys: If an area is currently marked, the character typed is inserted before and after the marked area. If no area is marked, two characters are inserted and the point is left in between. Disable this behaviour by typing <f11> M-e: this toggles the electric-pair-local-mode.		
• Bold	*		To insert a single * character inside the text there are several methods: • Insert a zero-width space right after the asterisk: Type: C-x 8 RET zero width space RET • Insert *-~ • Insert ==~ or ~*-~ markup
			If you want to use it at the beginning of a line without creating a header, insert a comma right before it; org-mode will strip the comma upon export: insert: , *
• Italic	/		To insert a single / character inside the text there are several methods: • Insert a zero-width space right after the slash: Type: C-x 8 RET zero width space RET • Insert /= or ~/~ markup • Add surrounding spaces: if you put a space before and after the slash it will not trigger italics: example: this / that
• Underline	_		To insert a single _ character inside the text there are several methods: • Insert a zero-width space right after the underscore: Type: C-x 8 RET zero width space RET • Insert =_ or ~_~ markup • Use a backslash before the underscore if your only concern about is how the document exported to HTML or PDF looks: _
			You may also want to disable subscript for the current file by adding the following configuration line at the top of the Org file. That stops org-mode from turning underscores into subscripts unless you explicitly wrap text in curly braces like this: _ {subscript} Add the following entry at the very top of the file and then refresh the buffer by typing C-c C-c on that line after typing it: #+OPTIONS: ^: {}
• Code	~		To insert a single ~ character inside the text there are several methods: • Insert a zero-width space right after the tilde: Type: C-x 8 RET zero width space RET • Insert ==~ markup • Add surrounding spaces: put a space before and after the tilde: example: value ~ 10 • Use a backslash before the tilde if your only concern about is how the document exported to HTML or PDF looks: \~
• Verbatim (literal)	=		To insert a single = character inside the text there are several methods: • Insert a zero-width space right after the equal: Type: C-x 8 RET zero width space RET • Insert --~ markup • Add surrounding spaces: put a space before and after the equal: example: value = 10
			To use it at the beginning of a line without org-mode interpreting it, insert a comma right before it; org-mode strips the comma upon export: insert: , =
• Strike-trough	+		To insert a single + character inside the text there are several methods: • Insert a zero-width space right after the plus: Type: C-x 8 RET zero width space RET • Insert += or ~+-~ markup • Add surrounding spaces: if you put a space before and after the slash it will not trigger italics: example: this + that • Use a backslash before the plus if your only concern about is how the document exported to HTML or PDF looks: \+
Example blocks See also: Org-mode code blocks	To write long technical text without escaping any Org-mode markup characters listed above, wrap your text in an Example Block: Org-mode treats everything inside this block as literal, unformatted text. For example: #+begin_example Here is a long technical note where no markup applies: * This is not a header or bold text. / This text will not be italicized. x = y + z_subscript; ~ This is just plain text. #+end_example		
Toggle electric-pair-mode in current buffer 🔧	<f11> M-e	(electric-pair-local-mode &optional ARG)	Toggle automatic parens pairing (Electric Pair mode) and org-mode special pair electric keys only in this buffer. • With a prefix argument ARG, enable Electric Pair mode if ARG is positive, and disable it otherwise. • Electric Pair mode is a global minor mode. When enabled, typing an open parenthesis automatically inserts the corresponding closing parenthesis, and vice versa. (Likewise for brackets, etc.). If the region is active, the parentheses (brackets, etc.) are inserted around the region instead.
Lighter := ε{I}			
Outlines	Org documents are an outline tree. Org headlines (also called headings) start on the left margin with one or more stars followed by space. They can also be shown indented as controlled by the following command:		
Toggle clean view mode. 🔧	<f12> TAB	(org-indent-mode &optional ARG)	Toggle use of a cleaner outline view , where: • hides headings leading stars (but still shows in Terminal frames (depending on colors)), • automatically indent text to align with their headline • activate proper automatic line wrap. You can activate this minor mode for individual files with: #+STARTUP: indent

Description	Keystroke	Function	Note
Move through headings	See: Motion commands. ARG is 1 by default. Supply a different value via a numeric argument , with negative value to move in opposite direction.		
Next heading	C-c C-n	(org-next-visible-heading ARG)	Move to the next visible heading.
Previous heading	C-c C-p	(org-previous-visible-heading ARG)	Move to the previous visible heading.
Next heading same level	C-c C-f	(org-forward-heading-same-level ARG &optional INVISIBLE-OK)	Move forward to the ARG'th subheading at same level as this one. Stop at the first and last subheadings of a superior heading.
Previous heading same level	C-c C-b	(org-backward-heading-same-level ARG &optional INVISIBLE-OK)	Move backward to the ARG'th subheading at same level as this one. Stop at the first and last subheadings of a superior heading.
Backward to higher level heading	C-c C-u	(outline-up-heading ARG &optional INVISIBLE-OK)	Move to the visible heading line of which the present line is a subheading. With argument, move up ARG levels.
Edit Structure	Modify the outline structure of the Org document by issuing the following commands on heading lines. ⚠ With PEL, M-<up> and M-<down> are normally bound to PEL scroll commands , but not in org-mode because they are bound to org-mode commands. To scroll up/down in org-mode: use the number keypad key 3 and 9 of the number keypad not num-locked, or when using hydra external package use the <f7> prefix with <up> and <down> keys. For more info see: ℹ Scrolling.		
• Insert headings	Insert outline headings (also called headlines) in the Org document with the following commands. • The org-blank-before-new-entry user-option controls whether a separator empty line is inserted before the new heading.		
Create heading at same level	Esc RET M-RET	(org-meta-return &optional ARG)	Insert new heading of same level as current. If cursor is at a plain list item, create new item. • If used in the middle of a line, <i>split</i> the line and the rest become a new headline.
Create heading at same level - don't split line	C-RET	(org-insert-heading-respect-content &optional INVISIBLE-OK)	Insert the line as if cursor is at end of line (never split current line). • This insert heading as if ' org-insert-heading-respect-content ' is currently set to t.
• Insert TODO heading	TODO notes are Org headings that have the TODO state. They can have: priorities , time stamps (scheduling & deadlines) and time tracking.		
Insert a new heading at same level and TODO state	M-S-RET C-c C-x M	(org-insert-todo-heading ARG &optional FORCE-HEADING)	Insert a new heading with the same level and TODO state as current heading. • If the heading has no TODO state, or if the state is DONE, use the first state (TODO by default). Also with one prefix arg (C-u), force first state. • With two prefix args (C-u C-u), force inserting at the end of the parent subtree.
Insert a new heading at same level and TODO state	C-S-RET	(org-insert-todo-heading-respect-content &optional ARG)	When point on TODO heading: insert a new TODO heading, never split current line. • This insert heading as if ' org-insert-heading-respect-content ' is currently set to t.
Line <-> Heading	C-c *	(org-ctrl-c-star)	When point on normal line or plain list item: change line to a subheading at its location.
	- When point is on a heading: turn into anormal line by removing the stars. - If there is an active region, turn all lines in the region into headlines. If the first line in the region was an item, turn only the item lines into headlines. Finally, if the first line is a headline, remove the stars from all headlines in the region.		
On a <i>new</i> empty heading: cycle through heading levels	<tab>	(org-cycle &optional ARG)	This works only if: - the line is empty (except for the star identifying it as a heading) - there are other headings of level 2 or more somewhere else in the document.
Demote current heading (make it a sub-heading)	M-<right>	(org-metaright &optional ARG)	Demote heading, list item at point or move table column right. • In front of a drawer or a block keyword, indent it correctly.
Promote current heading	M-<left>	(org-metaleft &optional ARG)	Promote heading, list item at point or move table column left.
Demote current sub-tree	M-S-<right>	(org-shiftmetaright)	Demote subtree or insert table column.
Promote current sub-tree	M-S-<left>	(org-shiftmetaleft)	Promote subtree or delete table column.
Move subtree/table row up (only inside its section)	M-<up>	(org-metaup &optional ARG)	Move subtree up or move table row up.
Move subtree/table row down (only inside its section)	M-<down>	(org-metadown &optional ARG)	Move subtree down or move table row down.
Move current line up (only inside its section)	M-S-<up>	(org-shiftmetaup &optional ARG)	Drag the line at point up. Any line and just that line: a heading line or a content line. In a table, kill the current row. On a clock timestamp, update the value of the timestamp like 'S-<up>' but also adjust the previous clocked item in the clock history. - Everywhere else, drag the line at point up.
Move current line down (only inside its section)	M-S-<down>	(org-shiftmetadown &optional ARG)	Drag the line at point down. Any line and just that line: a heading line or a content line. In a table, insert an empty row at the current line. On a clock timestamp, update the value of the timestamp like 'S-<down>' but also adjust the previous clocked item in the clock history. - Everywhere else, drag the line at point down.
Mark subtree	C-c @	(org-mark-subtree &optional UP)	Mark the current subtree. Puts point at the start of the current subtree, and mark at the end. With a numeric prefix, move up into the hierarchy of headlines by UP levels before marking the subtree.
Cut current subtree or region in table	C-c C-x C-w	(org-cut-special)	Cut region in table or cut current subtree.
Paste past subtree or rectangular region into table	C-c C-x C-y	(org-paste-special ARG)	Paste rectangular region into table, or past subtree relative to level.
Yank (paste)	C-y	(pel-overwrite-yank &optional ARG)	In org-mode the PEL command invokes (org-yank ARG) to yank like in org-mode: If the kill is a subtree, treat it specially.
	Pastes subtrees folded using the same command as C-c C-x C-y . With the default settings, no level adjustment takes place, but the yanked tree is folded unless doing so would swallow text previously visible. Any prefix argument forces a normal yank: a good way to force a normal yank is C-u C-y . If you use yank-pop after a yank, it yanks previous kill items plainly, without adjustment and folding. Look at the current kill and check if is a single subtree, or a series of subtrees. If it passes the test, and if the cursor is at the beginning of a line or after the stars of a currently empty headline, then the yank is handled specially according to the value of the following user-option variables: org-yank-folded-subtrees: By default, this variable is non-nil, which results in subtree(s) being folded after insertion, except if doing so would swallow text after the yanked text. org-yank-adjusted-subtrees: When non-nil (the default value is nil), the subtree will be promoted or demoted in order to fit into the local outline tree structure, which means that the level will be adjusted so that it becomes the smaller one of the two "visible" surrounding headings.		
Clone sub-tree	C-c C-x c	(org-clone-subtree-with-time-shift N &optional SHIFT)	Clone a subtree by making a number of sibling copies of it. Prompts for the number of copies to make; you can also specify whether any timestamps in the entry should be shifted. This can be useful, for example, to create a number of tasks related to a series of lectures to prepare. For more details, see the docstring of the command org-clone-subtree-with-time-shift
Refile and Copy	C-c C-w	(org-refile &optional ARG DEFAULT-BUFFER RFLOC MSG)	Refile entry or region to a different location. See Refile and Copy .
Sort entries	C-c ^	(org-sort &optional WITH-CASE)	Sort same-level entries. With an active region, all entries in the region are sorted. Otherwise, the children of the current headline are sorted. With a C-u prefix, sorting is case-sensitive.
	Prompts for the sorting method, which can be alphabetically, numerically, by time—first timestamp with active preferred, creation time, scheduled time, deadline time—by priority, by TODO keyword—in the sequence the keywords have been defined in the setup—or by the value of a property. Reverse sorting is possible as well. You can also supply your own function to extract the sorting key.		

Description	Keystroke	Function	Note
Change TODO items state and priority - basic TODO functionality - extended use of TODO - Progress Logging	Change Org state of headline item with the following commands. The state of TODO items is controlled by the org-todo-keywords user-option. The default is ((sequence "TODO" "DONE")). More complex list are possible, see the variable docstring. When pel-use-org user option is set, PEL sets it to ((sequence "TODO" "IN-PROGRESS" "DONE")) which provides an extra state. 🍷 Several commands are mapped to S-<cursor>. These are only available on headline. In other lines the using the Shift key with cursor is used for shift selection when org-support-shift-select user option is set to t to always.		
Rotate heading state of current item	S-<right>	(org-shiftright &optional ARG)	With point on a headline, cycle switch to the next TODO keyword. empty → TODO → IN PROGRESS → DONE.
	S-<left>	(org-shiftright &optional ARG)	With point on a headline, switch to the next TODO keyword. empty ← TODO ← IN PROGRESS ← DONE.
	C-c C-t	(org-todo)	Changes state in order (as in org-todo-keywords) : unmarked, TODO, IN PROGRESS, DONE.
Update state, log progress	C-u C-c C-t		Prompt for note, record the time of the TODO state change. The note is inserted as a list item below the headline, but can also be placed into a drawer, see Tracking TODO state changes .
Set task priority	C-c ,	(org-priority &optional ACTION SHOW)	Change the priority of an item. Prompts for priority level (A to C). Hit space to remove. With a 'C-u' prefix, show the priority in the minibuffer instead of changing it.
Increase task priority	S-<up>	(org-priority-up)	Increase the priority of the current item.
Decrease task priority	S-<down>	(org-priority-down)	Decrease the priority of the current item.
Todo Checkboxes	- TODO items can have checkboxes, written like this: [], with a space between the brackets. There can be a top-level count: - written like this: [/], it will show the number of items done over the total (like [24/46], or - written like this: [%], which shows the percentage of items done.		
Toggle checkbox status	C-c C-c	(org-ctrl-c-ctrl-c &optional ARG)	Toggle checkbox status. - With 'C-u' prefix: toggle checkbox presence at point: add or remove checkbox. - With 'C-u C-u' prefix, set it to '[-]', which is considered to be an intermediate state.
Toggle checkbox status	C-c C-x C-b	(org-toggle-checkbox &optional TOGGLE-PRESENCE)	Toggle the checkbox in the current line. - With prefix argument TOGGLE-PRESENCE, add or remove checkboxes. With a double prefix argument, set the checkbox to "[-]". - When there is an active region, toggle status or presence of the first checkbox there, and make every item inside have the same status or presence, respectively. (This does not seem to work with C-c C-c) - If point is on a headline, apply this to all checkbox items in the text below the heading, taking as reference the first item in subtree, ignoring planning line and any drawer following it.
Insert a new, empty, checkbox on the next line	M-S-RET	(org-insert-todo-heading ARG &optional FORCE-HEADING)	Insert a new heading with the same level and TODO state as current heading (inserts the checkbox on the current line). - If the heading has no TODO state, or if the state is DONE, use the first state (TODO by default). Also with one prefix arg, force first state. With two prefix args, force inserting at the end of the parent subtree. - When called at a plain list item, insert a new item with an unchecked check box.
Toggle the 'ORDERED' property	C-c C-x o	(org-toggle-ordered-property)	Toggle the 'ORDERED' property of the entry, to toggle if checkboxes must be checked off in sequence. A property is used for this behavior because this should be local to the current entry, not inherited like a tag. However, if you would like to track the value of this property with a tag for better visibility, customize org-track-ordered-property-with-tag.
Update the statistics cookie	C-c #	(org-update-statistics-cookies ALL)	Update the statistics cookie, either from TODO or from checkboxes. This should be called with the cursor in a line with a statistics cookie. When called with a C-u prefix, update all statistics cookies in the buffer.
Hyperlinks	Org mode supports links in the file to external files, web pages, emails and much more. Link format: [[LINK][DESCRIPTION]] or [[LINK]] It also supports internal links , links to other parts of the current file/buffer such as: [[#my-custom-id]] to entry with CUSTOM_ID property or [[*Some section]] to the headline with the name 'Some Section'. <<My Target>> to any element that has an element name using the following format: #+NAME: My Target		
Store a link to the current location (define a link target)	<f11> M-o l	(org-store-link ARG &optional INTERACTIVE?)	Store a link to the current location in ' org-stored-links ' that can later be inserted into an Org buffer with 'org-insert-link' (' C-c C-1 '). 🍷 Use <f11> M-o l in file at the beginning of a line.
	<f12> l		
	- A single 'C-u' negates 'org-link-context-for-files' for file links or 'org-gnus-prefer-web-links' for links to Usenet articles. - A 'C-u C-u' prefix ARG forces skipping storing functions that are not part of Org core. - A 'C-u C-u C-u' prefix ARG forces storing a link for each line in the active region.		
Insert a hyperlink or Edit the visible LINK part of an already formatted link.	C-c C-1	(org-insert-link &optional COMPLETE-FILE LINK-LOCATION DEFAULT-DESCRIPTION)	Insert a link at point. Supports several types of links; select type with tab-completion, then complete it and hit <RET> . Then enter the description text and hit <RET> . Inside the Org-mode file, insert the link that was created with C-c l . Use the up arrow to retrieve the link, then type the documentation inside the mini buffer and hit return to insert inside the org mode file. With a 'C-u' prefix, prompts for a file to link to.
Open/follow the link item Example: open directory in Dired	C-c C-o	(org-open-at-point &optional ARG REFERENCE-BUFFER)	With point over a rendered hyperlink: open a buffer for the target at the location of the target. - Some links will open using external software. For example, if the link is a directory, the OS program will be used. - To force opening the link inside Emacs use the 'C-u' prefix. For example, to open a link to a directory with Dired, use: C-u C-c C-o
Move to next hyperlink	C-c C-x C-n	(org-next-link &optional SEARCH-BACKWARD)	Move forward to the next link. If the link is in hidden text, expose it. When SEARCH-BACKWARD is non-nil, move backward.
Move to previous hyperlink	C-c C-x C-p	(org-previous-link)	Move backward to the previous link. If the link is in hidden text, expose it.
Narrowing tree/blocks	Also see ☞ Narrowing		
Narrow to subtree	C-x n s	(org-narrow-to-subtree &optional ELEMENT)	Narrow buffer to current subtree. With optional argument ELEMENT narrow to subtree around ELEMENT : for elisp code only.
Narrow to block	C-x n b	(org-narrow-to-block)	Narrow buffer to current block.
Widen	C-x n w	(widen)	Widen buffer to remove narrowing. This allows the buffer's full text to be seen and edited.
Control Visibility	Org documents are treated as outlines; the heading lines are section levels and can be hidden and shown with the following commands.		
Sub-Tree Visibility Cycling	<tab>	(org-cycle &optional ARG)	Expand/compress the sub-tree title lines: folded → see children → see all subtree. To see all: C-u C-u C-u <tab>
Global VisibilityCycling	S-<tab> C-u <tab>	(org-shifftab &optional ARG)	Rotate the entire buffer among the following states: - Overview, - Contents - Show all
Cycle subtree even if it is archived	C-<tab>	(org-cycle-force-archived)	Cycle subtree even if it is archived.
Reveal context around point	C-c C-r	(org-reveal &optional SIBLINGS)	Show current entry, hierarchy above it, and the following headline.
Show all sub-headings, hide their bodies	C-c C-k	(org-kill-note-or-show-branches)	Abort storing current note, or call 'outline-show-branches' to show all subheadings of this heading, but not their bodies.
Show all <i>direct</i> sub-headings	C-c <tab>	(outline-show-children &optional LEVEL)	If lines (or bodies) are already shown, nothing changes. Does not show the body (but does not hide them when already showing). By default show only 1 level of sub-headings, with numeric argument identify the number of levels to show: For example to show 3 sub-levels: C-u 3 C-c <tab>
Show current subtree in indirect buffer	C-c C-x b	(org-tree-to-indirect-buffer &optional ARG)	Take current subtree and open in an indirect buffer, not affecting current buffer's visibility. - Any edit in the indirect buffer goes inside the same file. - Very useful to see the layout and be able to expand information inside a subtree.

Description	Keystroke	Function	Note
Dates and Times	To assist project planning, TODO items can be labeled with a date and/or a time: an org timestamp. Format: <2003-09-16 Tue 12:00-12:30>		
• Creating Timestamps	Time/Date range: 2 timestamps connected by '--'. Format: <2004-08-23 Mon 10:00-11:00>--<2004-08-26 Thu 10:00-11:00>		
Add/replace active time stamp To insert a Time/Date range issue the command twice.	C-c .	(org-timestamp ARG &optional INACTIVE)	Insert/replace an active time stamp. Prompts. By default only the date is included. - With 'C-u' prefix: the time stamp contains date & time. - With 'C-u C-u' prefix: the time stamp contains date & time. No prompt.
	All parts of a date not specified by the user are filled in from the timestamp at point, if any, or the current date/time otherwise.		
Add/replace inactive time stamp	C-c !	(org-timestamp-inactive &optional ARG)	Insert an inactive time stamp. Prompts. By default only the date is included. - An inactive time stamp is enclosed in square brackets instead of angle brackets. It is inactive in the sense that it does not trigger agenda entries. So these are more for recording a certain time/date. - With 'C-u' prefix: the time stamp contains date & time. - With 'C-u C-u' prefix: the time stamp contains date & time. No prompt. Replace existing timestamp if there was any.
Normalize timestamp	C-c C-c	(org-ctrl-c-ctrl-c &optional ARG)	When point on a timestamp: normalize timestamp, insert/fix day name if missing or wrong
Insert date timestamp from calendar current position	C-c <	(org-date-from-calendar)	Insert time stamp corresponding to cursor date in *Calendar* buffer. If there is already a time stamp at the cursor position, update it.
Change timestamp date	S-<right>	(org-shiftright &optional ARG)	
	S-<left>	(org-shiftright &optional ARG)	With point on timestamp: decrement date. Use numeric arg to decrement by that number.
Go to calendar at date specified by timestamp	C-c >	(org-goto-calendar &optional ARG)	Go to the Emacs calendar at the current date. - If there is a time stamp in the current line, go to that date, otherwise go to todays' date. - With 'C-u' prefix: force the current date.
Open agenda at date	C-c C-o	(org-open-at-point &optional ARG)	When point on a timestamp: open the agenda at the day specified.
Evaluate time range	C-c C-y	(org-evaluate-time-range &optional TO-BUFFER)	Evaluate a time range by computing the difference between start and end. - Print result in the echo area, but with prefix arg insert result after time stamp in buffer. - If the time range is in a table, insert result into the next column. ⚠ A year is assumed to be exactly 365 days in order to avoid rounding problems.
• Clocking Work Time	Org mode allows tracking time for each task item; add info in them with the following commands.		
Start clock on current item	C-c C-x C-i	(org-clock-in &optional SELECT START-TIME)	Start the clock on the current item. - If necessary, clock-out of the currently active clock. - With a universal prefix (C-u), offer a list of recently clocked tasks to clock into.
Start clock o on last closed clocked item (restart clock)	C-c C-x C-x	(org-clock-in-last &optional ARG)	Clock in the last closed clocked item. When already clocking in, send a warning. - With 'C-u' prefix: select the task you want to clock in from the last clocked in tasks. - With 'C-u C-u' prefix: start clocking using the last clock-out time, if any. - With 'C-u C-u C-u' prefix: prompt for a todo state to switch to, overriding the existing value 'org-clock-in-switch-to-state'.
Cancel the current clock (remove all its current time)	C-c C-x C-q	(org-clock-cancel)	Cancel the running clock by removing the start timestamp.
Resolve any half-open clocks	C-c C-x C-z	(org-resolve-clocks &optional ONLY-DANGLING-P PROMPT-FN LAST-VALID)	Resolve all currently open Org clocks. If 'only-dangling-p' is non-nil, only ask to resolve dangling (i.e., not currently open and valid) clocks.
Set effort property See: Effort Estimates	C-c C-x e	(org-set-effort &optional INCREMENT VALUE)	Set the effort property of the current entry. If INCREMENT is non-nil, set the property to the next allowed value. Otherwise, if optional argument VALUE is provided, use it. Eventually, prompt for the new value if none of the previous variables is set.
Modify effort estimate	C-c C-x C-e	(org-clock-modify-effort-estimate &optional VALUE)	Modify the effort estimate of the item currently being clocked: add to or set the effort estimate of the item currently being clocked. - VALUE can be a number of minutes, or a string with format hh:mm or mm. - When the string starts with a + or a - sign, the current value of the effort property will be changed by that amount. - If the effort value is expressed as an unit defined in 'org-duration-units' (e.g. "3h"), the modified value will be converted to a hh:mm duration. This command will update the "Effort" property of the currently clocked item, and the value displayed in the mode line.
Stop clock on current item	C-c C-x C-o	(org-clock-out &optional SWITCH-TO-STATE FAIL-QUIETLY AT-TIME)	Stop the currently running clock. - Throw an error if there is no running clock and FAIL-QUIETLY is nil. - With a universal prefix (C-u), prompt for a state to switch the clocked out task to, overriding the existing value of 'org-clock-out-switch-to-state'.
Increment timestamp element	S-<up>	(org-timestamp-up &optional ARG)	With point over timestamp: increase/decrease the date item at the cursor by one. With point over the year, change the year, the month, the day or the time, change that. With point on the enclosing bracket, change the timestamp type. - With prefix ARG, change by that many units. - Call 'org-timestamp-up' or 'org-timestamp-down'.
Decrement timestamp element	S-<down>	(org-timestamp-down &optional ARG)	
Increment date	S-<right>	(org-shiftright &optional ARG)	
Decrement date	S-<left>	(org-shiftright &optional ARG)	With prefix ARG, change by that many units.
Move point to specified TODO item	C-c C-x C-j	(org-clock-goto &optional SELECT)	Go to the currently clocked-in entry, or to the most recently clocked one. - With prefix arg SELECT (C-u), offer recently clocked tasks for selection. - Type identified character to move to specified item.
Display clock times for headlines in current file	C-c C-x C-d	(org-clock-display &optional ARG)	Show subtree times in the entire buffer. By default, show the total time for the range defined in 'org-clock-display-default-range'. - With 'C-u' prefix: show the total time for today instead. - With 'C-u C-u' prefix: use a custom range, entered at prompt. - With 'C-u C-u C-u' prefix: display the total time in the echo area.
Generate a report for clock activity	C-c C-x C-r	(org-toggle-radio-button &optional ARG)	Toggle off all checkboxes and toggle on the one at point.
Create sparse tree(s) from TODO items	C-c /	(org-sparse-tree &optional ARG TYPE)	Create a sparse tree, prompt for the details. This command can create sparse trees. You first need to select the type of match used to create the tree:
	t Show all TODO entries. T Show entries with a specific TODO keyword. m Show entries selected by a tags/property match. p Enter a property name and its value (both with completion on existing names/values) and show entries with that property. r Show entries matching a regular expression ('/' can be used as well). b Show deadlines and scheduled items before a date. a Show deadlines and scheduled items after a date. d Show deadlines due within 'org-deadline-warning-days'. D Show deadlines and scheduled items between a date range.		

Description	Keystroke	Function	Note												
Org Syntax Check															
Lint org file report warnings	<f12> c	(org-lint)	Check current Org buffer for syntax mistakes. By default, run all checkers.												
	With a 'C-u' prefix ARG, select one category of checkers only. With a 'C-u C-u' prefix, run one precise checker by its name. All lint warnings are shown in the "Org Lint" buffer. In that buffer the following commands are available: <table> <tr> <td>C-j, TAB</td><td>Display the offending line</td><td>h</td><td>Hide all reports from the same checker</td></tr> <tr> <td>RET</td><td>Move point to the offending line</td><td>i</td><td>Also remove them from all subsequent checks</td></tr> <tr> <td>g</td><td>Check the document again</td><td>s</td><td>Sort reports by the column at point</td></tr> </table>			C-j, TAB	Display the offending line	h	Hide all reports from the same checker	RET	Move point to the offending line	i	Also remove them from all subsequent checks	g	Check the document again	s	Sort reports by the column at point
C-j, TAB	Display the offending line	h	Hide all reports from the same checker												
RET	Move point to the offending line	i	Also remove them from all subsequent checks												
g	Check the document again	s	Sort reports by the column at point												
Parse org file	(org-element-parse-buffer &optional GRANULARITY VISIBLE-ONLY KEEP-DEFERRED)		Recursively parse the buffer and return structure. If narrowing is in effect, only parse the visible part of the buffer. See output in the "Message" buffer.												
Org Commands	The following are powerful commands that perform useful operation that create Org files.														
Org Agenda - Agenda Views - Agenda Commands	<f11> M-o a <f12> A	(org-agenda &optional ARG KEYS RESTRICTION)	Dispatch agenda commands to collect entries to the agenda buffer. - Prompts for a command to execute. - Any prefix arg will be passed on to the selected command.												
	Type the following extra key to issue the command:	n Agenda and all TODOs a Agenda for current week or day / Multi-occur t List of all TODO entries m Match a TAGS/PROP/TODO query s Search for keywords ? Find :FLAGGED: entries * Toggle sticky agenda views	< Buffer, subtree/region restriction > Remove restriction e Export agenda views T Entries with special TODO kwd M Like m, but only TODO entries S Like s, but only TODO entries C Configure custom agenda commands # List stuck projects (!=configure)												
Switch between Org buffers.	<f11> M-o b <f12> B	(org-switchb &optional ARG)	Switch between Org buffers. - With 'C-u' prefix, restrict available buffers to files. - With 'C-u C-u' prefix, restrict available buffers to agenda files.												
Capture something	<f11> M-o c <f12> C	(org-capture &optional GOTO KEYS)	Select a template from 'org-capture-templates', and then file the newly captured information. The text is immediately inserted at the target location, and an indirect buffer is shown where you can edit it. Pressing 'C-c C-c' brings you back to the previous state of Emacs, to continue your work. - When called interactively with a 'C-u' prefix argument GOTO, don't capture anything, just go to the file/headline where the selected template stores its notes. - With a 'C-u C-u' prefix argument, go to the last note stored. When called with a 'C-0' (zero) prefix, insert a template at point. - When called with a 'C-1' (one) prefix, force prompting for a date when a datetree entry is made. - Instead of Control key for numerical prefixes you can also use the Meta key. If 'org-capture-use-agenda-date' is non-nil, capturing from the agenda will use the date at point as the default date. Then, a 'C-1' prefix will tell the capture process to use the HH:MM time of the day at point (if any) or the current HH:MM time.												
Archiving															
Archive current entry	C-c C-x C-a	(org-archive-subtree-default)	Move the current subtree inside an .org_archive file. The file has the same path and base name.												
Archiving Tree	🔗 Move tree to archive file														
Move current subtree to the archive	C-c C-x C-s	(org-archive-subtree &optional FIND-DONE)	Move the current subtree to the archive. - The archive can be a certain top-level heading in the current file, or in a different file. The tree will be moved to that location, the subtree heading be marked DONE, and the current time will be added. - C-u C-c C-x C-s : When called with a single prefix argument FIND-DONE, find whole trees without any open TODO items and archive them (after getting confirmation from the user). - C-u C-u C-c C-x C-s : When called with a double prefix argument, find whole trees with timestamps before today and archive them (after getting confirmation from the user). If the cursor is not at a headline when these commands are called, try all level 1 trees. If the cursor is on a headline, only try the direct children of this heading.												
Archiving - internal	🔗 Internal archiving														
Toggle archive tag for current headline	C-c C-x a	(org-toggle-archive-tag &optional FIND-DONE)	Toggle the archive tag for the current headline. C-u C-c C-x a : With prefix ARG, check all children of current headline and offer tagging the children that do not contain any open TODO items.												
Move the current entry to the Archive Sibling	C-c C-x A	(org-archive-to-archive-sibling)	Archive the current heading by moving it under the archive sibling. - The archive sibling is a sibling of the heading with the heading name 'org-archive-sibling-heading' and an 'org-archive-tag' tag. If this sibling does not exist, it will be created at the end of the subtree. - Archiving time is retained in the ARCHIVE_TIME node property.												
More information needed 🚧	The following rows do not contain valuable information. They are left over for future work. They will be removed soon and integrated with more information.🚧🚧🚧🚧🚧														
	S-<right>	(org-shiftright &optional ARG)	Act on the current element according to context. This does one of the following: - switch a timestamp at point one day into the future - on a headline, switch to the next TODO keyword - on an item, switch entire list to the next bullet type - on a property line, switch to the next allowed value - on a clocktable definition line, move time block into the future - in a table, move a single cell right												
	S-<left>	(org-shiftright &optional ARG)	Act on the current element according to context. This does one of the following: - switch a timestamp at point one day into the past - on a headline, switch to the previous TODO keyword. - on an item, switch entire list to the previous bullet type - on a property line, switch to the previous allowed value - on a clocktable definition line, move time block into the past - in a table, move a single cell left												
	S-<up>	(org-shiftup &optional ARG)	Act on current element according to context. Call 'org-timestamp-up' or 'org-priority-up', or 'org-previous-item', or 'org-table-move-cell-up'. See the individual commands belowfor more information.												
	S-<up>	(org-previous-item)	Move to the beginning of the previous item.												
	S-<up>	(org-table-move-cell-up)	Move a single cell up in a table. Swap with anything in target cell.												
	S-<down>	(org-shiftdown &optional ARG)	Act on current element according to context. Call 'org-timestamp-down' or 'org-priority-down', or 'org-next-item', or 'org-table-move-cell-down'. See the individual commands below for more information.												
	S-<down>	(org-next-item)	Move to the beginning of the next item.												
	S-<down>	(org-table-move-cell-down)	Move a single cell down in a table. Swap with anything in target cell.												

Org-Mode - Reference

Topic & link	Description
Org Mode @ Wikipedia	A good introduction to Org Mode concepts
 Org mode home and  The Org Manual	Org mode is actively developed. The Org Mode home page contains links to all you need.
Quick Reference for emacs Org-Mode key binds	
How to move a subtree to another subtree in org-mode emacs	Stack Overflow Q&A. Just to move the sub-tree itself (not its top level headline).
Command to copy and delete subtree in org-mode	Stack Overflow Q&A. Answer: C-C C-x C-w and C-c C-x C-y
Getting started with Org-Mode @ Youtube	
Literate DevOps with Emacs - youtube video	
David 'Otool Org Tutorial	
Hello Worg, the Org-Mode Community!	
Org Mode Tools	
Org-Mode Exporters - The New Org-mode Exporter Framework	
* ox.el @ github	
Pandoc support	
Pandoc-mode - An Emacs mode for interacting with Pandoc	
Org mode and Pandoc	
Keeping a lab notebook with org-mode, git, Papers, and Pandoc (Part II)	
Confluence Wiki Support for Org Mode	
https://www.emacswiki.org/emacs/ConfluenceMode	
confluence-el (10 years old)	
confluence-el : seems newer.	
ox-confluence - 2012-2014 : export org files to confluence using the ox.el	
sdelafond /org-confluence	That was integrated inside org-mode.
In org-mode, how do I export to JIRA wiki markup? @ StackExchange	
Clocking Work Time - The Org Manual	
Time Tracking in Emacs with org-clock	Short article written by David Charte , on November 2017.
Clocking time with Org-mode	Good description of the clocking time mechanism supported by org-mode. Written in April 2017 by Lee Hinman
Org Mode Time and Task Tools – Straightforward Emacs @YouTube	