

Inside vterm-mode

Description	Keystroke	Function	Note				
vterm-mode	📦 Emacs external vterm-mode provides “unparalleled performance and compatibility with standard command-line tools” (quote taken from vterm-mode) . 🔧 PEL activates it when the pel-use-vterm user-option is set to t. ⚠️ It requires Emacs >= 25.1 built with module support. • Also see: • The 🔗 Shells page for information on how to launch the various terminal shells. • The 🔧 Shells/Terminals Comparisons which compares the features of these terminal shells.						
Last updated on:	2026-09-20						
• PEL help commands	As described below, most Emacs key bindings are disabled in vterm-mode . With PEL, when pel-use-vterm and pel-vterm-supports-f12-keys user-options are both t , the following key sequences using <f12> prefix are bound to the identified PEL commands. • These bindings are not available in the term-copy-mode though.						
Open this PDF file. See also: 🔗 Help/Info	<f11> SPC z v <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the 🔗 vterm-Mode local PDF. With C-u , M-- , M- -1 or C- -1 prefix: open the remote GitHub hosted PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.				
	<f12> <f1>						
🔗 Customize PEL vterm management control	<f11> SPC z v <f2>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL vterm support	• If the prefix argument is non-nil (like C-u or M--) , display in other window.			
	<f12> <f2>						
🔗 Customize Emacs vterm control	<f11> SPC z v <f3>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs shell support: vterm	• If the prefix argument is non-nil (like C-u or M--) , display in other window.			
	<f12> <f3>						
• Navigation	With PEL, when pel-use-vterm and pel-vterm-supports-f12-keys and pel-vterm-supports-f12-navkeys user-options are all set to t , following						
Move point to previous prompt	<f12> <up>	(pel-shell-previous-prompt)	Move point to the previous prompt line.		• Use the pel-shell-prompt-line-regexp user-option to identify what to search.		
Move point to next prompt	<f12> <down>	(pel-shell-next-prompt)	Move point to the next prompt line.		• Use the pel-shell-prompt-line-regexp user-option to identify what to search.		
• Switch Mode	⚠️ By default, vterm-mode passes all key bindings directly to the inferior (sub) shell process and therefore will not allow access to any of the Emacs key binding except for one: C-c C-t, used to activate the vterm-copy-mode minor-mode where Emacs key bindings are working. When active the mode-line shows VTermCopy.						
Toggle vterm-copy-mode	C-c C-t	(vterm-copy-mode &optional ARG)	Toggle ‘vterm-copy-mode’.		• This is a minor mode. If called interactively, toggle the ‘Vterm-Copy mode’ mode. If the prefix argument is positive, enable the mode, and if it is zero or negative, disable the mode.	When ‘ vterm-copy-mode ’ is enabled, the terminal will not display additional output received from the underlying process and will behave similarly to buffer in ‘fundamental-mode’. This mode is typically used to copy text from vterm buffers or to use other Emacs key bindings.	
Open file at point See: 🔗 File-mngt	Then result of some commands, like compilation, build, or other, may generate a message that identifies a file with line number and possibly column number. With. PEL, you can use the pel-open-at-point command to open the file at the specified location and the pel-set-open-at-point-dir-home to establish the root directory. These commands are described in the 🔗 File-mngt page. A partial copy of the information is placed here for convenience.						
Set base directory for pel-open-at-point relative file names See: 🔗 File-mngt	<f11> f ;	(pel-set-open-at-point-dir-home)	Set the behaviour of ‘ pel-open-at-point ’ in current buffer . Which defaults to value selected by pel-open-file-at-point-dir-home user-option.				
			• Select method used to determine the directory from which a relative file name is built from following methods:		• Use visited file parent directory (the default).	• Use buffer's current working directory.	• Use a specified directory. Prompts for the directory name. Supports completion.
Open file or web-page whose name is at point ★★ See: 🔗 File-mngt	• M-* • <f11> f . • <u>6y</u>	(pel-open-at-point &optional N)	Open the file, library or the URL, named at point, with potential line & column #s.		• If necessary will search source code files in current project as specified by pel-filename-at-point-finders user-option. Type <f12> <f4> ? to show used file search method in supporting modes.	🌐 Supports glob characters, partial directory path. When multiple files are found it prompts using the method selected by pel-prompt-read-method user-option.	📦🔧 The <u>6y</u> key-chord is available if pel-use-key-chord is non-nil. See 🔗 Key-Chords .