Ping Identity™

PingDirectory®

OID Compatibility Plugin v1.0.0

User Guide



© 2005-2018 Ping Identity ® Corporation. All rights reserved.

PingDirectory OID Compatibility Plugin User Guide Version 1.0.0 February 2018

Ping Identity Corporation 1001 17th Street, Suite 100 Denver, CO 80202 USA

Phone: 877.898.2905 (+1 303.468.2882 outside North America)

Fax: 303.468.2909 E-mail: info@pingidentity.com

Web Site: http://www.pingidentity.com

Trademarks

Ping Identity, the Ping Identity logo and PingDirectory are registered trademarks of Ping Identity Corporation ("Ping Identity"). All other trademarks or registered trademarks are the property of their respective owners.

Disclaimer

This document is proprietary and not for general publication. It may be provided ad hoc for informational purposes only, and the information herein is subject to change without notice. Ping Identity does not provide any warranties and specifically disclaims any liability in connection with this document.

Note that Ping Identity may not provide support for any sample configurations provided in this document. The variability inherent among security environments prevents full testing and support for all possible platform configurations. If you need special assistance or would like to inquire about implementation or support programs, please contact Ping Identity Global Client Services (http://support.pingidentity.com).

Table of Contents

Purpose	 	
Prerequisites	 	
Installation		

Purpose

The "OID Compatibility" Plugin allows PingDirectory to provide OID compatibility for BIND result codes in case an account is locked or disabled.

Prerequisites

This document assumes that a functional PingDirectory, Version 6.*, has already been installed and configured.

Installation

- 1. Copy the included zip file to a temporary location on the server that is running PingDirectory.
- 2. Open a terminal window.
- 3. Change directories to the installation path of the target PingDirectory server.
- 4. Execute the "manage-extension" command in the bin directory of the installation path to install the zip file and follow any prompts to continue and restart the server:

```
bin/manage-extension --install <path to the zip file>
```

5. Execute the "dsconfig" command in the bin directory of the installation path to configure the plugin and press "f" at the prompt to finish the configuration of the plugin:

```
bin/dsconfig create-plugin \
--plugin-name "OID Compatibility Custom Plugin" \
--type third-party \
--set enabled:true \
--set plugin-type:postoperationbind \
--set invoke-for-internal-operations:false \
--set extension-class:com.pingidentity.ps.ds.plugin.OIDCompat \
--set extension-argument:account-disabled-message=<Message> \
--set extension-argument:account-disabled-code=<Code> \
--set extension-argument:account-failure-locked-message=<Message> \
--set extension-argument:account-failure-locked-code=<Code> \
--set extension-argument:account-reset-locked-message=<Message> \
--set extension-argument:account-reset-locked-code=<Code> \
--set extension-argument:account-expired-message=<Message> \
--set extension-argument:account-expired-code=<Code> \
--set extension-argument:account-not-yet-active-message=<Message> \
--set extension-argument:account-not-yet-active-code=<Code> \
--set extension-argument:account-idle-locked-message=<Message> \
--set extension-argument:account-idle-locked-code=<Code>
```

For each locked or disabled BIND result {disabled, failure locked, reset locked, expired, not yet active and idle locked}, the custom response can be configured as follows:

• 'account-*-message' is an optional argument and specifies the message to return to the client.

• 'account-*-code' is an optional argument and specifies the numerical code to return to the client.

Note that all arguments are optional, however, if the plugin is configured for a specific locked or disabled BIND result, both the message and code for that specific result must be defined.

6. Optional: To enable Server Extension debug messages, execute the following command:

```
bin/dsconfig set-log-publisher-prop \
   --publisher-name "Server SDK Extension Debug Logger" \
   --set enabled:true
```

7. Optional: To delete the plugin, execute the following command:

bin/dsconfig delete-plugin --plugin-name "OID Compatibility Custom Plugin"