Statistical Mechanics, Lecture notes

Università degli Studi di Torino
Academic Year 2026/2027
Prof. Billò, notes by Paolo Rocchietti March[1]

---

[1] paolo.rocchiettimarc@edu.unito.it

Contents

Lesson 1, 23/09 **3**

Thermodynamics **3**

Lesson 2, 29/09 **3**

1 Internal Energy as a TD potential **3**

2 Legendre Transform **3**

3 Response Functions **4**

4 Mechanical response functions **5**

5 Maxwell Relations **5**

6 Stability of equilibrium state **6**

Lesson 3, 30/09 **6**

7 Equilibrium in external field **7**

8 Second order equilibrium **7**

9 Multi-component systems **9**

10 Phase transitions **9**
10.1 First order transitions 10

Lesson 4, 09/10 **10**
10.2 Continuous transitions 12

11 Maxwell construction **13**

Lesson 5, 07/10 **13**

12 Coexistence of many phases **14**

13 Gibbs rule **14**

Statistical Mechanics **15**

14 Statistical approach to TD **15**

15 Observables **15**

Lesson 1, 23/09

Thermodynamics

VEDI APPUNTI TABLET

Lesson 2, 29/09

1 Internal Energy as a TD potential

[10 min. cfr with notes pt 2 on moodle/Remi] $N = const.$

2 Legendre Transform

What if the control variables are the intensive ones, e.g. system in a thermostat? It is useful to use T instead of S: the mathematical tool used is the *Legendre transform* (the one used to transform $L(q, \dot{q}) \to H(q, p)$, using $p = \frac{\partial L}{\partial \dot{q}}$)

$$E(S, V, N, X) \to F(T, V, N, X) := E(S, V, N, X) - TS$$

where S is found by inverting the relation $T = \frac{\partial E}{\partial S}$. F is the Helmholtz free energy

Using the fundamental equation of TD

$$E = TS - pV + \mu N + yX$$

the function F can also be written as

$$F = -pV + \mu N + yX :$$

differentiating this yields

$$\mathrm{d}F \leq -S\mathrm{d}T - p\mathrm{d}V + \mu\mathrm{d}N + y\mathrm{d}X$$

so keeping fixed T, V, N, X, the equilibrium is at minimal F.

What are the conjugated variables? As always

$$S = -\frac{\partial F}{\partial T}$$
$$p = -\frac{\partial F}{\partial V}$$
$$\mu = \frac{\partial F}{\partial N}$$

This process can be done with every intensive variable e.g. enthalpy:

$$E(S, V, N, X) \underset{p=-\frac{\partial E}{\partial V}}{\longrightarrow} H(S, p, N, X) := E(S, V, N, X) + pV$$

and

$$H = TS + \mu N + yX \underset{\text{d and fund. eq.}}{\longrightarrow} \mathrm{d}H \leq T\mathrm{d}S + v\mathrm{d}p + \mu\mathrm{d}N + y\mathrm{d}X$$

so fixing S, p, N, X, the equilibrium is at minimal H.

Doing this with respect to both couples (T, S) and (p, V) yields the Gibbs free energy:

$$G(T, p, N, X) = E(S, V, N, X) - TS + pV$$

using the fundamental equation yields

$$G = \mu N + yX$$

Note In simple systems (without (y, X)) $G = \mu N$. The differential is

$$\mathrm{d}G \leq -S\mathrm{d}T + V\mathrm{d}p + \mu\mathrm{d}N + y\mathrm{d}X$$

that shows that, fixing T, p, N, X, equilibrium is at minimal G.

The last Legendre Transform of interest is the one that yields the *Grand Canonical potential*:

$$E(S, V, N, X) \underset{(T,S),(\mu,N)}{\longrightarrow} \bar{\omega}(T, V, \mu, X) = E(S, V, N, X) - TS - \mu N$$

The fundamental equation yields

$$\bar{\omega} = -pV + yX$$

and differentiating yields

$$\mathrm{d}\bar{\omega} \leq -S\mathrm{d}T - p\mathrm{d}V - N\mathrm{d}\mu + y\mathrm{d}X$$

so the equilibrium is at the minimum of $\bar{\omega}$.

The pressure is simply

$$p = -\frac{\partial\bar{\omega}}{\partial V} = -\frac{\bar{\omega}}{V}$$

3 Response Functions

These functions describe the reaction of variables when another one changes (typically conjugated variables), are very easy to measure and they are deeply connected to the size of the fluctuations of the system (Fluctuation-dissipation theorem).

Def. Heat capacity

$$C = \frac{\delta Q}{\mathrm{d}T}$$

is the amount of heat to be furnished to change the T; it is not an exact differential, so it depends on the transformation.
Heat capacity at constant (V, N): if $\mathrm{d}V = \mathrm{d}N = \mathrm{d}X = 0 \to \delta W = 0$; by the first principle

$$\delta Q = \mathrm{d}E$$

so

$$C_{V,N,X} = C_V = \frac{\delta Q}{\mathrm{d}T} = \left.\frac{\partial E}{\partial T}\right|_{V,N,X}$$

or, using the definition of entropy

$$\delta Q = T\mathrm{d}S$$

and fixing (V, N, X)

$$\mathrm{d}S = \left.\frac{\partial S}{\partial T}\right|_{V,N,X}\mathrm{d}T$$

so

$$C_V = \frac{T\mathrm{d}S}{\mathrm{d}T} = T\left(\frac{\partial S}{\partial T}\right)_{V,N,X}.$$

A more natural approach springs from the Helmholtz free energy:

$$S = -\left.\frac{\partial F}{\partial S}\right|_{V,N,X} \to C_V = -T\frac{\partial^2 F}{\partial T^2}$$

Heat capacity at constant (p, N, X): the first principle states

$$\delta W = p\mathrm{d}V \to \delta Q = \mathrm{d}E + p\mathrm{d}V$$

so

$$C_p = \frac{\delta Q}{\mathrm{d}T} = \left.\frac{\partial E}{\partial T}\right|_{p,V,X} + p \left.\frac{\partial V}{\partial T}\right|_{p,V,X}$$

but also

$$E = G + TS - pV = G - T\frac{\partial G}{\partial T} - pV$$

so

$$C_p = \frac{\partial}{\partial T}\left(G - T\frac{\partial G}{\partial T} - pV\right) + p\frac{\partial V}{\partial T} = -T\left.\frac{\partial^2 G}{\partial T^2}\right|_{p,N,X}$$

4 Mechanical response functions

Susceptibility χ is the volume response to a change in pressure: this also varies depending on the transformation.

Isothermal: fixing (T, N, X)

$$\chi_T := -\left.\frac{\partial V}{\partial p}\right|_{T,N,X}$$

since the variables are (T, p, N, X), with only p independent, the most natural TD potential to use is G: some calculations show that

$$\chi_T = -\left.\frac{\partial^2 G}{\partial p^2}\right|_{T,N,X}$$

Adiabatic: fixing (S, N, X)

$$\chi_S = -\left.\frac{\partial V}{\partial p}\right|_{S,N,X}$$

the TD potential is the enthalpy H:

$$V = \left.\frac{\partial H}{\partial p}\right|_{S,N,X} \to \chi_S = \left.\frac{\partial^2 H}{\partial p^2}\right|_{S,N,X}$$

All these response functions are between conjugated variables: what happens if they are not? Consider the Thermal expansion coefficient

$$\alpha_{p,N,X} = \alpha_p = \left.\frac{\partial V}{\partial T}\right|_{p,N,X} \underset{\text{exercise}}{=} \left.\frac{\partial^2 G}{\partial p \partial T}\right|_{p,N,X}$$

5 Maxwell Relations

These are relations between TD quantities: consider the set of independent variables

$$\{Z_A\}$$

their conjugated variables

$$\{\xi_A\}$$

and a TD potential

$$\mathrm{d}\Phi = \sum \xi_A \mathrm{d}Z_A$$

it follows that

$$\frac{\partial \xi_A}{\partial Z_B} = \frac{\partial^2 \Phi}{\partial Z_A \partial Z_B} = \frac{\partial^2 \Phi}{\partial Z_B \partial Z_A} = \frac{\partial \xi_B}{\partial Z_A}$$

from other mathematical properties (like the "chain rule", see Billò notes) arise other relations. One finds

$$\frac{1}{T} C_p > \frac{1}{T} C_V + \frac{\alpha_p^2}{\chi_T}$$

6 Stability of equilibrium state

Even at equilibrium, at maximum S, there can be small fluctuations in TD variables. For all such fluctuations, the entropy **must decrease** to ensure stability.

What are the conditions for local equilibrium? Consider an isolated system at equilibrium subdivided in 2 parts, which can exchange particles and heat.

$$E = E_1 + E_2$$
$$V = V_1 + V_2$$
$$N = N_1 + N_2$$

Suppose some fluctuation occurs in E_i, V_i, N_i: the other part of the system must have an opposite fluctuation

$$\Delta E_2 = -\Delta E_1 ...$$

Assuming small fluctuations, the variation of S at first order is

$$\Delta S = \sum_{i=i}^{2} \left(\left.\frac{\partial S_i}{\partial E_i}\right|_{\text{eq}} \Delta E_i + \left.\frac{\partial S_i}{\partial V_i}\right|_{\text{eq}} \Delta V_i + \left.\frac{\partial S_i}{\partial N_i}\right|_{\text{eq}} \Delta N_i \right) = \left(\frac{1}{T_1^{\text{eq}}} - \frac{1}{T_2^{\text{eq}}} \right) \Delta E_1 + \left(\frac{p_1^{\text{eq}}}{T_1^{\text{eq}}} - \frac{p_2^{\text{eq}}}{T_2^{\text{eq}}} \right) + ...$$

Since $\Delta S \leq 0$, it must be that all the quantities are equal

$$T_1^{\text{eq}} = T_2^{\text{eq}} ...$$

Iterating this process for smaller and smaller partitions of the system proves that, unsurprisingly, at first order

$$\Delta S = 0.$$

The chemical potential condition

$$\mu_1^{\text{eq}} = \mu_2^{\text{eq}}$$

guarantees chemical equilibrium: supposing an isolated system with $\delta Q = \delta W = 0$, $\Delta S > 0$ and

$$\Delta S \approx -\left(\frac{\mu_1}{T_1} - \frac{\mu_2}{T} \right) \Delta N_1 > 0$$

so if $\mu_1 > \mu_2$ it must be that

$$\Delta N_1 < 0,$$

in other words, matter flows from higher to lower μ.

The quantity

$$-\boldsymbol{\nabla} \left(\frac{\mu}{T} \right)$$

is a generalized force (see first lesson), much like $\boldsymbol{\nabla} \left(\frac{1}{T} \right)$.

Lesson 3, 30/09

7 Equilibrium in external field

The TD system is often subject to external forces, like gravity: how can equilibrium be described in this case?

Consider a TD system and subdivide it into smaller systems s.t they are still TD systems with a large number of particles: the coordinates of the portion is $\mathbf{x}$.

Since μ is the energy needed to add particles to the system, the control variables used are T, p, N: from the definition of G

$$\mu = \frac{G}{N}$$

and from the fundamental equations

$$\frac{\partial \mu}{\partial p} = \frac{1}{N}\frac{\partial G}{\partial p} := \frac{V(T,p,N)}{N} = v(T,p)$$

where v is the volume per particle.

The chemical potential consists of two parts

$$\mu(T,p;\mathbf{x}) = \mu_0(T,p) + u(\mathbf{x})$$

where μ_0 is μ with the external field turned off and u is related to the field.

At the equilibrium, one expects that T remains constant, p depends on $\mathbf{x}$ (like the Stevino law) and μ remains constant and homogeneous.

These conditions translate to

$$\frac{\partial \mu}{\partial x^i} = 0 = \frac{\partial \mu}{\partial p}\cdot\frac{\partial p}{\partial x^i} + \frac{\partial u}{\partial x^i}$$

so

$$v(T,p)\frac{\partial p}{\partial x^i} + \frac{\partial u}{\partial x^i}.$$

Example: gravity In this case $u(\mathbf{x}) = mgz$, so

$$\frac{\mathrm{d}p}{\mathrm{d}z} v(T,p) = -mg$$

so v does not depend on T, adding the incompressibility of the fluid imposes constant v, so

$$\frac{\mathrm{d}p}{\mathrm{d}z} = -\frac{m}{v}gz = -\rho g z \to p(z) = p_0 - mgz$$

in the case of an ideal gas, using $pv = k_b T$ yields (prove it as an exercise)

$$p(T,z) = p_0 \exp\left[-\frac{mg}{kT}z\right]$$

8 Second order equilibrium

It was found that, at first order

$$T, p, \mu \text{ are homogeneous}$$
$$\Delta S = 0$$

To discuss the second order fluctuations, it is needed to re-express everything in terms of TD potentials: consider the control variables

$$\left\{ \underbrace{X_1, \dots X_r}_{\text{extensive}}; \underbrace{I_{r+1}, \dots I_n}_{\text{intensive}} \right\}$$

and the potential

$$\Phi(X_i; I_j) :$$

its differential is

$$\mathrm{d}\Phi = \sum_{i=1}^{r} I_i \mathrm{d}X_i - \sum_{j=r+1}^{n} X_j \mathrm{d}I_j$$

Note This generalizes the problem to have r extensive control variables and $r - n$ (?) intensive control variables.

Consider a TD system subdivided in two parts and a fluctuation in the extensive variables:

$$\delta X_i = \delta X_{i,1} + \delta X_{i,2} = 0$$

at first order

$$\Delta\Phi^{(1)} = \sum_{i=1}^{r} \left[\left(\frac{\partial \Phi}{\partial X_i} \right)_1 - \left(\frac{\partial \Phi}{\partial X_i} \right)_2 \right] \delta X_{i,1} \geq 0$$

As before, the only way to ensure this condition is

$$\left(\frac{\partial \Phi}{\partial X_i} \right)_1 = \left(\frac{\partial \Phi}{\partial X_i} \right)_2 \leftrightarrow I_{i,1} = I_{i,2}$$

with finer partitions this means that the intensive variables conjugated to the extensive control variables are homogeneous in the system, at leas at first order.

To get a non-trivial result, consider the second order of fluctuation of a single variable X_i (i.e. considering the fluctuations independent):

$$\Delta\Phi^{(2)} = \frac{1}{2} \left[\left(\frac{\partial^2 \Phi}{\partial X_i^2} \right)_1 + \left(\frac{\partial^2 \Phi}{\partial X_i^2} \right)_2 \right] (\delta X_{i,1})^2 \geq 0$$

where the minus sign was destroyed by the square; this statement is true only if

$$\frac{\partial^2 \Phi}{\partial X_i^2} = \frac{\partial I_i}{\partial X_i} \geq 0$$

from this follows that

$$\frac{\partial X_i}{\partial I_i} \geq 0$$

and, remembering the Legendre transform

$$\Phi(..., X_i, ...) \to \tilde{\Phi}(..., I_i ...) \leftrightarrow X_i = -\frac{\partial \tilde{\Phi}}{\partial I_i}$$

this gives

$$\frac{\partial^2 \tilde{\Phi}}{\partial I_i^2} \leq 0$$

This gives a geometric condition on the TD potentials at equilibrium: they are either a concave function of intensive variables or convex functions of extensive variables (or vice-versa **CHECK!!!!!!!**) **Example** Consider the Helmholtz free energy: the stability condition implies that

$$\frac{\partial^2 F}{\partial T^2} \leq 0$$

but

$$C_V = -T \frac{\partial^2 F}{\partial T^2} \to C_V \geq 0$$

and also

$$\underbrace{\frac{\partial^2 F}{\partial V^2}}_{\geq 0} = -\frac{\partial p}{\partial V} = -\frac{1}{\frac{\partial V}{\partial p}} = \frac{1}{\chi_T} \geq 0 \leftrightarrow \chi_T \geq 0$$

Example Consider the Gibbs energy $G(T, p, N)$:

$$\frac{\partial^2 G}{\partial T^2} \leq 0$$

and the C_p definition

$$C_p = -T\frac{\partial^2 G}{\partial T^2} \geq 0.$$

Again the χ_T definition is

$$\chi_T = -\underbrace{\frac{\partial^2 G}{\partial p^2}}_{\leq 0} \geq 0$$

which is consistent with the previous example.

From the relation

$$C_p = C_V + \frac{T\alpha_p^2}{\chi_T}$$

and the stability conditions discussed it follows that, in general

$$C_p \geq C_V$$

9 Multi-component systems

Some TD systems have different components mixed (e.g. the atmosphere), indexed with $a = 1, 2...c$ so the chemical potential is not unique: μ_a, N_a and these potentials depend separately from those variables (which vars???)

$$\mathrm{d}E = T\mathrm{d}S - p\mathrm{d}V + \sum_{a=1}^{c} \mu_a \mathrm{d}N_a + y\mathrm{d}X$$

Each potential has its own equilibrium condition $\mu_{a,1} = \mu_{a,2}$ and intensive variables depend only on $c - 1$ ratios

$$\nu_a = \frac{N_a}{N}$$

with the constraint

$$\sum_{a=1}^{c} N_a = N \leftrightarrow \sum_{a=1}^{c} \nu_a = 1$$

10 Phase transitions

This topic is very difficult to treat mathematically and one of the most important results of statistical mechanics is the description of this phenomenon.

What are the conditions of coexistence of different phases of matter in equilibrium (e.g. ice and water)? At equilibrium, the state of the TD system is characterized by E, V, N: it is not necessary that at equilibrium state these variables are homogeneous.

Each different phase (each defined by its state equation) of the system has its set of variables p_i, T_i, μ_i.

If the state is equilibrium, the intensive variables must be homogeneous:

$$p_1 = p_2, \quad T_1 = T_2, \quad \mu_1 = \mu_2$$

it is then natural to take p, T as control variables, making μ a dependent variable; since the phases have different equations of state, the potentials will be different: for the phase α

$$G_\alpha(T, p, N_\alpha) = \mu_\alpha N_\alpha \to \mu_\alpha = \frac{G_\alpha}{N_\alpha}.$$

The phases can only coexist on *curves of coexistence* in the state space: for generic values of p, T, $\mu_\alpha \neq \mu_\beta$ and so the phases do not coexist and, considering N constant, the system "selects" the phase which minimizes

$$\mu = \frac{G}{N}.$$

So phases α and β coexist if and only if the values of p, T are so that

$$\mu_\alpha(p, T) = \mu_\beta(p, T)$$

which typically is a curve $p(T)$ in the state space. When this curve is crossed, a phase transition occurs and it can be of two natures.

10.1 First order transitions

The coexistence curve is determined by the intersection of the surfaces $\mu_\alpha(T, p)$ and $\mu_\beta(T, p)$. In general, the value of the derivatives differ at the intersection point(s): fixing p they are

$$\left(\frac{\partial \mu_\alpha}{\partial T}\right)_p = \frac{1}{N_\alpha}\left(\frac{\partial G}{\partial T}\right)_p = -\frac{S_\alpha}{N_\alpha} := -s_\alpha$$

which is the entropy per particle, so in general

$$s_\alpha \neq s_\beta$$

Suppose $s_\alpha > s_\beta$: for $T = T(p) - \varepsilon$, $S_{(-)} = N s_\beta$, while for $T = T(p) + \varepsilon$, $S_{(+)} = N s_\alpha$; in this case the transition from β to α makes the entropy jump of

$$\Delta S = N(s_\alpha - s_\beta) > 0$$

this is nothing but the effect of latent heat, the heat to be furnished to the system just to do a phase transition

$$L = T(p)\Delta S.$$

From an enthalpy p.o.v,

$$H(S, p, N) = G + TS$$

since $\mu_\alpha = \mu_\beta$, $\Delta G = 0$ and so

$$\Delta H = \Delta(TS) = T\Delta S = L.$$

This is similar for fixed temperature transitions, with derivative

$$\left(\frac{\partial \mu}{\partial p}\right)_{T,N} = \frac{V}{N} = v$$

which is the volume per particle; so in general $v_\alpha \neq v_\beta$ and the volume of the system changes during the transition *even at constant pressure* (e.g. ice melting).

Lesson 4, 09/10

[...] qualcosa su T fissata, $p = p(T) \pm \varepsilon$ usando G si vede che c'è un ΔV

How can the shape of the transition curve $p(T)$ be determined? With the *Clausius-Clapeyron equation.*

Recall that

$$\mu(T,p) = \frac{G}{N} \quad \mathrm{d}\mu = -s\mathrm{d}T + v\mathrm{d}p$$

and this has to be satisfied at each point on the curve: consider the infinitesimal change in μ along the curve

$$\mu_\alpha \to \mu_\alpha + \mathrm{d}\mu_\alpha$$
$$\mu_\beta \to \mu_\beta + \mathrm{d}\mu_\beta$$

since $\mu_\alpha = \mu_\beta$ at all points,

$$\mathrm{d}\mu_\alpha = \mathrm{d}\mu_\beta$$

substituting yields

$$-s_\alpha \mathrm{d}T + v_\alpha \mathrm{d}p = -s_\beta \mathrm{d}T + v_\beta \mathrm{d}p$$

which implies

$$\frac{\mathrm{d}p}{\mathrm{d}T} = \frac{\Delta s}{\Delta v} = \frac{\Delta S}{\Delta V}$$

in terms of the latent heat $L = T\Delta S$ it can be written as

$$\frac{\mathrm{d}p}{\mathrm{d}T} = \frac{L}{T\Delta V} = \frac{1}{T}\frac{l}{\Delta v} = \frac{1}{T}\frac{l_{\mathrm{mol}}}{\Delta v_{\mathrm{mol}}} = \frac{1}{T}\frac{l_{\mathrm{sp}}}{\Delta v_{\mathrm{sp}}}$$

where $l = \frac{L}{N}$ is the latent heat per particle, l_{mol} is the molar latent heat and l_{sp} is the specific latent heat (J/kg).

Example water to ice transition
In standard conditions, $p_{\mathrm{atm}} = 101325$ Pa, $T_0 = 273.15$ K, the transition is possible and, contrary to many substances, water is denser than ice: the variation of specific volume for the transition is

$$\Delta v_{\mathrm{sp}} = v_{\mathrm{sp}}^{\mathrm{ice}} - v_{\mathrm{sp}}^{\mathrm{water}} = 9 \cdot 10^{-5} \text{ m}^3/\text{kg}$$

and the specific latent heat is

$$l_{\mathrm{sp}} = 2.3 \cdot 10^5 \text{ J/kg}$$

The question is, how much pressure is needed to melt the ice at temperature $T_0 - 1$ K?

In this case, $1 \text{ K} = \Delta T << T_0$ and the C-C equation becomes

$$\frac{\mathrm{d}p}{\mathrm{d}T} = \frac{1}{T}\frac{l_{\mathrm{sp}}}{\Delta v_{\mathrm{sp}}} \to \frac{\Delta p}{\Delta T} = \frac{1}{T}\frac{l_{\mathrm{sp}}}{v_{\mathrm{sp}}} \to \Delta p = \frac{\Delta T}{T_0}\frac{l_{\mathrm{sp}}}{\Delta v_{\mathrm{sp}}} \approx 10^7 \text{ Pa}$$

Example vapour at saturation
When the liquid and gas phases coexist, the vapour is at saturation; this is a first order transition in which $l > 0$ and $v_{\mathrm{gas}} >> v_{\mathrm{liquid}}$, so $\Delta v \approx v_{\mathrm{gas}}$. The C-C equations takes form as

$$\frac{\mathrm{d}p}{\mathrm{d}T} = \frac{l}{T v_{\mathrm{gas}}}$$

assuming a perfect gas that satisfies the ideal state equation

$$pV = NkT \to p v_{\mathrm{gas}} = kT$$

the equation becomes

$$\frac{\mathrm{d}p}{\mathrm{d}T} = \frac{l}{T}\frac{p}{kT} \to \frac{\mathrm{d}p}{p} = \frac{l}{k}\frac{\mathrm{d}T}{T^2} \to \ln\left(\frac{p}{p_0}\right) = -\frac{l}{k}\left(\frac{1}{T} - \frac{1}{T_0}\right)$$

so the form of the transition curve is an exponential

$$p(T) = p_0 \exp\left[-\frac{l}{k}\left(\frac{1}{T} - \frac{1}{T_0}\right)\right]$$

What about the pV plane? Since the control variables can always be chosen, it should not be fundamentally different: consider a coexistence curve with a point $(p(T_0), T_0)$ and $\frac{\mathrm{d}p}{\mathrm{d}T} > 0$ and a transition at constant T and decreasing p; the transition follows an isothermal curve in the pV plane, then at $p(T_0)$ it becomes "isobara" while the volume changes, this is the coexistence curve, and finally it becomes isothermal again. Consider the coexistence curve: during the "isobara"

$$V = N_\alpha v_\alpha \underset{\text{"isobara"}}{\longrightarrow} V = N_\alpha v_\alpha + N_\beta v_\beta \to v = \nu_\alpha v_\alpha + \nu_\beta v_\beta$$

where $\nu_i = N_i/N$; from this follows

$$v - v_\alpha = \nu_\beta(v_\beta - v_\alpha)$$

and

$$v_\beta - v = \nu_\alpha(v_\beta - v_\alpha)$$

their quotient yields

$$\frac{v - v_\alpha}{v_\beta - v} = \frac{\nu_\beta}{\nu_\alpha}$$

Considering all the different values of T shows that in the pV plane the coexistence happens in a 2D region instead of a curve.

v_α and v_β are implicitly determined by

$$\begin{cases} p_\alpha = p_\beta \\ \mu_\alpha = \mu_\beta \end{cases}$$

In terms of free energy per particle $f = F/N$, $p = -\frac{\partial f}{\partial v}$: since p is constant in the phase transition, $f(v)$ is linearly decreasing with slope

$$-p = \frac{f_\alpha - f_\beta}{v_\beta - v_\alpha}$$

so

$$f_\beta - f_\alpha = -p(v_\beta - v_\alpha) \to (f + pv)_\alpha = (f + pv)_\beta$$

recalling that F is related with a Legendre transform to the Gibbs free energy G,

$$f + pv = G/N = \mu$$

it implies

$$\mu_\alpha = \mu_\beta.$$

It can be shown that

$$f(v) = \nu_\alpha f_\alpha + \nu_\beta f_\beta$$

10.2 Continuous transitions

In this case the first derivatives of μ are continuous and that means

$$\Delta S = 0 \quad \Delta V = 0$$

and the discontinuity is at higher orders. Typically the coexistence in the plane p, T is represented by single points, as opposed to curves for first order transitions: these are called *critical points* and usually they are endpoints of first order transitions.

11 Maxwell construction

Suppose to know an approximated empirical equation of state for some system

$$p = p(V, T)$$

that in some regions *does not* obey the stability conditions, i.e. in some regions, at constant temperature,

$$\left.\frac{\partial p}{\partial V}\right|_{T,N} > 0$$

this is not possible and means that the equation of state is wrong, but suppose it works well in other regions: how can this be corrected?
There is a method to connect "good" regions with one another, due to Maxwell, that consists in supposing that the "bad" region represents a phase transition: for example connecting two points in the pV plane with a straight line at $p = \bar{p}$; this connection must be between two points V_1, V_2 so that the free energy at those points is the same as the one determined by the equation of state.

$$\mathrm{d}F = -S\mathrm{d}T - p\mathrm{d}V + \mu\mathrm{d}N$$

fixing T, N this becomes

$$F(V_2, T, N) - F(V_1, T, N) = -\int_{V_1}^{V_2} \mathrm{d}V p(V, T, N)$$

On the contrary, for the "isobara" the difference in free energy is

$$F(V_2, T, N) - F(V_1, T, N) = \bar{p}(V_2 - V_1)$$

so the condition is

$$\bar{p}(V_2 - V_1) = \int_{V_1}^{V_2} \mathrm{d}V p(V, T, N)$$

Example: Van Deer Waals
The VdW equation considers intermolecular interactions with a potential "wall" at distance d and for $r > d$ a $\sim -\frac{1}{r}$ potential: this is a good approximation of the real potential that governs intermolecular interactions; this also determines an effective volume

$$V_{\text{eff}} = V - b$$

as the single molecule's "volume" is $\sim d^3$ and this volume is unavailable for the rest of the system. The well after distance d forms bound states, which lowers the kinetic pressure:

$$p = p_{\text{kin}} - \frac{a}{V^2}$$

this defect in pressure is proportional to V^{-2} (why?).

The last hypothesis is that the kinetic pressure and the effective volume follow the ideal gas law

$$p_{\text{kin}} V_{\text{eff}} = nRT$$

substituting yields the VdW equation of state

$$\left(p + \frac{a}{V^2}\right)(V - b) = nRT$$

since $p(V)$ is approximately dependent on V^{-3}, some isothermals are non-physical, since they present horizontal flex points.

Lesson 5, 07/10

These non-physical isothermals appear under a critical temperature T_c, determined by the parameters a, b.

[equation of correspondent states]

12 Coexistence of many phases

Consider a p, V, T system with 1 type of component: at most three phases can coexist, because the equality of the chemical potentials depends only on 2 variables p, T, so only 2 conditions can have a single solution

$$\begin{cases} \mu_\alpha(p,T) = \mu_\beta(p,T) \\ \mu_\beta(p,T) = \mu_\gamma(p,T) \end{cases}.$$

The 3 phases can coexist at most in single points, called *triple points*.

Example: triple point of water




Fig. 12.1: The phase diagram of water.

The liquid-gas transition is continuous, but the coexistence line has an end, this means that their distinction is well-defined only "close" to the first order transition and that they are not so different from each other (they share the same symmetry in structure); at the critical point there usually is a partial symmetry breaking.

13 Gibbs rule

This is a statement about the number of phases that can coexist in multi-component systems.
Consider a system with c components (indexed by $i = 1, 2..c$), which presents f phases at equilibrium (indexed by $\alpha = 1, 2...f$); the portion of particles of type i in phase α is denoted by $\nu_{i,\alpha}$. For all α, it is true that

$$\sum_{i=1}^{c} \nu_{i,\alpha} = 1$$

so these are $f \cdot (c-1)$ constraints.
Moreover, for every component i the chemical potentials for each phase must be the same

$$\mu_{i,1}(T, p, \nu_{1,1}, ...\nu_{c-1,1}) = \mu_{i,2}(...) = \mu_{i,3} = ... = \mu_{i,f}$$

these are $f-1$ independent equations for every i, so these are $c(f-1)$ constraints.

So in total, the independent variables are $2 + c - f$ and this number must be positive, so the Gibbs rule states that

$$2 + c - f \geq 0$$

Statistical Mechanics

14 Statistical approach to TD

Thermodynamic systems contain very large numbers of particles, $N \sim \mathcal{N}_A \sim 10^{23}$, so the possible states are characterized by a large number of quantum numbers/canonical coordinates ($6N$ for point-like classic particles).
Example For quantum harmonic oscillators the microstates can be determined by the 3 quantum number for every oscillator, so a generic state is

$$|\nu(t)\rangle = \sum_A C_A(t) \, |\mathbf{n}_1, \mathbf{n}_2, ...\mathbf{n}_N\rangle \, .$$

Microstates evolve according to microscopic dynamics: Hamilton's equations

$$\begin{cases} \dot{q}^A = \dfrac{\partial H}{\partial p_A} \\ \dot{p}_A = -\dfrac{\partial H}{\partial q^A} \end{cases}$$

are $3N$ equations that, along with $6N$ initial conditions, completely determine the motion of the system.
Observation: the classical evolution is at odds with thermodynamics for 2 reasons:

1. Hamilton's equations obey the time-reversal symmetry, while the second principle of thermodynamics prescribes a preferential direction of the evolution of the system;
2. Poincaré cycles states that, if a phase space is limited, the trajectory of the system will return arbitrarily close to the starting point, given enough time.

This microscopic approach is not only inconceivable, since it involves solving $\sim \mathcal{N}_A$ coupled PDEs, but also redundant, as in TD the state of a gas could be determined with only a handful of macroscopic variables. The set of these variables is called a **macrostate** and each one includes a huge number of microstates: this state is at equilibrium, but the system still moves in the phase space and "visits" many microstates of the macrostate.

15 Observables

To measure an observable, the whole microstate must be known and the observable must be measured instantaneously: the value of the observable is the mean of the values found

$$O_{\text{obs}} = \frac{1}{M} \sum_{n=1}^{M} O_n$$

and the mean value in time is the integral mean over time on the system trajectory $\nu(t)$

$$\bar{O} = \frac{1}{T} \int_0^T \mathrm{d}t O(\nu(t)).$$

The statistical approach is different, the value is found using the average in terms of frequencies: given the set of microstates $\{\nu\}$, the value is

$$O_{\text{obs}} = \sum_{\{\nu\}} \frac{n(\nu)}{M} O(\nu)$$

where $n(\nu)$ is the number of times ????

This is similar to the definition of a mean value, with $P(\nu) = \frac{n(\nu)}{M}$: since the microstates are points in the phase space, the probability should be expressed in terms of an integral

$$\langle O \rangle = \int \mathrm{d}\mu \rho(q,p) O(q,p) = \int \mathrm{d}q \wedge \mathrm{d}p \rho(q,p) O(q,p)$$

where $\rho(q,p)$ is the probability that the microstate falls into an (hyper-)cube around (q,p); the main objective of statistical mechanics is to determine this probability density.

In general, for non-equilibrium states, the density evolves with time, but this evolution is determined by the *Liouville Theorem*.

Liouville Theorem

If a probability density $\rho(q,p,t)$ satisfies a continuity equation, then

$$\frac{\mathrm{d}\rho}{\mathrm{d}t} = \frac{\partial \rho}{\partial t} + \sum_A \left(\frac{\partial \rho}{\partial q^A} \dot{q}_A + \frac{\partial \rho}{\partial p_A} \dot{p}_A \right) = \frac{\partial \rho}{\partial t} + \{\rho, H\} = 0$$

Proof

The continuity equation is

$$\frac{\partial \rho}{\partial t} + \boldsymbol{\nabla} \cdot \mathbf{j} = 0$$

and the associated current $\mathbf{j}$ is given by "density times velocity", which in the phase space is

$$\mathbf{j} = \left(\rho \dot{q}^A, \rho \dot{p}_A \right)$$

expanding the divergence

$$0 = \frac{\partial \rho}{\partial t} + \frac{\partial}{\partial q^A} \left(\rho \dot{q}^A \right) + \frac{\partial}{\partial p_A} \left(\rho \dot{p}_A \right) = \frac{\partial \rho}{\partial t} + \frac{\partial \rho}{\partial q^A} \dot{q}^A + \frac{\partial \rho}{\partial p_A} \dot{p}_A + \rho \left(\frac{\partial \dot{q}^A}{\partial q^A} + \frac{\partial \dot{p}_A}{\partial p_A} \right)$$

recalling Hamilton's equations and commuting second derivatives yields the result.