



PRODUCT DOCUMENTATION

Single Sign-On for PCF[®]

Documentation

Version 1.3

Published: 11 March 2019

© 2019 Pivotal Software, Inc. All Rights Reserved.

Table of Contents

Table of Contents	2
Single Sign-On Overview	3
Release Notes	6
Installation	8
Getting Started with Single Sign-On	9
Using the System Plan	10
Manage Service Plans	13
Manage Service Instances	15
Configure Identity Providers	17
Identity Provider Discovery	21
Configure Applications	23
Web App	28
Native Mobile App	30
Service-to-Service App	31
Single-Page Javascript App	32
Manage Resources	33
Active Directory Federation Services Integration Guide Overview	35
Configure Active Directory Federation Services as an Identity Provider	36
Configure a Single Sign-On Service Provider	43
Testing	45
Troubleshooting	52
Azure Active Directory Integration Guide Overview	53
Configure Azure Active Directory as an Identity Provider	54
Configure a Single Sign-On Service Provider	61
Testing	63
Troubleshooting	70
CA Single Sign-On Integration Guide Overview	72
Configure CA Single Sign-On as an Identity Provider	73
Configure a Single Sign-On Service Provider	77
Testing	79
Troubleshooting	84
Okta Integration Guide Overview	86
Configure Okta as an Identity Provider	87
Configure a Single Sign-On Service Provider	91
Testing	93
Troubleshooting	99
PingFederate Integration Guide Overview	101
Configure PingFederate as an Identity Provider	102
Configure a Single Sign-On Service Provider	108
Testing	110
Troubleshooting	116
PingOne Cloud Integration Guide Overview	117
Configure PingOne Cloud as an Identity Provider	118
Configure a Single Sign-On Service Provider	122
Testing	124
Troubleshooting	131

Single Sign-On Overview

Note: Single Sign-On for PCF v1.3 is no longer supported. The support period for v1.3 has expired. To stay up-to-date with the latest software and security updates, upgrade to a supported version.

This topic provides an overview of the [Single Sign-On](#) service for Pivotal Cloud Foundry (PCF).

The Single Sign-On service is an all-in-one solution for securing access to applications and APIs on PCF. The Single Sign-On service provides support for native authentication, federated single sign-on, and authorization. Operators can configure native authentication and federated single sign-on, for example SAML, to verify the identities of application users. After authentication, the Single Sign-On service uses OAuth 2.0 to secure resources or APIs.

Single Sign-On

The Single Sign-On service allows users to log in through a single sign-on service and access other applications that are hosted or protected by the service. This improves security and productivity since users do not have to log in to individual applications.

Developers are responsible for selecting the authentication method for application users. They can select native authentication provided by the User Account and Authentication (UAA) or external identity providers. UAA is an open source identity server project under the Cloud Foundry (CF) foundation that provides identity based security for applications and APIs.

OAuth 2.0 Authorization

After authentication, the Single Sign-On service uses OAuth 2.0 for authorization. OAuth 2.0 is an authorization framework that delegates access to applications to access resources on behalf of a resource owner.

Developers define resources required by an application bound to a Single Sign-On (SSO) service instance and administrators grant resource permissions. See the [Configure Applications](#) topic for more details.

Product Snapshot

The following table provides version and version-support information about [Single Sign-On](#) for PCF:

Element	Details
Version	v1.3.6
Release date	November 9, 2017
Compatible Ops Manager version(s)	v1.9 or later
Compatible Elastic Runtime version(s)	v1.9 or later
IaaS support	AWS, GCP, OpenStack, and vSphere

Upgrading to the Latest Version

Consider the following compatibility information before upgrading Single Sign-On for PCF. Pivotal recommends upgrading PCF before upgrading SSO to the supported version. For example, when upgrading from PCF v1.8 to PCF v1.9, upgrade PCF so that SSO v1.2 is running on PCF v1.9, and then upgrade SSO v1.2 to SSO v1.3 as soon as possible.

Elastic Runtime Version	Supported Upgrades from SSO Versions	
	From	To
1.6.x	1.0.1–1.0.25	1.0.26
1.7.x	1.0.1–1.0.26	1.1.4
	1.1.0–1.1.3	
1.8.x	1.1.0–1.1.4	1.2.4
	1.2.0–1.2.3	
1.9.x & 1.10.x	1.2.0–1.2.x	1.3.x

-  **Note:** The Single Sign-On service tile operates in lockstep with Elastic Runtime.
- The SSO v1.1.x tiles are compatible with PCF v1.7.x
 - The SSO v1.2.x tiles are compatible with PCF v1.8.x and later
 - The SSO v1.3.x tiles are compatible with PCF v1.9.x and later

Single Sign-On for PCF

- [Installation](#)
- [Getting Started with Single Sign-On](#)
- [Manage Service Plans](#)
- [Manage Service Instances](#)
- [Configure Identity Providers](#)
- [Configure Applications](#)
 - [Authorization Code Grant Type](#)
 - [Implicit Grant Type](#)
 - [Client Credentials Grant Type](#)
 - [Resource Owner Password Credentials Grant Type](#)
- [Manage Resources](#)

Active Directory Federation Services (AD FS) Integration Guide

- [Active Directory Federation Services Integration Guide](#)
 - [Configure Active Directory Federation Services as an Identity Provider](#)
 - [Configure SSO Service](#)
 - [Testing](#)
 - [Troubleshooting](#)

Azure Active Directory Integration Guide

- [Azure Active Directory Integration Guide](#)
 - [Configure Azure Active Directory as an Identity Provider](#)
 - [Configure SSO Service](#)
 - [Testing](#)
 - [Troubleshooting](#)

CA Single Sign-On Integration Guide

- [CA Single Sign-On Integration Guide](#)
 - [Configure CA Single Sign-On as an Identity Provider](#)
 - [Configure SSO Service](#)
 - [Testing](#)
 - [Troubleshooting](#)

Okta Integration Guide

- [Okta Integration Guide](#)
 - [Configure Okta as an Identity Provider](#)
 - [Configure SSO Service](#)

- [Testing](#)
- [Troubleshooting](#)

PingFederate Integration Guide

- [PingFederate Integration Guide](#)
 - [Configure PingFederate as an Identity Provider](#)
 - [Configure SSO Service](#)
 - [Testing](#)
 - [Troubleshooting](#)

PingOne Cloud Integration Guide

- [PingOne Cloud Integration Guide](#)
 - [Configure PingOne as an Identity Provider](#)
 - [Configure SSO Service](#)
 - [Testing](#)
 - [Troubleshooting](#)

Additional Information

- [Release Notes](#)

Release Notes

View Release Notes for Another Version

To view the release notes for another product version, select the version from the drop-down list at the top of this page.

v1.3.x

v1.3.6

Release Date: November 9, 2017

- PCF updated stemcell to 3445 series. This is a security upgrade to bump Ubuntu stemcells for USN-3420-2: Linux kernel (Xenial HWE) vulnerabilities.

v1.3.5

Release Date: October 24, 2017

- This release addresses an issue with managing service instances when more than 50 Space Developers exist within a space.
- This release addresses a Java Buildpack issue that causes required memory to increase to 1GB.

v1.3.4

Release date: 30 August 2017

- This is a security upgrade that resolves the following CVEs:

- [CVE-2017-8040](#)
- [CVE-2017-8041](#)
- [CVE-2017-8044](#)

Additional information can be found at <https://pivotal.io/security>.

v1.3.3

Release date: 21 June 2017

- PCF updated stemcell to 3363 series.

v1.3.2

Release date: 10 April 2017

- This releases addresses the upgrade issues introduced in version 1.3.1 of the Single Sign-On Service tile.

v1.3.1

Release date: 29 March 2017

⚠ Critical: Pivotal Single Sign-On Service upgrade from 1.3.0 to 1.3.1 fails and causes failure of any further “Apply Changes” from Pivotal Operations Manager.

This notification applies only to customers who have installed Pivotal Single Sign-On Service 1.3.0 and are planning to upgrade to Pivotal Single Sign-On Service 1.3.1. Pivotal Single Sign-On Service 1.3.1 introduces a breaking change which affects customers trying to upgrade from 1.3.0 to 1.3.1 version of the tile. It also has the side effect of stopping any further “Apply Changes” in Pivotal Operations Manager with an error “Error 30014: release ‘identity_service_broker/65’ has already been uploaded with commit_hash as ‘6d038495’ and uncommitted_changes as ‘true’”. Please contact Pivotal Support immediately to get assistance with a mitigation for this issue. We will be releasing Pivotal Single Sign-On Service 1.3.2 which contains a fix for this issue in the next few days.

Please refrain from uploading Pivotal Single Sign-On Service Tile 1.3.1 to Pivotal Operations Manager until version 1.3.2 is available for download. Please note that a simple upload of the 1.3.1 tile to Ops Manager can trigger the issue with Apply Changes.

What's New

- The Single Sign-On service tile now supports network with multiple subnets at installation time.

v1.3.0

Release date: 20 December 2016

What's New

- Default system service plan secures developer apps and automates access to the Cloud Foundry API and pipelines. See the [Using the System Plan](#) topic for more information.
- Identity Provider Discovery streamlines the end user experience when multiple identity providers are enabled for a single app. See the [Identity Provider Discovery](#) topic for more information.
- You can set access and refresh token lifetimes at the app level.

Installation

This topic explains how to install Single Sign-On (SSO) for Pivotal Cloud Foundry.

Prerequisites

- Pivotal Cloud Foundry ([Ops Manager](#) and [Elastic Runtime](#)) version 1.9 or later.
- SSL Certificates.
- Application Security Groups.

Install SSO via Ops Manager

1. From [Pivotal Network](#), select a **Single Sign-On** tile version and download the product release file.
2. From the Ops Manager Installation Dashboard, select the **Import a Product** button to upload the product file.
3. Click the plus sign icon next to the uploaded product to add this product to your staging area.
4. Click on the **Single Sign-On** tile to enter any configurations.

 **Note:** The Single Sign-On service tile requires a network with only one subnet until version 1.3.0. Starting with 1.3.1 multiple subnets are supported.

 **Note:** The SSO Identity Service Broker is deployed as a PCF application from a BOSH errand, and has no associated BOSH VMs that require selecting a corresponding network. If you are forced to select a network during installation, select the **Deployment** network, also known as the PAS or ERT network.

5. Click **Apply Changes** to install the product.

Update SSL and Load Balancer

You must update the SSL certificate for the domains listed below for each plan you create. Depending on your infrastructure and load balancer, you must also update your load balancer configuration for the following domains:

- `*.SYSTEM-DOMAIN`
- `*.APPS-DOMAIN`
- `*.login.SYSTEM-DOMAIN`
- `*.uaa.SYSTEM-DOMAIN`

Configure Application Security Groups

The Single Sign-On service requires the following network connections:

- TCP connection to load balancer(s) on port 443
- TCP and UDP connection to Domain Name Servers on port 53
- (Optional) TCP connection to your external identity provider on port 80 or 443

To enable access to the Single Sign-On service, you must ensure your Application Security Group allows access to the load balancer(s) and domain name servers that provide access to Cloud Controller and UAA. Optionally, you can configure access to your external identity provider to receive SAML metadata. For more details on how to set up application security groups, see the [Application Security Groups](#) topic.

Getting Started with Single Sign-On

This topic outlines the steps for installing and configuring the [Single Sign-On](#) service.

Install and Set Up SSO for Applications

1. [Install Single Sign-On](#) via Ops Manager.
2. [Create a service plan](#). The Single Sign-On service is a multi-tenant service, and a service plan corresponds to a tenant. This allows an enterprise to segregate users or environments using plans. Each service plan is accessible at a tenant-specific URL in the format `https://AUTH-DOMAIN.login.SYSTEM-DOMAIN`.
3. [Create a service instance](#). Single Sign-On service plans can provide single sign-on capabilities for applications in various spaces. A service instance lets you bind an application to a service plan.
4. [Configure an identity provider](#). In addition to the [Internal User Store](#), you can configure [external identity providers](#) to provide single sign-on to applications. External identity providers must support SAML 2.0.
5. [Configure your applications](#). Single Sign-On supports both Pivotal Cloud Foundry-hosted applications as well as externally hosted applications. Your applications must be able to request an OAuth or OpenID Connect token.
6. [Create resources for your applications](#). If your registered applications need to make external API calls, you can assign the API endpoints as resources permitted for the application. This will whitelist the endpoints for use by the application or client.

SSO User Roles

A user's role determines which parts of an SSO configuration it can manage. SSO uses the existing user roles PCF Administrator and Space Developer, as well as a SSO-specific Plan Administrator role. This chart shows the management permissions for each role.

Management access by role	PCF Administrator	Plan Administrator	Space Developer
Service plans	X		
Service instances	X	X	X
Identity providers	X	X	
Applications	X	X	X
Resources	X	X	X

Using SSO for Pivotal Cloud Foundry Components

In addition to applications, SSO supports single sign-on for components of Pivotal Cloud Foundry, including Ops Manager and Apps Manager. This allows users already managed in an external identity provider to sign into Pivotal services. Refer to the following pages for instructions on configuring SSO to enable users in an external identity store to access PCF components:

- Ops Manager, on [Amazon Web Services](#), [vSphere](#), or [OpenStack](#)
- [Apps Manager](#)

Using the System Plan

This topic explains how to use the system plan for the Single Sign-On (SSO) service for Pivotal Cloud Foundry (PCF). The system plan is the default plan meant for developer apps, not end-user apps.

SSO for PCF comes with a default `system` plan that has the following features:

- Read-only
- Minimal configuration options
- Not deletable
- Allows developer-level access to system components like Elastic Runtime and its APIs
- Available only to PCF administrators

Restricting the visibility of this system plan to a single, developer-apps only org secures system components, following the principle of least privilege.

Examples of developer apps include scripts or pipelines that push other apps and services. Any app that uses the [Cloud Foundry API](#) is a developer app.

System Plan Best Practice

Pivotal recommends configuring your orgs and SSO plans as follows to prevent anyone from applying the system plan to end-user apps:

1. Restrict all developer apps to a single org.
2. Make the system plan visible only to the developer-apps org.
3. Configure other orgs with SSO service plans of their own.

Developers can then self-register their developer apps in the developer-apps org for use by other developers.

Administrators: Configure the System Plan for an Org

PCF administrators follow the steps below to enable the system plan and provide access to app developers:

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your User Account and Authentication (UAA) administrator credentials. In your Elastic Runtime tile in Ops Manager, the **Domain** settings show your system domain, and the **Credentials** tab shows the **UAA Admin Credentials**.
2. Navigate to the System Plan and enable the plan in the relevant org(s).

P Single Sign-On admin ▾

Plans > System

System

Plan Name*
System

Description*
This plan is reserved for app developer single sign-on.
This will appear as a plan feature in the Apps Manager Marketplace

Auth Domain* https://login.sys.banana.gcp.rele...gcf-app.com

Organizations

MY-ORG	⋮
MY-ORG	x
sree-org	x

Cancel Save Plan

Developers: Create a System Plan Instance for your App

Follow the steps below to create and use the `system` service plan with your developer apps.

1. Follow the steps to [Create a Service Instance](#) of SSO.

The screenshot shows the Pivotal Apps Manager interface. On the left, there's a sidebar with a 'P' icon, 'Pivotal Apps Manager' title, and a dropdown for 'admin'. The main area has a 'SERVICE' header with a 'Single Sign-On' icon and the text 'Single Sign-On as a Service'. Below it are 'Docs' and 'Support' links. To the right, there's an 'ABOUT THIS SERVICE' section with a detailed description of the Single Sign-On service, mentioning its quick and hassle-free nature for connecting applications via federated identity providers. A 'COMPANY' section indicates 'Pivotal'. At the bottom, there's a 'Configure Instance' panel for 'uaa' with fields for 'Instance Name' (set to 'MY-SERVICE-INSTANCE'), 'Add to Space' (set to 'MY-SPACE'), and 'Bind to App' (set to '[do not bind]'). Buttons for 'Show Advanced Options', 'Cancel', and 'Add' are at the bottom.

2. If your app runs on PCF, bind the application with the service instance you created. See the [Bind an Application Hosted on PCF](#) topic for more information.
3. If your app is a pipeline or a script that runs external to PCF but calls PCF APIs, do the following:
 - a. Follow the instructions to [Register an External Application](#) and use the guidelines below:
 - Choose **Native App** for your application type.
 - In the app configuration, set a value for the **Refresh token lifetime** based on your use case for automated access.
 - b. To give your pipeline or script access to your resources without your presence, embed a refresh token instead of hardcoding your credentials:
 - i. Run `uaac token sso get`.
 - ii. At the prompts, enter the Client ID and Secret from the **Next Steps** section of the SSO dashboard. Copy the authentication URL from the command output.
 - iii. Paste the authentication URL into a browser, and log in using your UAA Admin Credentials.
 - iv. Copy the **Temporary Authentication Code** from the browser into the UAAC to finish the authentication.
 - v. Run `uaac context`.
 - vi. Copy the value of the refresh token and use that in your code to get a new token based on your client id and secret using the standard OAuth refresh token flow as described in the [UAA API documentation](#).

Developers: Revoke System Plan Access for an External App

To revoke system plan access from an app that is external to PCF and is registered with the system plan to access PCF components, do one of the following:

- Regenerate the App Secret
- Delete the app

Manage Service Plans

This topic describes how Pivotal Cloud Foundry (PCF) Administrators manage Single Sign-On service plans.

Single Sign-On is a multi-tenant service, which enables a deployment to host multiple tenants as service plans. Each service plan can have its own administrators, applications and users. This lets enterprises segregate access by using separate plans. For example, the following tenants might require separate plans:

- Business units and geographical locations
- Employees, consumers, and partners
- Development, staging, and production instances


Administrators can create new Single Sign-On service plans at any time from the SSO dashboard.

Create or Edit Service Plans

You can use the SSO dashboard to create and configure service plans at any time.

 **Note:** You must create at least one plan for any service before your applications can use it.

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your User Account and Authentication (UAA) administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click **New Plan** on the SSO dashboard to create a new Single Sign-On service plan.



The screenshot shows the 'Create Plan' page of the Pivotal Single Sign-On interface. The top navigation bar includes a 'P' logo, the title 'Single Sign-On', and a user dropdown labeled 'admin ▾'. Below the title, there's a back button and a 'Create Plan' heading. The main form fields are:

- Plan Name***: A text input field containing 'SSO Plan' with a small info icon to its right.
- Description***: A text input field containing 'This is a Single Sign-On Service Plan description' with a note below stating 'This will appear as a plan feature in the Apps Manager Marketplace'.
- Auth Domain***: A text input field containing 'https://appcom.login.id-service.cf-app.com' with a note below stating 'appcom'.
- Instance Name***: A text input field containing 'Test_Instance' with a note below stating 'This will appear as a title on the Sign In page'.
- Plan Administrators**: A button labeled 'Add Users'.
- Organizations**: A button labeled 'Add Orgs' next to a list item 'sandbox' with a delete 'X' icon.

At the bottom right of the form are 'Cancel' and 'Create Plan' buttons.

3. Enter a **Plan Name**.
4. Enter a **Description** to appear as a plan feature in the Services Marketplace.
5. Enter an **Auth Domain** to be the URL where users authenticate to access applications covered by the service plan.
6. Enter an **Instance Name** to appear on the login page and in other user-facing content, such as email communications.
7. Add **Plan Administrators**. These users can view the plan and manage identity providers.
8. Under **Org Visibility**, select which organizations in your Pivotal Cloud Foundry deployment should have access to your Single Sign-On service plan. If you do not select any organizations, the plan will not be available for use and it will not be displayed in the Services Marketplace.
9. Click **Create Plan**. Your new plan appears in the Services Marketplace in the organizations you have selected. Users in those organizations view the plan either in Apps Manager or through the CF CLI by entering `cf marketplace` in a terminal window.

Delete Service Plans

1. Log in to the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Select the name of the plan you want to delete, and click **Edit Plan** in the drop-down menu.
3. Select **Delete** at the bottom of the page.
4. In the popup that appears, click **Delete Plan** to confirm that you want to delete the plan.

Note: This action cannot be undone. Deleting a Single Sign-On service plan removes from the SSO database all of the configurations, identity providers, users, application configurations and resources associated with the plan. It also deletes the associated service instances and service bindings. You must rebind any applications bound to the deleted service instances to new service instances.

Configure a Token Policy

Access tokens carry information about users and clients to servers that manage resources. Servers use access tokens to determine whether the client is authorized or not. Access tokens typically have a short-lived expiration time. *Refresh tokens* carry information necessary to retrieve a new access token after an existing access token expires. Refresh tokens typically have a longer expiration time than access tokens.

Note: The Single Sign-On service allows administrators to override the default expiry of access tokens (12 hours) and refresh tokens (30 days) by zone.

1. Log in to the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Select the name of the plan you want to configure a token policy for, and click **Configure** in the drop-down menu.
3. Enter the number of seconds for **Access Token Expiration** or select **Use System Default**.
4. Enter the number of seconds for **Refresh Token Expiration** or select **Use System Default**.
5. Click **Save**.

Manage Service Instances

This topic describes how Space Developers create an instance of a Single Sign-On service plan in their space and bind it to an application.

Create Service Instances

1. Log into Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> as a Space Developer.
2. Navigate to the organization that the service plan is enabled for.
3. Select **Marketplace** and select the Single Sign-On service you want to create an instance of.
4. Choose your service plan and click **Select this plan**.
5. In the **Configure Instance** box, enter an **Instance Name**.

The screenshot shows the Pivotal Apps Manager dashboard. On the left sidebar, under the 'ORG' section, 'MY-ORG' is selected. Under 'SPACES', 'MY-SPACE' is listed. The main content area displays the 'Single Sign-On' service details. The 'SERVICE' section shows a user icon and the text 'Single Sign-On as a Service'. Below it are links to 'Docs' and 'Support'. To the right, the 'ABOUT THIS SERVICE' section provides a brief description of the Single Sign-On service. Further right, the 'COMPANY' section shows 'Pivotal'. At the bottom, a 'Configure Instance' dialog box is open. It contains a summary of the selected service plan ('uaa') and fields for configuration: 'Instance Name' set to 'MY-SERVICE-INSTANCE', 'Add to Space' set to 'MY-SPACE', and 'Bind to App' set to '[do not bind]'. There are 'Show Advanced Options', 'Cancel', and 'Add' buttons.

1. From the **Add to Space** dropdown menu, choose a space for the instance. This space hosts your application. The default is `development`.
2. From the **Bind to App** dropdown menu, choose an application to bind the service instance to. This option defaults to `[do not bind]`. If you do not bind the instance to an app, you can bind it at a later time.
3. Click **Add** to create the service instance.

Delete Service Instances

1. Log into Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> as a Space Developer.
2. Navigate to the organization and space that contain the service instance you want to delete.
3. Under **Services** in the space page, find your service instance and click **Delete**.
4. Click **Delete** on the pop-up to confirm that you want to delete the service instance and service bindings.

Note: This action cannot be undone. Deleting a Single Sign-On service instance deletes the configurations on the service instance, as well as the

associated service bindings. You must bind any applications bound to the deleted service instance to a new service instance.

Configure Identity Providers

This topic describes how administrators can use an internal user store or an external identity provider to manage user access to a Single Sign-On (SSO) service plan.

For each plan, SSO provides an internal user store that manages users. As an alternative to an internal user store, administrators can use an external identity provider to allow users who are externally managed to access applications.

Configure Internal User Store

1. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` using your User Account and Authentication (UAA) administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Internal User Store**.
4. Under **Authentication Policy**, optionally select one of the following:
 - **Disable Internal Authentication:** Select this option to prevent authentication against the internal user store. You must have at least one external identity provider configured.

Note: The login page does not include the **Email** and **Password** fields if you select this option.
 - **Disable User Management:** Select this option to prevent all users, including administrators, from performing actions on internal users.

Note: The login page does not include **Create Account** and **Reset Password** links if you select this option.
5. Under **Password Policy Settings**, select **Use Recommended Settings**, **Use Default Settings**, or enter custom settings in the fields below.
6. Click **Save Identity Provider**.

Add Users to the Internal User Store

You cannot add users to Service Plans from the SSO dashboard. In order to add users to the internal user store for a given Service Plan, you must use the UAA Command Line Interface (UAAC). If you do not already have the UAAC installed, run `gem install cf-uaac` in a terminal window.

The following steps describe how to use UAAC to add users to the internal user store.

Step 1: Create an Admin Client

1. [Create an admin client](#) that can manage users in the Service Plan. Include the following scopes for the client:
 - `clients.admin`
 - `scim.read`
 - `scim.write`
2. Record the **App ID** and **App Secret**. These are used as your client ID and client secret.

Step 2: Create Users

1. Target the auth domain of your SSO service plan. This is the URL you provided when creating a Service Plan in the SSO dashboard.

```
$ uaac target https://YOUR-AUTH-DOMAIN.login.YOUR-SYSTEM-DOMAIN
```

2. Fetch the token for the admin client created in Step 1.

```
$ uaac token client get ADMIN-CLIENT-ID  
Client secret:
```

3. When prompted with `client secret`, enter the admin client secret from Step 1.

4. Add new users by providing the user's email address, username, and password.

```
$ uaac user add --emails YOUR-USER@EMAIL.COM  
User name: YOUR-USER  
Password: ****  
Verify password: ****  
user account successfully added
```

5. (Optional) You can also create groups and add users to them.

```
$ uaac group add  
Group name: YOUR-GROUP  
meta  
version: 0  
created: 2016-02-19T23:17:17.000Z  
lastmodified: 2016-02-19T23:17:17.000Z  
schemas: urn:scim:schemas:core:1.0  
id: 8725b5fd-8da2-4fcf-89b1-c57048f089c2  
displayname: YOUR-GROUP
```

To add a member to your new group, use the following command.

```
$ uaac member add YOUR-GROUP YOUR-USER
```

Define Password Policy for the Internal User Store

Administrators can define the password policy for SSO users that are stored in the internal user store. The internal user store password policy allows you to define and enforce password rules to manage the kind of passwords users can create.

1. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Internal User Store**.
4. Configure the following under the **Password Complexity** section:
 - **Min Length:** Specify the minimum password length.
 - **Uppercase:** Specify the minimum number of uppercase characters required in a password.
 - **Lowercase:** Specify the minimum number of lowercase characters required in a password.
 - **Special Characters:** Specify the minimum number of special characters required in a password.
 - **Numerals:** Specify the minimum number of numeric characters required in a password.
5. Configure the following under the **Lockout Policy** section:
 - **Failures Allowed:** Specify the number of failed login attempts allowed per hour before a user is locked out.
 - **Lockout Period:** Specify the number of seconds a user is locked out for after excessive failed login attempts.
 - **Password Expires:** Specify the number of months passwords are valid for before users needs to enter a new password.
6. Click **Save Identity Provider**.

Configure Service Provider SAML Settings

For each plan, the Single Sign-On service allows you to configure SAML settings when SAML is used for exchanging authentication and authorization data between the identity provider and the service provider. The SSO service provides the ability to sign authentication requests and require signed assertions from the external identity provider.

1. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.

2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Configure SAML Service Provider**.
4. Configure the following settings:
 - **Perform signed authentication requests:** The service provider signs requests sent to the external identity provider.
 - **Require signed assertions:** The service provider requires that responses from the external identity provider are signed.
5. Click **Save** to save the SAML configurations.
6. Click **Download Metadata**.

Add an External Identity Provider

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **New Identity Provider**.
4. Enter an **Identity Provider Name**.
5. Enter a **Description**. This is displayed to Space Developers when selecting an identity provider for their application.
6. Enter the external identity provider metadata in one of the following ways:
 - Option 1: Provide the **Identity Provider Metadata URL** and click **Fetch Metadata**.
 - Option 2: Click **Upload Identity Provider Metadata** to upload XML metadata that you downloaded from your external identity provider.
7. Configure any **User Attributes** to propagate from the identity provider to the service provider. These attributes can include e-mail addresses, first or last names, or external groups. They are sent to applications via OpenID tokens along with any other stored user information issued by the Single Sign-On service.
 - Select a **User Scheme Attribute** from the dropdown menu.
 - Enter a **SAML Attribute Name** with the corresponding attribute from the incoming SAML assertion.
8. Configure any **Custom Attributes** that should be propagated from the identity provider to the service provider. These attributes will be sent to applications via OpenID tokens issued by the Single Sign-On service.
 - Enter a **Custom Attribute Name**.
 - Enter a **SAML Attribute Name** with the corresponding attribute from the incoming SAML assertion.
9. Click **Create Identity Provider** to save the identity provider.

 **Note:** To configure the service provider SAML settings, such as the signing of authentication requests and incoming assertions, click on **Configure SAML Service Provider** on the Identity Providers page.

Delete an External Identity Provider

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click on the name of your external identity provider.
4. Click **Delete** at the bottom of the page.
5. In the popup that appears, click **Delete Identity Provider** to confirm that you want to delete the identity provider, along with all of its configurations.

 **Note:** Deleting an external identity provider deletes all of its configurations. Users will no longer be able to authenticate using the external identity provider. This action cannot be undone.

Configure Group Whitelist for an External Identity Provider

An administrator can create groups from an external identity provider in Group Whitelist. By creating these groups, they are propagated in the ID token when a user authenticates through an external identity provider. This provides information to the application about the external groups that the user belongs to. An administrator can use these groups to assign permissions by group rather than individual users. For more details on how to create resource permission mappings, see [Create or Edit Resource Permissions](#).

 **Note:** The `roles` scope must be requested by the application and the external group must be listed in the Group Whitelist.

1. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` using your UAA administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Group Whitelist**.
4. Add a group name from your external identity provider.
5. Click **Save Group Whitelist**.

Identity Provider Discovery

This topic describes Identity Provider (IdP) Discovery and how to configure it for your Pivotal Cloud Foundry (PCF) apps that use the Single Sign-On (SSO) service.

What it Does

If users with different email domains access the same PCF app, you can configure SSO to authenticate them through different identity providers.

In this situation, IdP Discovery streamlines the login experience by automatically redirecting the user to their own IdP and shielding them from seeing the IdPs of other app users.

When a user logs in to an app, an account chooser autofills their email address from any previous login, or presents a choice if they have logged in from more than one account. Users can add or remove accounts from the account chooser.

Example

As an example, consider an app used by a company `@company.com` and its competing suppliers `@supplier-1.com` and `@supplier-2.com`. With IdP Discovery, users from all three companies can log in from the same page, and do not have to see or choose from a list of login options that covers all the domains. IdP Discovery ascertains each user's IdP from their email domain.

Enable IdP Discovery

IdP Discovery is associated with a service plan, and configured for the apps bound to instances of that plan. To enable IdP Discovery for a service plan and the apps that use it, you must be a PCF Administrator or a Plan Administrator.

1. Enable IdP Discovery for the SSO Service Plan instance that your app is bound to:

- a. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` using your User Account and Authentication (UAA) administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
- b. Click the plan name and select **Configure** under the plan menu.
- c. Select the checkbox under the **Identity Provider Discovery** section and click **Save**.

The screenshot shows the Pivotal Single Sign-On (SSO) dashboard interface. At the top, there is a dark header with the Pivotal logo, the text "Single Sign-On", and a dropdown menu for "admin". Below the header, the URL "Plans > Acme INC > Configure" is displayed. The main content area is titled "Configure". Under this, there is a section titled "Token Policy" which includes "Access Token Expiration" and "Refresh Token Expiration" settings. Both sections have input fields for time units (Seconds) and checkboxes for "Use System Default" (with values 12 hours and 30 days respectively). Below the token policy section is another titled "Identity Provider Discovery", which contains a single checkbox labeled "Enabled" that is checked. At the bottom of this section is a blue "Save" button.

2. Click the plan name and select **Manage Identity Providers** under the plan menu.
3. Enter the Email domains you want to include as a comma-separated list under the configuration page for the identity provider plan.

Single Sign-On

Plans > Acme INC > Identity Providers > Internal User Store

Internal User Store

Email Domains

Provide comma-separated list of domains for identity provider discovery

company.com, supplier-1.com, supplier-2.com

Authentication Policy

Disable Internal Authentication

Disable User Management

Password Policy Settings

[Use Recommended Settings](#) [Use Default Settings](#)

Password Complexity		Lockout Policy	
Min Length	Uppercase	Failures Allowed	Lockout Period
1	0	5	300

4. In Apps Manager, navigate to your space, open the **Service** tab, and select your service instance.
5. Click the **Manage** link under the service name, and edit the app configuration by selecting the required Identity Providers.

Configure Applications

This topic describes how Space Developers bind internal applications or register external applications to their Single Sign-On (SSO) service instances.

If your application is hosted on Pivotal Cloud Foundry (PCF), refer to the [Bind an Application Hosted on PCF](#) section to bind the application to your SSO service instance from Apps Manager. If your application is externally hosted, refer to the [Register an External Application](#) section to register your application with your SSO service instance from the SSO dashboard.

When you bind or register an application with a SSO service instance, SSO creates an OAuth client. This OAuth client acts as an OAuth 2.0 authorization server and issues tokens.

Determine Your Application Type

Before you bind or register an application, you must know your SSO application type. Refer to the table below to determine the application type best suited for your application.

If your application authenticates end users, then your application type is `Web App`, `Native Mobile App`, or `Single-Page JavaScript App`. If your application does not authenticate end users, but rather accesses other services or APIs on its own behalf, then your application type is `Service-to-Service App`.

Application Type	SSO Application Type	OAuth Grant Type Equivalent
<code>Web</code>	<code>Web App</code>	<code>authorization code</code>
<code>Native Mobile, Desktop, or Command Line</code>	<code>Native Mobile App</code>	<code>password</code> (the resource owner's password)
<code>Service-to-Service</code>	<code>Service-to-Service App</code>	<code>client_credentials</code>
<code>Single-Page JavaScript</code>	<code>Single-Page JavaScript App</code>	<code>implicit</code>

 **Note:** The Native Mobile App application type is intended only for highly trusted applications such as company owned and managed applications.

Preconfigure an Application Hosted on PCF

Follow the steps below to create environment variables that you can then set during a bind.

Set Application Type:

- **Option 1:** Set the grant type environment variable by performing the following steps:
 1. Log in to Apps Manager at `https://apps.YOUR-SYSTEM-DOMAIN`.
 2. Navigate to your application.
 3. Click the Env Variables tab.
 4. Click Add an Env Variable.
 5. For Variable Name, enter `GRANT_TYPE`.
 6. For Value, enter the OAuth grant type for your application type. For example, if your application is a Single-Page JavaScript App, specify `implicit`.
 7. Bind and restage your application.
- **Option 2:** Set the grant type environment variable by including the following in your application manifest. If you choose this option, you do not have to configure environment variables after deploying your app.

```
---
applications:
  - name: APPLICATION NAME
    env:
      GRANT_TYPE: OAUTH GRANT TYPE
```

 **Note:** If you do not provide a `GRANT_TYPE`, the application type defaults to Web App.

Set Identity Provider:

Set the identity providers by including the following in your application manifest:

```
---  
applications:  
  - name: APPLICATION NAME  
    env:  
      SSO_IDENTITY_PROVIDERS: COMMA SEPARATED LIST OF IDENTITY PROVIDERS
```

Note: If you do not provide any `SSO_IDENTITY_PROVIDERS`, the internal user store will be selected by default.

Bind an Application Hosted on PCF

1. Log in to Apps Manager as a Space Developer.
2. Select the space where your application runs.
3. Under **Applications**, click the name of your application.
4. Click the **Services** tab.
5. Click **Bind a Service**.
6. Bind your application to a service to create an associated OAuth Client.
 - a. Select an existing SSO service instance from the dropdown menu and click **Bind**.
 - b. Create a new service instance:
 - i. Click **or add from Marketplace**.
 - ii. Select the **Single Sign-On** service under Services Marketplace.
 - iii. Select a Service Plan, then click **Select this plan**.
 - iv. Enter an **Instance Name**, select a space, select an app, then click **Add**.
7. Click **Manage** under the SSO service instance to launch the SSO dashboard.
8. Click your application.
9. Specify a value in the **App Launch URL** field that you want to set as the address of your application.
10. Upload an app icon for your application.
11. Click **Show on homepage** to display the application on the UAA or Pivotal Account home page.

Note: If you would like application to display on the home page, you must enter an **App Launch URL** or upload an app icon.

12. Select one or more **Identity Providers** for your application. Internal User Store is the default.

Note: When binding a PCF application, a Space Developer can choose from internal and external identity providers. If the Space Developer selects multiple identity providers, users must select which provider to use when they sign in. This option is available for all application types except `Service-to-Service App`.

13. If your Application Type is `Web App` or `Single-Page JavaScript App`, enter a whitelist of **Auth Redirect URIs** beneath **Redirect URIs**. The redirect query parameter specified on the OAuth request must match the URIs specified in this list. Otherwise, SSO rejects the request.
14. For the **Scopes** field, specify the permissions that the application can request on the user's behalf. This field defaults to `openid` for Web, Native Mobile, and Single-Page JavaScript Apps. This field defaults to `uaa.resource` for Service-to-Service Apps. If this application is purely for authentication purposes, then the `openid` scope is sufficient. If the application makes API calls on behalf of the end user, you must specify both the scopes enforced by the API and the scopes to be requested by the application.

Scope	Description
<code>openid</code>	Provides access to make OpenID Connect requests
<code>user_attributes</code>	Provides access to custom attributes from an external identity provider
<code>... - ...</code>	Provides access to external accounts from an identity provider

Scope	Description
uaa.resource	Provides access to the check_token endpoint for service-to-service flows

Note: Under **Scopes**, you can select resources defined in any space if the application type is a **Web App**, **Native Mobile App**, or **Single-Page JavaScript App**. If the application type is a **Service-to-Service App**, you can only select resources defined within the space.

- For **Auto-Approved Scopes**, select any scopes that the SSO service automatically approves when the app makes a request on behalf of a user. Select only scopes pertaining to applications owned and managed by your company. Do not select scopes that pertain to applications external to PCF.
- Click **Save Config**. The **Next Steps** page appears, describing the endpoints required for application integration. Refer to the [Integrate SSO with Applications](#) section below for more details.

Register an External Application

- Log in to Apps Manager as a Space Developer.
- Select the space where your service instance is located.
- Under **Services**, click **Manage** next to the SSO service instance. This launches the SSO dashboard.
- Click **New App**.
- Enter an **App Name**.
- Choose an application type under **Select an Application Type**.
- Enter an **App Launch URL** that specifies the address of your application.
- Upload an app icon for your application.
- Click **Show on homepage** to display the application on the UAA or Pivotal Account home page.

Note: To display the application on the home page, you must enter an **App Launch URL** or Upload an app icon.

- Select one or more **Identity Providers** for your application. Internal User Store is the default.

Note: When registering an externally hosted application, a Space Developer can choose from internal and external identity providers. If the Space Developer selects multiple identity providers, users must select which provider to use when they sign in. This option is available for all application types except **Service-to-Service App**.

- If your Application Type is **Web App** or **Single-Page JavaScript App**, enter a whitelist of **Auth Redirect URIs** beneath **Redirect URIs**. The redirect query parameter specified on the OAuth request must match the URIs specified in this list. Otherwise, SSO rejects the request.
- For the **Scopes** field, specify the permissions that the application can request on the user's behalf. This field defaults to **openid** for Web, Native Mobile, and Single-Page JavaScript Apps. This field defaults to **uaa.resource** for Service-to-Service Apps. If this application is purely for authentication purposes, then the **openid** scope is sufficient. If the application makes API calls on behalf of the end user, you must specify both the scopes enforced by the API and the scopes to be requested by the application.

Scope	Description
openid	Provides access to make OpenID Connect requests
user_attributes	Provides access to custom attributes from an external identity provider
roles	Provides access to external groups from an identity provider
uaa.resource	Provides access to check_token endpoint for service-to-service flows

Note: Add the **user_attributes** scope to the client scopes to return user attributes from the ID token.

Note: Under **Scopes**, you can select resources defined in any space if the application type is a **Web App**, **Native Mobile App**, or **Single-Page JavaScript App**. If the application type is a **Service-to-Service App**, you can only select resources defined within the space.

- For **Auto-Approved Scopes**, select any scopes that the SSO service automatically approves when the app makes a request on behalf of a user. Select

only scopes pertaining to applications owned and managed by your company. Do not select scopes that pertain to applications external to PCF.

14. Click **Create App**. The **Next Steps** page appears, describing the endpoints required for application integration. Refer to the [Integrate SSO with Applications](#) section below for more details.

Integrate SSO with Applications

Because SSO service is based on the OAuth protocol, your applications must be OAuth-aware.

Java Applications

If you are using Java, refer to the [Single Sign-On Service Sample Applications](#). These are sample applications created using [Spring Boot](#) for all four [application types](#). These applications use the SSO Service Connector, which auto-configures the application for OAuth. After binding the application to an SSO service instance, you must restart the application for the new SSO configuration to take effect.

Non-Java Applications

To configure non-Java applications for OAuth, supply the following properties as environment variables to your application after the SSO service bind. You can view this information on the **Next Steps** page of the SSO dashboard.

- **App ID**, also known as OAuth Client ID
- **App Secret**, also known as OAuth Client Secret
- **OAuth Authorization URL**, the endpoint for client authorization
- **OAuth Token URL**, the endpoint for token retrieval

To validate the token, you must verify the following:

1. The token is a properly signed JSON Web Token with an appropriate public key. The key can be downloaded from the **Token Verification Key** endpoint specified on the **Next Steps** page.
2. The value of `aud` in the token matches your **App ID**.
3. The value of `iss` matches `https://AUTH-DOMAIN.uaa.YOUR-SYSTEM-DOMAIN/oauth/token`.
4. The expiry time of the token, `exp`, has not passed.

Create Admin Client

You can create an admin client to perform administrative functions, such as manage identity providers, applications, users, groups, and resources in a specific zone where you create the client.

To create an admin client, complete the following steps:

1. Log in to Apps Manager.
2. Select the space where your service instance is located. This specifies the zone you manage as an admin client.
3. Under **Services**, click the **Single Sign-On** service.
4. Click **Manage** next to your SSO service instance to launch the SSO dashboard.
5. Click **New App**.
6. Enter an **App Name**.
7. Under **Select an Application Type**, select **Service-to-Service App**.
8. Click **Select Scopes** and choose what actions the admin client can perform from the following **Admin Permissions**:

Scope	Description
-------	-------------

Scope	Description
clients.admin	Provides superuser access to create, modify, and delete clients
clients.read	Provides access to read information about clients
clients.write	Provides access to create and modify clients
scim.create	Provides access to create users
scim.read	Provides access to read information about users and group memberships
scim.write	Provides access to create, modify, and delete users and group memberships
idps.read	Provides access to read information about identity providers
idps.write	Provides access to create, modify, and delete identity providers

9. Click **Create App**.

Delete Application

Complete the procedure that corresponds with your application type.

Delete a PCF Application

To delete an application hosted on PCF, complete the following steps:

1. Log in to Apps Manager as a Space Developer.
2. Select the space where your application is located.
3. Under **Applications**, click the name of your application.
4. On the Application Page, click **Delete App**.
5. On the popup, click **Delete** to confirm that you want to delete the application and its configurations from Apps Manager and the service dashboard.

Delete an External Application

To delete an external application not hosted on PCF, complete the following steps:

1. Log in to Apps Manager as a Space Developer.
2. Select the space where your service instance is located.
3. Under **Services**, click **Manage** next to your SSO service instance to launch the SSO dashboard.
4. Click your application.
5. Click **Delete** at the bottom of the page.
6. On the popup, click **Delete App** to confirm that you want to delete the application and its configurations.

 **Note:** Deleting an externally hosted application removes the application and its configurations from the SSO dashboard. However, it still exists on your hosted platform.


Web App

This topic describes the OAuth 2.0 Authorization Code grant type supported by Pivotal Single Sign-On (SSO). The authorization code grant type is the most commonly used grant type. This grant type is for server-side applications.

OAuth 2.0 Roles

- **Resource Owner:** A person or system capable of granting access to a protected resource.
 - **Application:** A client that makes protected requests using the authorization of the resource owner.
 - **Authorization Server:** The Single Sign-On server that issues access tokens to client applications after successfully authenticating the resource owner.
 - **Resource Server:** The server that hosts protected resources and accepts and responds to protected resource requests using access tokens.
- Applications access the server through APIs.

Authorization Code Flow



- Access Application:** The user accesses the application and triggers authentication and authorization.
- Authentication and Request Authorization:** The application prompts the user for their username and password. The first time the user goes through this flow for the application, the user sees an approval page. On this page, the user can choose permissions to authorize the application to access resources on their behalf.
- Authentication and Grant Authorization:** The authorization server receives the authentication and authorization grant.
- Send Authorization Code:** After the user authorizes the application, the authorization server sends an authorization code to the application.
- Request Code Exchange for Token:** The application receives the authorization code and requests an access token from the authorization server. This gives the application access to the approved permissions.
- Issue Access Token:** The authorization server validates the authorization code and issues an access token.
- Request Resource w/ Access Token:** The application attempts to access the resource from the resource server by presenting the access token.
- Return Resource:** If the access token is valid, the resource server returns the resources that the user authorized the application to receive.

The resource server runs in PCF under a given space and organization. Developers set the permissions for the resource server API endpoints. To do this, they create resources that correspond to API endpoints secured by the Single Sign-On service. Applications can then access these resources on behalf of users.

Native Mobile App

For Native Mobile and Desktop applications, Pivotal Single Sign-On (SSO) supports the Resource Owner Password OAuth 2.0 grant type. This password grant type is for highly trusted applications where resource owners share their credentials directly with the application.


OAuth 2.0 Roles

The following roles are available in an OAuth 2.0 scenario:

- **Resource Owner:** A person or system capable of granting access to a protected resource.
 - **Application:** A client that makes protected requests using the authorization of the resource owner.
 - **Authorization Server:** The Single Sign-On server that issues access tokens to client applications after successfully authenticating the resource owner.
 - **Resource Server:** The server that hosts protected resources and accepts and responds to protected resource requests using access tokens.
- Applications access the server through APIs.

Native Mobile App Flow

The following diagram shows the authentication flow used by mobile apps. In this scenario, the application is backed by a resource server and both are secured by the UAA authorization server.



1. **Authenticate w/ Username and Password:** The user authenticates with the application using their username and password.
2. **Send Username/Password:** The application sends the username and password to the authorization server for validation.
3. **Issue Access Token:** The authorization server validates the username and password and issues an access token.
4. **Request Resource w/ Access Token:** The application attempts to access the resource from the resource server by presenting the access token.
5. **Return Resource:** If the access token is valid, the resource server returns the resources that the user authorized the application to receive.

The resource server runs in PCF under a given space and organization. Developers set the permissions for the resource server API endpoints. To do this, they create resources that correspond to API endpoints secured by the Single Sign-On service. Applications can then access these resources on behalf of users.


Service-to-Service App

For Service-to-Service applications, Pivotal Single Sign-On (SSO) supports the Client Credentials OAuth 2.0 grant type. The client credentials grant type is for applications that can request an access token and access resources on its own. This is often the case when there are services that call APIs without users.

OAuth 2.0 Actors

- **Application:** A client that makes protected requests using the authorization of the resource owner.
- **Authorization Server:** The Single Sign-On server that issues access tokens to client applications after successfully authenticating the resource owner.
- **Resource Server:** The server that hosts protected resources and accepts and responds to protected resource requests using access tokens. Applications access the server through APIs.

Client Credentials Flow



1. **Authenticate w/ Client ID and Secret:** The application authenticates with the authorization server using its client ID and client secret.
2. **Issue Access Token:** The authorization server validates the client ID and client secret and issues an access token.
3. **Request Resource w/ Access Token:** The application attempts to access the resource from the resource server by presenting the access token.
4. **Return Resource:** If the access token is valid, the resource server returns the resources to the application.

The resource server runs in PCF under a given space and organization. Developers set the permissions for the resource server API endpoints. To do this, they create resources that correspond to API endpoints secured by the Single Sign-On service. Administrators can create admin clients to perform automated management actions without a user. See [Create Admin Client](#).


Single-Page Javascript App

This topic describes the OAuth 2.0 implicit grant type supported by Pivotal Single Sign-On (SSO). The implicit grant type is for applications with a client secret that is not guaranteed to be confidential.

OAuth 2.0 Roles

- **Resource Owner:** A person or system capable of granting access to a protected resource.
 - **Application:** A client that makes protected requests using the authorization of the resource owner.
 - **Authorization Server:** The Single Sign-On server that issues access tokens to client applications after successfully authenticating the resource owner.
 - **Resource Server:** The server that hosts protected resources and accepts and responds to protected resource requests using access tokens.
- Applications access the server through APIs.

Implicit Flow



1. **Access Application:** The user accesses the application and triggers authentication and authorization.
2. **Authentication and Request Authorization:** The application prompts the user for their username and password. The first time the user goes through this flow for the application, the user sees an approval page. On this page, the user can choose permissions to authorize the application to access resources on their behalf.
3. **Authentication and Grant Authorization:** The authorization server receives the authentication and authorization grant.
4. **Issue Access Token:** The authorization server validates the authorization code and returns an access token with the redirect URL.
5. **Request Resource w/ Access Token in URL:** The application attempts to access the resource from the resource server by presenting the access token in the URL.
6. **Return Resource:** If the access token is valid, the resource server returns the resources that the user authorized the application to receive.

The resource server runs in PCF under a given space and organization. Developers set the permissions for the resource server API endpoints. To do this, they create resources that correspond to API endpoints secured by the Single Sign-On service. Applications can then access these resources on behalf of users.

Manage Resources

This topic describes how a Space Developer defines resources required by an application bound to a Single Sign-On (SSO) service instance, as well as how an administrator grants resource permissions.

Resources are the API endpoints that users and applications need access to retrieve information from the resource server. Since developers know what endpoints exist for their applications, they are responsible for creating resources. After resources are created, administrators will assign these resources to users and applications so that users can grant applications delegated access to the resources on their behalf.

Create or Edit Resources

If an application requires access to specific resources such as API endpoints, the Space Developer must define permissions for those resources in the SSO dashboard.

1. Log into Apps Manager as a Space Developer.
2. Select the space where your service instance is located.
3. Under **Services**, click **Manage** next to your SSO service instance to launch the SSO dashboard.
4. Click the **Resources** tab.
5. Click **New Resource**.
6. Enter a **Resource Name**.
7. Create **Permissions** that the OAuth client for your application needs to access from the resource server.
 - a. Enter one or more **Attributes** or **Actions** for each permission.
 - b. Enter a **Description** for each permission.
8. Click **Save Resource**. The administrator must create resource permissions so that users can access the resource. See the [Create or Edit Resource Permissions](#) section below for more details.

 **Note:** Space Developers create resources within a space. Space Developers only see the resources created in the spaces they have access to and can only assign those to the applications in those spaces.

Delete Resources

1. Log into Apps Manager as a Space Developer.
2. Click the **Manage** link under the SSO service instance to launch the service dashboard.
3. Click the **Resources** tab.
4. Click your resource.
5. Click **Delete** at the bottom of the page.
6. On the popup, click **Delete Resource** to delete the resource.

 **Note:** Deleting a resource removes it from the permission mappings and from the application. You must reconfigure the updated permissions in both areas.

Create or Edit Resource Permissions

After a Space Developer defines resources required by an application, an administrator must grant access to those resources. SSO allows administrators to map groups of users from the identity provider to the resource permissions defined by the Space Developer.

Once resource permissions mappings are configured, when a user authenticates and obtains a token, the user's group memberships will automatically be mapped into scopes that are directly included in the token.

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your User Account and Authentication (UAA) administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Resource Permissions** for the identity provider that you want to define permissions for.
4. Click **New Permissions Mapping**.
5. Enter a **Group Name**.
6. Click **Select Permissions** to choose the permissions that users in the group should have access to.
7. Click **Save Permissions Mapping**.

 **Note:** Groups with unsupported characters in Permission Mappings are not editable.

Delete Resource Permissions

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> using your User Account and Authentication (UAA) administrator credentials. You can find these credentials in your Pivotal Elastic Runtime tile in Ops Manager under the Credentials tab.
2. Click the plan name and select **Manage Identity Providers** from the dropdown menu.
3. Click **Resource Permissions** for the identity provider that you want to define permissions for.
4. Click the group name of the resource permission you want to delete.
5. Click **Delete** at the bottom of the page.
6. On the popup, click **Delete Permissions Mapping** to delete the resource.

 **Note:** Groups with unsupported characters in Permission Mappings are not editable.

Active Directory Federation Services Integration Guide Overview

Active Directory Federation Services (AD FS) is a standards-based service that securely shares identity information between applications. This documentation describes how to configure a single sign-on partnership between AD FS as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate AD FS with Pivotal Cloud Foundry (PCF), you need the following:

Pivotal

- PCF, version 1.7.0 or later
- Single Sign-On, version 1.1.0 or later

Active Directory Federation Services

- Active Directory Federation Services subscription
- A user with Administrative privileges

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic.

Active Directory Federation Services Integration Guide

Configuring AD FS with SSO

Complete both steps below to integrate your deployment with AD FS and SSO.

1. [Configure Active Directory Federation Services as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure Active Directory Federation Services as an Identity Provider

This topic describes how to set up Active Directory Federation Services (AD FS) as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry (PCF) and AD FS.

Set up SAML in PCF

1. Log in to the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Plans' section of the PCF SSO dashboard. A dropdown menu for the 'ADFS PCF SSO' plan is open, displaying 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' option is highlighted with a red box.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Identity Providers' list. A button labeled 'Configure SAML Service Provider' is highlighted with a red box.

Name	Type	Actions
Internal User Store	Internal User Store	Resource Permissions Group Whitelist
ADFS PCF SSO	SAML	Resource Permissions Group Whitelist

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the 'Configure SAML Service Provider' dialog. A checkbox labeled 'Perform signed authentication requests' is checked. A 'Save' button is highlighted with a red box.


5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.

6. Click **Download Metadata** to download the service provider metadata.


7. Click **Save**.

Set up SAML in Active Directory Federation Services


1. Open the AD FS Management console.
2. Click **Add Relying Party Trust...** in the Actions pane.
3. On the Welcome step, click **Start**.




4. Select Import data about the relying party from a file, enter the path to the downloaded service provider metadata, and click Next.




5. Enter a name for Display name and click Next.




- Leave the default multi-factor authentication selection and click Next.



- Select Permit all users to access this relying party and click Next.




8. Review your settings and click **Next**.
9. Click **Close** to finish the wizard.
10. The claim rule editor should open by default. If it does not, select your Relying Party Trust and click **Edit Claim Rules...** in the Actions pane.
11. Create two claim rules by following these steps:
 - a. Click **Add Rule**.
 - b. Select **Send LDAP Attributes as Claims** for **Claim rule template** and click **Next**.




- c. Enter a **Claim rule name**.
- d. Select **Active Directory** for **Attribute store**.
- e. Select **E-Mail-Addresses** for **LDAP Attribute** and select **E-mail Address** for **Outgoing Claim Type**.

f. Click Finish.



g. Click Add Rule.

h. Select Transform an Incoming Claim for Claim rule template and click Next.




i. Enter a Claim rule name.

j. Select E-Mail Address for Incoming claim type.


k. Select Name ID for Outgoing claim type

l. Select Email for Outgoing name ID format.


m. Click Finish.



12. Double-click on the new Relying Party Trust to open the properties.
13. Select the **Encryption** tab and click **Remove** to remove the encryption certificate.



14. Select the **Advanced** tab and select SHA algorithm for the **Secure hash algorithm** that matches the [SHA Algorithm configured for PCF Elastic Runtime](#).



15. (Optional) If you are using a self-signed certificate, disable CRL checks by following these steps:

- Open Windows Powershell as an Administrator.
- Execute the following command:

```
> set-ADFSRelyingPartyTrust -TargetName "< Relying Party Trust >" -SigningCertificateRevocationCheck None
```

16. (Optional) If you are using a self-signed certificate, add it to the ADFS trust store. Obtain the OpsManager certificate from https://OPS_MANAGER_IP/api/v0/security/root_ca_certificate and add this CA certificate to the ADFS trust store, so ADFS can trust the “Service Provider Key Certificate” certificate signed by OpsManager ROOT CA.

Note: Prior to PCF 1.10+, steps 13 and 14 are required as all PCF components (including SSO tile) have certificates signed by an internal CA. In PCF 1.10+, customers can upload their own CA certificate to PCF.

- (Optional) To specify any application or group attributes that you want to map to users in the ID token, click **Edit Claim Rules...** and configure **Send LDAP Attributes as Claims**.

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.

Download Identity Provider Metadata

1. Download the metadata from your Active Directory Federation Services server at the following URL:

`https://YOUR-ADFS-HOSTNAME/federationmetadata/2007-06/federationmetadata.xml`

Setting up SAML

1. Log in to the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows a 'Plans' section with one item. Below it is a table with two columns: 'Name' and 'Sign In Header'. A dropdown menu is open over the first row, showing 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' option is highlighted with a red box.

Name	Sign In Header
ADFS PCF SSO ▾	example

3. Click **New Identity Provider** to create a new identity provider.

The screenshot shows the 'New Identity Provider' form. It includes fields for 'Identity Provider Name*', 'Identity Provider Description', 'Identity Provider Type*', and sections for 'Identity Provider Metadata' and 'Advanced SAML Settings'. At the bottom right are 'Cancel' and 'Create Identity Provider' buttons.

Identity Provider Name*
This name will show as a link on the login page

Identity Provider Description
Allows _____ to authenticate.

Identity Provider Type*
SAML

Identity Provider Metadata

Identity Provider Metadata URL*
`https://idp.company.com/SAML2`

Fetch Metadata

▶ SAML File Metadata (optional)

Advanced SAML Settings

▶ Attribute mappings (optional)

Create Identity Provider

4. To create a new identity provider, perform the following steps:

- a. Enter an identity provider name in **Identity Provider Name**.

- b. (Optional) Enter a description in **Identity Provider Description**.
 - c. Click **SAML File Metadata (optional)**, then click **Upload Identity Provider Metadata** to upload your metadata XML.
 - d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.
5. Click **Create Identity Provider**.
 6. Click **Resource Permissions**.
 7. Click **New Permissions Mapping** and perform the following steps:
 - a. Enter a **Group Name**.
 - b. For **Select Permissions**, select the permissions to grant to the members of the group from the external identity provider.
 8. Navigate to the identity provider list.
 9. Click **Group Whitelist** and enter the group names from the external identity provider that should be propagated in the ID token.

Testing

This topic describes how an administrator can test the connection between SSO and Active Directory Federation Services (AD FS). An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application. Click on the service instance and click **Manage**.

The screenshot shows the Apps Manager interface. At the top, there are two tabs: "Overview" (selected) and "Settings". Below these are two main sections: "Apps" and "Services".

Apps:

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

Services:

SERVICE	NAME	BOUND APPS	PLAN
 Pivotal Single Sign-On	SI	1	free - (MONTHLY) >

The screenshot shows the "Pivotal Single Sign-On" service instance management page. At the top, it displays the SERVICE (Pivotal Single Sign-On), INSTANCE NAME (SI), and SERVICE PLAN (ADFS PCF SSO). Below this are three buttons: "Manage" (highlighted with a red box), "Docs", and "Support".

Below the service details, there are three tabs: "App Binding (1)" (selected), "Plan", and "Settings".

App Binding (1):

Bound Apps	Edit Bindings
authcode-sample	Edit Bindings

3. Under the **Apps** tab, click your application.

The screenshot shows the Apps Manager interface. On the left, there's a button to 'NEW APP'. In the center, the 'authcode-sample' application is listed. It's categorized as a 'Web App'. Under 'IDENTITY PROVIDER', it shows 'Internal Identity Provider' and 'ADFS PCF SSO'. At the bottom right of the card, it says 'updated 4 days ago'.

4. Under Identity Providers, select the AD FS identity provider.

The screenshot shows the configuration page for the 'authcode-sample' application. At the top, it says 'authcode-sample Web App' and has a 'Next Steps' button. Below that, the 'App Name*' field contains 'authcode-sample'. The 'Identity Providers' section has two options: 'Internal User Store' (selected) and 'ADFS PCF SSO' (highlighted with a red box). The 'Redirect URIs' section lists 'https://authcode-sample.id-service.cf-app.com'. The 'Authorization' section includes 'Scopes' (todo, todo.read, todo.write), 'System Provided' (openid), and a 'Select Scopes' section. The 'Auto-Approved Scopes' section shows 'None selected'. At the bottom, there are 'Delete', 'Cancel', and 'Save Config' buttons.

5. Return to Apps Manager and click on the URL below your application to be redirected to the identity provider to authenticate.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-app... >

6. Click the link.

Authcode sample

What do you want to do?

- [Log in via Auth Code Grant Type](#)


7. On the identity provider sign-in page, enter your credentials and click **Sign in**.

ADFS Single Sign-On

Sign in with your organizational account

Sign in

8. The application asks for authorization to the necessary scopes. Click **Authorize**.



9. The access token and ID token displays.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{
  "user_id" : "5651953a-c864-4073-86b3-4fa97b45a0d1",
  "user_name" : "example@pivotal.io",
  "given_name" : "Example",
  "family_name" : "Example",
  "email" : "example@pivotal.io",
  "name" : "Example Example"
}
```

This is the Access Token that was used:

```
{
  "jti" : "bbe64fd09cbf4ed4a4fdf17c3ea8af04",
  "sub" : "5651953a-c864-4073-86b3-4fa97b45a0d1",
  "scope" : [ "todo.read", "openid", "todo.write" ],
  "client_id" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "cid" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "azp" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "grant_type" : "authorization_code",
  "user_id" : "5651953a-c864-4073-86b3-4fa97b45a0d1",
  "origin" : "ADFS PCF SSO",
  "user_name" : "example@pivotal.io",
  "email" : "example@pivotal.io",
  "auth_time" : 1472753888,
  "rev_sig" : "6f09b81d",
  "iat" : 1472753930,
  "exp" : 1472797130,
  "iss" : "https://example.uaa/oauth/token",
  "zid" : "2852ad03-e828-4200-9d7a-e04af30fe5bd",
  "aud" : [ "todo", "openid", "bbf58e64-14f1-46b4-9fd5-ca267376ec4c" ]
}
```

This is the ID Token:

```
{
  "sub" : "5651953a-c864-4073-86b3-4fa97b45a0d1",
  "user_name" : "example@pivotal.io",
  "origin" : "ADFS PCF SSO",
  "iss" : "https://example.uaa/oauth/token",
  "user_attributes" : { },
  "client_id" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "aud" : [ "bbf58e64-14f1-46b4-9fd5-ca267376ec4c" ],
  "zid" : "2852ad03-e828-4200-9d7a-e04af30fe5bd",
  "grant_type" : "authorization_code",
  "user_id" : "5651953a-c864-4073-86b3-4fa97b45a0d1",
  "azp" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "scope" : [ "openid" ],
  "auth_time" : 1472753888,
  "exp" : 1472797130,
  "iat" : 1472753930,
  "jti" : "bbe64fd09cbf4ed4a4fdf17c3ea8af04",
  "email" : "example@pivotal.io",
  "rev_sig" : "6f09b81d",
  "cid" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c"
}
```

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection

 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

1. Sign in to AD FS.

ADFS Single Sign-On

Sign in with your organizational account

Sign in

2. Navigate to your application and click it.
3. You are redirected to the page that lists applications you have access to.

The screenshot shows a web application interface. At the top left is a user profile icon with the letter 'E' and the email 'example@pivotal.io'. To its right is a 'Sign out' link. On the far right is the 'Pivotal' logo. Below the header is a navigation bar with tabs: 'Apps' (which is underlined in blue), 'Profile', 'Security', 'Approvals', and 'Notifications'. The main content area displays three application cards, each featuring a teal circular icon with a white 'P' and the text 'Application 1' or 'Application 2'. At the bottom of the page is a footer with the text '©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#)'.

Test Your Single Sign-Off

Test single sign-off to ensure that when users log out of the application, they are logged out of AD FS as well.

1. Sign in to the sample application. Information about the access and ID token displays, as well as the "What do you want to do?" section.
2. Under "What do you want to do?", click **Log out**.

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. You are logged out and redirected to the AD FS login page.

ADFS Single Sign-On

Sign in with your organizational account


Troubleshooting

This topic describes how to resolve errors that arise when configuring a single sign-on partnership between Active Directory Federation Services and Pivotal Single Sign-On (SSO).

Event Viewer

1. Navigate to Administrative Tools.

2. Launch Event Viewer.



3. Examine any errors and its details to diagnose problems.

Azure Active Directory Integration Guide Overview

Azure Active Directory (Azure AD) is Microsoft's multi-tenant cloud based directory and identity management service. This documentation describes how to configure a single sign-on partnership between Azure AD as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry® as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate Azure AD with Pivotal Cloud Foundry® (PCF), you need:

Pivotal

- PCF, version 1.7.0 or later.
- Single Sign-On, version 1.1.0 or later.

Azure Active Directory

- Azure Active Directory subscription.
- A user with admin privileges.

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic.

Azure AD Integration Guide

Configuring Azure AD with SSO

Complete both steps below to integrate your deployment with Azure AD and SSO.

1. [Configure Azure AD as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure Azure Active Directory as an Identity Provider

This topic describes how to set up Azure Active Directory (AD) as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry® (PCF) and Azure AD.

Set up SAML in PCF

1. Log into the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Plans' section of the PCF SSO dashboard. A single plan named 'Azure PCF SSO' is listed. Below the plan name, there are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red box.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Identity Providers' page under the 'Azure PCF SSO' plan. It lists two providers: 'Internal User Store' (Type: Internal User Store) and 'Azure PCF SSO' (Type: SAML). Below the table, there are 'Resource Permissions' and 'Group Whitelist' links. The 'Configure SAML Service Provider' button is highlighted with a red box.

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the 'Configure SAML Service Provider' dialog. It includes a checkbox for 'Perform signed authentication requests' (which is checked), a checkbox for 'Require signed assertions' (which is unchecked), and a 'Save' button. A 'Download Metadata' link is also visible.

5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.

6. Click **Download Metadata** to download the service provider metadata.

7. Click **Save**.

Set up SAML in Azure Active Directory

1. Sign into Azure AD at <https://manage.windowsazure.com> as an administrator.
2. Navigate to the applications dashboard by clicking on your directory and the Applications tab.
3. Click the **Add** button to add a new application.

The screenshot shows the Microsoft Azure Active Directory portal. The top navigation bar includes 'Microsoft Azure' with a dropdown, a link to 'Check out the new portal', and a user 'admin'. The main title is 'example directory'. Below the title, there are tabs for 'USERS', 'GROUPS', 'APPLICATIONS', 'DOMAINS', 'DIRECTORY INTEGRATION', 'CONFIGURE', 'REPORTS', and 'LICENSES'. A search bar at the top right allows filtering by 'Applications my company uses' or 'Application name or Client ID'. The main content area displays a table with one row for 'Office 365 Management APIs', which is a 'Web application' published by 'Microsoft Corporation'. At the bottom, there is a dark navigation bar with icons for 'NEW', 'ADD' (highlighted with a red box), 'VIEW ENDPOINTS', and 'DELETE'.

4. Select Add an application my organization is developing

The screenshot shows the Microsoft Azure Active Directory portal with a modal dialog box overlaid. The dialog box has a title 'What do you want to do?' and two options: 'Add an application my organization is developing' and 'Add an application from the gallery'. The first option is highlighted with a red box. The background shows the same 'example directory' Applications page as the previous screenshot, with the 'ADD' button also highlighted with a red box in the bottom navigation bar.

5. Enter the Name and Type for the application.

Microsoft Azure | Check out the new portal | admin

example directory

USERS GROUPS APPLICATIONS DOMAINS DIRECTORY INTEGRATION CONFIGURE REPORTS LICENSES

Show Applications my company uses Search Application name or Client ID

ADD APPLICATION

Tell us about your application

NAME

Type

WEB APPLICATION AND/OR WEB API ?

NATIVE CLIENT APPLICATION ?

APP URL

2

NEW ADD VIEW ENDPOINTS DELETE ?

- Enter the **Sign-On URL** and **App ID URI** for the application.

Microsoft Azure | Check out the new portal | admin

example directory

USERS GROUPS APPLICATIONS DOMAINS DIRECTORY INTEGRATION CONFIGURE REPORTS LICENSES

Show Applications my company uses Search Application name or Client ID

ADD APPLICATION

App properties

SIGN-ON URL

APP ID URI

1 2

← → ?

NEW ADD VIEW ENDPOINTS DELETE ?

- Click the application and configure the following properties:

- a. Enter the application **Name**.
- b. Enter the **AssertionConsumerService Location URL** from your downloaded service provider metadata into **Sign-On URL**. For example, `https://AUTH-DOMAIN/saml/SSO/alias/AUTH-DOMAIN`.
- c. Configure the application **Logo**, **Application is Multi-Tenant** and **User Assignment Required to Access App** properties.
- d. Enter your **Auth Domain URL** into **App ID URI**.
- e. Enter the **AssertionConsumerService Location URL** from your downloaded service provider metadata into **Reply URL**.

Microsoft Azure | v Check out the new portal admin

example app

DASHBOARD USERS CONFIGURE OWNERS

Example App Office 365 Manage...

properties

NAME Example App

SIGN-ON URL <http://example.login.id-service.cf-app.com/saml/SSO/alias/example.login>

LOGO 

APPLICATION IS MULTI-TENANT YES NO

CLIENT ID e06bacb9-c697-4ab8-a231-907db9a647d9

USER ASSIGNMENT REQUIRED TO ACCESS APP YES NO

keys

Select dur... VALID FROM EXPIRES ON THE KEY VALUE WILL BE DISPLAYED AFTER YOU SAVE IT.

single sign-on

APP ID URI <http://example.login.id-service.cf-app.com>

REPLY URL <https://example.login.id-service.cf-app.com/saml/SSO/alias/ex> (ENTER A REPLY URL)

permissions to other applications

Windows Azure Active Directory Application Permissions: 1 Delegated Permissions: 5

Add application

Actions

NEW VIEW ENDPOINTS UPLOAD LOGO MANAGE DELETE SAVE DISCARD

- Click the Save button.

9. Click **View Endpoints** and download the **Federation Metadata Document**

The screenshot shows the Microsoft Azure portal interface. On the left is a sidebar with various icons. The main area shows an application named "example app". Under "properties", there's a "SIGN-ON URL" field containing "https://example.login.id-service.cf-app.com/saml/SSO/alias/example.login". A modal window titled "App Endpoints" is open, displaying a list of endpoints. The "FEDERATION METADATA DOCUMENT" endpoint, which is "https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287", is highlighted with a red box.

Endpoint Type	Endpoint URL
FEDERATION METADATA DOCUMENT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287
WS-FEDERATION SIGN-ON ENDPOINT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287
SAML-P SIGN-ON ENDPOINT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287
SAML-P SIGN-OUT ENDPOINT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287
MICROSOFT AZURE AD GRAPH API ENDPOINT	https://graph.windows.net/025c050a-9f19-4074-882f-4b522871e8c3
OAUTH 2.0 TOKEN ENDPOINT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287
OAUTH 2.0 AUTHORIZATION ENDPOINT	https://login.microsoftonline.com/025c050a-9f19-4074-882f-4b52287

Set up Claims Mapping

- To enable user attribute mappings, grant the application the following permissions to Windows Azure Active Directory:

- Read directory data.
- Read all groups.
- Read all users' full profiles or Read all users' basic profiles.

permissions to other applications

Windows Azure Active Directory

Application Permissions: 1	Delegated Permissions: 5
<input checked="" type="checkbox"/> Read directory data	
<input type="checkbox"/> Read and write domains	
<input type="checkbox"/> Read and write directory data	
<input type="checkbox"/> Read and write devices	

Add application

NEW VIEW ENDPOINTS UPLOAD LOGO MANAGE MANIFEST DELETE SAVE DISCARD

2. To pass group membership claims to the application, perform the following steps:

- a. Click **Manage Manifest**.
- b. Click **Download Manifest** followed by **Download manifest**.
- c. Locate `groupMembershipClaims` and set the value to either:
 - `SecurityGroup` - Groups claim will contain identifiers of all security groups of which the user is a member.
 - `All` - Groups claim will contain the identifiers of all security groups and distribution lists of which the user is a member.
- d. Click **Manage Manifest**.
- e. Click **Upload Manifest** and select the modified manifest.

permissions to other applications

Windows Azure Active Directory Application Permissions: 1 Delegated Permissions: 5

Add application


VIEW ENDPOINTS UPLOAD LOGO MANAGE MANIFEST DELETE

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.


Setting up SAML

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.



The screenshot shows the 'Plans' section of the Pivotal SSO dashboard. A single plan named 'Azure PCF SSO' is listed. Below the plan name, there are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red rectangle.

3. Click **New Identity Provider** to create a new identity provider.



The screenshot shows the 'New Identity Provider' configuration page. It includes fields for 'Identity Provider Name*', 'Identity Provider Description', 'Identity Provider Type*', and 'Identity Provider Metadata URL*'. There are also sections for 'Advanced SAML Settings' and a note about file imports. At the bottom right are 'Cancel' and 'Create Identity Provider' buttons.

Identity Provider Name*
This name will show as a link on the login page

Identity Provider Description
Allows Enter a group name to authenticate.

Identity Provider Type*
SAML

Identity Provider Metadata

Identity Provider Metadata URL*
 https://idp.company.com/SAML2

Fetch Metadata

▶ SAML File Metadata (optional)

Advanced SAML Settings

▶ Attribute mappings (optional)

Create Identity Provider

4. To create a new identity provider, perform the following steps:

- a. Enter an identity provider name into **Identity Provider Name**.
- b. (Optional) Enter a description into **Identity Provider Description**.
- c. Click **SAML File Metadata (optional)** followed by clicking the **Upload Identity Provider Metadata** button to upload your metadata XML.



Note: The Single Sign-On does not support DOS file format imports. Convert the file in one of the following ways:

- Option 1: Execute `dos2unix` on the metadata file.

- Option 2: Create a Unix file, then copy and paste the contents from the downloaded metadata file to the newly created file.

d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.

5. Click **Create Identity Provider**.

Configure Group Permissions

1. Add groups to be propagated from the external identity provider to the ID token by following these steps:

- a. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` as a Plan Administrator.
- b. Select your plan and click **Manage Identity Providers** on the dropdown menu.
- c. Click **Group Whitelist** next to your identity provider.
- d. Enter the group names.
- e. Click **Save Group Whitelist**.

2. Map the groups to resources defined in the SSO service by following these steps:

- a. Log into the SSO dashboard at `https://p-identity.YOUR-SYSTEM-DOMAIN` as a Plan Administrator.
- b. Select your plan and click **Manage Identity Providers** on the dropdown menu.
- c. Click **Resource Permissions**.
- d. Click **New Permissions Mapping** and perform the following steps:
 - i. Enter a **Group Name**.
 - ii. For **Select Permissions**, select the permissions that the members of the group from the external identity provider should have access to.
 - iii. Click **Save Permissions Mapping**.

Testing

This topic describes how an administrator can test the connection between SSO and Azure Active Directory. An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application. Click on the service instance and click **Manage**.

The screenshot shows the Apps Manager interface. At the top, there are two tabs: "Overview" (selected) and "Settings". Below these are two main sections: "Apps" and "Services".

Apps: A table with columns: NAME, INSTANCES, MEMORY, LAST PUSH, and ROUTE. One row is shown for "authcode-sample" with 1 instance, 512MB memory, last pushed 4 days ago, and a route to <http://authcode-sample.id-service.cf-ap...>.

Services: A table with columns: SERVICE, NAME, BOUND APPS, and PLAN. One row is shown for "Pivotal Single Sign-On" with an instance name "SI", 1 bound app, and a free - (MONTHLY) plan.

The screenshot shows the management page for the "Pivotal Single Sign-On" service instance. At the top, it displays the SERVICE (Pivotal Single Sign-On), INSTANCE NAME (SI), and SERVICE PLAN (Azure PCF SSO). Below this are three buttons: "Manage" (highlighted with a red box), "Docs", and "Support".

Below the service details, there are three tabs: "App Binding (1)" (selected), "Plan", and "Settings". Under "App Binding (1)", there is a table titled "Bound Apps" with one entry: "authcode-sample". To the right of this table is a button labeled "Edit Bindings".

3. Under the **Apps** tab, click your application.

The screenshot shows the Pivotal Apps Manager interface. On the left, there's a button labeled 'NEW APP'. To its right, the application 'authcode-sample' is listed. It is categorized as a 'Web App'. The 'IDENTITY PROVIDER' section shows 'Internal Identity Provider' and 'Azure PCF SSO' as options. Below this, it says 'updated 4 days ago'.

4. Under Identity Providers, select the Azure AD identity provider.

The screenshot shows the configuration page for the 'authcode-sample' application. In the 'Identity Providers' section, two options are available: 'Internal User Store' and 'Azure PCF SSO'. The 'Azure PCF SSO' option is highlighted with a red box. Other sections visible include 'Redirect URIs' (with a single entry: 'https://authcode-sample.id-service.cf-app.com'), 'Authorization' (with 'Scopes' like 'todo.read' and 'todo.write' under 'System Provided' and 'openid' under 'Select Scopes'), and 'Auto-Approved Scopes' (which is currently empty). At the bottom right are 'Cancel' and 'Save Config' buttons.

5. Return to Apps Manager and click on the URL below your application to be redirected to the identity provider to authenticate.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-app... >

6. Click the link.

Authcode sample

What do you want to do?

- Log in via Auth Code Grant Type

7. On the identity provider sign-in page, enter your credentials and click **Sign In**.

Microsoft Azure

Work or school, or personal Microsoft account

Email or phone


Password

Keep me signed in

Sign in Back

[Can't access your account?](#)

8. The application asks for authorization to the necessary scopes. Click **Authorize**.



9. The access token and ID token displays.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{
  "user_id" : "57a4a8e4-d5fc-426c-861d-78c8588fc65b",
  "user_name" : "acAv4K7uBrkDx9ehb9pfAsU3whJqBIIuobxd9DHMayM",
  "given_name" : "Example",
  "family_name" : "Example",
  "email" : "example@pivotal.io",
  "name" : "Example Example"
}
```

This is the Access Token that was used:

```
{
  "jti" : "80785d63a02f4fef8fc5e6d65bcb2136",
  "sub" : "57a4a8e4-d5fc-426c-861d-78c8588fc65b",
  "scope" : [ "todo.read", "openid", "todo.write" ],
  "client_id" : "d3092f73-ab0c-495d-91ea-79772d8d93ee",
  "cid" : "d3092f73-ab0c-495d-91ea-79772d8d93ee",
  "azp" : "d3092f73-ab0c-495d-91ea-79772d8d93ee",
  "grant_type" : "authorization_code",
  "user_id" : "57a4a8e4-d5fc-426c-861d-78c8588fc65b",
  "origin" : "Azure PCF SSO",
  "user_name" : "acAv4K7uBrkDx9ehb9pfAsU3whJqBIIuobxd9DHMayM",
  "email" : "example@pivotal.io",
  "auth_time" : 1469645071,
  "rev_sig" : "6dade7f6",
  "iat" : 1469645071,
  "exp" : 1469688271,
  "iss" : "https://example.uaa/oauth/token",
  "zid" : "dbff701b-1a02-4a0f-a141-47b2acdd5a30",
  "aud" : [ "todo", "openid", "d3092f73-ab0c-495d-91ea-79772d8d93ee" ]
}
```

This is the ID Token:

```
{
  "sub" : "57a4a8e4-d5fc-426c-861d-78c8588fc65b",
  "user_name" : "acAv4K7uBrkDx9ehb9pfAsU3whJqBIIuobxd9DHMayM",
  "origin" : "Azure PCF SSO",
  "iss" : "https://example.uaa/oauth/token",
  "client_id" : "d3092f73-ab0c-495d-91ea-79772d8d93ee",
  "aud" : [ "d3092f73-ab0c-495d-91ea-79772d8d93ee" ],
  "zid" : "dbff701b-1a02-4a0f-a141-47b2acdd5a30",
  "grant_type" : "authorization_code",
  "user_id" : "57a4a8e4-d5fc-426c-861d-78c8588fc65b",
  "azp" : "d3092f73-ab0c-495d-91ea-79772d8d93ee",
  "scope" : [ "openid" ],
  "auth_time" : 1469645071,
  "exp" : 1469688271,
  "iat" : 1469645071,
  "jti" : "80785d63a02f4fef8fc5e6d65bcb2136",
  "email" : "example@pivotal.io",
  "rev_sig" : "6dade7f6",
  "cid" : "d3092f73-ab0c-495d-91ea-79772d8d93ee"
}
```

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection

 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

- Sign in to Azure AD.

Microsoft Azure

Work or school, or personal Microsoft account

Email or phone
Password

Keep me signed in

Sign in Back

[Can't access your account?](#)

2. Navigate to your application and click it.
3. You are redirected to the page that lists applications you have access to.

The screenshot shows a user profile with the email example@example.com and a sign-out link. Below the profile, there is a navigation bar with tabs: Apps (which is underlined), Profile, Security, Approvals, and Notifications. Under the Apps tab, there are three application cards, each featuring a teal circle with a white 'P' and the application name: Application 1, Application 2, and Application 2 (repeated). At the bottom of the screen, there is a copyright notice: ©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#).

Test Your Single Sign-Off

Test single sign-off to ensure that when users log out of the application, they are logged out of Azure AD as well.

1. Sign into the sample application. Information about the access and ID token displays, as well as the “What do you want to do?” section.
2. Under “What do you want to do?”, click **Log out**.

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. You are logged out and redirected to the Azure AD login page.

Microsoft Azure

Work or school, or personal Microsoft account

Email or phone
 Password

Keep me signed in

Sign in Back

[Can't access your account?](#)

Troubleshooting

This topic describes how to resolve common errors that arise when configuring a single sign-on partnership between Azure Active Directory and Pivotal Single Sign-On (SSO).

App ID Not Found

Symptom:

Sign In

Sorry, but we're having trouble signing you in.

We received a bad request.

Additional technical information:
Correlation ID: 33100be1-d5af-409f-aa63-59784905e8fe
Timestamp: 2016-07-27 22:02:30Z
AADSTS70001: Application with identifier 'http://example.cf-app.com' was not found in the directory 025c050a-9f19-4074-882f-4b522871e8c3

Explanations:

- The App ID URI is misconfigured on Azure AD.

Reply URL Does Not Match

Symptom:

Sign In

Sorry, but we're having trouble signing you in.

We received a bad request.

Additional technical information:
Correlation ID: 148c57c2-6082-493c-9dd9-2c646bf0f0b9
Timestamp: 2016-07-27 22:03:47Z
AADSTS50011: The reply address 'https://example.cf-app.com/saml/SSO/alias/example.cf-app.com' does not match the reply addresses configured for the application: http://example.cf-app.com.

Explanation:

- The Reply URL is misconfigured on Azure AD.

Missing Name ID

Symptom:

Identity Provider Metadata

Identity Provider Metadata URL*

Fetch Metadata

Error processing metadata

▼ SAML File Metadata (optional)

Upload Identity Provider Metadata federationmetadata.xml

Explanation:

- The identity provider metadata has the `RoleDescriptor` elements or is missing configurations for Name ID. See [Configure Identity Provider Metadata](#).

CA Single Sign-On Integration Guide Overview

CA Single Sign-On (formerly known as CA SiteMinder) is a Web Access Management system that supports advanced authentication, risk-based security policies, and federated identities. This documentation describes how to configure a single sign-on partnership between CA Single Sign-On as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate CA Single Sign-On with Pivotal Cloud Foundry (PCF), you need the following:

Pivotal

- PCF, version 1.7.0 or later
- Single Sign-On, version 1.1.0 or later

CA Single Sign-On

- CA Single Sign-On 12.52
- A Signed Certificate by a Certificate Authority

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic..

CA Single Sign-On Integration Guide

Configuring CA Single Sign-On with SSO

Complete both steps below to integrate your deployment with CA Single Sign-On and SSO.

1. [Configure CA Single Sign-On as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure CA Single Sign-On as an Identity Provider

This topic describes how to set up CA Single Sign-On as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry (PCF) and CA Single Sign-On.

Set up SAML in PCF

1. Log in to the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Identity Providers' section of the PCF SSO dashboard. At the top, there's a 'Plans' section with a 'New Plan' button. Below it is a table with columns for 'Name' and 'Sign In Header'. A dropdown menu is open under 'Name', showing 'CA SSO PCF SSO' and other options. Under 'Sign In Header', there's a field with 'example'. At the bottom of the table, there are two buttons: 'Edit Plan' and 'Manage Identity Providers', with the latter being highlighted by a red box.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Configure SAML Service Provider' page. At the top, it says 'Plans > CA SSO PCF SSO > Identity Providers'. Below that is a table with columns for 'Name', 'Type', and 'Actions'. It lists two entries: 'Internal User Store' (Type: Internal User Store) and 'CA SSO PCF SSO' (Type: SAML). Under the 'Actions' column for the SAML entry, there are 'Resource Permissions' and 'Group Whitelist' links. At the top right of the table, there's a 'Configure SAML Service Provider' button, which is highlighted with a red box.

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the configuration page for the SAML Service Provider. It has a 'Configure SAML Service Provider' header. Below it, there are two checkboxes: 'Perform signed authentication requests' (which is checked) and 'Require signed assertions'. At the bottom right is a 'Save' button, which is highlighted with a blue box. To the right of the 'Save' button is a 'Download Metadata' link.

5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.

6. Click **Download Metadata** to download the service provider metadata.

7. Click **Save**.

Set up SAML in CA Single Sign-On

1. Sign in as a CA Single Sign-On administrator.
2. Click the **Federation** tab.
3. Click on the **Entities** link.
4. Click the **Create Entity** button and perform the following steps:
 - a. Select **Local for Entity Location**.
 - b. Select **SAML2 IDP** for **New Entity Type**.

c. Click the **Next** button.

5. In the **Entities** section, perform the following steps:

- Enter an **Entity ID**.
- Enter an **Entity Name**.
- Enter a **Description**.
- Enter the fully-qualified domain name for your CA Single Sign-On as the **Base URL**.
- Select or import a **Signing Private Key Alias**.
- Select a **Name ID format**.
- Click the **Next** button.

6. Confirm the Entity Details and click the **Finish** button.

The screenshot shows the 'View Federation Entities > View Entity' interface. The 'Entity Type' is set to 'SAML2 IDP'. The 'Entity ID' is 'smidp' and the 'Entity Name' is 'smidp'. The 'Base URL' is 'https://sc5.casecurecenter.com'. The 'Description' field contains 'Default SLO Confirm URL: https://sc5.casecurecenter.com/affwebservices/public/saml2slo'. Other URLs listed include 'SSO Service URL', 'SLO Service URL', 'SOAP Service URL', 'User Consent Service URL', 'Attribute Service URL', and 'SOAP Manage NameID Service URL'. The 'Default Signature and Encryption Options' section shows 'Signing Private Key Alias: signingcert' and 'Signed Authentication Requests Required: No'. The 'Supported Name ID Formats and Attributes' section lists supported formats like 'Email Address' and 'Unspecified'.

7. Click the **Federation** tab.

8. Click on the **Entities** link.

9. Click the **Import Metadata** button and perform the following steps:

- Click **Browse** and select the downloaded metadata for **Metadata file**.
- Select **Remote Entity** for **Import As**.
- Select **Create New** for **Operation**.
- Click the **Next** button.

10. In the **Select Entity Defined in Metadata File** section, perform the following steps:

- Enter an **Entity Name**.
- Click the **Next** button.

11. In the **Select Key Entries to Import** section, perform the following steps:

- Enter an **Alias**.
- Click the **Next** button.

12. Confirm the Entity Details and click the **Finish** button.

The screenshot shows the 'View Federation Entities > View Entity' interface. The 'Entity Type' is set to 'SAML2 SP'. The 'Entity ID' is 'http://sso.login.coral.springapps.io' and the 'Entity Name' is 'pdl-corral'. The 'Description' field contains 'pdl-corral imported via metadata'. The 'Remote Assertion Consumer Service URLs' section lists two entries: 'Index' 0 (Binding: HTTP-POST, URL: https://sso.login.coral.springapps.io/saml/SSO/alias/sso.login.coral.springapps.io) and 'Index' 1 (Binding: HTTP-Artifact, URL: https://sso.login.coral.springapps.io/saml/SingleLogoutService/alias/sso.login.coral.springapps.io). The 'Remote SLO Service URLs' section lists two entries: 'Binding' (HTTP-POST, URL: https://sso.login.coral.springapps.io/saml/SingleLogoutService/alias/sso.login.coral.springapps.io) and 'Binding' (HTTP-Redirect, URL: https://sso.login.coral.springapps.io/saml/SingleLogoutService/alias/sso.login.coral.springapps.io). The 'Signature and Encryption Options' section shows 'Verification Certificate Alias: pdl-corral' and 'Encryption Certificate Alias: pdl-corral'. The 'Name ID Formats' section lists supported formats like 'Email Address' and 'Unspecified'.

13. Click on the **Federation** tab.

14. Click **Create Partnership** and select **SAML2 IDP -> SP**.

15. In the **Configure Partnership** section, perform the following steps:

- Enter a **Partnership Name**.
- Enter a **Description**.
- Select a previously created local entity for **Local IDP**.
- Select a previously created remote entity for **Remote SP**.
- Enter a **Skew Time**.
- Add any **User Directories**.
- Click the **Next** button.

The screenshot shows the 'Configure Partnership' step of a partnership configuration wizard. It includes fields for Partnership Name (pcf-corral-sso), Description, Local IDP IDP, Remote SP IDP, Base URL, Skew Time, and User Directories. A note says changes won't be automatically reflected; 'Get Updates' buttons are available for both entities. Below, a list of available directories is shown, with 'netauto' selected.

- Configure **Federation Users** by adding the users you want to include in the partnership and click **Next**.

The screenshot shows the 'Federation Users' step. It lists 'Federated Users' with columns for Directory (netauto) and User Class (All Users in Directory). An 'Add Row' button is available.

- In the **Assertion Configuration** section, perform the following steps:

- Select a **Name ID Format**.
- Select **User Attribute** as the **Name ID Type**.
- Enter `mail` as the **Value**.
- (Optional) Under **Assertion Attributes**, specify any application or group attributes that you want to map to users in the ID token.

Note: The value for sending a user's groups is **FMATTR:SM_USERGROUPS**.

- Click the **Next** button.

The screenshot shows the 'Assertion Configuration' step. It includes a note about supported formats, a table for 'Assertion Attributes' (roles, mail), and a 'Plug-in Class' section.

Assertion Attributes	Retrieval Method	Format	Type	Value	DN Spec	Encrypt
roles	SSO	URI	User Attribute	FMATTR:SM_USERGROUPS	regEx	No
mail	SSO	URI	User Attribute	mail	regEx	No

- In the **SSO and SLO** section, perform the following steps:

- Enter the **Authentication URL**.
- Select **HTTP-Post** for **SSO Binding**.
- Select **Both IDP and SP initiated** for **Transactions Allowed**.
- Click the **Next** button.

Idle Timeout: 1 : 0 (Hours:Minutes)
Maximum Timeout: 2 : 0 (Hours:Minutes)

Enable Enhanced Session Assurance:

- Authentication Request Binding: HTTP-Redirect
- SSO Binding: HTTP-Artifact
- Audience: Accept ACS URL in the AuthnRequest
- Transactions Allowed: 0 and 0 instances
- SSO Validity Duration (Seconds): 60

Recommended SP Session Duration: Use Assertion Validity - Customize

- Enable Negative Authentication Response
- Enable User Consent

User Consent Service URL: https://p6.casemanagercenter.com/affwebservices/public/saml2userconsent
User Consent Post Form: https://p6.casemanagercenter.com/affwebservices/public/saml2userconsent

Minimum Authentication Level: S
Custom Post Form: Set 'OneTimeUse' Condition

Validation Period: 0 : 0 : 0 (Hours:Minutes:Seconds)

Consumer Service URLs

X	Binding	URL	Default
	HTTP-POST	https://sso.login.coral.springapps.io/saml/SSO/alias/sso.login.coral.springapps	<input checked="" type="checkbox"/>

19. In the **Signature and Encryption** section, perform the following steps:

- Select your key alias for **Signing Private Key Alias**.
- Select your certificate alias for **Verification Certificate Alias**.
- Click the **Next** button.

Signature

- Disable Signature Processing
- Signing Private Key Alias: ssignpost
- Signing Algorithm: RSAwithSHA-256
- Verification Certificate Alias: ssign
- Artifact Signature Options: sign neither
- Post Signature Options: sign both
- Require Signed Authentication Requests
- Require Signed ArtifactResolve
- Sign ArtifactResponse

Encryption

- Encryption Options: Encrypt Name ID
- Encryption Certificate Alias: select one
- Block Algorithms: SHA-256
- Key Algorithms: RSA-VIS
- Decryption Private Key Alias: select one

20. Confirm the Partnership Details and click the **Finish** button.

21. Click the **Action** button and click **Activate**.

Federation Partnership List							Create Partnership
Actions	Name	Local Type	Remote Type	Remote Entity ID	Status	FIPS Status	
Action	pc-coral-con	SAML2 IDP	smpidp	SAML2 SP	http://sso.login.coral.springapps.io	Defined	
Action	pc-coral-con	IDP	smpidp	SAML2 SP	https://myclouddemo-dev-ed.my.salesforce.com	Active	
Action	pc-coral-con	IDP	smpidp	SAML2 SP	ssotest.login.run.pivotal.io	Active	

22. Click the **Action** button and click **Export Metadata**.

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.

Setting up SAML

1. Log in to the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Plans' section of the Pivotal SSO dashboard. A dropdown menu is open under a plan named 'CASSO PCF SSO'. The 'Manage Identity Providers' option is highlighted with a red box.

3. Click **New Identity Provider** to create a new identity provider.

The screenshot shows the 'New Identity Provider' creation form. It includes fields for 'Identity Provider Name*', 'Identity Provider Description', 'Identity Provider Type*', and 'Identity Provider Metadata URL*'. There are also sections for 'Advanced SAML Settings' and buttons for 'Cancel' and 'Create Identity Provider'.

Identity Provider Name*
This name will show as a link on the login page

Identity Provider Description
Allows _____ to authenticate.

Identity Provider Type*
SAML

Identity Provider Metadata

Identity Provider Metadata URL*
https://idp.company.com/SAML2

Fetch Metadata

▶ SAML File Metadata (optional)

Advanced SAML Settings

▶ Attribute mappings (optional)

Create Identity Provider

4. To create a new identity provider, perform the following steps:
 - a. Enter an identity provider name in **Identity Provider Name**.
 - b. (Optional) Enter a description in **Identity Provider Description**.
 - c. Click **SAML File Metadata (optional)** followed by clicking the **Upload Identity Provider Metadata** button to upload your metadata XML.
 - d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.
5. Click **Create Identity Provider**.
6. Click **Resource Permissions**.

7. Click **New Permissions Mapping** and perform the following steps:
 - a. Enter a **Group Name**.
 - b. For **Select Permissions**, select the permissions that the members of the group from the external identity provider should have access to.
8. Navigate to the identity provider list.
9. Click **Group Whitelist** and enter the group names from the external identity provider that should be propagated in the ID token.

Testing

This topic describes how an administrator can test the connection between SSO and CA Single Sign-On. An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application. Select the service instance and click **Manage**.

The screenshot shows the Apps Manager interface. At the top, there are two tabs: "Overview" (selected) and "Settings". Below these are two main sections: "Apps" and "Services".

Apps:

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-app... >

Services:

SERVICE	NAME	BOUND APPS	PLAN
 Pivotal Single Sign-On	SI	1	free - (MONTHLY) >

A red box highlights the "Manage" link next to the "Pivotal Single Sign-On" service instance.

The screenshot shows the details for the "Pivotal Single Sign-On" service instance. At the top, it displays the SERVICE, INSTANCE NAME (SI), and SERVICE PLAN (CA SSO PCF SSO). Below this are three buttons: "Manage" (which is highlighted with a red box), "Docs", and "Support".

Under the "App Binding (1)" tab, there is a "Bound Apps" section which lists "authcode-sample". A "Edit Bindings" button is located in the top right corner of this section.

3. Under the **Apps** tab, click your application.

The screenshot shows the Pivotal Apps Manager interface. On the left, there's a button labeled 'NEW APP'. To its right, the application 'authcode-sample' is listed. It is categorized as a 'Web App'. The 'IDENTITY PROVIDER' section shows 'Internal Identity Provider' and 'CA SSO PCF SSO' as options. Below this, it says 'updated 4 days ago'.

4. Under Identity Providers, select the CA Single Sign-On identity provider.

The screenshot shows the configuration page for the 'authcode-sample' application. In the 'Identity Providers' section, two options are listed: 'Internal User Store' and 'CA SSO PCF SSO'. The 'CA SSO PCF SSO' option is highlighted with a red box. Other sections visible include 'Redirect URIs' (with a field containing 'https://authcode-sample.id-service.cf-app.com'), 'Authorization' (with 'Scopes' and 'System Provided' sections), and 'Select Scopes' (with an 'Auto-Approved Scopes' section and a dropdown menu). At the bottom right are 'Cancel' and 'Save Config' buttons.

5. Return to Apps Manager and click on the URL below your application to be redirected to the identity provider to authenticate.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

6. Click the link.

https://authcode-sample

Authcode sample

What do you want to do?

- [Log in via Auth Code Grant Type](#)

7. On the identity provider sign-in page, enter your credentials and click **Sign On**.

Please Login

Username:

Password:

8. The application asks for authorization to the necessary scopes. Click **Authorize**.

Application Authorization

authcode-sample

<https://authcode-sample>

authcode-sample has requested permission to access your account. If you do not recognize this application or its URL, you should click deny. The application will not see your password.

openid

Read TODO list

You can change your approval of permissions or revoke access for this application at any time from account settings. By approving access, you agree to authcode-sample's terms of service and privacy policy.

9. The access token and ID token displays.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{
  "user_id" : "5127dc38-a8c4-4acf-b19e-458b987d5030",
  "user_name" : "example@pivotal.io",
  "given_name" : "Example",
  "family_name" : "Example",
  "email" : "example@pivotal.io",
  "name" : "Example Example"
}
```

This is the Access Token that was used:

```
{
  "jti" : "9f4678734f8a40edaba71ca765e2864c",
  "sub" : "5127dc38-a8c4-4acf-b19e-458b987d5030",
  "scope" : [ "todo.read", "openid", "todo.write" ],
  "client_id" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "cid" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "azp" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "grant_type" : "authorization_code",
  "user_id" : "5127dc38-a8c4-4acf-b19e-458b987d5030",
  "origin" : "CA SSO PCF SSO",
  "user_name" : "example@pivotal.io",
  "email" : "example@pivotal.io",
  "auth_time" : 1473722751,
  "rev_sig" : "2044b4e1",
  "iat" : 1473722751,
  "exp" : 1473765951,
  "iss" : "https://example.uaa/oauth/token",
  "zid" : "2852ad03-e828-4200-9d7a-e04af30fe5bd",
  "aud" : [ "todo", "openid", "bbf58e64-14f1-46b4-9fd5-ca267376ec4c" ]
}
```

This is the ID Token:

```
{
  "sub" : "5127dc38-a8c4-4acf-b19e-458b987d5030",
  "user_name" : "example@pivotal.io",
  "origin" : "CA SSO PCF SSO",
  "iss" : "https://example.uaa/oauth/token",
  "client_id" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "aud" : [ "bbf58e64-14f1-46b4-9fd5-ca267376ec4c" ],
  "zid" : "2852ad03-e828-4200-9d7a-e04af30fe5bd",
  "grant_type" : "authorization_code",
  "user_id" : "5127dc38-a8c4-4acf-b19e-458b987d5030",
  "azp" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c",
  "scope" : [ "openid" ],
  "auth_time" : 1473722751,
  "exp" : 1473765951,
  "iat" : 1473722751,
  "jti" : "9f4678734f8a40edaba71ca765e2864c",
  "email" : "example@pivotal.io",
  "rev_sig" : "2044b4e1",
  "cid" : "bbf58e64-14f1-46b4-9fd5-ca267376ec4c"
}
```

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection

 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

- Sign in to CA Single Sign-On.

Please Login

Username:

Password:

2. Navigate to your application and click it.
3. You are redirected to the page that lists applications you have access to.

The screenshot shows a user profile on the left with an 'E' icon and the email 'example@pivotal.io'. To the right is the 'Pivotal' logo. Below the profile are navigation tabs: Apps (underlined), Profile, Security, Approvals, and Notifications. Under the 'Apps' tab, there are three cards: 'Application 1' (with a green 'P' icon), 'Application 2' (with a green 'P' icon), and 'Application 2' (with a green 'P' icon). At the bottom of the screen is a footer with the text '©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#)'.

Test Your Single Sign-Off

Test single sign-off to ensure that when users log out of the application, they are logged out of CA Single Sign-On as well.

1. Sign in to the sample application. Information about the access and ID token displays, as well as the "What do you want to do?" section.
2. Under "What do you want to do?", click Log out.

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. You are logged out and redirected to the CA Single Sign-On login page.

Please Login

Username:

Password:

Troubleshooting

This topic describes how to resolve common errors that arise when configuring a single sign-on partnership between PingOne Cloud and Pivotal Single Sign-On (SSO).

CA Single Sign-On Partnership is Inactive

Symptom:

```
The following error occurred: 403 - Request Forbidden. Transaction ID: d59fb04a-950bf795-1a3cf7c7-0bcb12dc-81689d7c-bc failed.
```

Explanations:

- The CA Single Sign-On is inactive in CA Single Sign-On.

Service Provider Entity ID Misconfigured

Symptom:

```
HTTP Status 403 - Request Forbidden. Transaction ID: 174f32c9-98739353-1c861a37-2f05277b-847a8663-988 failed.

type Status report
message Request Forbidden. Transaction ID: 174f32c9-98739353-1c861a37-2f05277b-847a8663-988 failed.
description Access to the specified resource has been forbidden.
```

Explanation:

- The service provider Entity ID is misconfigured in CA Single Sign-On.

Incoming SAML message is invalid

Symptom:

```
HTTP Status 401 - Authentication Failed: Incoming SAML message is invalid

type Status report
message Authentication Failed: Incoming SAML message is invalid
description This request requires HTTP authentication.
```

Explanation:

- The identity provider Entity ID is misconfigured in CA Single Sign-On or in PCF Single Sign-On.
- The Name ID Format was misconfigured in CA Single Sign-On

Assertion Consumer Service URL Misconfigured

Symptom:

HTTP Status 401 - Authentication Failed: Error determining metadata contracts	
type	Status report
message	Authentication Failed: Error determining metadata contracts
description	This request requires HTTP authentication.

Explanation:

- The service provider Assertion Consumer Service (ACS) is misconfigured in CA Single Sign-On.

Audience Field Misconfigured

Symptom:

HTTP Status 401 - Authentication Failed: Error validating SAML message	
type	Status report
message	Authentication Failed: Error validating SAML message
description	This request requires HTTP authentication.

Explanation:

- The service provider Audience Field is misconfigured in CA Single Sign-On.

Expired Certificate

Symptom:

The following error occurred: 500 - Internal Error occurred while trying to process the request. Transaction ID: 27ef9b01-154b7e0b-383ebe10-7e1a10f-e0c04

Explanation:

- The certificate has expired in CA Single Sign-On.

Identity Provider SSO URL Misconfigured

Symptom:

HTTP Status 404 - /affwebservices/public/saml2ss	
type	Status report
message	/affwebservices/public/saml2ss
description	The requested resource is not available.

Explanation:

- The identity provider SSO URL is misconfigured in PCF Single Sign-On.

Okta Integration Guide Overview

Okta is an enterprise identity management and single sign-on service that integrates with applications in the cloud, on-premises, or on a mobile device. This documentation describes how to configure a single sign-on partnership between Okta as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate Okta with Pivotal Cloud Foundry (PCF), you need:

Pivotal

- PCF, version 1.7.0 or later.
- Single Sign-On, version 1.1.0 or later.

Okta

- Okta, version 2016.07 or later.
- A user with Application Admin privileges.

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic.

Okta Integration Guide

Configuring Okta with SSO

Complete both steps below to integrate your deployment with Okta and SSO.

1. [Configure Okta as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure Okta as an Identity Provider

This topic describes how to set up Okta as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry (PCF) and Okta.

Set up SAML in PCF

1. Log into the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Plans' section of the PCF SSO dashboard. A specific plan named 'Okta PCF SSO' is selected. At the bottom of the list, there are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red box.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Identity Providers' list under the 'Okta PCF SSO' plan. There are two entries: 'Okta PCF SSO' (Type: SAML) and 'Internal User Store' (Type: Internal User Store). At the top right of the list, there are two buttons: 'New Identity Provider' and 'Configure SAML Service Provider'. The 'Configure SAML Service Provider' button is highlighted with a red box.

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the 'Configure SAML Service Provider' dialog. It contains two checkboxes: 'Perform signed authentication requests' (which is checked) and 'Require signed assertions'. At the bottom right, there is a 'Save' button highlighted with a blue box, and at the top right, there is a 'Download Metadata' button.

5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.

6. Click **Download Metadata** to download the service provider metadata.

7. Click **Save**.

Set up SAML in Okta

1. Sign in as an Okta administrator.
2. Navigate to your application, then click the **Sign On** tab.
3. Under **Settings**, click **Edit**, and select **SAML 2.0**.

Okta PCF SSO

Active

General Sign On Mobile Import People Groups

Settings

SIGN ON METHODS

The sign-on method determines how a user signs into and manages their credentials for an application. Some sign-on methods require additional configuration in the 3rd party application.

SAML 2.0

Default Relay State

SAML 2.0 is not configured until you complete the setup instructions.

[View Setup Instructions](#)

Identity Provider metadata is available if this application supports dynamic configuration.

CREDENTIALS DETAILS

Application username format Okta username

Password reveal Allow users to securely see their password (Recommended)

About

SAML 2.0 streamlines the end user experience by not requiring the user to know their credentials. Users cannot edit their credentials when SAML 2.0 is configured for this application. Additional configuration in the 3rd party application may be required to complete the integration with Okta.

Application Username

Choose a format to use as the default username value when assigning the application to users.

If you select None you will be prompted to enter the username manually when assigning an application with password or profile push provisioning features.

4. Click the **General** tab.
5. Under SAML Settings, click the **Edit** button followed by the **Next** button to configure SAML.

 Edit SAML Integration

1 General Settings 2 Configure SAML 3 Feedback

A SAML Settings

GENERAL

Single sign on URL <https://example.login.id-service.cf-app.com/saml/SSO/alias/example> Use this for Recipient URL and Destination URL

Audience URI (SP Entity ID) example.login.id-service.cf-app.com

Default RelayState
If no value is set, a blank RelayState is sent

Name ID format [EmailAddress](#)

Application username [Okta username](#)

[Show Advanced Settings](#)

ATTRIBUTE STATEMENTS (OPTIONAL) [LEARN MORE](#)

Name	Name format (optional)	Value
firstName	Unspecified	user.firstName <input type="button" value="x"/>
lastName	Unspecified	user.lastName <input type="button" value="x"/>
email	Unspecified	user.email <input type="button" value="x"/>

[Add Another](#)

GROUP ATTRIBUTE STATEMENTS (OPTIONAL)

Name	Name format (optional)	Filter
<input type="text"/>	Unspecified	<input type="button" value="Starts with"/> <input type="text"/> <input type="button" value="x"/>

[Add Another](#)

6. In the **SAML Settings** section, perform the following steps:

- Enter the **AssertionConsumerService Location URL** from your downloaded service provider metadata into **Single sign on URL**. For example, <https://AUTH-DOMAIN/saml/SSO/alias/AUTH-DOMAIN>.
- Enter your Auth Domain URL into **Audience URI (SP Entity ID)**. You can view the Auth Domain for a plan by logging into the SSO dashboard, clicking the name of your plan, and selecting **Edit Plan**. For example, <https://AUTH-DOMAIN.login.SYSTEM-DOMAIN>.
- Select a **Name ID format**.
- Select an **Application username**.

7. (Optional) To configure single logout, perform the following steps:

- Click **Show Advanced Settings**.
- For **Enable Single Logout**, select **Allow application** to initiate single logout.
- Enter the **SingleLogoutService Location URL** from your downloaded service provider metadata into **Single Logout URL**.
- Enter your **Auth Domain URL** into **SP Issuer**.
- Click **Upload Signature Certificate** to upload the signature certificate from your downloaded service provider metadata.

8. (Optional) Under **Attribute Statements (Optional)**, specify any attribute statements that you want to map to users in the ID token.
9. (Optional) Under **Group Attribute Statements (Optional)**, specify any group attribute statements that you want to map to users in the ID token. This is a group that users are in within Okta.
10. Click the **Next** button followed by the **Finish** button.
11. Click **Identity Provider metadata** to download the metadata, or copy and save the link address of the **Identity Provider metadata**.

Okta PCF SSO

Active

General Sign On Mobile Import People Groups

Settings Edit

SIGN ON METHODS

The sign-on method determines how a user signs into and manages their credentials for an application. Some sign-on methods require additional configuration in the 3rd party application.

SAML 2.0

Default Relay State

SAML 2.0 is not configured until you complete the setup instructions. [View Setup Instructions](#)

Identity Provider metadata is available if this application supports dynamic configuration.

CREDENTIALS DETAILS

Application username format Okta username

Password reveal Allow users to securely see their password (Recommended)

About

SAML 2.0 streamlines the end user experience by not requiring the user to know their credentials. Users cannot edit their credentials when SAML 2.0 is configured for this application. Additional configuration in the 3rd party application may be required to complete the integration with Okta.

Application Username

Choose a format to use as the default username value when assigning the application to users.

If you select None you will be prompted to enter the username manually when assigning an application with password or profile push provisioning features.

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.


Setting up SAML

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.



A screenshot of the Pivotal SSO dashboard. The 'Plans' tab is selected, showing a list of plans. One plan, 'Okta PCF SSO', is listed. Below the plan name are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red box.

3. Click **New Identity Provider** to create a new identity provider.



The screenshot shows the 'New Identity Provider' configuration page. It includes fields for 'Identity Provider Name*', 'Identity Provider Description', 'Identity Provider Type*', and sections for 'Identity Provider Metadata' and 'Advanced SAML Settings'. At the bottom right are 'Cancel' and 'Create Identity Provider' buttons.

Identity Provider Name*
This name will show as a link on the login page

Identity Provider Description
Allows _____ to authenticate.

Identity Provider Type*
SAML

Identity Provider Metadata

Identity Provider Metadata URL*

Fetch Metadata

▶ SAML File Metadata (optional)

Advanced SAML Settings

▶ Attribute mappings (optional)

Create Identity Provider

4. To create a new identity provider, perform the following steps:
 - a. Enter an identity provider name into **Identity Provider Name**.
 - b. (Optional) Enter a description into **Identity Provider Description**.
 - c. Specify Identity Provider Metadata from Step 11 of the [Configure Okta as an Identity Provider](#) topic.
 - i. Option 1: Enter your **Input Identity Provider Metadata URL** and **Fetch Metadata** to fetch your identity provider metadata from an endpoint.
 - ii. Option 2: Click **SAML File Metadata (optional)** to upload your metadata XML manually.
 - d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.
5. Click **Create Identity Provider**.

6. Click **Resource Permissions**.
7. Click **New Permissions Mapping** and perform the following steps:
 - a. Enter a **Group Name**.
 - b. For **Select Permissions**, select the permissions that the members of the group from the external identity provider should have access to.
8. Navigate to the identity provider list.
9. Click **Group Whitelist** and enter the group names from the external identity provider that should be propagated in the ID token.

Testing

This topic describes how an administrator can test the connection between SSO and Okta services. An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application and click **Manage**.

The screenshot shows the Apps Manager interface. The top navigation bar has tabs for **Overview** and **Settings**. Below this is a section titled **Apps** with a table:

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

Below the Apps section is a section titled **Services** with a table:

SERVICE	NAME	BOUND APPS	PLAN
Pivotal Single Sign-On	SI	1	free - (MONTHLY) >

A red box highlights the "Pivotal Single Sign-On" service entry.

The screenshot shows the details of the "Pivotal Single Sign-On" service instance. At the top, it displays the SERVICE, INSTANCE NAME (SI), and SERVICE PLAN (Okta PCF SSO). Below this is a "Manage" button, which is highlighted with a red box, and links to "Docs | Support".

The main content area has tabs for **App Binding (1)**, **Plan**, and **Settings**. The **App Binding (1)** tab is selected. It shows a "Bound Apps" section with a table:

authcode-sample	Edit Bindings
-----------------	---------------

3. Under the **Apps** tab, click your application.

The screenshot shows the app binding details for the "authcode-sample" application. The top navigation bar has tabs for **Apps** and **Resources**. The **Resources** tab is selected. On the left, there is a "NEW APP" button. On the right, the "authcode-sample" application card is displayed with the following details:

- APP TYPE:** Web App
- IDENTITY PROVIDER:** Okta PCF SSO, Internal Identity Provider
- LAST UPDATED:** updated 2 hours ago

4. Under **Identity Providers**, select the Okta identity provider.

authcode-sample Web App

App Name*
authcode-sample

Identity Providers

Select a Identity Provider

Okta PCF SSO (highlighted with a red box) **Internal User Store**

Redirect URIs

The Authentication Response will be sent to the following locations:

Auth Redirect URIs*
Provide a comma-separated list of URIs
https://authcode-sample.id-service.cf-app.com

Authorization

Scopes
Permissions requested by the application
todo

todo.read X todo.write X

System Provided

openid X

Select Scopes

Auto-Approved Scopes
Permissions automatically approved on behalf of the user
None selected ▾

Delete

Cancel **Save Config**

5. Return to Apps Manager and click on the URL below your application to be redirected to the identity provider to authenticate.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

6. Click the link.


https://authcode-sample

Authcode sample


What do you want to do?

- Log in via Auth Code Grant Type

7. On the identity provider sign-in page, enter your credentials and click **Sign In**.



8. The application asks for authorization to the necessary scopes. Click **Authorize**.



9. The access token and ID token displays.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{  
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",  
  "user_name" : "example@pivotal.io",  
  "given_name" : "Example",  
  "family_name" : "Example",  
  "email" : "example@pivotal.io",  
  "name" : "Example Example"  
}
```

This is the Access Token that was used:

```
{  
  "jti" : "c1148dda64a840589b2936deba1149a9",  
  "sub" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",  
  "scope" : [ "todo.read", "openid", "todo.write" ],  
  "client_id" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",  
  "cid" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",  
  "azp" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",  
  "grant_type" : "authorization_code",  
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",  
  "origin" : "Okta PCF SSO",  
  "user_name" : "example@pivotal.io",  
  "email" : "example@pivotal.io",  
  "auth_time" : 1465240181,  
  "rev_sig" : "f59bcff6",  
  "iat" : 1465240182,  
  "exp" : 1465283382,  
  "iss" : "https://example.uaa/oauth/token",  
  "zid" : "23835dc6-7f12-4c27-bf22-3ed29923d590",  
  "aud" : [ "todo", "openid", "27b2d43c-2f0d-48e8-979c-b11f841e972d" ]  
}
```

This is the ID Token:

```
{  
  "sub" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",  
  "user_name" : "example@pivotal.io",  
  "origin" : "Okta PCF SSO",  
  "iss" : "https://example.uaa/oauth/token",  
  "client_id" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",  
  "aud" : [ "27b2d43c-2f0d-48e8-979c-b11f841e972d" ],  
  "zid" : "23835dc6-7f12-4c27-bf22-3ed29923d590",  
  "grant_type" : "authorization_code",  
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",  
  "azp" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",  
  "scope" : [ "openid" ],  
  "auth_time" : 1465240181,  
  "exp" : 1465283382,  
  "iat" : 1465240182,  
  "jti" : "c1148dda64a840589b2936deba1149a9",  
  "email" : "example@pivotal.io",  
  "rev_sig" : "f59bcff6",  
  "cid" : "27b2d43c-2f0d-48e8-979c-b11f841e972d"  
}
```

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection

 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

1. Sign into Okta.

Sign In

Username

Password

Remember me (?)

Sign In

Your security image (?)

Forgot password? | Help |

2. Navigate to the application tile and click it.



3. You are redirected to the page that lists applications you have access to.

example@pivotal.io

Sign out

Pivotal

Apps Profile Security Approvals Notifications

Application 1

Application 2

Application 2

©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#)

Test Your Single Sign-Off


Test single sign-off to ensure that when users log out of the application, they are logged out of Okta as well.

1. Sign into the sample application. Information about the access and ID token displays, as well as the “What do you want to do?” section.
2. Under “What do you want to do?”, click **Log out**.

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. You are logged out and redirected to the Okta login page.




The screenshot shows the Pivotal sign-in interface. At the top left is the Pivotal logo. Below it is a teal header bar with the word "Sign In". The main form area has a light gray background. It contains fields for "Username" and "Password", each with a corresponding input box. To the right of these fields is a "Your security image" section containing a large question mark icon inside a square frame. Below the input fields are two buttons: "Sign In" and "Remember me". At the bottom of the form are links for "Forgot password?" and "Help".

Troubleshooting

This topic describes how to resolve common errors that arise when configuring a single sign-on partnership between Okta and Pivotal Single Sign-On (SSO).

Page Not Found

Symptom:




Explanations:

- The Okta instance is inactive.
- The Recipient URL is misconfigured in Okta.
- The identity provider SSO URL is misconfigured in the SSO plan settings.

No Valid Assertion

Symptom:



Explanations:

- The service provider Entity ID is misconfigured in Okta.
- The Destination URL is misconfigured in Okta.

Webpage Not Available

Symptom:



This webpage is not available

DNS_PROBE_FINISHED_NXDOMAIN

[Details](#)

Explanation:

- The SSO URL is misconfigured in Okta.

Metadata Not Found

Symptom:



Metadata for issuer <http://www.okta.com/exk5s2s8y0ugC73JY0h7> wasn't found

Explanation:

- The identity provider Entity ID is misconfigured in the SSO plan settings.

PingFederate Integration Guide Overview

PingFederate is a federation server that provides identity management, single sign-on, and API security for the enterprise. This documentation describes how to configure a single sign-on partnership between PingFederate as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate PingFederate with Pivotal Cloud Foundry (PCF), you need:

Pivotal

- PCF, version 1.7.0 or later.
- Single Sign-On, version 1.1.0 or later.

Ping

- PingFederate
- A user with Administrator privileges.

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic.

PingFederate Integration Guide

Configuring PingFederate with SSO

Complete both steps below to integrate your deployment with PingFederate and SSO.

1. [Configure PingFederate as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure PingFederate as an Identity Provider

This topic describes how to set up PingFederate as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry (PCF) and PingFederate.

Set up SAML in PCF

1. Log into the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and choose **Manage Identity Providers** from the dropdown menu.

The screenshot shows the 'Plans' section of the PCF SSO dashboard. A single plan named 'PingFederate PCF SSO' is listed. Below the plan name, there are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red border.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Identity Providers' list. It includes a header row with columns for 'Name', 'Type', and 'Actions'. Two entries are listed: 'Internal User Store' (Internal User Store type) and 'PingFederate PCF SSO' (SAML type). To the right of the 'Actions' column for the SAML entry are links for 'Resource Permissions' and 'Group Whitelist'. Above the list, a blue link labeled 'Configure SAML Service Provider' is highlighted with a red box.

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the 'Configure SAML Service Provider' settings page. It has two checkboxes: 'Perform signed authentication requests' (which is checked) and 'Require signed assertions' (which is unchecked). At the bottom left is a blue 'Save' button, and at the top right is a blue 'Download Metadata' button.

5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.


6. Click **Download Metadata** to download the service provider metadata.

7. Click **Save**.


Set up SAML in PingFederate

Configure the Connection


1. Sign in as a PingFederate administrator.
2. Navigate to your identity provider configurations by clicking on the **IDP Configuration** tab.
3. Under **SP Connections**, click the **Create New** button.



4. Select the **Browser SSO Profiles** connection template on the **Connection Type** tab and click **Next**.
5. Select **Browser SSO** on the **Connection Options** tab and click **Next**.
6. Select **File** as the method for importing metadata and click **Choose file** to choose the SSO metadata on the **Import Metadata** tab. Click **Next**.



7. Review the information on the **Metadata Summary** tab and click **Next**.
8. Ensure that the **Partner's Entity ID**, **Connection Name**, and **Base URL** fields pre-populate based on the metadata. Click **Next**.



Configure Browser SSO

1. Click **Configure Browser SSO** on the **Browser SSO** tab.
2. Select the **IdP-Initiated SSO** and **SP-Initiated SSO** options on the **SAML Profiles** tab and click **Next**.

SP Connection | Browser SSO

SAML Profiles **Assertion Lifetime** **Assertion Creation** **Protocol Settings** **Summary**

A SAML Profile defines what kind of messages may be exchanged between an Identity Provider and a Service Provider, and how the messages are transported (bindings). As an IdP, you configure this information for your SP connection.

Single Sign-On (SSO) Profiles Single Logout (SLO) Profiles

IDP-INITIATED SSO IDP-INITIATED SLO

SP-INITIATED SSO SP-INITIATED SLO

Cancel Save Draft Next

3. Enter your desired assertion validity time from on the **Assertion Lifetime** tab and click **Next**.

Assertion Creation

1. Click **Configure Assertion Creation** on the **Assertion Creation** tab.
2. Choose the **Standard** option on the **Identity Mapping** tab and click **Next**.
3. Select a **Subject Name Format** for the **SAML SUBJECT** on the **Attribute Contract** tab and click **Next**.

SP Connection | Browser SSO | Assertion Creation

Identity Mapping **Attribute Contract** **Authentication Source Mapping** **Summary**

An Attribute Contract is a set of user attributes that this server will send in the assertion.

Attribute Contract Subject Name Format

SAML SUBJECT

Extend the Contract Attribute Name Format Action

urn:oasis:names:tc:SAML:2.0:attrname-format:basic Add

Cancel Save Draft Previous Next

4. Click **Map New Adapter Instance** on the **Authentication Source Mapping** tab.
5. Select an **Adapter Instance** and click **Next**. The adapter must include the user's email address.

PingFederate

MAIN

SP Connection | Browser SSO | Assertion Creation | IdP Adapter Mapping

Adapter Instance Mapping Method Attribute Contract Fulfillment Issuance Criteria Summary

Select an IdP adapter instance that may be used to authenticate users for this partner. Attributes returned by the adapter instance you choose (the Adapter Contract) may be used to fulfill the Attribute Contract with your partner.

ADAPTER INSTANCE Adapter

Adapter Contract

username

OVERRIDE INSTANCE SETTINGS

6. Select the **Use only the adapter contract values in the SAML assertion** option on the **Mapping Method** tab and click **Next**.

PingFederate

MAIN

SP Connection | Browser SSO | Assertion Creation | IdP Adapter Mapping

Adapter Instance **Mapping Method** Attribute Contract Fulfillment Issuance Criteria Summary

You can choose to fulfill the Attribute Contract with your partner using either the values provided by the "HTTP Basic IdP Adapter" adapter, or you can use these values plus additional attributes retrieved from local data stores.

Adapter Contract

email

givenName

username

RETRIEVE ADDITIONAL ATTRIBUTES FROM MULTIPLE DATA STORES USING ONE MAPPING
 RETRIEVE ADDITIONAL ATTRIBUTES FROM A DATA STORE – INCLUDES OPTIONS
 TO USE ALTERNATE DATA STORES AND/OR A FAILSAFE MAPPING
 USE ONLY THE ADAPTER CONTRACT VALUES IN THE SAML ASSERTION

7. Select your adapter instance as the **Source** and the email as the **Value** on the **Attribute Contract Fulfillment** tab and click **Next**.

PingFederate

MAIN

SP Connection | Browser SSO | Assertion Creation | IdP Adapter Mapping

Adapter Instance Mapping Method **Attribute Contract Fulfillment** Issuance Criteria Summary

Fulfill your Attribute Contract with values from the authentication adapter or with dynamic text values.

Attribute Contract	Source	Value	Actions
SAML_SUBJECT	Adapter <input type="button" value="▼"/>	email <input type="button" value="▼"/>	None available

8. (Optional) Select any authorization conditions you would like on the **Issuance Criteria** tab and click **Next**.

9. Click **Done** on the **Summary** tab.

10. Click **Next** on the **Authentication Source Mapping** tab.

11. Click **Done** on the **Summary** tab.

12. Click **Next** on the **Assertion Creation** tab.

Protocol Settings

1. Click **Configure Protocol Settings** on the **Protocol Settings** tab.
2. Select POST for **Binding** and specify the single sign-on endpoint url in the **Endpoint URL** field on the **Assertion Consumer Service URL** tab. Click **Next**

Default	Index	Binding	Endpoint URL	Action
default	0	POST	https://example.login.id-service.cf-app.com/saml/SSO/alias/example.login.id-service.cf-app.com	Edit Delete

3. Select POST on the **Allowable SAML Bindings** tab and click **Next**.

ARTIFACT	POST	REDIRECT	SOAP
<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

4. Select your desired signature policies for assertions on the **Signature Policy** tab and click **Next**.
5. Select your desired encryption policy for assertions on the **Encryption Policy** tab and click **Next**.
6. Click **Done** on the **Protocol Settings Summary** tab.
7. Click **Done** on the **Browser SSO Summary** tab.

Configure Credentials

1. Click **Configure Credentials** on the **Credentials** tab.
2. Select the **Signing Certificate** to use with the Single Sign-On service and select **Include the certificate in the signature element**. Click **Next**.

SP Connection | Credentials

Digital Signature Settings Summary

You may need to digitally sign SAML messages or security tokens to protect against tampering. Please select a key/certificate to use from the list below.

SIGNING CERTIFICATE: 21:51:3D:A7:E1:5F (cn=Pivotal)

INCLUDE THE CERTIFICATE IN THE SIGNATURE <KEYINFO> ELEMENT.
 INCLUDE THE RAW KEY IN THE SIGNATURE <KEYVALUE> ELEMENT.

SIGNING ALGORITHM: RSA SHA256

Manage Certificates

Cancel Save Draft Next

3. Click **Done** on the **Summary** tab.
4. Click **Next** on the **Credentials** tab.
5. Select **Active** for the **Connection Status** on the **Activation & Summary** tab and click **Save**.
6. Click **Manage All** under **SP Connections**.
7. Click **Export Metadata** for the desired service provider connection.
8. Choose a **Signing Certificate** on the **Metadata Signing** tab and click **Next**.
9. Click **Export** on the **Export & Summary** tab and click **Done**.

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.

Setting up SAML

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and choose **Manage Identity Providers** from the dropdown menu.

The screenshot shows a navigation bar with 'Plans 1' and a 'New Plan' button. Below this is a table with two columns: 'Name' and 'Sign In Header'. A row contains the text 'PingOne PCF SSO' under 'Name' and 'example' under 'Sign In Header'. Underneath the table are two buttons: 'Edit Plan' and 'Manage Identity Providers', with 'Manage Identity Providers' highlighted by a red box.

3. Click **New Identity Provider**.

The screenshot shows the 'New Identity Provider' form. It includes fields for 'Identity Provider Name*' (with a note: 'This name will show as a link on the login page'), 'Identity Provider Description' (with a note: 'Allows _____ to authenticate.'), 'Identity Provider Type*' (set to 'SAML'), and 'Identity Provider Metadata' sections. The 'Identity Provider Metadata URL*' field contains 'https://idp.company.com/SAML2'. Below it is a 'Fetch Metadata' button and a note about optional SAML File Metadata. The 'Advanced SAML Settings' section has a note about optional Attribute mappings. At the bottom are 'Cancel' and 'Create Identity Provider' buttons.

4. To create a new identity provider, perform the following steps:
 - a. Enter an identity provider name into **Identity Provider Name**.
 - b. (Optional) Enter a description into **Identity Provider Description**.
 - c. Click **SAML File Metadata (optional)**, then click the **Upload Identity Provider Metadata** button to upload your metadata XML.
 - d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.
5. Click **Create Identity Provider**.
6. Click **Resource Permissions**.

7. Click **New Permissions Mapping** and perform the following steps:
 - a. Enter a **Group Name**.
 - b. For **Select Permissions**, select the permissions that the members of the group from the external identity provider should have access to.
8. Navigate to the identity provider list.
9. Click **Group Whitelist** and enter the group names from the external identity provider to propagate in the ID token when a user authenticates.

Testing

This topic describes how an administrator can test the connection between SSO and PingFederate. An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application. Click the service instance and then click **Manage**.

The screenshot shows the Apps Manager interface. At the top, there are two tabs: "Overview" (selected) and "Settings". Below these are two main sections: "Apps" and "Services".

Apps: A table with columns: NAME, INSTANCES, MEMORY, LAST PUSH, and ROUTE. One row is shown for "authcode-sample" with 1 instance, 512MB memory, last pushed 4 days ago, and a route to <http://authcode-sample.id-service.cf-ap...>.

Services: A table with columns: SERVICE, NAME, BOUND APPS, and PLAN. One row is shown for "Pivotal Single Sign-On" with an instance name "SI", 1 bound app, and a free - (MONTHLY) plan.

The screenshot shows the management page for the "Pivotal Single Sign-On" service instance. At the top, it displays the SERVICE (Pivotal Single Sign-On), INSTANCE NAME (SI), and SERVICE PLAN (PingFederate PCF SSO). Below this are three buttons: "Manage" (highlighted with a red box), "Docs", and "Support".

Underneath, there are three tabs: "App Binding (1)" (selected), "Plan", and "Settings". The "App Binding" tab shows a table with one entry: "authcode-sample". To the right of this table is a "Edit Bindings" button.

3. Under the **Apps** tab, click your application.

The screenshot shows the Pivotal Apps Manager interface. On the left, there's a button labeled 'NEW APP'. To its right, the application 'authcode-sample' is listed. The app details include 'APP TYPE: Web App', 'IDENTITY PROVIDER: Internal Identity Provider', and 'PingFederate PCF SSO'. Below this information, it says 'updated 4 days ago'.

4. Under Identity Providers, select the PingFederate identity provider. a

The screenshot shows the configuration page for the 'authcode-sample' application. In the 'Identity Providers' section, two options are listed: 'Internal User Store' and 'PingFederate PCF SSO'. The 'PingFederate PCF SSO' option is highlighted with a red box. Other sections visible include 'Redirect URIs', 'Authorization', and 'Select Scopes'.

Identity Providers

Select a Identity Provider

Internal User Store **PingFederate PCF SSO** PingFederate PCF SSO

Redirect URIs

The Authentication Response will be sent to the following locations:

Auth Redirect URIs*

Provide a comma-separated list of URIs

https://authcode-sample.id-service.cf-app.com

Authorization

Scopes

Permissions requested by the application

todo

todo.read X todo.write X

System Provided

openid X

Select Scopes

Auto-Approved Scopes

Permissions automatically approved on behalf of the user

None selected ▾

Delete Cancel Save Config

5. Return to Apps Manager and click the URL below your application to authenticate with the identity provider.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

6. Click the link to **Log in via Auth Code Grant Type**.

Authcode sample

What do you want to do?

- [Log in via Auth Code Grant Type](#)

7. On the identity provider sign-in page, enter your credentials and click **Sign On**.

Sign On

Username

Password

Login

8. The application asks for authorization to the necessary scopes. Click **Authorize**.

Application Authorization

authcode-sample
<https://authcode-sample>

authcode-sample has requested permission to access your account. If you do not recognize this application or its URL, you should click deny. The application will not see your password.

openid

Read TODO list

You can change your approval of permissions or revoke access for this application at any time from account settings. By approving access, you agree to authcode-sample's terms of service and privacy policy.

DENY AUTHORIZE

9. View the access token and ID token.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{
  "user_id" : "a112e6d9-8a23-47be-8f53-a2142a8e449c",
  "user_name" : "example@pivotal.io",
  "given_name" : "Example",
  "family_name" : "Example",
  "email" : "example@pivotal.io",
  "name" : "Example Example"
}
```

This is the Access Token that was used:

```
{
  "jti" : "22a45c21e05f4c038e146bfb4b27f4d5",
  "sub" : "a112e6d9-8a23-47be-8f53-a2142a8e449c",
  "scope" : [ "todo.read", "openid", "todo.write" ],
  "client_id" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783",
  "cid" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783",
  "azp" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783",
  "grant_type" : "authorization_code",
  "user_id" : "a112e6d9-8a23-47be-8f53-a2142a8e449c",
  "origin" : "PingFederate PCF SSO",
  "user_name" : "example@pivotal.io",
  "email" : "example@pivotal.io",
  "auth_time" : 1466471054,
  "rev_sig" : "df31a473",
  "iat" : 1466471057,
  "exp" : 1466514257,
  "iss" : "https://example.uaa/oauth/token",
  "zid" : "700cdf33-b0df-4b3c-9a9f-d0586782f664",
  "aud" : [ "todo", "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783", "openid" ]
}
```

This is the ID Token:

```
{
  "sub" : "a112e6d9-8a23-47be-8f53-a2142a8e449c",
  "user_name" : "example@pivotal.io",
  "origin" : "PingFederate PCF SSO",
  "roles" : [ "Everyone" ],
  "iss" : "https://example.uaa/oauth/token",
  "client_id" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783",
  "aud" : [ "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783" ],
  "zid" : "700cdf33-b0df-4b3c-9a9f-d0586782f664",
  "grant_type" : "authorization_code",
  "user_id" : "a112e6d9-8a23-47be-8f53-a2142a8e449c",
  "azp" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783",
  "scope" : [ "openid" ],
  "auth_time" : 1466471054,
  "exp" : 1466514257,
  "iat" : 1466471057,
  "jti" : "22a45c21e05f4c038e146bfb4b27f4d5",
  "email" : "example@pivotal.io",
  "rev_sig" : "df31a473",
  "cid" : "ac2a00fb-1a04-4ed6-b818-2a4f7bd8c783"
}
```


What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection


 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

1. Sign in to PingFederate.



The image shows a 'Sign On' form with a light gray background. It contains two input fields: 'Username' and 'Password', both with placeholder text. Below the fields is a blue 'Login' button.

2. Navigate to your application and click it.
3. View the list of applications you have access to.




The image shows a dashboard interface for managing applications. At the top left is a user profile icon with the email 'example@pivotal.io' and a 'Sign out' link. To the right is the Pivotal logo. Below the header is a navigation bar with tabs: 'Apps' (which is underlined in green), 'Profile', 'Security', 'Approvals', and 'Notifications'. The main content area displays three application cards, each featuring a teal circular icon with a white 'P' and the text 'Application 1' or 'Application 2'. At the bottom of the page is a copyright notice: '©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#)'.

Test Your Single Sign-Off

Test single sign-off to ensure that when users log out of the application, they are logged out of PingFederate as well.


1. Sign into the sample application. Information about the access and ID token displays, as well as the "What do you want to do?" section.
2. Under **What do you want to do?**, click **Log out**.



The image shows a modal dialog box with a light gray background. The title is 'What do you want to do?'. Inside the dialog, there is a list of three items, each preceded by a small teal circular icon with a white 'P':

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. Ensure that you are logged out and redirected to the PingFederate login page.




The image shows a 'Sign On' form with a light gray background, identical to the one at the top of the page. It contains two input fields: 'Username' and 'Password', both with placeholder text. Below the fields is a blue 'Login' button.

Troubleshooting

This topic describes how to resolve common errors that arise when configuring a single sign-on partnership between PingFederate and Pivotal Single Sign-On (SSO).

Error

Symptom:



Explanations:

- Connection Status is disabled on PingFederate.
- The service provider Entity ID is misconfigured on PingFederate.
- The identity provider Single Sign-On URL is misconfigured in the SSO plan settings.

Metadata Not Found

Symptom:



Explanation:

- The identity provider Entity ID is misconfigured in the SSO plan settings.

PingOne Cloud Integration Guide Overview

PingOne Cloud is an identity-as-a-service solution that delivers secure single sign-on to SaaS, legacy and web applications. This documentation describes how to configure a single sign-on partnership between PingOne Cloud as the Identity Provider (IdP) and the Single Sign-On Service (SSO) for Pivotal Cloud Foundry as the Service Provider (SP).

SSO supports service provider-initiated authentication flow and single logout. It does not support identity provider-initiated authentication flow. All SSO communication takes place over SSL.

Prerequisites

To integrate PingOne Cloud with Pivotal Cloud Foundry (PCF), you need:

Pivotal

- PCF, version 1.7.0 or later.
- Single Sign-On, version 1.1.0 or later.

PingOne Cloud

- PingOne Cloud
- A user with Application Admin privileges.

 **Note:** To configure SAML, you must have the Single Sign-On service broker installed on your PCF deployment. You need to create a plan, grant any plan administrators, and specify any organizations this plan should be the authentication authority for. For help configuring plans, see the [Manage Service Plans](#) topic..

PingOne Cloud Integration Guide

Configuring PingOne Cloud with SSO

Complete both steps below to integrate your deployment with PingOne Cloud and SSO.

1. [Configure PingOne Cloud as an Identity Provider](#)
2. [Configure a Single Sign-On Service Provider](#)

Testing and Troubleshooting

- [Testing](#)
- [Troubleshooting](#)

Configure PingOne Cloud as an Identity Provider

This topic describes how to set up PingOne Cloud as your identity provider by configuring SAML integration in both Pivotal Cloud Foundry (PCF) and PingOne Cloud.

Set up SAML in PCF

1. Log into the Single Sign-On (SSO) dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.

The screenshot shows the 'Plans' section of the PCF SSO dashboard. A dropdown menu is open under a plan named 'PingOne PCF SSO'. The 'Manage Identity Providers' option is highlighted with a red box.

3. Click **Configure SAML Service Provider**.

The screenshot shows the 'Identity Providers' section of the PCF SSO dashboard. A 'Configure SAML Service Provider' button is highlighted with a red box.

4. (Optional) Select **Perform signed authentication requests** to enforce SSO private key signature and identity provider validation.

The screenshot shows the 'Configure SAML Service Provider' dialog. The 'Perform signed authentication requests' checkbox is checked. A 'Save' button is highlighted with a blue box.

5. (Optional) Select **Require signed assertions** to validate the origin of signed responses.

6. Click **Download Metadata** to download the service provider metadata.

7. Click **Save**.

Set up SAML in PingOne Cloud

1. Sign in as a PingOne Cloud administrator.
2. Navigate to your application by clicking on the **Applications** tab.
3. Click the **Add Application** button and choose **New SAML Application**.

The screenshot shows the Ping Identity application management interface. At the top, there's a dark header bar with the Ping Identity logo, a navigation menu (Dashboard, Applications, Users, Setup, Account), and a user welcome message ('Welcome, Administrator'). Below the header is a secondary navigation bar with 'My Applications' and 'Application Catalog'. The main content area is titled 'My Applications' and displays a list of applications. A search bar at the top of this list is labeled 'Search Application Catalog'. Below it are two buttons: 'New SAML Application' and 'New Basic SSO Application', both of which are highlighted with a red rectangle. At the bottom of the list is a link: 'Request Ping Identity add a new application to the application catalog'. On the right side of the main content area, there's a button labeled 'Pause All SSO'.

4. Enter the **Application Name**, **Application Description**, **Category** and any **Graphics**.

5. Click the **Continue to Next Step** button to configure SAML.

2. Application Configuration

I have the SAML configuration

I have the SSO URL

You will need to download this SAML metadata to configure the application:

SAML Metadata [Download](#)

Provide SAML details about the application you are connecting to:

Protocol Version SAML v 2.0 SAML v 1.1

Upload Metadata [Select File](#) [Or use URL](#)

Assertion Consumer Service (ACS) *

Entity ID *

Application URL

Single Logout Endpoint [Select](#)

Single Logout Response Endpoint [Select](#)

Single Logout Binding Type Redirect Post

Verification Certificate [Choose File](#) No file chosen
saml20metadata.cer

Signing Algorithm

Force Re-authentication

Keep the following in mind when creating your connection:

1. Both SP- and IdP-Initiated SSO are allowed
2. Map SAML SUBJECT in your attribute contract, plus any attributes (configure them in PingOne later)
3. Allow outbound POST or redirect bindings
4. Allow inbound POST

NEXT: SSO Attribute Mapping

[Cancel](#)

[Back](#)

[Continue to Next Step](#)

6. In the **Application Configuration** section, perform the following steps:

- a. Select **I have the SAML configuration**.
- b. For **SAML Metadata**, click **Download** to download the identity provider metadata.
- c. For **Protocol Version**, select **SAML v 2.0**.
- d. For **Upload Metadata**, click **Select File** and select the service provider metadata.
- e. Click the **Continue to Next Step** button.

7. (Optional) Under **SSO Attribute Mapping**, specify any application or group attributes that you want to map to users in the ID token.

3. SSO Attribute Mapping

Map the necessary application provider (AP) attributes to attributes used by your identity provider (IdP).

Application Attribute	Identity Bridge Attribute or Literal Value	Required
1 firstName	First Name <input type="checkbox"/> As Literal <input type="button" value="Advanced"/>	<input type="checkbox"/> <input type="button" value="X"/>
2 lastName	Last Name <input type="checkbox"/> As Literal <input type="button" value="Advanced"/>	<input type="checkbox"/> <input type="button" value="X"/>
3 email	Email <input type="checkbox"/> As Literal <input type="button" value="Advanced"/>	<input type="checkbox"/> <input type="button" value="X"/>
4 group	memberOf <input type="checkbox"/> As Literal <input type="button" value="Advanced"/>	<input type="checkbox"/> <input type="button" value="X"/>

[NEXT: Review Setup](#)


- Click the **Save & Publish** button followed by the **Finish** button.

Configure a Single Sign-On Service Provider

This topic describes how to add an external identity provider to your Pivotal Single Sign-On (SSO) service plan.


Setting up SAML

1. Log into the SSO dashboard at <https://p-identity.YOUR-SYSTEM-DOMAIN> as a Plan Administrator.
2. Select your plan and click **Manage Identity Providers** on the dropdown menu.



The screenshot shows the 'Plans' section of the Pivotal SSO dashboard. A single plan named 'PingOne PCF SSO' is listed. Below the plan name, there are two buttons: 'Edit Plan' and 'Manage Identity Providers'. The 'Manage Identity Providers' button is highlighted with a red box.

3. Click **New Identity Provider** to create a new identity provider.



The screenshot shows the 'New Identity Provider' creation form. It includes fields for 'Identity Provider Name*' (with a note: 'This name will show as a link on the login page'), 'Identity Provider Description' (with a note: 'Allows _____ to authenticate.'), 'Identity Provider Type*' (set to 'SAML'), and 'Identity Provider Metadata' (with a 'Fetch Metadata' button). At the bottom right are 'Cancel' and 'Create Identity Provider' buttons.

Identity Provider Name*	<input type="text"/>
This name will show as a link on the login page	
Identity Provider Description	<input type="text"/>
Allows _____ to authenticate.	
Identity Provider Type*	SAML
Identity Provider Metadata	
Identity Provider Metadata URL*	<input type="text" value="https://idp.company.com/SAML2"/>
Fetch Metadata	
▶ SAML File Metadata (optional)	
Advanced SAML Settings	
▶ Attribute mappings (optional)	
Create Identity Provider	

4. To create a new identity provider, perform the following steps:
 - a. Enter an identity provider name into **Identity Provider Name**.
 - b. (Optional) Enter a description into **Identity Provider Description**.
 - c. Click **SAML File Metadata (optional)** followed by clicking the **Upload Identity Provider Metadata** button to upload your metadata XML.
 - d. (Optional) Under **Advanced SAML Settings**, click **Attribute Mappings** to enter the mappings.
5. Click **Create Identity Provider**.
6. Click **Resource Permissions**.

7. Click **New Permissions Mapping** and perform the following steps:
 - a. Enter a **Group Name**.
 - b. For **Select Permissions**, select the permissions that the members of the group from the external identity provider should have access to.
8. Navigate to the identity provider list.
9. Click **Group Whitelist** and enter the group names from the external identity provider that should be propagated in the ID token.

Testing

This topic describes how an administrator can test the connection between SSO and PingOne Cloud. An administrator can test both service provider and identity provider connections.

Test Your Service Provider Connection

1. Log in to Apps Manager at <https://apps.YOUR-SYSTEM-DOMAIN> and navigate to the organization and space where your application is located.
2. Under **Services**, locate the service instance of the Single Sign-On (SSO) plan bound to your application. Click on the service instance and click **Manage**.

The screenshot shows the Apps Manager interface. At the top, there are two tabs: "Overview" (selected) and "Settings". Below these are two main sections: "Apps" and "Services".

Apps:

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-ap... >

Services:

SERVICE	NAME	BOUND APPS	PLAN
 Pivotal Single Sign-On	SI	1	free - (MONTHLY) >

The screenshot shows the management page for the "Pivotal Single Sign-On" service instance. At the top, it displays the SERVICE, INSTANCE NAME (SI), and SERVICE PLAN (PingOne PCF SSO). Below this are three buttons: "Manage" (highlighted with a red box), "Docs", and "Support".

Below the service details, there are three tabs: "App Binding (1)" (selected), "Plan", and "Settings".

App Binding (1):

Bound Apps	Edit Bindings
authcode-sample	Edit Bindings

3. Under the **Apps** tab, click your application.

The screenshot shows the Pivotal Apps Manager interface. On the left, there's a button labeled 'NEW APP'. To its right, the application 'authcode-sample' is listed. It is categorized as a 'Web App' and uses 'Internal Identity Provider' and 'PingOne PCF SSO' for authentication. The status bar at the bottom indicates it was 'updated 4 days ago'.

4. Under Identity Providers, select the PingOne identity provider.

The screenshot shows the configuration page for the 'authcode-sample' application. In the 'Identity Providers' section, two options are listed: 'Internal User Store' and 'PingOne PCF SSO'. The 'PingOne PCF SSO' option is highlighted with a red box. Below this section, there are fields for 'Auth Redirect URIs*', 'Scopes', 'Select Scopes', and 'Auto-Approved Scopes'. At the bottom right, there are 'Cancel' and 'Save Config' buttons.

5. Return to Apps Manager and click on the URL below your application to be redirected to the identity provider to authenticate.

Overview **Settings**

Apps

NAME	INSTANCES	MEMORY	LAST PUSH	ROUTE
authcode-sample	1	512MB	4 days ago	http://authcode-sample.id-service.cf-app... >

6. Click the link.

Authcode sample

What do you want to do?

- Log in via Auth Code Grant Type

7. On the identity provider sign-in page, enter your credentials and click **Sign On**.

Ping Identity

Sign On

USERNAME


PASSWORD

Remember Me

Sign On

[Forgot Password](#)

8. The application asks for authorization to the necessary scopes. Click **Authorize**.



9. The access token and ID token displays.

Authcode sample

You've used the authcode flow! Here's the result of calling /userinfo:

```
{
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",
  "user_name" : "example@pivotal.io",
  "given_name" : "Example",
  "family_name" : "Example",
  "email" : "example@pivotal.io",
  "name" : "Example Example"
}
```

This is the Access Token that was used:

```
{
  "jti" : "c1148dda64a840589b2936deba1149a9",
  "sub" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",
  "scope" : [ "todo.read", "openid", "todo.write" ],
  "client_id" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",
  "cid" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",
  "azp" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",
  "grant_type" : "authorization_code",
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",
  "origin" : "PingOne PCF SSO",
  "user_name" : "example@pivotal.io",
  "email" : "example@pivotal.io",
  "auth_time" : 1465240181,
  "rev_sig" : "f59bcff6",
  "iat" : 1465240182,
  "exp" : 1465283382,
  "iss" : "https://example.uaa/oauth/token",
  "zid" : "23835dc6-7f12-4c27-bf22-3ed29923d590",
  "aud" : [ "todo", "openid", "27b2d43c-2f0d-48e8-979c-b11f841e972d" ]
}
```

This is the ID Token:

```
{
  "sub" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",
  "user_name" : "example@pivotal.io",
  "origin" : "PingOne PCF SSO",
  "iss" : "https://example.uaa/oauth/token",
  "client_id" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",
  "aud" : [ "27b2d43c-2f0d-48e8-979c-b11f841e972d" ],
  "zid" : "23835dc6-7f12-4c27-bf22-3ed29923d590",
  "grant_type" : "authorization_code",
  "user_id" : "1bd4153a-08eb-4aed-bb9c-929b45df026d",
  "azp" : "27b2d43c-2f0d-48e8-979c-b11f841e972d",
  "scope" : [ "openid" ],
  "auth_time" : 1465240181,
  "exp" : 1465283382,
  "iat" : 1465240182,
  "jti" : "c1148dda64a840589b2936deba1149a9",
  "email" : "example@pivotal.io",
  "rev_sig" : "f59bcff6",
  "cid" : "27b2d43c-2f0d-48e8-979c-b11f841e972d"
}
```


What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

Test Your Identity Provider Connection

 Note: SSO does not support identity provider-initiated flow into applications, but it does redirect the user to the User Account and Authentication (UAA) page to select applications assigned to the user.

1. Sign in to PingOne.



2. Navigate to your application and click it.
3. You are redirected to the page that lists applications you have access to.

A screenshot of a Pivotal application dashboard. In the top left corner, there is a user profile icon with the letter "E" and the email address "example@pivotal.io", along with a "Sign out" link. To the right of the profile is the Pivotal logo. Below the profile, there is a navigation bar with five tabs: "Apps" (which is underlined in teal), "Profile", "Security", "Approvals", and "Notifications". The main content area displays three application cards, each featuring a teal circular icon with a white letter "P" and the text "Application 1", "Application 2", and "Application 2" respectively. At the bottom of the page, there is a small footer note: "©2016 Pivotal Software, Inc. All Rights Reserved. [Privacy Policy](#) — [Terms of Service](#)".

Test Your Single Sign-Off


Test single sign-off to ensure that when users log out of the application, they are logged out of PingOne as well.

1. Sign into the sample application. Information about the access and ID token displays, as well as the "What do you want to do?" section.
2. Under "What do you want to do?", click **Log out**.

What do you want to do?

- [TODO List \(You need to configure the Resource Server sample app before using this\)](#)
- [See your account profile \(so you can de-authorize this client\)](#)
- [Log out](#)

3. You are logged out and redirected to the PingOne login page.




Troubleshooting

This topic describes how to resolve common errors that arise when configuring a single sign-on partnership between PingOne Cloud and Pivotal Single Sign-On (SSO).

Error

Symptom:




Explanations:

- Single Sign-On is disabled on PingOne.
- The service provider Entity ID is misconfigured on PingOne.
- The identity provider Single Sign-On URL is misconfigured in the SSO plan settings.

Something went amiss

Symptom:




Explanation:

- The service provider Assertion Consumer Service (ACS) is misconfigured on PingOne.

Metadata Not Found

Symptom:



Metadata for issuer https://pingone.com/idp/cd-2128514304.pivotal wasn't found

Explanation:

- The identity provider Entity ID is misconfigured in the SSO plan settings.

Missing Name ID

Symptom:

Identity Provider Metadata

Identity Provider Metadata URL*

https://idp.company.com/SAML2

Fetch Metadata

Error processing metadata

▼ SAML File Metadata (optional)

Upload Identity Provider Metadata saml2-metadata-idp.xml

Explanation:

- The identity provider metadata is missing configurations for Name ID. See [Configure Identity Provider Metadata](#).