# WEEK 2

ASCII (American Standard Code for Information Interchange) is a character encoding standard used for representing text in computers. Each character (letter, number, symbol) is assigned a unique 7- or 8-bit binary number, known as its ASCII code.

# For example:

The letter a has an ASCII value of 97, which in binary is 01100001. The letter A (uppercase) has an ASCII value of 65, which in binary is 01000001.

## Steps for ASCII ENCODING

- 1. Convert the letter to Decimal
- 2. Convert the decimal to binary
- 3. Join the binary of each letter to encode the ASCII for the word.

# Example 1: Encoding a word Let's go through the encoding for the word "bet" (from the problem): b (lowercase) has an decimal value of 98, which in binary is 01100010. e (lowercase) has an decimal value of 101, which in binary is 01100101. t (lowercase) has an decimal value of 116, which in binary is 01110100.

# How to convert a letter to decimal ??

Character	Decimal	Binary	Hexadecimal	
A	65	01000001	0x41	
В	66	01000010	0x42	
a	97	01100001	0x61	
b	98	01100010	0x62	
1	49	00110001	0x31	
@	64	01000000	0x40	

Character	Decimal	Hexadecimal	Binary
à	97	0x61	01100001
b	98	0x62	01100010
	99	0x63	01100011
ď	100	0x64	01100100
e	101	0x65	01100101
f	102	0x66	01100110
	103	0x67	01100111
h	104	0x68	01101000
	105	0x69	01101001
	106	0x6A	01101010
k	107	0x68	01101011
	108	0x6C	01101100
m	109	0x6D	01101101
	110	0x6E	01101110
	111	0x6F	01101111
р	112	0x70	01110000
q	113	0x71	01110001
	114	0x72	01110010
5	115	0x73	01110011
t	116	0x74	01110100
	117	0x75	01110101
	118	0x76	01110110
w	119	0x77	01110111
x	120	0x78	01111000
у.	121	0x79	01111001
Z.	122	↓ 7A	01111010

Character	Decimal	Hexadecimal	Binary
A	65	0x41	01000001
В	66	0x42	01000010
c	67	0x43	01000011
D	-68	0x44	01000100
E	69	0x45	01000101
F	70	0x46	01000110
G	71	0x47	01000111
Н	72	0x48	01001000
	73	0x49	01001001
1	74	0x4A	01001010
К	75	0x46	01001011
	76	0x4C	01001100
М	77	0x4D	01001101
N.	78	0x4E	01001110
0	79	0x4F	01001111
P	80	0x50	01010000
Q	81	0x51	01010001
R	82	0x52	01010010
S	83	0x53	01010011
I	84	0x54	01010100
U	85	0x55	01010101
٧	86	0x56	01010110
w	87	0x57	01010111
X	88	0x58	01011000
Ý	89	0x59	01011001
z	90	<b>→</b> 5A	01011010

# How to convert a decimal to binary ??

#### 1. Use of Power 2

Steps:

Start with the highest power of 2 less than or equal to the number you're converting. Subtract the value of that power from the number.

Continue with the next highest power, repeating the process until you reach zero. Write down 1 if you used the power of 2, and 0 if you didn't.

## For Example:

Convert decimal 97 to binary:

- The largest power of 2 less than or equal to 97 is  $2^6=64$ . So, subtract 64 from 97: 97-64=33.
- The next largest power of 2 less than or equal to 33 is  $2^5=32$ . So, subtract 32 from 33: 33-32=1.
- The next largest power of 2 less than or equal to 1 is  $\mathbf{2}^0=1$ . So, subtract 1 from 1: 1-1=0.
- Now, write 1 for powers of 2 you used, and 9 for powers of 2 you didn't use.

So, 97 in binary is:

• 
$$2^7 = 128 \rightarrow 0$$
 (since 128 > 97)

• 
$$2^6 = 64 \rightarrow 1$$

• 
$$2^5 = 32 \rightarrow 1$$

• 
$$2^4 = 16 \rightarrow 0$$

• 
$$2^3 = 8 \rightarrow 0$$

• 
$$2^2 = 4 \rightarrow 0$$

• 
$$2^1 = 2 \rightarrow 0$$

• 
$$2^0 = 1 \rightarrow 1$$

Thus,  $97_{10} = 01100001_2$ .

### 2. Divide by 2 method

Steps:

Divide the decimal number by 2.

Record the remainder (0 or 1).

Divide the quotient by 2 again and repeat until the quotient is 0. The binary representation is the remainders read in reverse order.

## For Example:

#### Example:

Convert 97 to binary using division by 2:

- $97 \div 2 = 48$  remainder 1
- $48 \div 2 = 24$  remainder 0
- $24 \div 2 = 12$  remainder 0
- $12 \div 2 = 6$  remainder 0
- $6 \div 2 = 3$  remainder 0
- $3 \div 2 = 1$  remainder 1
- $1 \div 2 = 0$  remainder 1

Now, read the remainders from bottom to top:

 $97_{10} = 1100001_2$  or, written in 8 bits:  $01100001_2$ .

# UNICODE

1. What is Unicode?

Unicode is a standard for encoding characters from almost all writing systems. Each character has a unique code point (a number) like U+543A9, where:

"U+" indicates it's a Unicode code point.
"543A9" is the hexadecimal value representing a specific character.

Steps to convert Unicode into UTF-8 Code:-

Convert the Unicode code point (in hexadecimal) to binary.

Determine the number of bytes required based on the length of the binary.

Use the appropriate format for UTF-8 and fill in the binary bits into the structure.

Convert each byte into hexadecimal to get the UTF-8 representation.

# Step 1: Converting Unicode (in hexadecimal) to binary

Since there are only 16 possible hexadecimal digits (@ to F), you can memorize their binary equivalents in groups. Here's a quick mnemonic grouping for easier recall:

Hex Digit	Binary Equivalent	Memory Tip
0	0000	All zeros
1.	0001	One at the end
2	0010	One in the second position
3	0011	Two ones at the end
4	0100	One in the third position
5	0101	4 (0100) + 1
6	0110	4 (0100) + 2
7	0111	4 (0100) + 3 (0011)
8	1000	One in the fourth position
9	1001	8 (1000) + 1
A (10)	1010	8 (1000) + 2
B (11)	1011	8 (1000) + 3
C (12)	1100	8 (1000) + 4 (0100)
D (13)	1101	8 (1000) + 5 (0101)
E (14)	1110	8 (1000) + 6 (0110)
F (15)	1111	All ones

# For Example:-

- Hex B2:
  - B in hex is 1011 in binary.
  - 2 in hex is 0010 in binary.
  - So, B2 in hex becomes 10110010 in binary.
- Hex 3F:
  - 3 in hex is 0011 in binary.
  - F in hex is 1111 in binary.
  - So, 3F in hex becomes 00111111 in binary.
- Hex 7A:
  - 7 in hex is 0111 in binary.
  - A in hex is 1010 in binary.
  - So, 7A in hex becomes @1111010 in binary.

# Step 2: Determining number of Bytes required for UTF-8 encoding

	, ,	'	
Code Point Range	Number of Bytes	Binary Format	Bits Used for Encoding
U+0000 to U+007F	1 byte	Øxxxxxxx	7 bits
U+0080 to U+07FF	2 bytes	110xxxxx 10xxxxxxx	11 bits
U+0800 to U+FFFF	3 bytes	1110xxxx 10xxxxxx 10xxxxxx	16 bits
U+10000 to U+10FFFF	4 bytes	11110xxx 10xxxxxx 10xxxxxx 10xxxxxx	21 bits

Steps to Determine the Number of Bytes:

Find the length of the binary representation of the Unicode code point (1). Check which range the binary representation falls into by counting the number of bits.

Determine how many bytes are needed based on the table above.

## For Example:-

#### Example 1: U+543A9

- 1. Convert the code point to binary (from Step 1):
  - 543A9\_{16} = 1010100001110101001\_2 (21 bits)
- 2. Count the number of bits: There are 21 bits.
- 3. Determine the range:
  - 21 bits falls into the range U+10000 to U+10FFFF , which means we need 4 bytes.

#### Example 2: U+0024 (Dollar Sign \$)

- 1. Convert the code point to binary:
  - 0024\_{16} = 00100100\_2 (7 bits)
- 2. Count the number of bits. There are 7 bits.
- 3. Determine the range:
  - 7 bits falls into the range U+8000 to U+807F, which means we need 1 byte.

#### Example 3: U+20AC (Euro Sign €)

- 1. Convert the code point to binary:
  - 20AC\_{16} 10000010101100\_2 (14 bits)
- 2. Count the number of bits: There are 14 bits.
- 3. Determine the range:
  - 14 bits falls into the range U+0800 to U+FFFF, which means we need 3 bytes.

# Step 3: Construct the UTF-8 Byte sequence

## UTF-8 Encoding Patterns:

Number of Bytes	Binary Format	Bits Available for Encoding
1 byte	Øxxxxxxx	7 bits
2 bytes	110xxxxx 10xxxxxx	11 bits
3 bytes	1110xxxx 10xxxxxx 10xxxxxx	16 bits
4 bytes	11110xxx 10xxxxxx 10xxxxxx 10xxxxxx	21 bits

## Example:-

#### Example: U+00A9 (Copyright ©)

- 1. Binary representation of U+00A9: 10100011 (9 bits).
- 2. UTF-8 format for 2 bytes: 110xxxxxx 10xxxxxxx.
- 3. Pad the binary with leading zeros (if needed) to make 11 bits: 00010100011 (11 bits).
- 4. Insert the bits into the UTF-8 format:
  - First 5 bits go into the first byte: 11000010
  - Next 6 bits go into the second byte: 10100011
  - UTF-8: 11000010 10100011
- 5. Final result (in hexadecimal): C2 A9.

So, the UTF-8 encoding for U+00A9 is C2 A9.