CSC 3510 Computer Organization

The page describes how to install the environment needed for programming in ARM AARCH64 assembly language.

Our platform - emulated Cortex-A53's

The emulated machines will be command-line only. A good development environment would be to edit on your native machine and sftp code down to the emulated machine where you run and debug. VS Code has a nice SFTP plug-in (search liximomo) that can do this for you every time you save a file.

Additionally, VSCode supports editing via ssh by downloading the *Remote Development-SSH* extention (which can be found here).

The official getting started docs can be found here. This has the advantage of giving you direct access to the VM (including terminal), not just syncing files.

Installing QEMU on MacOS

Get QEMU

This assumes you already have brew. If you don't you will need to install that first.

/bin/bash -c "\$(curl -fsSL https://raw.githubusercontent.com/Homebrew/install/HEAD/install.s

After brew is installed, install gemu.

brew install gemu

or, if QEMU is already installed - check for an upgrade:

brew upgrade qemu

brew may ask you to change the ownership of certain directories. Do as it suggests and rerun the qemu installation.

Ensure you have QEMU

From a terminal, enter qemu-system-aarch64 and hit return. The program should be found.

Installing debian

I have built a working system for us to use directly.

Getting the distro

Go to here.

Download aarch64.zip.

Unzipping the distro

- 1. Create the folder you wish to use for the distro.
- 2. Change directory into that directory.
- 3. Unzip the zip file in this directory.
- 4. Confirm files are present.

Here is a sample:

Adding a QEMU alias

Edit the file that your terminal runs at launch. This could be a different file depending upon your Mac. On the most recent machines, this will be ~/.zprofile. It may be that you have ~/.profile instead. If you have neither, make one or the other. Do ps. If you see bash make ~/.profile. If you see zsh make ~/.zprofile.

Add this line to the bottom of the file.

alias ARM='qemu-system-aarch64 -M virt -m 2048 -cpu cortex-a53 -kernel vmlinuz-4.9.0-8-arm64 Save the file and exit.

Ensure the alias works

You can use this alias when you are in the directory where you installed the distro. It will not work anywhere else. Ensure you are in the right directory now.

Run:

```
source ~/.zprofile
```

~/.zprofile may be a different file depending upon your Mac.

Now run alias.

You should get this plus some other text potentially:

```
[Donnager] /tmp/aarch64 $ alias
ARM='qemu-system-aarch64 -M virt -m 2048 -cpu cortex-a53 -kernel vmlinuz-4.9.0-8-arm64 -in
```

Ensure the distro boots

Run:

ARM

Exit the distro by entering root as the user and a as the password. When the shell prompt is shown, type shutdown now. Always do this to exit the distro.

Installing QEMU on Windows

Don't.

Installing QEMU on WSL

1. Install WSL.

This means you may have to enable the Windows Subsystem for Linux in the old Add Remove Programs -> Windows Features settings.

Enable WSL

- 1. Completely update your Windows machine.
- 2. Open Settings app.
- 3. Click on Apps.
- 4. On right hand side, click on Programs and Features. Yet another settings dialog appears following a completely different standard. Microsoft is wonderful.
- 5. On the left of the new dialog click Turn Windows features on or off.
- 6. Scroll down to Windows Subsystem for Linux.
- 7. Ensure this is checked. If it is not, checking it will enbable WSL.
- 8. Hit OK and close settings related windows.

There is a tiny change your computer BIOS might need to enable Virtualization Technology. You won't find out until much later. Modern machine need this less and less.

Install Ubuntu on Windows

From a command prompt type

wsl --install -d Ubuntu

Follow the rest of the prompts and you'll have a brand spanken new Ubuntu Jammy.

Install QEMU

1. sudo -i

- 2. Enter password.
- 3. apt update If this is your first time, there may be hundreds of packages to grade. Don't. Rather do it at home. See below.
- 4. apt install qemu-system
- 5. Enter
- 6. Wait
- 7. exit This will leave the super user shell.

QEMU is now installed - **at home**, this is how you would update the rest of WSL:

- 1. sudo -i
- 2. apt update
- 3. apt upgrade
- 4. exit

Adding a QEMU alias (Windows)

Edit the file that your terminal runs at launch. This will be ~/.bashrc.

Add this line to the bottom of the file.

alias ARM='qemu-system-aarch64 -M virt -m 2048 -cpu cortex-a53 -kernel vmlinuz-4.9.0-8-arm64 Save the file and exit. How? vi, of course.

- 0. Copy the above line into your copy / paste buffer.
- 1. cd
- $2.\ {\tt vi\ .bashrc}$
- $3. \ G$
- 4. A<enter>
- 5. Paste (use right click)
- 6. ESC
- 7. :wq<enter>

The next time you log in, you should have the alias. You can confirm this by:

> alias

You should see the ARM alias. If you don't something is wrong.

Ensure the alias works (repeat)

You can use this alias when you are in the directory where you installed the distro. It will not work anywhere else. Ensure you are in the right directory now.

Run:

source ~/.bashrc

Now run alias.

You should get this plus some other text potentially:

```
[Donnager] /tmp/aarch64 $ alias ARM='qemu-system-aarch64 -M virt -m 2048 -cpu cortex-a53 -kernel vmlinuz-4.9.0-8-arm64 -in
```

Get the distro

Go to here

- 1. Download aarch64.zip.
- 2. Choose to Open with.
- 3. Create the folder where your distro will live.
- 4. Drag all the files to that folder.

Change directory to where your distro lives

This is not as trivial as it sounds. Your home directory in Ubuntu is not your Windows home directory.

- 1. Change directory to here: /mnt/c/Users
- 2. Then cd to your user account name.
- 3. **THIS** is your Windows home directory.
- 4. cd to the distro.

Ensure the distro boots (repeat)

Run:

ARM

Exit the distro by entering root as the user and a as the password. When the shell prompt is shown, type shutdown now. Always do this to exit the distro.

BOTH PLATFORMS - NEVER USE THE CONSOLE WINDOW

Once you have launched the virtual machine, ssh into it.

ssh user@localhost -p 2222

Don't use the console directly.