0.1 Finite Difference Methods

Finite Difference Methods(FDM) are used for approximating the solution of partial differential equations over a set of finite points, arranged in a geometrical structure called a **mesh**¹, in the continuous domain of solution. The methods involve the idea of reducing the given PDE, by means of truncated taylor series approximation of the derivatives, to a difference equation which is much easier to digest numerically.

0.1.1 Finite Difference Approximations

The quality of the solution depends on the quality of approximations made to the derivatives. Consider this one-dimensional structured mesh of nodes $(x_0, x_1, x_2, ..., x_i, ..., x_n)$ at which the solution $U(x_i)$ is to be found, such that the difference $h = x_{i+1} - x_i$ is constant throughout the mesh and $x_i = x_0 + ih$ Let U_i represent the solution at the *i*-th node and

$$\left. \frac{\partial U}{\partial x} \right|_{x_i} = U_x(x_0 + ih) \equiv U_x|_i$$

$$\left. \frac{\partial^2 U}{\partial x^2} \right|_{x_i} = U_{xx}(x_0 + ih) \equiv U_{xx}|_i$$

The first order derivative can be defined as,

$$U_x|_i = \lim_{h \to 0} \frac{U_{i+1} - U_i}{h}$$
or,
$$U_x|_i = \lim_{h \to 0} \frac{U_i - U_{i-1}}{h}$$
or,
$$U_x|_i = \lim_{h \to 0} \frac{U_{i+1} - U_{i-1}}{2h}$$

Finite difference approximations are obtained by dropping the limit and can be written as,

Forward Difference
$$U_x|_i \approx \frac{U_{i+1} - U_i}{h} \equiv \delta_x^+ U_i$$

Backward Difference $U_x|_i \approx \frac{U_i - U_{i-1}}{h} \equiv \delta_x^- U_i$
Central Difference $U_x|_i \approx \frac{U_{i+1} - U_{i-1}}{2h} \equiv \delta_{2x} U_i$

Where $\delta_x^+, \delta_x^-, \delta_{2x}$ are called the **first-order finite difference operators** and the expansion is called the **finite difference quotient**, each representing forward, backward and centered respectively. Second and Higher order finite difference Quotients can also be obtained,

$$\begin{aligned} U_{xx}|_{i} &= \lim_{h \to 0} \frac{U_{x}(x_{i} + \frac{h}{2}) - U_{x}(x_{i} - \frac{h}{2})}{h} \\ &= \lim_{h \to 0} \frac{1}{h} \left[\frac{U(x+h) - U(x)}{h} - \frac{(U(x) - U(x-h))}{h} \right] \\ &= \lim_{h \to 0} \frac{U_{i+1} - 2U_{i} + U_{i-1}}{h^{2}} \\ &\approx \left[\delta_{x}^{2} U_{i} \equiv \frac{1}{h^{2}} (U_{i+1} - 2U_{i} + U_{i-1}) \right] \end{aligned} \quad \text{[Central second-order Difference]}$$

¹An object which consists of points which are spaced in a specific geometrical pattern is referred to as a **mesh** and each point in this mesh is called a **node**. The distance between any two adjacent nodes in a mesh with uniform spacing is called its **meshsize**

0.1.2 Local Truncation Error of Finite Difference Approximations

The 'error' that accompanies 'approximations' in the method must be accounted for. In this section, the truncation error in the derivative approximations is ascertained which will later help us deduce the error in PDE's solved using these approximations.

The local truncation error for derivative approximations is defined here as the difference between the exact value of the derivate and the approximated value at node i, it can be calculated using Taylor series expansions about i,

For First-order Forward difference operator,

$$\tau \equiv \delta_x^+ U_i - U_x|_i$$

$$= \frac{1}{\Delta x} (U_{i+1} - U_i) - U_x|_i$$

$$= \frac{1}{\Delta x} \left[\left(U_i + \Delta x U_x|_i + \frac{1}{2} \Delta x^2 U_{xx}|_i + \mathcal{O}(\Delta x^3) \right) - U_i \right] - U_x|_i$$

$$= \frac{1}{2} \Delta x U_{xx}|_i + \mathcal{O}(\Delta x^2) = \mathcal{O}(\Delta x)$$

For First-order Backward difference operator,

$$s\tau \equiv \delta_x^- U_i - U_x|_i$$

$$= \frac{1}{\Delta x} (U_i - U_{i-1}) - U_x|_i$$

$$= \frac{1}{\Delta x} \left[U_i - \left(U_i - \Delta x U_x|_i + \frac{1}{2} \Delta x^2 U_{xx}|_i + \mathcal{O}(\Delta x^3) \right) \right] - U_x|_i$$

$$= -\frac{1}{2} \Delta x U_{xx}|_i + \mathcal{O}(\Delta x^2) = \mathcal{O}(\Delta x)$$

For First-order Central difference operator,

$$\begin{split} \tau &\equiv \delta_{2x} U_i - U_x|_i \\ &= \frac{1}{2\Delta x} \left(U_{i+1} - U_{i-1} \right) - U_x|_i \\ &= \frac{1}{2\Delta x} \left[\left(U_i + \Delta x U_x|_i + \frac{1}{2} \Delta x^2 U_{xx}|_i + \frac{1}{6} \Delta x^3 U_{xxx}|_i + \frac{1}{12} \Delta x^4 U_{xxxx}|_i + \mathcal{O}(\Delta x^5) \right) \\ &- \left(U_i - \Delta x U_x|_i + \frac{1}{2} \Delta x^2 U_{xx}|_i - \frac{1}{6} \Delta x^3 U_{xxx}|_i + \frac{1}{12} \Delta x^4 U_{xxxx}|_i + \mathcal{O}(\Delta x^5) \right) \right] - U_x|_i \\ &= -\frac{1}{6} \Delta x^2 U_{xxx_i} + \mathcal{O}(\Delta x^4) = \mathcal{O}(\Delta x^2) \end{split}$$

where in the above expressions we assume that the Higher order derivatives of U at i are well defined. For a fairly small Δx (less than 1) we can confidently say that $\mathcal{O}(\Delta x^2)$ is samller than $\mathcal{O}(\Delta x)^1$. Thus we note that the centered difference approximation (second-order approximation) approximates the derivative more accurately than either of the *one-sided differences*²

0.2 Iterative Methods

0.3 Problems

Analysis

¹The definition of the "big \mathcal{O} " notation says that if for given functions f(x) and g(x) for $x \in S$ where S is some subset of \mathbf{R} , there exists a positive constant A such that $|f(x)| \leq A|g(x)| \ \forall \ x \in S$, we say that f(x) is the "big \mathcal{O} " of g(x) or that f(x) is of order of g(x), mathematically given by $f(x) = \mathcal{O}(g(x))$

²Forward and Backward differences are also called one-sided differences