CS-446/646

Semaphores & Monitors

C. Papachristos

Robotic Workers (RoboWork) Lab University of Nevada, Reno



Semaphore Motivation

Problem with *Lock*:

Ensures Mutual Exclusion, but not execution order

Producer-Consumer problem: Ensuring execution order makes sense

- > Producer: Creates resources
- > Consumer. Uses resources
- ➤ Bounded Buffer: Shared between them
- Execution order: *Producer* should just wait if *Bounded Buffer* is full, *Consumer* should just wait if *Bounded Buffer* is empty
 - e.g. \$ cat entries.txt | sort | uniq | wc

Semaphore Definition

Abstract data type (i.e. a high-level mechanism) to provide Synchronization

Described by Dijkstra in the "THE (Technische Hogeschool Eindhoven) Operating System" in 1968

A Synchronization object that contains an integer counter variable

- ➤ No operation to access integer counter variable directly
- Semaphore safety property: Integer counter value never allowed to go below 0
- ➤ Integer counter variable must be initialized to some value:
 - > sem_init (sem_t *s, int pshared, unsigned int value)
- > Operations to manipulate integer counter variable:
- > sem wait (or down (), P() -robieren): Decrements, Blocks until semaphore is Open
- > sem_post (or up(), V() -erhogen): Increments, allows another *Thread* to enter

```
int sem_wait(sem_t *s) {
    // 1. wait until value of
    // semaphore s becomes > 0
    // 2. if there are 1 or more
    // 2. decrement value by 1
}
```

Blocking in Semaphores

Associated with each Semaphore is a Queue of waiting Threads

When P() / sem_wait() is called by a Thread:

- > If Semaphore is Open, Thread continues
- > If Semaphore is Closed, Thread will Block on Queue

When V() / sem_post() Opens the Semaphore:

- > If a Thread is waiting on the Queue, it is Unblocked
- > If no Threads are waiting on the Queue, the signal is remembered for the next Thread
 - ➤ In other words, **V()** has "memory"
 - In contrast to *Condition Vars* (will see these later)
 - > This "memory" property is derived from the integer counter value



Semaphore Types

Mutex Semaphore (or Binary Semaphore)

- > Represents single access to a resource; X=1
- > Guarantees Mutual Exclusion to a Critical Section

Counting Semaphore (or General Semaphore)

- Represents a resource with many units available, or a resource to which we want to limit concurrent access (e.g. reading); **x>1**
 - Is initialized to number of resources available
- ➤ Multiple *Threads* can pass the *Semaphore* "wait" test
- Number of *Threads* determined by *Semaphore* "counter"

```
Note:
No direct access to counter // critical section
sem post(s);
```

Initializes the Semaphore at sem.

value specifies the initial value for it.

pshared indicates whether this Semaphore is to be shared between the Threads of a Process, or between Processes (sem can be part of a region of Shared Memory).

```
int sem_post(sem_t *sem);
Increments (Unlocks) the Semaphore at sem.
```

```
int sem wait(sem t *sem);
```

Decrements (*Locks*) the *Semaphore* at **sem**. If the *Semaphore* currently has the value zero, then the call *Blocks* until either it becomes possible to perform the decrement or a *Signal* handler *Interrupts* the call.

CS446/646 C. Papachristos



Semaphore Uses

Mutual Exclusion

> Case of Binary Semaphore

```
sem_init(s, 0 \text{ or } 1, X=1)
```

```
sem_wait(s);
// critical section
sem_post(s);
sem_wait(s);
// critical section
sem_post(s);
```

Execution Ordering

➤ Case of Limiting Concurrent Access → Counting Semaphore

```
sem init(s, 0 \text{ or } 1, X=0)
```

```
// 1st half
// of computation
sem_post(s);
```

```
sem_wait(s);
// 2<sup>nd</sup> half
// of computation
```

Producer-Consumer (Bounded-Buffer) Problem

Bounded Buffer

> size N, Access entry 0... N-1, then "wraps around" to 0 again

Producer Thread: Writes data to Bounded Buffer

Consumer Thread: Reads data from Bounded Buffer

Execution ordering constraints:

- > Producer shouldn't try to produce if Bounded Buffer is full
- Consumer shouldn't try to consume if Bounded Buffer is empty



Producer-Consumer (Bounded-Buffer) Problem

```
Solution – 1<sup>st</sup> version
Two Semaphores
> sem t filled; // # of filled slots
> sem t empty; // # of empty slots
Problem: Does this also achieve Mutual Exclusion?
               sem init(&filled, 0, 0);
               sem init(&empty, 0, N);
 void* producer(void* arg) {
                                  void* consumer(void* arg) {
                                                                   Note:
                                    sem wait(&filled);
   sem wait(&empty);
                                                                   Sequencing
   ... // fill a slot
                                    ... // empty a slot
   sem post(&filled);
                                    sem post(&empty);
                                                                   operations
```

CS446/646 C. Papachristos

Producer-Consumer (Bounded-Buffer) Problem

Solution – Final version

```
Three Semaphores
```

```
sem t filled; // # of filled slots
> sem t empty; // # of empty slots
> sem t mutex; // # mutual exclusion
                                               Note: Can also use a pthread mutex t
               sem init(&filled, 0, 0);
               sem init(&empty, 0, N);
                                                                    Note:
               sem init(&mutex, 0, 1);
                                                                    Fill / Empty
 void* producer(void* arg) { void* consumer(void* arg) {
                                                                    operations
   sem wait(&empty);
                                    sem wait(&filled);
                                                                    correspond to
                                                        Data Structure
                                    sem wait(&mutex);
   sem wait(&mutex);
                                                                    manipulating the
                                                          "internal
   ... // fill a slot
                                    ... // empty a slot
                                                                    Circular Buffer's
                                                           access"
   sem post(&mutex);
                                    sem post(&mutex);
                                                         Critical Section head & tail
   sem_post(&filled);
                                    sem_post(&empty);
```

Semaphore Summary

- > Semaphores can be used to solve any of the traditional Synchronization problems
- > Drawbacks:
 - They are essentially shared global variables
 - Can potentially be accessed anywhere in Program
 - No direct connection between the *Semaphore* and the data being controlled by it
 - > Used for both Critical Sections (Mutual Exclusion) and Execution Ordering (Scheduling)
 - No control or guarantees for their proper usage
- When used in complex code can lead to bugginess
 - Solution: Leverage Object-Oriented Programming to support controlled behaviors

Monitors

An Object-Oriented Language construct that controls access to shared data

> Synchronization code added by compiler, enforced at runtime

A module that encapsulates

- > Shared Data Structures
- > Procedures that operate on the shared data structures
- > Synchronization between concurrent Threads that invoke these procedures
- > Guarantees that access of its data through *Threads* is done in legitimate ways only

Monitors

A Monitor guarantees Mutual Exclusion

- > Only one *Thread* can execute **any** *Monitor* Procedure **at a time**
 - The *Thread* is "inside the *Monitor*"
- If a second *Thread* invokes a *Monitor* procedure when a first *Thread* is already executing one, the second *Thread* shall *Block*
 - i.e. the *Monitor* has to have a *Wait Queue*
- ➤ If a *Thread* that is "inside a *Monitor*" *Blocks*, then another *Thread* can enter the *Monitor*

Note: A Monitor Invariant is a safety property associated with the Monitor

- ➤ It's an assertion regarding the *Monitored Variables*
- > It holds whenever a *Thread* enters or exits the *Monitor*
 - i.e. the assertion holds whenever there is no *Thread* executing "inside the *Monitor*"



Monitors

A *Monitor* is like one big *Super-Lock* for a set of operations/methods

It is however a *Language*-level implementation

Compiler automatically inserts the necessary Synchronization operations upon entry and exit of Monitor Procedures Example of (part of) the operalock(this.m); monitor account { tions inserted at Compile-Time.

```
Monitor
Procedures
```

```
int balance;
                                                    ++balance;
public void deposit()
                                                    unlock(this.m);
 ++balance;
public void withdraw()
                                                   lock(this.m);
  --balance;
                                                   --balance;
                                                   unlock(this.m);
```

C++ does not have *Monitors*

Note: But check out synchronized, C++20 Synchronized Blocks (experimental):

Condition Variables

Remember: A Monitor also needs to take care of Wait, Wakeup, Queueing functionalities

- ➤ Not just Locking
- What if a *Thread* has to wait for something to happen/change, but is already "inside the *Monitor*"?
 - Bad if left to just Busy-Wait
 - Worse: No one can now get "inside the Monitor" (e.g. not even to take corrective actions)
 - Have to be able to let a different *Thread* enter "inside the *Monitor*"

In order to achieve the above, a *Monitor* can use a different *Synchronization* mechanism:

Condition Variables

A Condition Variable is associated with a condition needed for a Thread to make progress once it is "inside the Monitor"

Condition Variables (with respect to Monitors)

Operations on Condition Variables

wait()

Suspends the calling *Thread* and releases the *Monitor Lock* (when it resumes, it will reacquire the *Lock*) For **wait()** to be called, the *Thread* has to already be "inside the *Monitor*"

(Should be) called when the *Condition Predicate* is **false**

signal()

Resumes one *Thread* waiting in wait(), if any

(Should be) called once *Condition Predicate* becomes **true**, and wants to **Wakeup one** waiting *Thread*

broadcast(): Resumes all Threads waiting in wait()

(Should be) called once *Condition Predicate* becomes **true**, and wants to **Wakeup all** waiting *Threads*

Note: Condition Variables are not boolean objects; they are associated with a boolean Condition Predicate

- o if (cv) then ... does not make sense
- ✓ if (num_resources == 0) then wait(cv) does



Condition Variables (with respect to Monitors)

Although operations have similar names with Semaphores, they are different

• But one can be used to implement the other

Access to the *Monitor* is controlled by a *Lock*

wait(): Blocks the calling Thread, and gives up the Lock

- To call wait (), the *Thread* has to be "inside the Monitor" (hence holds the *Lock*)
 - Semaphore's sem wait() just blocks the Thread on the Queue

signal (): Causes a waiting Thread to Wakeup

- > If there is no wait() ing Thread, the signal() is lost
 - Remember: Semaphore's sem_post() increases its count, allowing future entry even if no Thread is Waiting right now
- ➤ I.e. Semaphores are "sticky", Condition Variables have no "memory"
 - > If no one is Waiting for a signal (), it is lost



Condition Variables (with respect to Monitors)

Producer-Consumer with Monitors

```
monitor ProducerConsumer {
 int nfilled = 0;
  cond has_empty, has_filled;
  void produce() {
    if (nfilled == N)
      wait (has empty);
      // fill a slot
    ++ nfilled;
    signal (has_filled);
  void consume() {
   if (nfilled == 0)
      wait (has filled);
      // empty a slot
      nfilled;
    signal (has_empty);
};
```

A (one) Monitor with two Condition Variables:

- > has_empty: Buffer has at least one empty slot
- > has_filled: Buffer has at least one filled slot

nfilled: Number of filled slots

E.g.:

- Fig. If a *Thread* tries to **consume ()** and the Buffer is empty, it will be blocked at the *CV*. If another *Thread* tries to **consume ()** again, it will also be blocked at the *CV*, etc.
- If a third Thread tries to **produce()**, it will pass the other CV's wait, and **signal()** (one of) the first 2 Threads

I.e. (each) Condition Variable also has to have a Queue



Condition Variable Signal Semantics

When **signal()** wakes up a waiting *Thread*, which *Thread* to run "inside the *Monitor*"?

The Signaling Thread (/ Signaler), or the Waiting Thread (/ Waiter)?

Hoare Semantics:

Suspends Signaler, and immediately transfers control to a Waiter

- The Condition that the Waiter was anticipating is guaranteed to hold when waiter executes
- Difficult to implement in practice, Signaler must restore Monitor Invariants before signaling Remember: Assertions that hold whenever no Thread is

Mesa Semantics

Remember: Assertions that hold whenever no *Thread* is "inside the *Monitor*"; i.e. implementation needs to remember state because *Thread* hasn't completed yet

Signal moves a single *Waiter* from the blocked state to a runnable state, then the *Signaler* continues until it "exits the *Monitor*"

- Problem: Condition Variable's Predicate is not necessarily true when Waiter gets to run again
 - Return from wait() is only a hint that something changed, always have to recheck Predicate
- E.g. Spurious Wakeup Fill one single slot and **signal()**, but before a scheduled woken consumer grabs the Queue Lock to continue, a different (e.g. fourth) Thread enters the Queue, grabs the Lock, consumes the one filled slot. The woken Thread will find the Predicate changed once it runs.

 C. Papachristos

Condition Variables

Producer-Consumer with Monitors

```
monitor ProducerConsumer {
  int nfilled = 0;
  cond has empty, has filled;
  void produce() {
    while (nfilled == N)
      wait (has empty);
    ... // fill a slot
    ++ nfilled;
    signal (has filled);
  void consume() {
    while (nfilled == 0)
      wait (has filled);
    ... // empty a slot
    -- nfilled;
    signal (has_empty);
```

Spurious Wakeup — pthread

- > pthread_cond_signal() is only guaranteed to unblock at least one *Thread*
- Even worse, a *Thread* blocked in pthread_cond_wait can return with no pthread_cond_signal/broadcast() call

Spurious Wakeup Fix:

- When woken up, a *Thread* must recheck the *Predicate* associated to the *Condition Variable* it was waiting on
- Most systems use Mesa Semantics
 - e.g. pthread



Monitor & Condition Variables with pthread

```
Producer-Consumer with Monitors
class ProducerConsumer {
  int nfull = 0;
 pthread mutex t m;
  pthread cond t has empty,
                 has full;
  public:
  void produce() {
    pthread mutex lock(&m);
    while (nfull == N)
      pthread_cond_wait(&has_empty,
                         &m);
    ... // fill slot
    ++ nfull;
    pthread cond signal(has full);
    pthread mutex unlock(&m);
```

C/C++ don't provide *Monitors*, but we can implement such functionality using pthread_mutex_t and pthread_cond_t

For the *Producer-Consumer* problem, we need 1 *Mutex* and 2 *Condition Variables*

- Manually lock and unlock *Mutex* for *Monitor* procedures
- int pthread_cond_wait(
 pthread_cond_t *restrict cond,
 pthread_mutex_t *restrict mutex);

Atomically waits on cond and releases mutex

The function shall *Block* on a *Condition Variable*. It shall be called with *mutex* locked by the calling *Thread* or Undefined Behavior results. The function **atomically** releases **mutex** and causes the calling *Thread* to *Block* on **cond**... Upon successful return, the **mutex** shall have been locked and shall be owned by the calling *Thread*.

Monitor & Condition Variables with pthread

```
Producer-Consumer with Monitors
class ProducerConsumer {
  int nfull = 0;
 pthread_mutex_t m;
  pthread_cond_t has_empty,
                  has full;
  public:
  void produce() {
    pthread mutex lock(&m);
    while (nfull == N)
      pthread_cond_wait(&has_empty,
                         &m);
    ... // fill slot
    ++ nfull;
    pthread cond signal(has full);
    pthread mutex unlock(&m);
      Note: Unlock the Mutex after calling
      pthread cond signal()
```

```
C/C++ don't provide Monitors, but we can implement such functionality using pthread mutex t and pthread cond t
```

For the *Producer-Consumer* problem, we need 1 *Mutex* and 2 *Condition Variables*

- Manually lock and unlock *Mutex* for *Monitor* procedures

Atomically waits on **cond** and releases **mutex**

The function shall *Unblock* at least one of the *Threads* that are *Blocked* on the specified *Condition Variable* cond... may be called by a *Thread* whether or not it currently owns the *Mutex* that *Threads* calling pthread_cond_wait() ... have associated with the *Condition Variable*... however, if predictable *Scheduling* behaviour is required, then that *Mutex* is *Locked* by the pthread_cond_signal()-calling Thread

CS446/646 C. Papachristos

CS-446/646 Time for Questions! CS446/646 C. Papachristos