Semiempirical NDDO Guide

Schrödinger Software Release 2015-2



Semiempirical NDDO Guide Copyright © 2015 Schrödinger, LLC. All rights reserved.

While care has been taken in the preparation of this publication, Schrödinger assumes no responsibility for errors or omissions, or for damages resulting from the use of the information contained herein.

Canvas, CombiGlide, ConfGen, Epik, Glide, Impact, Jaguar, Liaison, LigPrep, Maestro, Phase, Prime, PrimeX, QikProp, QikFit, QikSim, QSite, SiteMap, Strike, and WaterMap are trademarks of Schrödinger, LLC. Schrödinger, BioLuminate, and MacroModel are registered trademarks of Schrödinger, LLC. MCPRO is a trademark of William L. Jorgensen. DESMOND is a trademark of D. E. Shaw Research, LLC. Desmond is used with the permission of D. E. Shaw Research. All rights reserved. This publication may contain the trademarks of other companies.

Schrödinger software includes software and libraries provided by third parties. For details of the copyrights, and terms and conditions associated with such included third party software, use your browser to open third_party_legal.html, which is in the docs folder of your Schrödinger software installation.

This publication may refer to other third party software not included in or with Schrödinger software ("such other third party software"), and provide links to third party Web sites ("linked sites"). References to such other third party software or linked sites do not constitute an endorsement by Schrödinger, LLC or its affiliates. Use of such other third party software and linked sites may be subject to third party license agreements and fees. Schrödinger, LLC and its affiliates have no responsibility or liability, directly or indirectly, for such other third party software and linked sites, or for damage resulting from the use thereof. Any warranties that we make regarding Schrödinger products and services do not apply to such other third party software or linked sites, or to the interaction between, or interoperability of, Schrödinger products and services and such other third party software.

May 2015

Document Conventions

In addition to the use of italics for names of documents, the font conventions that are used in this document are summarized in the table below.

Font	Example	Use
Sans serif	Project Table	Names of GUI features, such as panels, menus, menu items, buttons, and labels
Monospace	\$SCHRODINGER/maestro	File names, directory names, commands, environment variables, command input and output
Italic	filename	Text that the user must replace with a value
Sans serif uppercase	CTRL+H	Keyboard keys

Links to other locations in the current document or to other PDF documents are colored like this: Document Conventions.

In descriptions of command syntax, the following UNIX conventions are used: braces { } enclose a choice of required items, square brackets [] enclose optional items, and the bar symbol | separates items in a list from which one item must be chosen. Lines of command syntax that wrap should be interpreted as a single command.

File name, path, and environment variable syntax is generally given with the UNIX conventions. To obtain the Windows conventions, replace the forward slash / with the backslash \ in path or directory names, and replace the \$ at the beginning of an environment variable with a % at each end. For example, \$SCHRODINGER/maestro becomes *SCHRODINGER*\maestro.

Keyboard references are given in the Windows convention by default, with Mac equivalents in parentheses, for example CTRL+H (%H). Where Mac equivalents are not given, COMMAND should be read in place of CTRL. The convention CTRL-H is not used.

In this document, to *type* text means to type the required text in the specified location, and to *enter* text means to type the required text, then press the ENTER key.

References to literature sources are given in square brackets, like this: [10].

Semiempirical NDDO Calculations

Schrödinger Software Release 2015-2 provides access to basic semiempirical NDDO capabilities. Two versions are available: the Semiempirical NDDO module is based on the public domain version of MOPAC 7.1 available at www.openmopac.net; and MOPAC2012 is the commercially available version of MOPAC, which requires a license. With these tools you can calculate heats of formation, optimized geometries, force constants, and a selection of properties as indicated below. The semiempirical NDDO programs can be run from Maestro or from the command line.

In the version that is based on the public domain version of MOPAC 7.1, we have changed some of the behavior. The use of some keywords has been explicitly blocked because the feature does not actually work correctly. The supported keywords are listed in this manual. Input files for commercial releases of MOPAC may not work with this module.

1 The Semiempirical NDDO Module Panel

Semiempirical NDDO jobs can be set up and run from Maestro by using the Semiempirical NDDO Module or the MOPAC2012 panel. To open these panels, choose Applications \rightarrow Semiempirical NDDO \rightarrow Semiempirical NDDO or Applications \rightarrow Semiempirical NDDO \rightarrow MOPAC2012 in the main window.




Figure 1. The Semiempirical NDDO Module panel.




Figure 2. The MOPAC2012 panel.

The input structures can come from a file, from the Project Table, or from the Workspace. You can choose the structure source from the Use structures from option menu. If the input structure source is a file, enter the file name in the Input file text box, or click the Browse button and navigate to the input file. The structure file can be in Maestro, SD, or MOL2 format.

You can choose the method to use from the Method option menu. The available methods in the Semiempirical NDDO panel are RM1, AM1, PM3, MNDO and MNDO/d. In the MOPAC2012 panel, these are supplemented with PM6, PM6-D3, PM6-DH+, PM6-DH2, PM6-DH2X, PM7, and PM7-TS [3,4]. The variants of PM6 are corrected for one or more of dispersion, hydrogen bonding, and halogen bonding. PM7-TS is intended only for barrier heights of transition states. If you want to optimize the geometry, select Optimize geometry; to run a single point calculation, deselect this option.

You can set the charge and spin multiplicity for the molecule in the Charge and Multiplicity boxes, and choose the type of wave function for open-shell molecules. The type is automatically set to ROHF if you set the multiplicity higher than 1. The maximum multiplicity is 6.

If you want to calculate properties, select the appropriate options in the Molecular and atomic properties section. These options correspond to keywords given in Section 3.2: the SAR properties option corresponds to the **SUPER** keyword. Likewise, if you want to generate grids for the display of surfaces in Maestro, select the appropriate options in the Plot properties section. These options correspond to keywords given in Section 3.3 for the Semiempirical NDDO module.

To specify other options, you can enter keywords in the Keywords text box. The keywords you can use with the Semiempirical NDDO module are described in Section 3.

If you are running a calculation on a large structure (1000 or more atoms) with the MOPAC2012 program, you can add the MOZYME keyword to the Keywords text box to speed up the calculations, especially if you are running on biological systems, for which this keyword was designed.

In addition to a Maestro file, the output from the job includes output files (.out) for each structure. You can collect these files into a zip file by selecting Archive output files (the default).

To start the job, enter a name in the Job name text box and click Run, or click the Settings button, make settings in the Job Settings dialog box, then click Run. You can choose not to incorporate the results into the Maestro project, or to append new entries to the project. The output properties include the semiempirical energy as an entry property, and the atomic partial charges as atom-level properties.

2 Running a Semiempirical NDDO Job from the Command Line

To run a semiempirical NDDO job from the command line, use the following syntax:

\$SCHRODINGER/run semi emp.py [-MOPAC2012] [options] [job-options] structure-file

The input structure file can contain multiple structures, which will all be processed in the job. The file can be in Maestro, SD, or MOL2 format. For a description of the command options, run the command with the -h option.

As an example, if you have a Maestro file called myfile.mae that contains three ligands whose geometries you would like to optimize with the PM3 method, and you want to print out the final bond order matrix, and the sigma-pi bond order matrix, you would use this command:

```
$SCHRODINGER/run semi emp.py -method pm3 -keywords "bonds pi" myfile.mae
```

This job produces output files named myfile_1.out, myfile_2.out, and myfile_3.out, together with an output structure file called myfile_out.mae, which contains the final geometries, the method used, the semi-empirical energy, and the atomic charges (which are calculated by default). This structure file may be manually imported into Maestro. Atoms may be labeled with their partial charges by selecting Atomic Charge from the list of available labels in the Atom Labels panel. These charges may also be used in docking calculations with Glide. In addition, a log file is produced, which includes information about the job options used.

3 Keywords Supported in the Semiempirical NDDO Module

The keywords that are supported in the Semiempirical NDDO module for use with the -keywords command option are given in this section. Keywords are not case-sensitive. The keywords listed below are the only keywords that are supported with this module. Any other keywords that exist in the original code might work, but you use them at your own risk, as they might not give the results you expect.

For a full list of supported keywords for MOPAC2012, go to http://openmopac.net/manual/allkeys.html.

3.1 General Keywords

RM1, AM1, PM3, MNDO, MNDOD

These keywords select the method used to calculate the semi-empirical heat of formation. RM1 is the default, and is recommended. It is a reparameterization for some of the elements covered by AM1. The Semiempirical NDDO module automatically uses AM1 parameters for elements covered by AM1 that are not covered by RM1. The elements covered by the methods (as they were implemented in the source MOPAC 7.1 code) are given in Table 1.

				l methods.

Method	Elements covered
RM1	H, C, N, O, F, P, S, Cl, Br, I
AM1	H, B, C, N, O, F, Al, Si, P, S, Cl, Zn, Ge, As, Se, Br, Sb, Te, I, La, Ce, Pr, Nd, Pm, Sm, Eu, Gd, Tb, Dy, Ho, Er, Tm, Yb, Lu, Hg
PM3	H, Li, Be, C, N, O, F, Na, Mg, Al, Si, P, S, Cl, Zn, Ga, Ge, As, Se, Br, Cd, In, Sn, Te, I, Hg, Tl, Pb, Bi
MNDO	H, Li, Be, B, C, N, O, F, Na, Al, Si, P, S, Cl, K, Zn, Ge, Br, Sn, I, Hg, Pb
MNDOD	Na, Mg, Al, Si, P, S, Cl, Zn, Br, Cd, I, Hg

The literature citations for the sources of parameters for these elements is printed by the program when the parameters are used, so please consult the output file for this information.

CHARGE=n

For charged molecules, CHARGE must be set to the overall molecular charge.

DOUBLET

The default spin multiplicity is singlet, but spin doublets may be modeled by including the DOUBLET keyword. The doublet wave function is spin-restricted.

MMOK, NOMM

One of these two keywords must be set whenever a calculation is performed on a molecule containing a peptide bond. For the convenience of batch processing large numbers of structures, MMOK is set by default, and is ignored for molecules that do not contain a peptide bond. With MMOK set, a correction factor (derived from molecular mechanics) is applied to the rotational barrier around each peptide bond. This is to compensate for the fact that all of the NDDO methods in the module underestimate this rotational barrier. To prevent this correction from being applied, set NOMM.

FORCE, THERMO(nnn,mmm,III)

The FORCE keyword requests calculation of the vibrational frequencies for the input molecule. The THERMO keyword, without any of the optional arguments in parentheses, requests calculation of the thermodynamic properties such as internal energy, enthalpy, and entropy, plus the vibrational, rotational, translational partition functions. By default, the thermodynamic functions are calculated at 298K and at 10K increments from 200K to 400K. A different starting temperature, final temperature, and increment can be specified using the (nnn,mmm,lll) options. For example, use THERMO (273, 293, 20) to print thermodynamic properties at 298K (which is always done) and at 273K and 293K.

3.2 Molecular Properties

MULLIK

By default, atomic charges are calculated by summing up the density matrix elements for each atom's basis functions. To take into account the overlap of basis functions between atoms, use this keyword to perform a Mulliken analysis.

ESP

Print the atomic charges that best reproduce the molecular electrostatic potential.

BONDS

Print the bond orders for all pairs of atoms.

PΙ

Print bond orders broken down into sigma and pi components.

SUPER

Several atomic properties which have proven useful in developing structure-activity relationships can be calculated with the keyword SUPER. These include the HOMO and LUMO energies, the molecular hardness and electronegativity, which are added as structure-level properties. For each atom, the electrophilic and nucleophilic frontier electron density, the electrophilic, nucleophilic, and radical superdelocalizability, and the atom self-polarizability are calculated as atom-level properties; these are summed to give a total value, added as a structure-level property. The atomic properties are calculated according to the equations given in Ref 1. For applications, see the review article, Ref 2, and citations therein.

VECTORS

Print the coefficients, energies, and symmetries for the molecular orbitals near the HOMO and LUMO.

3.3 Plot Keywords

These keywords are used by the Semiempirical NDDO module to generate a 3-dimensional grid of electronic properties that can be used in Maestro to display surfaces. For ESP, ALIE, and ALEA surfaces, an analysis of the values of the property on the isodensity surface is included in the output and recorded as Maestro properties in the output structure file. See Appendix 6.3.6.7 of the *Jaguar User Manual* for a fuller description of the analysis (as applied to ESP surfaces).

PLOTDEN

Evaluate the electron density on a grid and write the data to the file *jobname*_density.vis.

PLOTESP

Evaluate the molecular electrostatic potential on a grid and write the data to the file *jobname_*potential.vis. Since the ESP is usually visualized as a color-coded mapping onto an isosurface of the electron density, the electron density is also evaluated on the same grid, as if PLOTDEN had been set.

PLOTALIE

Evaluate the average local ionization energy on a grid and write the data to the file *jobname_*alie.vis. Since the ALIE is usually visualized as a color-coded mapping onto an isosurface of the electron density, the electron density is also evaluated on the same grid, as if PLOTDEN had been set.

PLOTALEA

Evaluate the average local electron affinity on a grid and write the data to the file *jobname_*alea.vis. Since the ALEA is usually visualized as a color-coded mapping onto an isosurface of the electron density, the electron density is also evaluated on the same grid, as if PLOTDEN had been set.

PLOTMO[=N]

If PLOTMO is set by itself, then the HOMO and LUMO are evaluated on a grid and written to files called *jobname_MO_n.vis*, where *n* is the molecular orbital index number corresponding to the HOMO or LUMO. If PLOTMO=*N* is used, where *N* is a positive integer, then the *N* highest occupied orbitals and the *N* lowest unoccupied orbitals are tabulated on the grid. If you want all molecular orbitals to be tabulated, set N to a large number such as 999.

GRIDEXT=N.M

By default, the grid on which the above properties are evaluated extends 3.5 angstroms beyond the nuclei. This should be adequate to avoid truncating displayed isosurfaces as long as the isovalues are not too small. However, if you find that a displayed isosurface has been truncated, you can specify a larger grid extension distance by setting GRIDEXT to a value larger than 3.5. Note that increasing GRIDEXT increases the calculation time.

GRIDRES=N.M

The default grid resolution is 5.0 points per angstrom along each side of the grid box. This yields reasonably smooth displayed surfaces while keeping calculation times short. If a higher quality surface is desired, set GRIDRES to a number larger than 5.0. Note that increasing GRIDRES increases the calculation time.

4 Limitations

The following limitations should be noted:

- Spin states higher than sextet are not available.
- ESP and SUPER calculations cannot be run with the MNDO/d method.
- UHF (unsupported keyword) cannot be used for ESP, MULLIKEN, or SUPER calculations.

5 Troubleshooting

If you use a Maestro structure file as input, and you experience a problem running the module and want to see the input file that is created from the .mae file, include the -SAVE option on the command line. This option creates a .zip file of the job scratch directory, including the input file, which has the name *jobname*.mop. You might be able to edit this file to work around the problem, and then submit the job using the .mop file as input.

6 Citing Semiempirical NDDO Programs

The use of the Semiempirical NDDO module should be acknowledged in publications as:

Semiempirical NDDO Module 2015-2, Schrödinger LLC, New York, NY, 2015.

The use of the MOPAC2012 program should be acknowledged in publications as:

MOPAC2012, James J. P. Stewart, Stewart Computational Chemistry, Colorado Springs, CO, USA, HTTP://OpenMOPAC.net (2012).

References

- 1. Gancia, E.; Montana, J. G.; Manallack, D. T. J. Mol. Graph. Model. 2001, 19, 349.
- 2. Karelson, M.; Lobanov, V. S.; Katritzky, A. R. Chem. Rev. 1996, 96, 1027.
- 3. Stewart, J. J. P. Optimization of Parameters for Semiempirical Methods V: Modification of NDDO Approximations and Application to 70 Elements. *J. Mol. Modeling* **2007**, *13*, 1173.
- 4. Stewart, J. J. P. Optimization of parameters for semiempirical methods VI: more modifications to the NDDO approximations and re-optimization of parameters. *J. Mol. Modeling* **2013**, *19*, 1.

Getting Help

Information about Schrödinger software is available in two main places:

- The docs folder (directory) of your software installation, which contains HTML and PDF documentation. Index pages are available in this folder.
- The Schrödinger web site, http://www.schrodinger.com/, In particular, you can use the Knowledge Base, http://www.schrodinger.com/kb, to find current information on a range of topics, and the Known Issues page, http://www.schrodinger.com/knownissues, to find information on software issues.

Finding Information in Maestro

Maestro provides access to nearly all the information available on Schrödinger software.

To get information:

- Pause the pointer over a GUI feature (button, menu item, menu, ...). In the main window, information is displayed in the Auto-Help text box, which is located at the foot of the main window, or in a tooltip. In other panels, information is displayed in a tooltip.
 - If the tooltip does not appear within a second, check that Show tooltips is selected under General \rightarrow Appearance in the Preferences panel, which you can open with CTRL+, (\Re ,). Not all features have tooltips.
- Click the Help button in the lower right corner of a panel or press F1, for information about a panel or the tab that is displayed in a panel. The help topic is displayed in the Help panel. The button may have text or an icon:



- Choose Help → Online Help or press CTRL+H (第H) to open the default help topic.
- When help is displayed in the Help panel, use the navigation links in the help topic or search the help.
- Choose Help → Documentation Index, to open a page that has links to all the documents.
 Click a link to open the document.

 Choose Help → Search Manuals to search the manuals. The search tab in Adobe Reader opens, and you can search across all the PDF documents. You must have Adobe Reader installed to use this feature.

For information on:

- Problems and solutions: choose Help → Knowledge Base or Help → Known Issues → product.
- New software features: choose Help → New Features.
- Python scripting: choose Help → Python Module Overview.
- Utility programs: choose Help → About Utilities.
- Keyboard shortcuts: choose Help → Keyboard Shortcuts.
- Installation and licensing: see the *Installation Guide*.
- Running and managing jobs: see the *Job Control Guide*.
- Using Maestro: see the *Maestro User Manual*.
- Maestro commands: see the Maestro Command Reference Manual.

Contacting Technical Support

If you have questions that are not answered from any of the above sources, contact Schrödinger using the information below.

Web: http://www.schrodinger.com/supportcenter

E-mail: <u>help@schrodinger.com</u>

Mail: Schrödinger, 101 SW Main Street, Suite 1300, Portland, OR 97204

Phone: +1 888 891-4701 (USA, 8am – 8pm Eastern Time)

+49 621 438-55173 (Europe, 9am – 5pm Central European Time)

Fax: +1 503 299-4532 (USA, Portland office)

FTP: ftp://ftp.schrodinger.com

Generally, using the web form is best because you can add machine output and upload files, if necessary. You will need to include the following information:

- All relevant user input and machine output
- Semiempirical NDDO purchaser (company, research institution, or individual)
- Primary Semiempirical NDDO user
- Installation, licensing, and machine information as described below.

Gathering Information for Technical Support

The instructions below describe how to gather the required machine, licensing, and installation information, and any other job-related or failure-related information, to send to technical support. Where the instructions depend on the profile used for Maestro, the profile is indicated.

For general enquiries or problems:

- 1. Open the Diagnostics panel.
 - Maestro: Help → Diagnostics
 - Windows: Start → All Programs → Schrodinger-2015-2 → Diagnostics
 - Mac: Applications → Schrodinger2015-2 → Diagnostics
 - Command line: \$SCHRODINGER/diagnostics
- 2. When the diagnostics have run, click Technical Support.

A dialog box opens, with instructions. You can highlight and copy the name of the file.

3. Upload the file specified in the dialog box to the support web form.

If you have already submitted a support request, use the upload link in the email response from Schrödinger to upload the file. If you need to submit a new request, you can upload the file when you fill in the form.

If your job failed:

- 1. Open the Monitor panel, using the instructions for your profile as given below:
 - Maestro/Jaguar/Elements: Tasks \rightarrow Monitor Jobs
 - BioLuminate/MaterialsScience: Tasks → Job Monitor
- 2. Select the failed job in the table, and click Postmortem.

The Postmortem panel opens.

- 3. If your data is not sensitive and you can send it, select Include structures and deselect Automatically obfuscate path names.
- 4. Click Create.

An archive file is created, and an information dialog box with the name and location of the file opens. You can highlight and copy the name of the file.

5. Upload the file specified in the dialog box to the support web form.

If you have already submitted a support request, use the upload link in the email response from Schrödinger to upload the file. If you need to submit a new request, you can upload the file when you fill in the form.

- 6. Copy and paste any log messages from the window used to start the interface or the job into the web form (or an e-mail message), or attach them as a file.
 - Windows: Right-click in the window and choose Select All, then press ENTER to copy the text.
 - Mac: Start the Console application (Applications → Utilities), filter on the application that you used to start the job (Maestro, BioLuminate, Elements), copy the text.

If Maestro failed:

- 1. Open the Diagnostics panel.
 - Windows: Start → All Programs → Schrodinger-2015-2 → Diagnostics
 - Mac: Applications → SchrodingerSuite2015-2 → Diagnostics
 - Linux/command line: \$SCHRODINGER/diagnostics
- 2. When the diagnostics have run, click Technical Support.

A dialog box opens, with instructions. You can highlight and copy the name of the file.

3. Upload the file specified in the dialog box to the support web form.

If you have already submitted a support request, use the upload link in the email response from Schrödinger to upload the file. If you need to submit a new request, you can upload the file when you fill in the form.

4. Upload the error files to the support web form.

The files should be in the following location:

- Windows: %LOCALAPPDATA%\Schrodinger\appcrash
 (Choose Start → Run and paste this location into the Open text box.)
 Attach maestro error pid.txt and maestro.exe pid timestamp.dmp.
- Mac: \$HOME/Library/Logs/CrashReporter
 (Go → Home → Library → Logs → CrashReporter)
 Attach maestro error pid.txt and maestro timestamp machinename.crash.
- Linux: \$HOME/.schrodinger/appcrash
 Attach maestro error pid.txt and crash report timestamp pid.txt.

If a Maestro panel failed to open:

- 1. Copy the text in the dialog box that opens.
- 2. Paste the text into the support web form.

120 West 45th Street 17th Floor New York, NY 10036

155 Gibbs St Suite 430 Rockville, MD 20850-0353

Quatro House Frimley Road Camberley GU16 7ER United Kingdom

101 SW Main Street Suite 1300 Portland, OR 97204

Dynamostraße 13 D-68165 Mannheim Germany

8F Pacific Century Place 1-11-1 Marunouchi Chiyoda-ku, Tokyo 100-6208

Japan

245 First Street Riverview II, 18th Floor Cambridge, MA 02142

Zeppelinstraße 73 D-81669 München Germany

No. 102, 4th Block 3rd Main Road, 3rd Stage Sharada Colony Basaveshwaranagar Bangalore 560079, India

8910 University Center Lane Suite 270 San Diego, CA 92122

Potsdamer Platz 11 D-10785 Berlin Germany

SCHRÖDINGER.