Schrödinger Product Installation on Linux

The instructions below are for a new installation of Schrödinger Suite 2012 Update 2 software on a typical Linux platform. If you need more details or encounter problems, refer to the *Installation Guide*, which is included at the top level of the DVD or the download along with these instructions.

Checking your system

1. Check that your system has sufficient disk space:

```
df -h
```

To install all products, at least 8 GB is needed for each architecture (32 bit or 64 bit). 25 GB is required for the PDB and BLAST databases for Prime.

2. Check that your system version is adequate:

```
uname -r
```

For recent Linux distributions, the version reported should be at least 2.6.12.

Installing the software

3. If installing from DVD, mount the product DVD.

You must have a DVD-ROM drive or a DVD-R Read/Write or DVD+/-R Read/Write drive. DVD+R Read/Write drives cannot read our DVDs.

If installing from a download, extract the tar file:

```
tar -xvf Schrodinger Internet Download.tar
```

4. Change to the top-level directory on the DVD or the download:

```
cd topleveldir
```

For a download this directory should be the subdirectory Schrodinger_Internet_Download in the directory you extracted the tar file.

5. Run the install script:

```
sh ./INSTALL
```

Using sh is sometimes necessary when installing from DVD.

6. Enter the information requested by the INSTALL script.

The installation directory must not contain a previous Schrödinger software release. It is created if it does not exist. See Section 3.3 of the *Installation Guide* for details.

 $7. \ \ Set the \ {\tt SCHRODINGER} \ environment \ variable \ to \ the \ installation \ directory:$

```
bash: export SCHRODINGER=installdir csh/tcsh: setenv SCHRODINGER installdir
```

8. Set the SCHRODINGER PYTHONPATH environment variable if PYTHONPATH is defined:

```
bash:     export SCHRODINGER_PYTHONPATH=""
csh/tcsh:     setenv SCHRODINGER PYTHONPATH
```

Setting up access to remote hosts

9. Edit the file \$SCHRODINGER/schrodinger.hosts and add entries for all hosts or batch queues on which the software will be run. Do not remove the localhost entry.

See Section 7.1 and Section 7.3 of the *Installation Guide* for details. The minimum required for a host entry is name: *hostname*

10. Set up passwordless ssh access between all hosts on which the software will be run.

See Section 7.2 of the *Installation Guide* for details.

11. Perform any necessary cluster configuration (see Section 7.5 of the *Installation Guide*).

Setting up licensing

- 12. Log on to the license server host (if you are not already logged on to it).
- 13. Run the machid script to obtain information for the license:

```
$SCHRODINGER/machid > machid.out
```

- 14. Send the output of machid to help@schrodinger.com to obtain a license.
- 15. When you receive the license information, which is sent as an attachment, save it as \$SCHRODINGER/license. You can overwrite the existing file, which is a placeholder.
- 16. On the license server host, start the license server, and check that it is running.

```
licadmin SERVERUP licadmin STAT
```

See Chapter 6 of the *Installation Guide* for details.

Checking the installation

17. Run the installation checker:

```
$SCHRODINGER/installation check
```

18. Start Maestro to ensure that it is correctly installed.

```
$SCHRODINGER/maestro &
```

- 19. Choose Help → Manuals Index to ensure that the PDF viewer is working correctly from Maestro.
- 20. Choose Help \rightarrow Online Help to ensure that the browser is working correctly from Maestro.