NAME

```
gcc - GNU project C and C++ compiler
```

SYNOPSIS

```
gcc [-c|-S|-E] [-std=standard]
[-g] [-pg] [-Olevel]
[-Wwarn...] [-Wpedantic]
[-Idir...] [-Ldir...]
[-Dmacro[=defn]...] [-Umacro]
[-foption...] [-mmachine-option...]
[-o outfile] [@file] infile...
```

Only the most useful options are listed here; see below for the remainder. \mathbf{g} ++ accepts mostly the same options as \mathbf{gcc} .

DESCRIPTION

When you invoke GCC, it normally does preprocessing, compilation, assembly and linking. The "overall options" allow you to stop this process at an intermediate stage. For example, the -c option says not to run the linker. Then the output consists of object files output by the assembler.

Other options are passed on to one stage of processing. Some options control the preprocessor and others the compiler itself. Yet other options control the assembler and linker; most of these are not documented here, since you rarely need to use any of them.

Most of the command-line options that you can use with GCC are useful for C programs; when an option is only useful with another language (usually C++), the explanation says so explicitly. If the description for a particular option does not mention a source language, you can use that option with all supported languages.

The **gcc** program accepts options and file names as operands. Many options have multi-letter names; therefore multiple single-letter options may *not* be grouped: $-\mathbf{d}\mathbf{v}$ is very different from $-\mathbf{d} - \mathbf{v}$.

You can mix options and other arguments. For the most part, the order you use doesn't matter. Order does matter when you use several options of the same kind; for example, if you specify **-L** more than once, the directories are searched in the order specified. Also, the placement of the **-l** option is significant.

Many options have long names starting with **-f** or with **-W**——for example, **-fmove-loop-invariants**, **-Wformat** and so on. Most of these have both positive and negative forms; the negative form of **-ffoo** is **-fno-foo**. This manual documents only one of these two forms, whichever one is not the default.

OPTIONS

Option Summary

Here is a summary of all the options, grouped by type. Explanations are in the following sections.

Overall Options

C Language Options

```
-ansi
                -std=standard
                                        -fgnu89-inline
                                                                 -aux-info
                                                                                    filename
-fallow-parameterless-variadic-functions
                                            -fno-asm
                                                        -fno-builtin
                                                                        -fno-builtin-function
-fhosted
            -ffreestanding
                             -fopenmp
                                         -fms-extensions
                                                            -fplan9-extensions
                                                                                  -trigraphs
-traditional
                                                                           -fcond-mismatch
                   -traditional-cpp
                                           -fallow-single-precision
                              -fsigned-bitfields
                                                     -fsigned-char
                                                                         -funsigned-bitfields
-flax-vector-conversions
-funsigned-char
```

C++ Language Options

```
-fabi-version=n -fno-access-control -fcheck-new -fconstexpr-depth=n -ffriend-injection

-fno-elide-constructors -fno-enforce-eh-specs -ffor-scope -fno-for-scope

-fno-implicit-templates -fno-implicit-inline-templates

-fno-implement-inlines -fms-extensions -fno-nonansi-builtins -fnothrow-opt
```

```
-fno-operator-names -fno-optional-diags
                                              -fpermissive -fno-pretty-templates
    -fno-rtti -fstats -ftemplate-backtrace-limit=n -ftemplate-depth=n -fno-threadsafe-statics
                                -nostdinc++ -fno-default-inline -fvisibility-inlines-hidden
    -fuse-cxa-atexit -fno-weak
    -fvisibility-ms-compat
                               -fext-numeric-literals
                                                          -Wabi
                                                                       -Wconversion-null
    -Wctor-dtor-privacy -Wdelete-non-virtual-dtor -Wliteral-suffix -Wnarrowing -Wnoexcept
                                -Wreorder
    -Wnon-virtual-dtor
                                                  -Weffc++
                                                                    -Wstrict-null-sentinel
    -Wno-non-template-friend
                                         -Wold-style-cast
                                                                     -Woverloaded-virtual
    -Wno-pmf-conversions -Wsign-promo
Objective-C and Objective-C++ Language Options
                                      -fgnu-runtime
                                                       -fnext-runtime
    -fconstant-string-class=class-name
                                                                        -fno-nil-receivers
    -fobjc-abi-version=n
                         -fobjc-call-cxx-cdtors
                                                 -fobjc-direct-dispatch
                                                                        -fobjc-exceptions
    -fobjc-gc -fobjc-nilcheck -fobjc-std=objc1 -freplace-objc-classes -fzero-link -gen-decls
    -Wassign-intercept
                            -Wno-protocol
                                                 -Wselector
                                                                  -Wstrict-selector-match
    -Wundeclared-selector
Language Independent Options
                                               -fdiagnostics-show-location=[once|every-line]
    -fmessage-length=n
    -fno-diagnostics-show-option -fno-diagnostics-show-caret
Warning Options
    -fsyntax-only -fmax-errors=n -Wpedantic -pedantic-errors -w -Wextra -Wall -Waddress
    -Waggregate-return -Waggressive-loop-optimizations -Warray-bounds -Wno-attributes
    -Wno-builtin-macro-redefined
                                     -Wc++-compat
                                                       -Wc++11-compat
                                                                            -Wcast-align
    -Wcast-qual
                    -Wchar-subscripts
                                           -Wclobbered
                                                            -Wcomment
                                                                            -Wconversion
    -Wcoverage-mismatch
                            -Wno-cpp
                                         -Wno-deprecated
                                                            -Wno-deprecated-declarations
                                                   -Wdouble-promotion
    -Wdisabled-optimization
                              -Wno-div-by-zero
                                                                          -Wempty-body
    -Wenum-compare -Wno-endif-labels -Werror -Werror=* -Wfatal-errors -Wfloat-equal
    -Wformat
                  -Wformat=2
                                   -Wno-format-contains-nul
                                                                 -Wno-format-extra-args
                          -Wformat-security
    -Wformat-nonliteral
                                               -Wformat-y2k
                                                                 -Wframe-larger-than=len
    -Wno-free-nonheap-object
                                 -Wjump-misses-init
                                                       -Wignored-qualifiers
                                                                              -Wimplicit
    -Wimplicit-function-declaration
                                         -Wimplicit-int
                                                              -Winit-self
                                                                                -Winline
    -Wmaybe-uninitialized -Wno-int-to-pointer-cast -Wno-invalid-offsetof -Winvalid-pch
    -Wlarger-than=len
                       -Wunsafe-loop-optimizations -Wlogical-op -Wlong-long -Wmain
    -Wmaybe-uninitialized
                                   -Wmissing-braces
                                                               -Wmissing-field-initializers
    -Wmissing-include-dirs -Wno-mudflap -Wno-multichar -Wnonnull
                                                                          -Wno-overflow
    -Woverlength-strings -Wpacked -Wpacked-bitfield-compat -Wpadded -Wparentheses
                                                                         -Wpointer-arith
    -Wpedantic-ms-format
                                     -Wno-pedantic-ms-format
    -Wno-pointer-to-int-cast -Wredundant-decls -Wno-return-local-addr -Wreturn-type
    -Wsequence-point
                             -Wshadow
                                               -Wsign-compare
                                                                       -Wsign-conversion
    -Wsizeof-pointer-memaccess
                                -Wstack-protector
                                                    -Wstack-usage=len
                                                                        -Wstrict-aliasing
                                      -Wstrict-overflow
                                                                      -Wstrict-overflow=n
    -Wstrict-aliasing=n
    -Wsuggest-attribute=[pure|const|noreturn|format]
                                                   -Wmissing-format-attribute -Wswitch
    -Wswitch-default
                      -Wswitch-enum -Wsync-nand -Wsystem-headers
                                                                           -Wtrampolines
    -Wtrigraphs
                    -Wtype-limits
                                     -Wundef
                                                  -Wuninitialized
                                                                    -Wunknown-pragmas
    -Wno-pragmas
                       -Wunsuffixed-float-constants
                                                       -Wunused
                                                                       -Wunused-function
    -Wunused-label
                     -Wunused-local-typedefs
                                               -Wunused-parameter -Wno-unused-result
    -Wunused-value
                               -Wunused-variable
                                                             -Wunused-but-set-parameter
    -Wunused-but-set-variable
                                                                       -Wvariadic-macros
                                           -Wuseless-cast
                                      -Wvla
                                                -Wvolatile-register-var
    -Wvector-operation-performance
                                                                          -Wwrite-strings
    -Wzero-as-null-pointer-constant
C and Objective-C-only Warning Options
                                 - Wmissing-declarations\\
    -Wbad-function-cast
                                                               -Wmissing-parameter-type
    -Wmissing-prototypes -Wnested-externs -Wold-style-declaration -Wold-style-definition
    -Wstrict-prototypes
                                     -Wtraditional
                                                                 -Wtraditional-conversion
    -Wdeclaration-after-statement -Wpointer-sign
```

Debugging Options

-dletters -dumpspecs -dumpmachine -dumpversion **-fsanitize**=style -fdbg-cnt-list -fdbg-cnt=counter-value-list -fdisable-ipa-pass_name -fdisable-rtl-pass_name -fdisable-rtl-pass-name=range-list -fdisable-tree-pass_name -fdisable-tree-pass-name=range--fdump-noaddr -fdump-unnumbered -fdump-unnumbered-links -fdump-translation-unit[-n]-fdump-class-hierarchy[-n]-fdump-ipa-all -fdump-ipa-cgraph -fdump-ipa-inline -fdump-passes -fdump-statistics -fdump-tree-all -fdump-tree-original[-n] -fdump-tree-optimized[-n] -fdump-tree-cfg -fdump-tree-alias-fdump-tree-ssa[-n]-fdump-tree-pre[-n]-fdump-tree-ccp[-n]-fdump-tree-ch -fdump-tree-dce[-n]-fdump-tree-gimple[-raw] -fdump-tree-mudflap[-n]-fdump-tree-dom[-n]-fdump-tree-dse[-n]-fdump-tree-phiprop[-n]-fdump-tree-phiopt[-*n*] -fdump-tree-forwprop[-n]-fdump-tree-copyrename[-n]-fdump-tree-nrv -fdump-tree-vect -fdump-tree-sink -fdump-tree-sra[-n]-fdump-tree-forwprop[-n]-fdump-tree-fre[-n]-fdump-tree-vrp[-n]-ftree-vectorizer-verbose=n -fdump-tree-storeccp[-n]-fdump-final-insns=file -fcompare-debug[=opts] -fcompare-debug-second -feliminate-dwarf2-dups -fno-eliminate-unused-debug-types -feliminate-unused-debug-symbols -femit-class-debug-always **-fenable**-*kind*-*pass* -fenable-kind-pass=range-list -fpre-ipa-mem-report -fdebug-types-section -fmem-report-wpa -fmem-report -fpost-ipa-mem-report -fprofile-arcs -fopt-info **-fopt-info**-options[=file] -fsched-verbose=n -fsel-sched-verbose -frandom-seed=string -fsel-sched-dump-cfg -fsel-sched-pipelining-verbose -fstack-usage -ftest-coverage -ftime-report -fvar-tracking -fvar-tracking-assignments -fvar-tracking-assignments-toggle -g -glevel -gtoggle -gcoff -gdwarf-version -ggdb -grecord-gcc-switches -gno-record-gcc-switches -gstabs -gstabs+ -gstrict-dwarf -gno-strict-dwarf -gvms -gxcoff -gxcoff+ -fno-merge-debug-strings -fno-dwarf2-cfi-asm -fdebug-prefix-map=old=new -femit-struct-debug-baseonly -femit-struct-debug-reduced -femit-struct-debug-detailed[=spec-list] -print-file-name=library -print-libgcc-file-name -print-multi-directory -print-multi-lib -print-multi-os-directory -print-prog-name=program -print-search-dirs -print-sysroot -print-sysroot-headers-suffix -save-temps -save-temps=cwd -save-temps=obj -time[=file]

Optimization Options

-faggressive-loop-optimizations -falign-functions[=n] -falign-jumps[=n] -falign-labels[=n] -falign-loops[=n]-fassociative-math -fauto-inc-dec -fbranch-probabilities -fbranch-target-load-optimize -fbranch-target-load-optimize2 -fbtr-bb-exclusive -fcaller-saves -fcheck-data-deps -fcombine-stack-adjustments -fconserve-stack -fcprop-registers -fcrossjumping -fcse-follow-jumps -fcompare-elim -fcse-skip-blocks -fcx-fortran-rules -fcx-limited-range -fdata-sections -fdce -fdelayed-branch -fdelete-null-pointer-checks -fdevirtualize -fdse -fearly-inlining -fipa-sra -fexpensive-optimizations -ffat-lto-objects -ffast-math -ffinite-math-only -ffloat-store -fexcess-precision=style -fforward-propagate -ffp-contract=style -ffunction-sections -fgcse -fgcse-after-reload -fgcse-las -fgcse-lm -fgraphite-identity -fgcse-sm -fhoist-adjacent-loads -fif-conversion -fif-conversion2 -findirect-inlining -finline-functions -finline-functions-called-once -finline-limit=n -finline-small-functions -fipa-cp -fipa-cp-clone -fipa-pta -fipa-profile -fipa-pure-const -fipa-reference -fira-algorithm=algorithm -fira-region=region -fira-hoist-pressure -fira-loop-pressure -fno-ira-share-spill-slots -fno-ira-share-save-slots -fira-verbose=n -fivopts -floop-block -fkeep-inline-functions -fkeep-static-consts -floop-interchange -floop-strip-mine -floop-nest-optimize -floop-parallelize-all -flto -flto-compression-level -flto-partition=alg -flto-report -fmerge-all-constants -fmerge-constants -fmodulo-sched -fmodulo-sched-allow-regmoves -fmove-loop-invariants fmudflap -fmudflapir -fmudflapth -fno-branch-count-reg -fno-default-inline -fno-function-cse -fno-defer-pop -fno-guess-branch-probability -fno-inline -fno-math-errno -fno-peephole -fno-peephole2 -fno-sched-interblock -fno-sched-spec -fno-signed-zeros -fno-toplevel-reorder

```
-fno-trapping-math
                              -fno-zero-initialized-in-bss
                                                                    -fomit-frame-pointer
-foptimize-register-move
                             -foptimize-sibling-calls
                                                        -fpartial-inlining
                                                                              -fpeel-loops
                          -fprefetch-loop-arrays
                                                    -fprofile-report
-fpredictive-commoning
                                                                       -fprofile-correction
-fprofile-dir=path -fprofile-generate -fprofile-generate=path -fprofile-use -fprofile-use=path
-fprofile-values -freciprocal-math -free -fregmove -frename-registers -freorder-blocks
-freorder-blocks-and-partition
                                       -freorder-functions
                                                                   -frerun-cse-after-loop
-freschedule-modulo-scheduled-loops
                                          -frounding-math
                                                                 -fsched2-use-superblocks
-fsched-pressure
                              -fsched-spec-load
                                                             -fsched-spec-load-dangerous
-fsched-stalled-insns-dep[=n]
                                   -fsched-stalled-insns[=n]
                                                                  -fsched-group-heuristic
                                                                   -fsched-rank-heuristic
                                   -fsched-spec-insn-heuristic
-fsched-critical-path-heuristic
-fsched-last-insn-heuristic -fsched-dep-count-heuristic -fschedule-insns -fschedule-insns2
-fsection-anchors
                   -fselective-scheduling
                                           -fselective-scheduling2
                                                                    -fsel-sched-pipelining
-fsel-sched-pipelining-outer-loops
                                               -fshrink-wrap
                                                                          -fsignaling-nans
-fsingle-precision-constant -fsplit-ivs-in-unroller
                                                    -fsplit-wide-types
                                                                        -fstack-protector
-fstack-protector-all
                        -fstrict-aliasing
                                           -fstrict-overflow
                                                               -fthread-jumps
                                                                                  -ftracer
-ftree-bit-ccp -ftree-builtin-call-dce -ftree-ccp -ftree-ch -ftree-coalesce-inline-vars
-ftree-coalesce-vars -ftree-copy-prop -ftree-copyrename -ftree-dce -ftree-dominator-opts
-ftree-dse -ftree-forwprop -ftree-fre -ftree-loop-if-convert -ftree-loop-if-convert-stores
                -ftree-phiprop -ftree-loop-distribution -ftree-loop-distribute-patterns
-ftree-loop-im
-ftree-loop-ivcanon -ftree-loop-linear -ftree-loop-optimize
                                                                -ftree-parallelize-loops=n
-ftree-pre -ftree-partial-pre -ftree-pta -ftree-reassoc -ftree-sink -ftree-slsr -ftree-sra
-ftree-switch-conversion
                             -ftree-tail-merge
                                                   -ftree-ter
                                                                  -ftree-vect-loop-version
-ftree-vectorize
                   -ftree-vrp
                                 -funit-at-a-time
                                                      -funroll-all-loops
                                                                            -funroll-loops
-funsafe-loop-optimizations
                                    -funsafe-math-optimizations
                                                                         -funswitch-loops
-fvariable-expansion-in-unroller -fvect-cost-model -fvpt -fweb -fwhole-program -fwpa
-fuse-ld=linker -fuse-linker-plugin --param name=value -O -O0 -O1 -O2 -O3 -Os
-Ofast -Og
```

Preprocessor Options

-Aquestion=answer -A-question[=answer] -C -dD -dI -dM -dN -Dmacro[=defn] -E -H -idirafter dir -include file -imacros file -iprefix file -iwithprefix dir -iwithprefixbefore dir -isystem dir -imultilib dir -isysroot dir -M -MM -MF -MG -MP -MQ -MT -nostdinc -P -fdebug-cpp -ftrack-macro-expansion -fworking-directory -remap -trigraphs -undef -Umacro -Wp,option -Xpreprocessor option -no-integrated-cpp

Assembler Option

-Wa, option -Xassembler option

Linker Options

object-file-name -llibrary -nostartfiles -nodefaultlibs -nostdlib -pie -rdynamic -s -static -static-libgcc -static-libstdc++ -static-libasan -static-libtsan -shared -shared-libgcc -symbolic -T script -Wl,option -Xlinker option -u symbol

Directory Options

-Bprefix -Idir -iplugindir=dir -iquotedir -Ldir -specs=file -I- --sysroot=dir --no-sysroot-suffix

Machine Dependent Options

AArch64 Options -mbig-endian -mlittle-endian -mgeneral-regs-only -mcmodel=tiny -mcmodel=small -mcmodel=large -mstrict-align -momit-leaf-frame-pointer -mtls-dialect=desc -mtls-dialect=traditional -mfix-cortex-a53-835769 -mno-fix-cortex-a53-835769 -march=name -mtune=name

Adapteva Epiphany Options -mhalf-reg-file -mprefer-short-insn-regs -mbranch-cost=num -mcmove -mnops=num -msoft-cmpsf -msplit-lohi -mpost-inc -mpost-modify -mstack-offset=num -mround-nearest -mlong-calls -mshort-calls -msmall16 -mfp-mode=mode -mvect-double -max-vect-align=num -msplit-vecmove-early -m1reg-reg

-mno-apcs-frame -mabi=name -mapcs-stack-check ARM**Options** -mapcs-frame -mno-apcs-stack-check -mapcs-float -mno-apcs-float -mapcs-reentrant -mno-apcs-reentrant -msched-prolog -mno-sched-prolog -mlittle-endian -mbig-endian -mwords-little-endian -mfloat-abi=name -mfp16-format=name -mthumb-interwork -mno-thumb-interwork -mcpu=name -march=name -mfpu=name -mstructure-size-boundary=n -mlong-calls -mabort-on-noreturn -mno-long-calls -msingle-pic-base -mno-single-pic-base -mpic-register=*reg* -mnop-fun-dllimport -mpoke-function-name -mthumb -mtpcs-frame -mtpcs-leaf-frame -marm -mcaller-super-interworking -mcallee-super-interworking -mtp=name -mtls-dialect=dialect -mword-relocations -mfix-cortex-m3-ldrd -munaligned-access

AVR Options -mmcu=mcu -maccumulate-args -mbranch-cost=cost -mcall-prologues -mint8 -mno-interrupts -mrelax -mstrict-X -mtiny-stack -Waddr-space-convert

Blackfin **Options** -mcpu=cpu[-sirevision]-msim -momit-leaf-frame-pointer -mno-omit-leaf-frame-pointer -mspecld-anomaly -mno-specld-anomaly -mcsync-anomaly -mno-csync-anomaly -mlow-64k -mno-low64k -mstack-check-l1 -mno-id-shared-library -mid-shared-library -mshared-library-id=n -mleaf-id-shared-library -mno-leaf-id-shared-library -msep-data -mno-sep-data -mlong-calls -mno-long-calls -mfast-fp -minline-plt -mmulticore -mcorea -mcoreb -msdram -micplb

C6X Options -mbig-endian -mlittle-endian -march=cpu -msim -msdata=sdata-type

CRIS -mcpu=cpu **Options** -march=cpu -mtune=cpu -mmax-stack-frame=n -melinux-stacksize=n -metrax4 -metrax100 -mpdebug -mcc-init -mno-side-effects -m8-bit-mstack-align -mdata-align -m32-bit -mconst-align -m16-bit -mno-prologue-epilogue -mno-gotplt -melf -maout -melinux -mlinux -sim -sim2 -mmul-bug-workaround -mno-mul-bug-workaround

CR16 Options -mmac -mcr16cplus -mcr16c -msim -mint32 -mbit-ops -mdata-model=model

-all load -allowable_client -arch -arch_errors_fatal Darwin **Options** -arch_only -bundle -bundle loader -client name -compatibility version -bind at load -current version -dead strip -dependency-file -dylib file -dylinker install name -dynamic -exported_symbols_list -filelist -flat_namespace -force_cpusubtype_ALL -force flat namespace -headerpad_max_install_names -iframework -image_base -init -install name -keep_private_externs -multi module -multiply defined -multiply_defined_unused -noall_load -no_dead_strip_inits_and_terms -nofixprebinding -nomultidefs -noprebind -noseglinkedit -pagezero size -prebind -prebind all twolevel modules -private bundle -read only relocs -sectobjectsymbols -whyload -seg1addr -sectcreate -sectobjectsymbols -sectorder -segaddr -segs_read_only_addr -segs_read_write_addr -seg_addr_table -seg_addr_table_filename -seglinkedit -segprot -segs_read_only_addr -segs_read_write_addr -single_module -static -sub library -sub umbrella -twolevel namespace -umbrella -undefined -unexported symbols list -weak reference mismatches -whatsloaded -F -gused -gfull -mmacosx-version-min=version -mkernel -mone-byte-bool

DECAlpha **Options** -mno-fp-regs -msoft-float -mieee -mieee-with-inexact -mieee-conformant -mfp-rounding-mode=mode -mfp-trap-mode=mode -mtrap-precision=mode -mbuild-constants -mcpu=cpu-type -mtune=cpu-type -mbwx -mcix -mfloat-vax -mfloat-ieee -mexplicit-relocs -msmall-data -mlarge-data -msmall-text -mlarge-text -mmemory-latency=time

FR30 Options -msmall-model -mno-lsim

FRV Options -mgpr-32 -mgpr-64 -mfpr-32 -mfpr-64 -mhard-float -msoft-float -malloc-cc -mfixed-cc -mdword -mno-dword -mdouble -mno-double -mmedia -mno-media -mmuladd -mno-muladd -mfdpic -minline-plt -mgprel-ro

-multilib-library-pic -mlinked-fp -mlong-calls -malign-labels -mlibrary-pic -macc-4 -macc-8 -mpack -mno-pack -mno-eflags -mcond-move -mno-cond-move -moptimize-membar -mno-optimize-membar -mscc -mno-scc -mcond-exec -mno-cond-exec -mvliw-branch -mno-vliw-branch -mmulti-cond-exec -mno-multi-cond-exec -mnested-cond-exec -mno-nested-cond-exec -mtomcat-stats -mTLS -mtls -mcpu=cpu

GNU/Linux Options -mglibc -muclibc -mbionic -mandroid -tno-android-cc -tno-android-ld H8/300 Options -mrelax -mh -ms -mn -mexr -mno-exr -mint32 -malign-300

HPPA Options -march=architecture-type -mbig-switch -mdisable-fpregs -mdisable-indexing -mfast-indirect-calls -mgas -mgnu-ld -mhp-ld -mfixed-range=register-range -mjump-in-delay -mlinker-opt -mlong-calls -mlong-load-store -mno-big-switch -mno-disable-fpregs -mno-disable-indexing -mno-fast-indirect-calls -mno-gas -mno-portable-runtime -mno-jump-in-delay -mno-long-load-store -mno-soft-float -mno-space-regs -msoft-float -mpa-risc-1-0 -mpa-risc-1-1 -mpa-risc-2-0 -mportable-runtime -mschedule=cpu-type -mspace-regs -msio -mwsio -munix=unix-std -nolibdld -static -threads

i386 and x86-64 Options -mtune=cpu-type -march=cpu-type -mfpmath=unit -masm=dialect -mno-fancy-math-387 -mno-fp-ret-in-387 -msoft-float -mno-wide-multiply -mrtd -malign-double -mpreferred-stack-boundary=num -mincoming-stack-boundary=num -mcld -mcx16 -msahf -mmovbe -mcrc32 -mrecip -mrecip=opt -mvzeroupper -mprefer-avx128 -mmmx -msse -msse2 -msse3 -msse3 -msse4.1 -msse4.2 -msse4 -mavx -mavx2 -maes -mpclmul -mfsgsbase -mrdrnd -mf16c -mfma -msse4a -m3dnow -mpopcnt -mabm -mbmi -mtbm -mfma4 -mxop -mlzcnt -mbmi2 -mrtm -mlwp -mthreads -mno-align-stringops -minline-all-stringops -minline-stringops-dynamically -mstringop-strategy=alg -mpush-args -maccumulate-outgoing-args -m128bit-long-double -m96bit-long-double -mlong-double-64 -mlong-double-80 -mregparm=num -msseregparm -mveclibabi=type -mvect8-ret-in-mem -mpc32 -mpc64 -mpc80 -mstackrealign -momit-leaf-frame-pointer -mno-red-zone -mno-tls-direct-seg-refs -mcmodel=code-model -mabi=name -maddress-mode=mode -m32 -m64 -mx32 -mlarge-data-threshold=num -msse2avx -mfentry -m8bit-idiv -mavx256-split-unaligned-load -mavx256-split-unaligned-store

i386 and x86-64 Windows Options -mconsole -mcygwin -mno-cygwin -mdll -mnop-fun-dllimport -mthread -municode -mwin32 -mwindows -fno-set-stack-executable

-mbig-endian -mlittle-endian -mgnu-as -mgnu-ld -mvolatile-asm-stop -mregister-names -msdata -mno-sdata -mconstant-gp -mauto-pic -mfused-madd -minline-float-divide-min-latency -minline-float-divide-max-throughput -mno-inline-float-divide -minline-int-divide-min-latency -minline-int-divide-max-throughput -mno-inline-int-divide -minline-sqrt-min-latency -minline-sqrt-max-throughput -mno-inline-sqrt -mdwarf2-asm -mearly-stop-bits -mfixed-range=register-range -mtls-size=tls-size -mtune=cpu-type -milp32 -mlp64 -msched-br-data-spec -msched-ar-data-spec -msched-control-spec -msched-br-in-data-spec -msched-ar-in-data-spec -msched-in-control-spec -msched-prefer-non-data-spec-insns -msched-spec-ldc -msched-spec-control-ldc -msched-prefer-non-control-spec-insns -msched-stop-bits-after-every-cycle -msched-count-spec-in-critical-path -msel-sched-dont-check-control-spec -msched-fp-mem-deps-zero-cost -msched-max-memory-insns-hard-limit -msched-max-memory-insns=max-insns

LM32 Options -mbarrel-shift-enabled -mdivide-enabled -mmultiply-enabled -msign-extend-enabled -muser-enabled

M32R/D Options **-m32r2 -m32rx -m32r -mdebug -malign-loops -mno-align-loops -missue-rate**=*number* **-mbranch-cost**=*number* **-mmodel**=*code-size-model-type* **-msdata**=*sdata*-

type -mno-flush-func -mflush-func=name -mno-flush-trap -mflush-trap=number -G num

M32C Options -mcpu=cpu -msim -memregs=number

MCore **Options** -mhardlit -mno-hardlit -mdiv -mno-div -mrelax-immediates -mwide-bitfields -mno-wide-bitfields -m4byte-functions -mno-relax-immediates -mno-4byte-functions -mcallgraph-data -mno-callgraph-data -mslow-bytes -m340-mno-slow-bytes -mno-lsim -mlittle-endian -mbig-endian -m210-mstack-increment

MeP Options -mabsdiff -mall-opts -maverage -mbased=n -mbitops -mc=n -mclip -mconfig=name -mcop -mcop32 -mcop64 -mivc2 -mdc -mdiv -meb -mel -mio-volatile -ml -mleadz -mm -mminmax -mmult -mno-opts -mrepeat -ms -msatur -msdram -msim -msimnovec -mtf -mtiny=n

MicroBlaze Options -msoft-float -mhard-float -msmall-divides -mcpu=cpu -mmemcpy -mxl-soft-mul -mxl-soft-div -mxl-barrel-shift -mxl-pattern-compare -mxl-stack-check -mxl-gp-opt -mno-clearbss -mxl-multiply-high -mxl-float-convert -mxl-float-sqrt -mbig-endian -mlittle-endian -mxl-reorder -mxl-mode-app-model

MIPS Options -EL -EB -march-arch -mtune=arch -mips1 -mips2 -mips3 -mips4 -mips32 -mips32r2 -mips64 -mips64r2 -mips16 -mno-mips16 -mflip-mips16 -minterlink-mips16 -mno-interlink-mips16 -mabi=abi -mabicalls -mno-abicalls -mshared -mno-shared -mplt -mno-plt -mxgot -mno-xgot -mgp32 -mgp64 -mfp32 -mfp64 -mhard-float -msoft-float -mno-float -msingle-float -mdouble-float -mdsp -mno-dsp -mdspr2 -mno-dspr2 -mmcu -**mfpu**=fpu-type -msmartmips -mno-smartmips -mmno-mcu -mpaired-single -mno-paired-single -mdmx -mno-mdmx -mips3d -mno-mips3d -mmt -mno-mt -mllsc -mno-llsc -mlong64 -mlong32 -msvm32 -mno-sym32 -Gnum -mlocal-sdata -mno-local-sdata -mno-extern-sdata -mextern-sdata -mgpopt -mno-gopt -membedded-data -mno-embedded-data -muninit-const-in-rodata -mno-uninit-const-in-rodata -mcode-readable=setting -msplit-addresses -mexplicit-relocs -mno-explicit-relocs -mno-split-addresses -mcheck-zero-division -mno-check-zero-division -mdivide-traps -mdivide-breaks -mmemcpy -mno-memcpy -mlong-calls -mno-long-calls -mmad -mno-mad -mfused-madd -mno-fused-madd -mno-fix-24k -mfix-r4000-mno-fix-r4000 -mfix-r4400 -nocpp -mfix-24k -mno-fix-r4400 -mfix-r10000 -mno-fix-r10000 -mfix-vr4120 -mno-fix-vr4120 -mfix-sb1 -mno-fix-vr4130 -mfix-vr4130 -mno-fix-sb1 -mflush-func=func -mno-flush-func -mbranch-cost=num -mbranch-likely -mno-branch-likely -mno-fp-exceptions -mvr4130-align -mfp-exceptions -mno-vr4130-align -msynci -mno-synci -mrelax-pic-calls -mno-relax-pic-calls -mmcount-ra-address

MMIX **Options** -mlibfuncs -mno-libfuncs -mepsilon -mno-epsilon -mabi=gnu -mabi=mmixware -mknuthdiv -mtoplevel-symbols -melf -mzero-extend -mno-branch-predict -mbranch-predict -mbase-addresses -mno-base-addresses -msingle-exit -mno-single-exit

MN10300 Options -mmult-bug -mno-mult-bug -mno-am33 -mam33-2 -mam34 -mtune=cpu-type -mreturn-pointer-on-d0 -mno-crt0 -mrelax -mliw -msetlb

Moxie Options -meb -mel -mno-crt0

PDP-11 Options -mfpu -msoft-float -mac0 -mno-ac0 -m40 -m45 -m10 -mbcopy

-mbcopy-builtin -mint32 -mno-int16 -mint16 -mno-int32 -mfloat32 -mno-float64
 -mfloat64 -mno-float32 -mabshi -mno-abshi -mbranch-expensive -mbranch-cheap
 -munix-asm -mdec-asm

PowerPC Options See RS/6000 and PowerPC Options.

RL78 Options -msim -mmul=none -mmul=g13 -mmul=rl78

RS/6000 and PowerPC Options -mcpu=cpu-type -mtune=cpu-type -mcmodel=code-model -mno-altivec -mpowerpc-gpopt -mpowerpc64 -maltivec -mno-powerpc-gpopt -mpowerpc-gfxopt -mno-powerpc-gfxopt -mmfcrf -mno-mfcrf -mpopcntb -mno-popcntb -mpopentd -mno-popentd -mfprnd -mno-fprnd -mcmpb -mno-cmpb -mmfpgpr -mno-mfpgpr -mhard-dfp -mno-hard-dfp -mfull-toc -mminimal-toc -mno-fp-in-toc -mno-sum-in-toc -m64 -m32 -mxl-compat -mno-xl-compat -mpe -malign-power -malign-natural -msoft-float -mhard-float -mmultiple -mno-multiple -msingle-float -mdouble-float -msimple-fpu -mstring -mno-string -mupdate -mno-update -mavoid-indexed-addresses -mno-avoid-indexed-addresses -mfused-madd -mno-fused-madd -mno-bit-align -mstrict-align -mno-strict-align -mbit-align -mrelocatable -mno-relocatable -mrelocatable-lib -mno-relocatable-lib -mtoc -mno-toc -mlittle -mlittle-endian -mbig -mbig-endian -mdynamic-no-pic -maltivec -mswdiv -msingle-pic-base -mprioritize-restricted-insns=priority -msched-costly-dep=dependence_type -minsert-sched-nops=scheme -mcall-sysv -mcall-netbsd -maix-struct-return -msvr4-struct-return -mabi=abi-type -msecure-plt -mbss-plt -mblock-move-inline-limit=num -misel -mno-isel -misel=yes -misel=no -mspe -mno-spe -mspe=yes -mspe=no -mpaired -mgen-cell-microcode -mwarn-cell-microcode -mvrsave -mno-vrsave -mmulhw -mno-mulhw -mdlmzb -mno-dlmzb -mfloat-gprs=yes -mfloat-gprs=no -mfloat-gprs=single -mfloat-gprs=double -mprototype -mno-prototype -msim -mmvme -mads -myellowknife -memb -msdata -msdata=opt -mvxworks -G num -pthread -mrecip -mrecip-precision -mno-recip-precision -mno-recip-precision -mno-friz -mpointers-to-nested-functions -mveclibabi=type -mno-pointers-to-nested-functions -msave-toc-indirect -mno-save-toc-indirect -mpower8-fusion -mno-mpower8-fusion -mpower8-vector -mno-power8-vector -mcrypto -mno-crypto -mdirect-move -mno-direct-move -mquad-memory -mno-quad-memory -mquad-memory-atomic -mno-quad-memory-atomic -mcompat-align-parm -mno-compat-align-parm

S/390 and zSeries Options -mtune=cpu-type -march=cpu-type -mhard-float -msoft-float -mhard-dfp -mno-hard-dfp -mlong-double-64 -mlong-double-128 -mbackchain -mno-backchain -mpacked-stack -mno-packed-stack -msmall-exec -mno-small-exec -mmvcle -mno-mvcle -m64 -m31 -mdebug -mno-debug -mesa -mzarch -mtpf-trace -mno-tpf-trace -mfused-madd -mno-fused-madd -mwarn-framesize -mwarn-dynamicstack -mstack-size -mstack-guard -mhotpatch=halfwords,halfwords

Score Options -meb -mel -mnhwloop -muls -mmac -mscore5 -mscore5u -mscore7 -mscore7d

SH Options -m1 -m2 -m2e -m2a-nofpu -m2a-single-only -m2a-single -m2a -m3 -m3e -m4-nofpu -m4-single-only -m4-single -m4 -m4a-nofpu -m4a-single-only -m4a-single -m4a -m4al -m5-64media -m5-64media-nofpu -m5-32media -m5-32media-nofpu -m5-compact -m5-compact-nofpu -mb -ml -mdalign -mrelax -mbigtable -mfmovd -mhitachi -mrenesas -mno-renesas -mnomacsave -mieee -mno-ieee -mbitops -misize

-minline-ic_invalidate -mpadstruct -mspace -mprefergot -musermode -multcost=number
 -mdiv=strategy -mdivsi3_libfunc=name -mfixed-range=register-range -mindexed-addressing
 -mgettrcost=number -mpt-fixed -maccumulate-outgoing-args -minvalid-symbols
 -matomic-model=atomic-model -mbranch-cost=num -mzdcbranch -mno-zdcbranch
 -mcbranchdi -mcmpeqdi -mfused-madd -mno-fused-madd -mfsca -mno-fsca -mfsrra
 -mno-fsrra -mpretend-cmove -mtas

Solaris 2 Options -mimpure-text -mno-impure-text -pthreads -pthread

SPARC -mcmodel=code-model **Options** -mcpu=cpu-type -mtune=cpu-type -mmemory-model=mem-model -m32 -m64 -mapp-regs -mno-app-regs -mfaster-structs -mflat -mno-flat -mfpu -mno-fpu -mhard-float -msoft-float -mno-faster-structs -mhard-quad-float -msoft-quad-float -mstack-bias -mno-stack-bias -munaligned-doubles -mno-unaligned-doubles -muser-mode -mno-user-mode -mv8plus -mno-vis -mvis2 -mno-vis2 -mno-v8plus -mvis -mvis3 -mno-vis3 -mcbcond -mno-cbcond -mfmaf -mno-fmaf -mpopc -mno-popc -mfix-at697f -mfix-ut699

SPU Options -mwarn-reloc -merror-reloc -msafe-dma -munsafe-dma -mbranch-hints -msmall-mem -mlarge-mem -mstdmain -mfixed-range=register-range -mea32 -mea64 -maddress-space-conversion -mno-address-space-conversion -mcache-size=cache-size -matomic-updates -mno-atomic-updates

System V Options -Qy -Qn -YP,paths -Ym,dir

TILE-Gx Options -mcpu=cpu -m32 -m64 -mcmodel=code-model

TILEPro Options -mcpu=cpu -m32

VAX Options -mg -mgnu -munix

VMS Options -mvms-return-codes -mdebug-main=prefix -mmalloc64 -mpointer-size=size

VxWorks Options -mrtp -non-static -Bstatic -Bdynamic -Xbind-lazy -Xbind-now

x86-64 Options See i386 and x86-64 Options.

Xstormy16 Options -msim

Xtensa Options -mconst16 -mno-const16 -mfused-madd -mno-fused-madd -mforce-no-pic -mserialize-volatile -mno-serialize-volatile -mtext-section-literals -mno-text-section-literals -mno-target-align -mno-target-align -mno-longcalls

-ffixed-reg

-fexceptions

-fnon-call-exceptions

zSeries Options See S/390 and zSeries Options.

-fcall-used-reg

Code Generation Options -fcall-saved-reg

-fdelete-dead-exceptions -funwind-tables -fasynchronous-unwind-tables -fno-gnu-unique -finhibit-size-directive -finstrument-functions -finstrument-functions-exclude-function-list=sym,sym,... -fno-ident -finstrument-functions-exclude-file-list=file,file,... -fno-common -fpcc-struct-return -fpic -fPIC -fpie -fPIE -fno-jump-tables -frecord-gcc-switches -freg-struct-return -fshort-enums -fshort-double -fshort-wchar -fverbose-asm -fpack-struct[=*n*] -fstack-check -fstack-limit-register=reg -fstack-limit-symbol=sym -fno-stack-limit -fsplit-stack -fleading-underscore -ftls-model=model -fstack-reuse=reuse_level -ftrapy -fwrapv -fbounds-check -fvisibility -fstrict-volatile-bitfields -fsync-libcalls

Options Controlling the Kind of Output

Compilation can involve up to four stages: preprocessing, compilation proper, assembly and linking, always in that order. GCC is capable of preprocessing and compiling several files either into several assembler input files, or into one assembler input file; then each assembler input file produces an object file, and linking combines all the object files (those newly compiled, and those specified as input) into an executable file.

For any given input file, the file name suffix determines what kind of compilation is done:

```
file.c
```

C source code that must be preprocessed.

file.i

C source code that should not be preprocessed.

file.ii

C++ source code that should not be preprocessed.

file.m

Objective-C source code. Note that you must link with the *libobjc* library to make an Objective-C program work.

file.mi

Objective-C source code that should not be preprocessed.

file.mm

file.M

Objective–C++ source code. Note that you must link with the *libobjc* library to make an Objective–C++ program work. Note that **.M** refers to a literal capital M.

file.mii

Objective–C++ source code that should not be preprocessed.

file.h

C, C++, Objective-C or Objective-C++ header file to be turned into a precompiled header (default), or C, C++ header file to be turned into an Ada spec (via the **-fdump-ada-spec** switch).

```
file.cc
file.cp
file.cxx
file.cpp
file.CPP
file.c++
file.C
```

C++ source code that must be preprocessed. Note that in .cxx, the last two letters must both be literally x. Likewise, .C refers to a literal capital C.

file.mm

file.M

Objective–C++ source code that must be preprocessed.

file.mii

Objective–C++ source code that should not be preprocessed.

file.hh file.H file.hp file.hxx file.hpp

file.HPP

```
file.h++
file.tcc
     C++ header file to be turned into a precompiled header or Ada spec.
file.f
file.for
file.ftn
     Fixed form Fortran source code that should not be preprocessed.
file.F
file.FOR
file.fpp
file.FPP
file.FTN
     Fixed form Fortran source code that must be preprocessed (with the traditional preprocessor).
file.f90
file.f95
file.f03
file.f08
     Free form Fortran source code that should not be preprocessed.
file.F90
file.F95
file.F03
file.F08
     Free form Fortran source code that must be preprocessed (with the traditional preprocessor).
file.go
     Go source code.
file.ads
     Ada source code file that contains a library unit declaration (a declaration of a package, subprogram,
     or generic, or a generic instantiation), or a library unit renaming declaration (a package, generic, or
     subprogram renaming declaration). Such files are also called specs.
file.adb
     Ada source code file containing a library unit body (a subprogram or package body). Such files are
     also called bodies.
file.d
     D source code file.
file.di
     D interface code file.
file.dd
     D documentation code file.
file.s
     Assembler code.
file.S
file.sx
     Assembler code that must be preprocessed.
other
     An object file to be fed straight into linking. Any file name with no recognized suffix is treated this
```

You can specify the input language explicitly with the -x option:

-x language

Specify explicitly the *language* for the following input files (rather than letting the compiler choose a default based on the file name suffix). This option applies to all following input files until the next $-\mathbf{x}$ option. Possible values for *language* are:

```
c c-header cpp-output
c++ c++-header c++-cpp-output
objective-c objective-c-header objective-c-cpp-output
objective-c++ objective-c++-header objective-c++-cpp-output
assembler assembler-with-cpp
ada
d
f77 f77-cpp-input f95 f95-cpp-input
go
java
```

-x none

Turn off any specification of a language, so that subsequent files are handled according to their file name suffixes (as they are if $-\mathbf{x}$ has not been used at all).

-pass-exit-codes

Normally the **gcc** program exits with the code of 1 if any phase of the compiler returns a non-success return code. If you specify **–pass–exit–codes**, the **gcc** program instead returns with the numerically highest error produced by any phase returning an error indication. The C, C++, and Fortran front ends return 4 if an internal compiler error is encountered.

If you only want some of the stages of compilation, you can use $-\mathbf{x}$ (or filename suffixes) to tell **gcc** where to start, and one of the options $-\mathbf{c}$, $-\mathbf{S}$, or $-\mathbf{E}$ to say where **gcc** is to stop. Note that some combinations (for example, $-\mathbf{x}$ **cpp-output** $-\mathbf{E}$) instruct **gcc** to do nothing at all.

-c Compile or assemble the source files, but do not link. The linking stage simply is not done. The ultimate output is in the form of an object file for each source file.

By default, the object file name for a source file is made by replacing the suffix .c, .i, .s, etc., with .o.

Unrecognized input files, not requiring compilation or assembly, are ignored.

-S Stop after the stage of compilation proper; do not assemble. The output is in the form of an assembler code file for each non-assembler input file specified.

By default, the assembler file name for a source file is made by replacing the suffix .c, .i, etc., with .s.

Input files that don't require compilation are ignored.

-E Stop after the preprocessing stage; do not run the compiler proper. The output is in the form of preprocessed source code, which is sent to the standard output.

Input files that don't require preprocessing are ignored.

-o file

Place output in file *file*. This applies to whatever sort of output is being produced, whether it be an executable file, an object file, an assembler file or preprocessed C code.

If **–o** is not specified, the default is to put an executable file in *a.out*, the object file for *source.suffix* in *source.o*, its assembler file in *source.s*, a precompiled header file in *source.suffix.gch*, and all preprocessed C source on standard output.

-v Print (on standard error output) the commands executed to run the stages of compilation. Also print the version number of the compiler driver program and of the preprocessor and the compiler proper.

-###

Like $-\mathbf{v}$ except the commands are not executed and arguments are quoted unless they contain only alphanumeric characters or ./-_. This is useful for shell scripts to capture the driver-generated

command lines.

-pipe

Use pipes rather than temporary files for communication between the various stages of compilation. This fails to work on some systems where the assembler is unable to read from a pipe; but the GNU assembler has no trouble.

--help

Print (on the standard output) a description of the command-line options understood by **gcc**. If the **-v** option is also specified then **--help** is also passed on to the various processes invoked by **gcc**, so that they can display the command-line options they accept. If the **-Wextra** option has also been specified (prior to the **--help** option), then command-line options that have no documentation associated with them are also displayed.

--target-help

Print (on the standard output) a description of target-specific command-line options for each tool. For some targets extra target-specific information may also be printed.

--help={*class*|[^]*qualifier*}[,...]

Print (on the standard output) a description of the command-line options understood by the compiler that fit into all specified classes and qualifiers. These are the supported classes:

optimizers

Display all of the optimization options supported by the compiler.

warnings

Display all of the options controlling warning messages produced by the compiler.

target

Display target-specific options. Unlike the **—target-help** option however, target-specific options of the linker and assembler are not displayed. This is because those tools do not currently support the extended **—help=** syntax.

params

Display the values recognized by the --param option.

language

Display the options supported for *language*, where *language* is the name of one of the languages supported in this version of GCC.

common

Display the options that are common to all languages.

These are the supported qualifiers:

undocumented

Display only those options that are undocumented.

joined

Display options taking an argument that appears after an equal sign in the same continuous piece of text, such as: **—help=target**.

senarate

Display options taking an argument that appears as a separate word following the original option, such as: **–o output-file**.

Thus for example to display all the undocumented target-specific switches supported by the compiler, use:

```
--help=target, undocumented
```

The sense of a qualifier can be inverted by prefixing it with the ^ character, so for example to display all binary warning options (i.e., ones that are either on or off and that do not take an argument) that have a description, use:

```
--help=warnings, ^joined, ^undocumented
```

The argument to --help= should not consist solely of inverted qualifiers.

Combining several classes is possible, although this usually restricts the output so much that there is nothing to display. One case where it does work, however, is when one of the classes is *target*. For example, to display all the target-specific optimization options, use:

```
--help=target,optimizers
```

The —help= option can be repeated on the command line. Each successive use displays its requested class of options, skipping those that have already been displayed.

If the $-\mathbf{Q}$ option appears on the command line before the $--\mathbf{help}=$ option, then the descriptive text displayed by $--\mathbf{help}=$ is changed. Instead of describing the displayed options, an indication is given as to whether the option is enabled, disabled or set to a specific value (assuming that the compiler knows this at the point where the $--\mathbf{help}=$ option is used).

Here is a truncated example from the ARM port of **gcc**:

```
% gcc -Q -mabi=2 --help=target -c
The following options are target specific:
-mabi= 2
-mabort-on-noreturn [disabled]
-mapcs [disabled]
```

The output is sensitive to the effects of previous command-line options, so for example it is possible to find out which optimizations are enabled at **-O2** by using:

```
-Q -O2 --help=optimizers
```

Alternatively you can discover which binary optimizations are enabled by -O3 by using:

```
gcc -c -Q -O3 --help=optimizers > /tmp/O3-opts
gcc -c -Q -O2 --help=optimizers > /tmp/O2-opts
diff /tmp/O2-opts /tmp/O3-opts | grep enabled
```

-no-canonical-prefixes

Do not expand any symbolic links, resolve references to /../ or /./, or make the path absolute when generating a relative prefix.

--version

Display the version number and copyrights of the invoked GCC.

-wrapper

Invoke all subcommands under a wrapper program. The name of the wrapper program and its parameters are passed as a comma separated list.

```
gcc -c t.c -wrapper gdb, --args
```

This invokes all subprograms of **gcc** under **gdb** —**args**, thus the invocation of **cc1** is **gdb** —**args cc1** ...

-fplugin=name.so

Load the plugin code in file *name*.so, assumed to be a shared object to be dlopen'd by the compiler. The base name of the shared object file is used to identify the plugin for the purposes of argument parsing (See **-fplugin-arg**-*name-key=value* below). Each plugin should define the callback functions specified in the Plugins API.

-fplugin-arg-name-key=value

Define an argument called key with a value of value for the plugin called name.

-fdump-ada-spec[-slim]

For C and C++ source and include files, generate corresponding Ada specs.

-fada-spec-parent=unit

In conjunction with **-fdump-ada-spec**[-slim] above, generate Ada specs as child units of parent *unit*.

-fdump-go-spec=file

For input files in any language, generate corresponding Go declarations in *file*. This generates Go const, type, var, and func declarations which may be a useful way to start writing a Go interface to code written in some other language.

@file

Read command-line options from *file*. The options read are inserted in place of the original @*file* option. If *file* does not exist, or cannot be read, then the option will be treated literally, and not removed.

Options in *file* are separated by whitespace. A whitespace character may be included in an option by surrounding the entire option in either single or double quotes. Any character (including a backslash) may be included by prefixing the character to be included with a backslash. The *file* may itself contain additional @file options; any such options will be processed recursively.

Compiling C++ Programs

C++ source files conventionally use one of the suffixes **.**C, **.**cc, **.**ccpp, **.**CPP, **.**c++, **.**cp, or **.**cxx; C++ header files often use **.**hh, **.**hpp, **.**H, or (for shared template code) **.**tcc; and preprocessed C++ files use the suffix **.**ii. GCC recognizes files with these names and compiles them as C++ programs even if you call the compiler the same way as for compiling C programs (usually with the name **gcc**).

However, the use of **gcc** does not add the C++ library. \mathbf{g} ++ is a program that calls GCC and automatically specifies linking against the C++ library. It treats $\cdot \mathbf{c}$, $\cdot \mathbf{h}$ and $\cdot \mathbf{i}$ files as C++ source files instead of C source files unless $-\mathbf{x}$ is used. This program is also useful when precompiling a C header file with a $\cdot \mathbf{h}$ extension for use in C++ compilations. On many systems, \mathbf{g} ++ is also installed with the name \mathbf{c} ++.

When you compile C++ programs, you may specify many of the same command-line options that you use for compiling programs in any language; or command-line options meaningful for C and related languages; or options that are meaningful only for C++ programs.

Options Controlling C Dialect

The following options control the dialect of C (or languages derived from C, such as C++, Objective-C and Objective-C++) that the compiler accepts:

-ansi

In C mode, this is equivalent to -std=c90. In C++ mode, it is equivalent to -std=c++98.

This turns off certain features of GCC that are incompatible with ISO C90 (when compiling C code), or of standard C++ (when compiling C++ code), such as the asm and typeof keywords, and predefined macros such as unix and vax that identify the type of system you are using. It also enables the undesirable and rarely used ISO trigraph feature. For the C compiler, it disables recognition of C++ style // comments as well as the inline keyword.

The alternate keywords __asm__, __extension__, __inline__ and __typeof__ continue to work despite -ansi. You would not want to use them in an ISO C program, of course, but it is useful to put them in header files that might be included in compilations done with -ansi. Alternate predefined macros such as __unix__ and __vax__ are also available, with or without -ansi.

The **–ansi** option does not cause non-ISO programs to be rejected gratuitously. For that, **–Wpedantic** is required in addition to **–ansi**.

The macro __STRICT_ANSI__ is predefined when the **-ansi** option is used. Some header files may notice this macro and refrain from declaring certain functions or defining certain macros that the ISO standard doesn't call for; this is to avoid interfering with any programs that might use these names for other things.

Functions that are normally built in but do not have semantics defined by ISO C (such as alloca and

ffs) are not built-in functions when -ansi is used.

-std=

Determine the language standard. This option is currently only supported when compiling C or C++.

The compiler can accept several base standards, such as **c90** or **c++98**, and GNU dialects of those standards, such as **gnu90** or **gnu++98**. When a base standard is specified, the compiler accepts all programs following that standard plus those using GNU extensions that do not contradict it. For example, -**std=c90** turns off certain features of GCC that are incompatible with ISO C90, such as the asm and typeof keywords, but not other GNU extensions that do not have a meaning in ISO C90, such as omitting the middle term of a ?: expression. On the other hand, when a GNU dialect of a standard is specified, all features supported by the compiler are enabled, even when those features change the meaning of the base standard. As a result, some strict-conforming programs may be rejected. The particular standard is used by -**Wpedantic** to identify which features are GNU extensions given that version of the standard. For example -**std=gnu90** -**Wpedantic** warns about C++ style // comments, while -**std=gnu99** -**Wpedantic** does not.

A value for this option must be provided; possible values are

c90

c89

iso9899:1990

Support all ISO C90 programs (certain GNU extensions that conflict with ISO C90 are disabled). Same as **–ansi** for C code.

iso9899:199409

ISO C90 as modified in amendment 1.

c99

c9x

iso9899:1999 iso9899:199x

ISO C99. Note that this standard is not yet fully supported; see http://gcc.gnu.org/c99status.html for more information. The names c9x and iso9899:199x are deprecated.

c11

c1x

iso9899:2011

ISO C11, the 2011 revision of the ISO C standard. Support is incomplete and experimental. The name **c1x** is deprecated.

gnu90

gnu89

GNU dialect of ISO C90 (including some C99 features). This is the default for C code.

gnu99

gnu9x

GNU dialect of ISO C99. When ISO C99 is fully implemented in GCC, this will become the default. The name **gnu9x** is deprecated.

gnu11

gnu1x

GNU dialect of ISO C11. Support is incomplete and experimental. The name **gnu1x** is deprecated.

c++98

c++03

The~1998~ISO~C ++ standard~plus~the~2003~technical~corrigen dum~and~some~additional~defect~reports.~Same~as~-ansi~for~C ++ code.

gnu++98

gnu++03

GNU dialect of -std=c++98. This is the default for C++ code.

c++11

c++0x

The 2011 ISO C++ standard plus amendments. Support for C+11 is still experimental, and may change in incompatible ways in future releases. The name **c++0x** is deprecated.

gnu++11

gnu++0x

GNU dialect of -std=c++11. Support for C++11 is still experimental, and may change in incompatible ways in future releases. The name gnu++0x is deprecated.

c++1y

The next revision of the ISO C⁺⁺ standard, tentatively planned for 2017. Support is highly experimental, and will almost certainly change in incompatible ways in future releases.

gnu++1y

GNU dialect of **-std=c++1y**. Support is highly experimental, and will almost certainly change in incompatible ways in future releases.

-fgnu89-inline

The option **-fgnu89-inline** tells GCC to use the traditional GNU semantics for inline functions when in C99 mode.

This option is accepted and ignored by GCC versions 4.1.3 up to but not including 4.3. In GCC versions 4.3 and later it changes the behavior of GCC in C99 mode. Using this option is roughly equivalent to adding the gnu_inline function attribute to all inline functions.

The option **–fno–gnu89–inline** explicitly tells GCC to use the C99 semantics for inline when in C99 or gnu99 mode (i.e., it specifies the default behavior). This option was first supported in GCC 4.3. This option is not supported in **–std=c90** or **–std=gnu90** mode.

The preprocessor macros __GNUC_GNU_INLINE__ and __GNUC_STDC_INLINE__ may be used to check which semantics are in effect for inline functions.

-aux-info filename

Output to the given filename prototyped declarations for all functions declared and/or defined in a translation unit, including those in header files. This option is silently ignored in any language other than C

Besides declarations, the file indicates, in comments, the origin of each declaration (source file and line), whether the declaration was implicit, prototyped or unprototyped (**I**, **N** for new or **O** for old, respectively, in the first character after the line number and the colon), and whether it came from a declaration or a definition (**C** or **F**, respectively, in the following character). In the case of function definitions, a K&R–style list of arguments followed by their declarations is also provided, inside comments, after the declaration.

-fallow-parameterless-variadic-functions

Accept variadic functions without named parameters.

Although it is possible to define such a function, this is not very useful as it is not possible to read the arguments. This is only supported for C as this construct is allowed by C++.

-fno-asm

Do not recognize asm, inline or typeof as a keyword, so that code can use these words as identifiers. You can use the keywords __asm__, __inline__ and __typeof__ instead. -ansi implies -fno-asm.

In C++, this switch only affects the typeof keyword, since asm and inline are standard keywords. You may want to use the **-fno-gnu-keywords** flag instead, which has the same effect. In C99 mode (**-std=c99** or **-std=gnu99**), this switch only affects the asm and typeof keywords, since inline is

a standard keyword in ISO C99.

-fno-builtin

-fno-builtin-function

Don't recognize built-in functions that do not begin with __builtin_ as prefix.

GCC normally generates special code to handle certain built-in functions more efficiently; for instance, calls to alloca may become single instructions which adjust the stack directly, and calls to memcpy may become inline copy loops. The resulting code is often both smaller and faster, but since the function calls no longer appear as such, you cannot set a breakpoint on those calls, nor can you change the behavior of the functions by linking with a different library. In addition, when a function is recognized as a built-in function, GCC may use information about that function to warn about problems with calls to that function, or to generate more efficient code, even if the resulting code still contains calls to that function. For example, warnings are given with **–Wformat** for bad calls to printf when printf is built in and strlen is known not to modify global memory.

With the **-fno-builtin**-function option only the built-in function function is disabled. function must not begin with **__builtin**_. If a function is named that is not built-in in this version of GCC, this option is ignored. There is no corresponding **-fbuiltin**-function option; if you wish to enable built-in functions selectively when using **-fno-builtin** or **-ffreestanding**, you may define macros such as:

-fhosted

Assert that compilation targets a hosted environment. This implies **-fbuiltin**. A hosted environment is one in which the entire standard library is available, and in which main has a return type of int. Examples are nearly everything except a kernel. This is equivalent to **-fno-freestanding**.

-ffreestanding

Assert that compilation targets a freestanding environment. This implies **-fno-builtin**. A freestanding environment is one in which the standard library may not exist, and program startup may not necessarily be at main. The most obvious example is an OS kernel. This is equivalent to **-fno-hosted**.

-fopenmp

Enable handling of OpenMP directives #pragma omp in C/C++ and !\$omp in Fortran. When **-fopenmp** is specified, the compiler generates parallel code according to the OpenMP Application Program Interface v3.0 <http://www.openmp.org/>. This option implies **-pthread**, and thus is only supported on targets that have support for **-pthread**.

-fgnu-tm

When the option **–fgnu–tm** is specified, the compiler generates code for the Linux variant of Intel's current Transactional Memory ABI specification document (Revision 1.1, May 6 2009). This is an experimental feature whose interface may change in future versions of GCC, as the official specification changes. Please note that not all architectures are supported for this feature.

For more information on GCC's support for transactional memory,

Note that the transactional memory feature is not supported with non-call exceptions (**-fnon-call-exceptions**).

-fms-extensions

Accept some non-standard constructs used in Microsoft header files.

In C++ code, this allows member names in structures to be similar to previous types declarations.

```
typedef int UOW;
struct ABC {
    UOW UOW;
};
```

Some cases of unnamed fields in structures and unions are only accepted with this option.

-fplan9-extensions

Accept some non-standard constructs used in Plan 9 code.

This enables **-fms-extensions**, permits passing pointers to structures with anonymous fields to functions that expect pointers to elements of the type of the field, and permits referring to anonymous fields declared using a typedef. This is only supported for C, not C++.

-trigraphs

Support ISO C trigraphs. The **-ansi** option (and **-std** options for strict ISO C conformance) implies **-trigraphs**.

-traditional

-traditional-cpp

Formerly, these options caused GCC to attempt to emulate a pre-standard C compiler. They are now only supported with the **–E** switch. The preprocessor continues to support a pre-standard mode. See the GNU CPP manual for details.

-fcond-mismatch

Allow conditional expressions with mismatched types in the second and third arguments. The value of such an expression is void. This option is not supported for C++.

-flax-vector-conversions

Allow implicit conversions between vectors with differing numbers of elements and/or incompatible element types. This option should not be used for new code.

-funsigned-char

Let the type char be unsigned, like unsigned char.

Each kind of machine has a default for what char should be. It is either like unsigned char by default or like signed char by default.

Ideally, a portable program should always use signed char or unsigned char when it depends on the signedness of an object. But many programs have been written to use plain char and expect it to be signed, or expect it to be unsigned, depending on the machines they were written for. This option, and its inverse, let you make such a program work with the opposite default.

The type char is always a distinct type from each of signed char or unsigned char, even though its behavior is always just like one of those two.

-fsigned-char

Let the type char be signed, like signed char.

Note that this is equivalent to **-fno-unsigned-char**, which is the negative form of **-funsigned-char**. Likewise, the option **-fno-signed-char** is equivalent to **-funsigned-char**.

-fsigned-bitfields

- -funsigned-bitfields
- -fno-signed-bitfields
- -fno-unsigned-bitfields

These options control whether a bit-field is signed or unsigned, when the declaration does not use either signed or unsigned. By default, such a bit-field is signed, because this is consistent: the basic integer types such as int are signed types.

Options Controlling C++ Dialect

This section describes the command-line options that are only meaningful for C++ programs. You can also use most of the GNU compiler options regardless of what language your program is in. For example, you might compile a file firstClass. C like this:

In this example, only **–frepo** is an option meant only for C++ programs; you can use the other options with any language supported by GCC.

Here is a list of options that are *only* for compiling C++ programs:

-fabi-version=n

Use version n of the C++ ABI. The default is version 2.

Version 0 refers to the version conforming most closely to the C++ ABI specification. Therefore, the ABI obtained using version 0 will change in different versions of G++ as ABI bugs are fixed.

Version 1 is the version of the C++ ABI that first appeared in G++ 3.2.

Version 2 is the version of the C++ ABI that first appeared in G++ 3.4.

Version 3 corrects an error in mangling a constant address as a template argument.

Version 4, which first appeared in G++ 4.5, implements a standard mangling for vector types.

Version 5, which first appeared in G++ 4.6, corrects the mangling of attribute const/volatile on function pointer types, decltype of a plain decl, and use of a function parameter in the declaration of another parameter.

Version 6, which first appeared in G++ 4.7, corrects the promotion behavior of C++11 scoped enums and the mangling of template argument packs, const/static_cast, prefix ++ and --, and a class scope function used as a template argument.

See also -Wabi.

-fno-access-control

Turn off all access checking. This switch is mainly useful for working around bugs in the access control code.

-fcheck-new

Check that the pointer returned by operator new is non-null before attempting to modify the storage allocated. This check is normally unnecessary because the C++ standard specifies that operator new only returns 0 if it is declared *throw()*, in which case the compiler always checks the return value even without this option. In all other cases, when operator new has a non-empty exception specification, memory exhaustion is signalled by throwing std::bad_alloc. See also **new (nothrow)**.

-fconstexpr-depth=n

Set the maximum nested evaluation depth for C++11 constexpr functions to n. A limit is needed to detect endless recursion during constant expression evaluation. The minimum specified by the standard is 512.

-fdeduce-init-list

Enable deduction of a template type parameter as std::initializer_list from a brace-enclosed initializer list, i.e.

```
template <class T> auto forward(T t) -> decltype (realfn (t))
{
   return realfn (t);
}

void f()
{
   forward({1,2}); // call forward<std::initializer_list<int>>}
}
```

This deduction was implemented as a possible extension to the originally proposed semantics for the C++11 standard, but was not part of the final standard, so it is disabled by default. This option is deprecated, and may be removed in a future version of G++.

-ffriend-injection

Inject friend functions into the enclosing namespace, so that they are visible outside the scope of the class in which they are declared. Friend functions were documented to work this way in the old Annotated C++ Reference Manual, and versions of G++ before 4.1 always worked that way. However, in ISO C++ a friend function that is not declared in an enclosing scope can only be found using argument dependent lookup. This option causes friends to be injected as they were in earlier releases.

This option is for compatibility, and may be removed in a future release of G++.

-fno-elide-constructors

The C++ standard allows an implementation to omit creating a temporary that is only used to initialize another object of the same type. Specifying this option disables that optimization, and forces G++ to call the copy constructor in all cases.

-fno-enforce-eh-specs

Don't generate code to check for violation of exception specifications at run time. This option violates the C++ standard, but may be useful for reducing code size in production builds, much like defining **NDEBUG**. This does not give user code permission to throw exceptions in violation of the exception specifications; the compiler still optimizes based on the specifications, so throwing an unexpected exception results in undefined behavior at run time.

-fextern-tls-init

-fno-extern-tls-init

The C++11 and OpenMP standards allow **thread_local** and **threadprivate** variables to have dynamic (runtime) initialization. To support this, any use of such a variable goes through a wrapper function that performs any necessary initialization. When the use and definition of the variable are in the same translation unit, this overhead can be optimized away, but when the use is in a different translation unit there is significant overhead even if the variable doesn't actually need dynamic initialization. If the programmer can be sure that no use of the variable in a non-defining TU needs to trigger dynamic initialization (either because the variable is statically initialized, or a use of the variable in the defining TU will be executed before any uses in another TU), they can avoid this overhead with the **-fno-extern-tls-init** option.

On targets that support symbol aliases, the default is **-fextern-tls-init**. On targets that do not support symbol aliases, the default is **-fno-extern-tls-init**.

-ffor-scope

-fno-for-scope

If **-ffor-scope** is specified, the scope of variables declared in a *for-init-statement* is limited to the **for** loop itself, as specified by the C++ standard. If **-fno-for-scope** is specified, the scope of variables declared in a *for-init-statement* extends to the end of the enclosing scope, as was the case in old versions of G++, and other (traditional) implementations of C++.

If neither flag is given, the default is to follow the standard, but to allow and give a warning for oldstyle code that would otherwise be invalid, or have different behavior.

-fno-gnu-keywords

Do not recognize typeof as a keyword, so that code can use this word as an identifier. You can use the keyword __typeof__ instead. -ansi implies -fno-gnu-keywords.

-fno-implicit-templates

Never emit code for non-inline templates that are instantiated implicitly (i.e. by use); only emit code for explicit instantiations.

-fno-implicit-inline-templates

Don't emit code for implicit instantiations of inline templates, either. The default is to handle inlines differently so that compiles with and without optimization need the same set of explicit instantiations.

-fno-implement-inlines

To save space, do not emit out-of-line copies of inline functions controlled by **#pragma implementation**. This causes linker errors if these functions are not inlined everywhere they are

called.

-fms-extensions

Disable Wpedantic warnings about constructs used in MFC, such as implicit int and getting a pointer to member function via non-standard syntax.

-fno-nonansi-builtins

Disable built-in declarations of functions that are not mandated by ANSI/ISO C. These include ffs, alloca, _exit, index, bzero, conjf, and other related functions.

-fnothrow-opt

Treat a throw() exception specification as if it were a noexcept specification to reduce or eliminate the text size overhead relative to a function with no exception specification. If the function has local variables of types with non-trivial destructors, the exception specification actually makes the function smaller because the EH cleanups for those variables can be optimized away. The semantic effect is that an exception thrown out of a function with such an exception specification results in a call to terminate rather than unexpected.

-fno-operator-names

Do not treat the operator name keywords and, bitand, bitor, compl, not, or and xor as synonyms as keywords.

-fno-optional-diags

Disable diagnostics that the standard says a compiler does not need to issue. Currently, the only such diagnostic issued by G++ is the one for a name having multiple meanings within a class.

-fpermissive

Downgrade some diagnostics about nonconformant code from errors to warnings. Thus, using **-fpermissive** allows some nonconforming code to compile.

-fno-pretty-templates

When an error message refers to a specialization of a function template, the compiler normally prints the signature of the template followed by the template arguments and any typedefs or typenames in the signature (e.g. void f(T) [with T = int] rather than void f(int)) so that it's clear which template is involved. When an error message refers to a specialization of a class template, the compiler omits any template arguments that match the default template arguments for that template. If either of these behaviors make it harder to understand the error message rather than easier, you can use -fno-pretty-templates to disable them.

-frepo

Enable automatic template instantiation at link time. This option also implies **-fno-implicit-templates**.

-fno-rtti

Disable generation of information about every class with virtual functions for use by the C++ run-time type identification features (**dynamic_cast** and **typeid**). If you don't use those parts of the language, you can save some space by using this flag. Note that exception handling uses the same information, but G++ generates it as needed. The **dynamic_cast** operator can still be used for casts that do not require run-time type information, i.e. casts to void * or to unambiguous base classes.

-fstats

Emit statistics about front-end processing at the end of the compilation. This information is generally only useful to the G++ development team.

-fstrict-enums

Allow the compiler to optimize using the assumption that a value of enumerated type can only be one of the values of the enumeration (as defined in the C++ standard; basically, a value that can be represented in the minimum number of bits needed to represent all the enumerators). This assumption may not be valid if the program uses a cast to convert an arbitrary integer value to the enumerated type.

-ftemplate-backtrace-limit=n

Set the maximum number of template instantiation notes for a single warning or error to n. The default value is 10.

-ftemplate-depth=n

Set the maximum instantiation depth for template classes to n. A limit on the template instantiation depth is needed to detect endless recursions during template class instantiation. ANSI/ISO C++ conforming programs must not rely on a maximum depth greater than 17 (changed to 1024 in C++11). The default value is 900, as the compiler can run out of stack space before hitting 1024 in some situations.

-fno-threadsafe-statics

Do not emit the extra code to use the routines specified in the C++ ABI for thread-safe initialization of local statics. You can use this option to reduce code size slightly in code that doesn't need to be thread-safe

-fuse-cxa-atexit

Register destructors for objects with static storage duration with the __cxa_atexit function rather than the atexit function. This option is required for fully standards-compliant handling of static destructors, but only works if your C library supports __cxa_atexit.

-fno-use-cxa-get-exception-ptr

Don't use the __cxa_get_exception_ptr runtime routine. This causes std::uncaught_exception to be incorrect, but is necessary if the runtime routine is not available.

-fvisibility-inlines-hidden

This switch declares that the user does not attempt to compare pointers to inline functions or methods where the addresses of the two functions are taken in different shared objects.

The effect of this is that GCC may, effectively, mark inline methods with __attribute__ ((visibility ("hidden"))) so that they do not appear in the export table of a DSO and do not require a PLT indirection when used within the DSO. Enabling this option can have a dramatic effect on load and link times of a DSO as it massively reduces the size of the dynamic export table when the library makes heavy use of templates.

The behavior of this switch is not quite the same as marking the methods as hidden directly, because it does not affect static variables local to the function or cause the compiler to deduce that the function is defined in only one shared object.

You may mark a method as having a visibility explicitly to negate the effect of the switch for that method. For example, if you do want to compare pointers to a particular inline method, you might mark it as having default visibility. Marking the enclosing class with explicit visibility has no effect.

Explicitly instantiated inline methods are unaffected by this option as their linkage might otherwise cross a shared library boundary.

-fvisibility-ms-compat

This flag attempts to use visibility settings to make GCC's C++ linkage model compatible with that of Microsoft Visual Studio.

The flag makes these changes to GCC's linkage model:

- 1. It sets the default visibility to hidden, like **-fvisibility=hidden**.
- 2. Types, but not their members, are not hidden by default.
- The One Definition Rule is relaxed for types without explicit visibility specifications that are defined in more than one shared object: those declarations are permitted if they are permitted when this option is not used.

In new code it is better to use **-fvisibility=hidden** and export those classes that are intended to be externally visible. Unfortunately it is possible for code to rely, perhaps accidentally, on the Visual Studio behavior.

Among the consequences of these changes are that static data members of the same type with the same name but defined in different shared objects are different, so changing one does not change the other; and that pointers to function members defined in different shared objects may not compare equal. When this flag is given, it is a violation of the ODR to define types with the same name differently.

-fno-weak

Do not use weak symbol support, even if it is provided by the linker. By default, G++ uses weak symbols if they are available. This option exists only for testing, and should not be used by end-users; it results in inferior code and has no benefits. This option may be removed in a future release of G++.

-nostdinc++

Do not search for header files in the standard directories specific to C++, but do still search the other standard directories. (This option is used when building the C++ library.)

In addition, these optimization, warning, and code generation options have meanings only for C++ programs:

-fno-default-inline

Do not assume **inline** for functions defined inside a class scope.

Note that these functions have linkage like inline functions; they just aren't inlined by default.

```
-Wabi (C, Objective-C, C++ and Objective-C++ only)
```

Warn when G++ generates code that is probably not compatible with the vendor-neutral C++ ABI. Although an effort has been made to warn about all such cases, there are probably some cases that are not warned about, even though G++ is generating incompatible code. There may also be cases where warnings are emitted even though the code that is generated is compatible.

You should rewrite your code to avoid these warnings if you are concerned about the fact that code generated by G++ may not be binary compatible with code generated by other compilers.

The known incompatibilities in **-fabi-version=2** (the default) include:

A template with a non-type template parameter of reference type is mangled incorrectly:

```
extern int N;
template <int &> struct S {};
void n (S<N>) {2}
```

This is fixed in **-fabi-version=3**.

• SIMD vector types declared using __attribute ((vector_size)) are mangled in a non-standard way that does not allow for overloading of functions taking vectors of different sizes.

The mangling is changed in **-fabi-version=4**.

The known incompatibilities in **-fabi-version=1** include:

• Incorrect handling of tail-padding for bit-fields. G++ may attempt to pack data into the same byte as a base class. For example:

```
struct A { virtual void f(); int f1 : 1; };
struct B : public A { int f2 : 1; };
```

In this case, G++ places $B: \pm f2$ into the same byte as $A: \pm f1$; other compilers do not. You can avoid this problem by explicitly padding A so that its size is a multiple of the byte size on your platform; that causes G++ and other compilers to lay out B identically.

• Incorrect handling of tail-padding for virtual bases. G++ does not use tail padding when laying out virtual bases. For example:

```
struct A { virtual void f(); char c1; };
struct B { B(); char c2; };
struct C : public A, public virtual B {};
```

In this case, G++ does not place B into the tail-padding for A; other compilers do. You can avoid this problem by explicitly padding A so that its size is a multiple of its alignment (ignoring virtual

base classes); that causes G++ and other compilers to lay out C identically.

• Incorrect handling of bit-fields with declared widths greater than that of their underlying types, when the bit-fields appear in a union. For example:

```
union U { int i : 4096; };
```

Assuming that an int does not have 4096 bits, G++ makes the union too small by the number of bits in an int.

• Empty classes can be placed at incorrect offsets. For example:

```
struct A {};

struct B {
   A a;
   virtual void f ();
};

struct C : public B, public A {};
```

G++ places the A base class of C at a nonzero offset; it should be placed at offset zero. G++ mistakenly believes that the A data member of B is already at offset zero.

Names of template functions whose types involve typename or template template parameters
can be mangled incorrectly.

```
template <typename Q>
void f(typename Q::X) {}

template <template <typename> class Q>
void f(typename Q<int>::X) {}
```

Instantiations of these templates may be mangled incorrectly.

It also warns about psABI-related changes. The known psABI changes at this point include:

• For SysV/x86–64, unions with long double members are passed in memory as specified in psABI. For example:

```
union U {
  long double ld;
  int i;
};
```

union U is always passed in memory.

-Wctor-dtor-privacy (C++ and Objective-C++ only)

Warn when a class seems unusable because all the constructors or destructors in that class are private, and it has neither friends nor public static member functions. Also warn if there are no non-private methods, and there's at least one private member function that isn't a constructor or destructor.

-Wdelete-non-virtual-dtor (C++ and Objective-C++ only)

Warn when **delete** is used to destroy an instance of a class that has virtual functions and non-virtual destructor. It is unsafe to delete an instance of a derived class through a pointer to a base class if the base class does not have a virtual destructor. This warning is enabled by **-Wall**.

-Wliteral-suffix (C++ and Objective-C++ only)

Warn when a string or character literal is followed by a ud-suffix which does not begin with an underscore. As a conforming extension, GCC treats such suffixes as separate preprocessing tokens in order to maintain backwards compatibility with code that uses formatting macros from <inttypes.h>. For example:

```
#define __STDC_FORMAT_MACROS
#include <inttypes.h>
#include <stdio.h>

int main() {
  int64_t i64 = 123;
  printf("My int64: %"PRId64"\n", i64);
}
```

In this case, PRId64 is treated as a separate preprocessing token.

This warning is enabled by default.

-Wnarrowing (C++ and Objective–C++ only)

Warn when a narrowing conversion prohibited by C++11 occurs within { }, e.g.

```
int i = { 2.2 }; // error: narrowing from double to int
```

This flag is included in **-Wall** and **-Wc++11-compat**.

With -std=c++11, -Wno-narrowing suppresses the diagnostic required by the standard. Note that this does not affect the meaning of well-formed code; narrowing conversions are still considered ill-formed in SFINAE context.

-Wnoexcept (C++ and Objective–C++ only)

Warn when a noexcept-expression evaluates to false because of a call to a function that does not have a non-throwing exception specification (i.e. *throw()* or **noexcept**) but is known by the compiler to never throw an exception.

-Wnon-virtual-dtor (C++ and Objective-C++ only)

Warn when a class has virtual functions and an accessible non-virtual destructor, in which case it is possible but unsafe to delete an instance of a derived class through a pointer to the base class. This warning is also enabled if **-Weffc++** is specified.

-Wreorder (C++ and Objective–C++ only)

Warn when the order of member initializers given in the code does not match the order in which they must be executed. For instance:

```
struct A {
  int i;
  int j;
  A(): j (0), i (1) { }
};
```

The compiler rearranges the member initializers for i and j to match the declaration order of the members, emitting a warning to that effect. This warning is enabled by -Wall.

-fext-numeric-literals (C++ and Objective-C++ only)

Accept imaginary, fixed-point, or machine-defined literal number suffixes as GNU extensions. When this option is turned off these suffixes are treated as C++11 user-defined literal numeric suffixes. This is on by default for all pre-C++11 dialects and all GNU dialects: -std=c++98, -std=gnu++98, -std=gnu++1y. This option is off by default for ISO C++11 onwards (-std=c++11, ...).

The following -W... options are not affected by -Wall.

-Weffc++ (C++ and Objective–C++ only)

Warn about violations of the following style guidelines from Scott Meyers' *Effective C++*, *Second Edition* book:

• Item 11: Define a copy constructor and an assignment operator for classes with dynamically-allocated memory.

- Item 12: Prefer initialization to assignment in constructors.
- Item 14: Make destructors virtual in base classes.
- Item 15: Have operator = return a reference to *this.
- Item 23: Don't try to return a reference when you must return an object.

Also warn about violations of the following style guidelines from Scott Meyers' *More Effective C*++ book:

- Item 6: Distinguish between prefix and postfix forms of increment and decrement operators.
- Item 7: Never overload &&, | |, or ,.

When selecting this option, be aware that the standard library headers do not obey all of these guidelines; use grep - v to filter out those warnings.

-Wstrict-null-sentinel (C++ and Objective-C++ only)

Warn about the use of an uncasted NULL as sentinel. When compiling only with GCC this is a valid sentinel, as NULL is defined to __null. Although it is a null pointer constant rather than a null pointer, it is guaranteed to be of the same size as a pointer. But this use is not portable across different compilers.

-Wno-non-template-friend (C++ and Objective-C++ only)

Disable warnings when non-templatized friend functions are declared within a template. Since the advent of explicit template specification support in G++, if the name of the friend is an unqualified-id (i.e., **friend foo(int)**), the C++ language specification demands that the friend declare or define an ordinary, nontemplate function. (Section 14.5.3). Before G++ implemented explicit specification, unqualified-ids could be interpreted as a particular specialization of a templatized function. Because this non-conforming behavior is no longer the default behavior for G++, **-Wnon-template-friend** allows the compiler to check existing code for potential trouble spots and is on by default. This new compiler behavior can be turned off with **-Wno-non-template-friend**, which keeps the conformant compiler code but disables the helpful warning.

-Wold-style-cast (C++ and Objective-C++ only)

Warn if an old-style (C-style) cast to a non-void type is used within a C++ program. The new-style casts (**dynamic_cast**, **static_cast**, **reinterpret_cast**, and **const_cast**) are less vulnerable to unintended effects and much easier to search for.

-Woverloaded-virtual (C++ and Objective-C++ only)

Warn when a function declaration hides virtual functions from a base class. For example, in:

```
struct A {
   virtual void f();
};

struct B: public A {
   void f(int);
};
```

the A class version of f is hidden in B, and code like:

```
B* b;
b->f();
```

fails to compile.

-Wno-pmf-conversions (C++ and Objective-C++ only)

Disable the diagnostic for converting a bound pointer to member function to a plain pointer.

-Wsign-promo (C++ and Objective-C++ only)

Warn when overload resolution chooses a promotion from unsigned or enumerated type to a signed type, over a conversion to an unsigned type of the same size. Previous versions of G++ tried to

preserve unsignedness, but the standard mandates the current behavior.

Options Controlling Objective-C and Objective-C++ Dialects

(NOTE: This manual does not describe the Objective-C and Objective-C++ languages themselves.

This section describes the command-line options that are only meaningful for Objective-C and Objective-C++ programs. You can also use most of the language-independent GNU compiler options. For example, you might compile a file some_class.m like this:

```
gcc -g -fgnu-runtime -0 -c some_class.m
```

In this example, **–fgnu–runtime** is an option meant only for Objective-C and Objective–C++ programs; you can use the other options with any language supported by GCC.

Note that since Objective-C is an extension of the C language, Objective-C compilations may also use options specific to the C front-end (e.g., **-Wtraditional**). Similarly, Objective-C++ compilations may use C++-specific options (e.g., **-Wabi**).

Here is a list of options that are *only* for compiling Objective-C and Objective-C++ programs:

-fconstant-string-class=class-name

Use *class-name* as the name of the class to instantiate for each literal string specified with the syntax @"...". The default class name is NXConstantString if the GNU runtime is being used, and NSConstantString if the NeXT runtime is being used (see below). The **-fconstant-cfstrings** option, if also present, overrides the **-fconstant-string-class** setting and cause @"..." literals to be laid out as constant CoreFoundation strings.

-fgnu-runtime

Generate object code compatible with the standard GNU Objective-C runtime. This is the default for most types of systems.

-fnext-runtime

Generate output compatible with the NeXT runtime. This is the default for NeXT-based systems, including Darwin and Mac OS X. The macro __NEXT_RUNTIME__ is predefined if (and only if) this option is used.

-fno-nil-receivers

Assume that all Objective-C message dispatches ([receiver message:arg]) in this translation unit ensure that the receiver is not nil. This allows for more efficient entry points in the runtime to be used. This option is only available in conjunction with the NeXT runtime and ABI version 0 or 1.

-fobjc-abi-version=n

Use version *n* of the Objective-C ABI for the selected runtime. This option is currently supported only for the NeXT runtime. In that case, Version 0 is the traditional (32-bit) ABI without support for properties and other Objective-C 2.0 additions. Version 1 is the traditional (32-bit) ABI with support for properties and other Objective-C 2.0 additions. Version 2 is the modern (64-bit) ABI. If nothing is specified, the default is Version 0 on 32-bit target machines, and Version 2 on 64-bit target machines.

-fobjc-call-cxx-cdtors

For each Objective-C class, check if any of its instance variables is a C++ object with a non-trivial default constructor. If so, synthesize a special - (id) .cxx_construct instance method which runs non-trivial default constructors on any such instance variables, in order, and then return self. Similarly, check if any instance variable is a C++ object with a non-trivial destructor, and if so, synthesize a special - (void) .cxx_destruct method which runs all such default destructors, in reverse order.

The - (id) .cxx_construct and - (void) .cxx_destruct methods thusly generated only operate on instance variables declared in the current Objective-C class, and not those inherited from superclasses. It is the responsibility of the Objective-C runtime to invoke all such methods in an object's inheritance hierarchy. The - (id) .cxx_construct methods are invoked by the runtime immediately after a new object instance is allocated; the - (void) .cxx_destruct methods are invoked immediately before the runtime deallocates an object instance.

As of this writing, only the NeXT runtime on Mac OS X 10.4 and later has support for invoking the – (id) .cxx_construct and – (void) .cxx_destruct methods.

-fobjc-direct-dispatch

Allow fast jumps to the message dispatcher. On Darwin this is accomplished via the comm page.

-fobjc-exceptions

Enable syntactic support for structured exception handling in Objective-C, similar to what is offered by C++ and Java. This option is required to use the Objective-C keywords @try, @throw, @catch, @finally and @synchronized. This option is available with both the GNU runtime and the NeXT runtime (but not available in conjunction with the NeXT runtime on Mac OS X 10.2 and earlier).

-fobjc-gc

Enable garbage collection (GC) in Objective-C and Objective-C++ programs. This option is only available with the NeXT runtime; the GNU runtime has a different garbage collection implementation that does not require special compiler flags.

-fobjc-nilcheck

For the NeXT runtime with version 2 of the ABI, check for a nil receiver in method invocations before doing the actual method call. This is the default and can be disabled using **-fno-objc-nilcheck**. Class methods and super calls are never checked for nil in this way no matter what this flag is set to. Currently this flag does nothing when the GNU runtime, or an older version of the NeXT runtime ABI, is used.

-fobjc-std=objc1

Conform to the language syntax of Objective-C 1.0, the language recognized by GCC 4.0. This only affects the Objective-C additions to the C/C++ language; it does not affect conformance to C/C++ standards, which is controlled by the separate C/C++ dialect option flags. When this option is used with the Objective-C or Objective-C++ compiler, any Objective-C syntax that is not recognized by GCC 4.0 is rejected. This is useful if you need to make sure that your Objective-C code can be compiled with older versions of GCC.

-freplace-objc-classes

Emit a special marker instructing ld(1) not to statically link in the resulting object file, and allow dyld(1) to load it in at run time instead. This is used in conjunction with the Fix-and-Continue debugging mode, where the object file in question may be recompiled and dynamically reloaded in the course of program execution, without the need to restart the program itself. Currently, Fix-and-Continue functionality is only available in conjunction with the NeXT runtime on Mac OS X 10.3 and later.

-fzero-link

When compiling for the NeXT runtime, the compiler ordinarily replaces calls to objc_getClass("...") (when the name of the class is known at compile time) with static class references that get initialized at load time, which improves run-time performance. Specifying the **-fzero-link** flag suppresses this behavior and causes calls to objc_getClass("...") to be retained. This is useful in Zero-Link debugging mode, since it allows for individual class implementations to be modified during program execution. The GNU runtime currently always retains calls to objc_get_class("...") regardless of command-line options.

-gen-decls

Dump interface declarations for all classes seen in the source file to a file named sourcename.decl.

-Wassign-intercept (Objective-C and Objective-C++ only)

Warn whenever an Objective-C assignment is being intercepted by the garbage collector.

-Wno-protocol (Objective-C and Objective-C++ only)

If a class is declared to implement a protocol, a warning is issued for every method in the protocol that is not implemented by the class. The default behavior is to issue a warning for every method not explicitly implemented in the class, even if a method implementation is inherited from the superclass. If you use the **-Wno-protocol** option, then methods inherited from the superclass are considered to

be implemented, and no warning is issued for them.

-Wselector (Objective-C and Objective-C++ only)

Warn if multiple methods of different types for the same selector are found during compilation. The check is performed on the list of methods in the final stage of compilation. Additionally, a check is performed for each selector appearing in a @selector(...) expression, and a corresponding method for that selector has been found during compilation. Because these checks scan the method table only at the end of compilation, these warnings are not produced if the final stage of compilation is not reached, for example because an error is found during compilation, or because the **_fsyntax_only** option is being used.

-Wstrict-selector-match (Objective-C and Objective-C++ only)

Warn if multiple methods with differing argument and/or return types are found for a given selector when attempting to send a message using this selector to a receiver of type id or Class. When this flag is off (which is the default behavior), the compiler omits such warnings if any differences found are confined to types that share the same size and alignment.

-Wundeclared-selector (Objective-C and Objective-C++ only)

Warn if a @selector(...) expression referring to an undeclared selector is found. A selector is considered undeclared if no method with that name has been declared before the @selector(...) expression, either explicitly in an @interface or @protocol declaration, or implicitly in an @implementation section. This option always performs its checks as soon as a @selector(...) expression is found, while **-Wselector** only performs its checks in the final stage of compilation. This also enforces the coding style convention that methods and selectors must be declared before being used.

-print-objc-runtime-info

Generate C header describing the largest structure that is passed by value, if any.

Options to Control Diagnostic Messages Formatting

Traditionally, diagnostic messages have been formatted irrespective of the output device's aspect (e.g. its width, ...). You can use the options described below to control the formatting algorithm for diagnostic messages, e.g. how many characters per line, how often source location information should be reported. Note that some language front ends may not honor these options.

-fmessage-length=n

Try to format error messages so that they fit on lines of about n characters. The default is 72 characters for g++ and 0 for the rest of the front ends supported by GCC. If n is zero, then no linewrapping is done; each error message appears on a single line.

-fdiagnostics-show-location=once

Only meaningful in line-wrapping mode. Instructs the diagnostic messages reporter to emit source location information *once*; that is, in case the message is too long to fit on a single physical line and has to be wrapped, the source location won't be emitted (as prefix) again, over and over, in subsequent continuation lines. This is the default behavior.

-fdiagnostics-show-location=every-line

Only meaningful in line-wrapping mode. Instructs the diagnostic messages reporter to emit the same source location information (as prefix) for physical lines that result from the process of breaking a message which is too long to fit on a single line.

-fno-diagnostics-show-option

By default, each diagnostic emitted includes text indicating the command-line option that directly controls the diagnostic (if such an option is known to the diagnostic machinery). Specifying the **-fno-diagnostics-show-option** flag suppresses that behavior.

-fno-diagnostics-show-caret

By default, each diagnostic emitted includes the original source line and a caret '' indicating the column. This option suppresses this information.

Options to Request or Suppress Warnings

Warnings are diagnostic messages that report constructions that are not inherently erroneous but that are risky or suggest there may have been an error.

The following language-independent options do not enable specific warnings but control the kinds of diagnostics produced by GCC.

-fsyntax-only

Check the code for syntax errors, but don't do anything beyond that.

$-\mathbf{fmax}-\mathbf{errors}=n$

Limits the maximum number of error messages to n, at which point GCC bails out rather than attempting to continue processing the source code. If n is 0 (the default), there is no limit on the number of error messages produced. If **-Wfatal-errors** is also specified, then **-Wfatal-errors** takes precedence over this option.

-w Inhibit all warning messages.

-Werror

Make all warnings into errors.

-Werror=

Make the specified warning into an error. The specifier for a warning is appended; for example **–Werror=switch** turns the warnings controlled by **–Wswitch** into errors. This switch takes a negative form, to be used to negate **–Werror** for specific warnings; for example **–Wno–error=switch** makes **–Wswitch** warnings not be errors, even when **–Werror** is in effect.

The warning message for each controllable warning includes the option that controls the warning. That option can then be used with **-Werror**= and **-Wno-error**= as described above. (Printing of the option in the warning message can be disabled using the **-fno-diagnostics-show-option** flag.)

Note that specifying **-Werror**=*foo* automatically implies **-W***foo*. However, **-Wno-error**=*foo* does not imply anything.

-Wfatal-errors

This option causes the compiler to abort compilation on the first error occurred rather than trying to keep going and printing further error messages.

You can request many specific warnings with options beginning with **-W**, for example **-Wimplicit** to request warnings on implicit declarations. Each of these specific warning options also has a negative form beginning **-Wno-** to turn off warnings; for example, **-Wno-implicit**. This manual lists only one of the two forms, whichever is not the default. For further language-specific options also refer to **C++ Dialect Options** and **Objective-C and Objective-C++ Dialect Options**.

When an unrecognized warning option is requested (e.g., **-Wunknown-warning**), GCC emits a diagnostic stating that the option is not recognized. However, if the **-Wno-** form is used, the behavior is slightly different: no diagnostic is produced for **-Wno-unknown-warning** unless other diagnostics are being produced. This allows the use of new **-Wno-** options with old compilers, but if something goes wrong, the compiler warns that an unrecognized option is present.

-Wpedantic

-pedantic

Issue all the warnings demanded by strict ISO C and ISO C++; reject all programs that use forbidden extensions, and som
other programs that do not follow ISO C and ISO C+. For ISO C, follows the version of the ISO C standard specified by any -std option used.
Valid to c and to c

Like **-Wpedantic**, except that errors are produced rather than warnings.

-Wall

This enables all the warnings about constructions that some users consider questionable, and that are easy to avoid (or modify to prevent the warning), even in conjunction with macros. This also enables some language-specific warnings described in C++ Dialect Options and Objective-C and Objective-C++ Dialect Options.

- -Wall turns on the following warning flags:
- -Waddress -Warray-bounds (only with -O2) -Wc++11-compat -Wchar-subscripts -Wenum-compare (in C/ObjC; this is on by default in C++) -Wimplicit-int (C and Objective-C only) -Wimplicit-function-declaration (C and Objective-C only) -Wcomment -Wformat -Wmain (only for C/ObjC and unless -ffreestanding) -Wmaybe-uninitialized -Wmissing-braces (only for C/ObjC) -Wnonnull -Wparentheses -Wpointer-sign -Wreorder -Wreturn-type -Wsequence-point -Wsign-compare (only in C++) -Wstrict-aliasing -Wstrict-overflow=1 -Wswitch -Wtrigraphs -Wuninitialized -Wunknown-pragmas -Wunused-function -Wunused-label -Wunused-value -Wunused-variable -Wvolatile-register-var

Note that some warning flags are not implied by **-Wall**. Some of them warn about constructions that users generally do not consider questionable, but which occasionally you might wish to check for; others warn about constructions that are necessary or hard to avoid in some cases, and there is no simple way to modify the code to suppress the warning. Some of them are enabled by **-Wextra** but many of them must be enabled individually.

-Wextra

This enables some extra warning flags that are not enabled by **-Wall**. (This option used to be called **-W**. The older name is still supported, but the newer name is more descriptive.)

-Wclobbered -Wempty-body -Wignored-qualifiers -Wmissing-field-initializers -Wmissing-parameter-type (C only) -Wold-style-declaration (C only) -Woverride-init -Wsign-compare -Wtype-limits -Wuninitialized -Wunused-parameter (only with -Wunused or -Wall) -Wunused-but-set-parameter (only with -Wunused or -Wall)

The option -Wextra also prints warning messages for the following cases:

- A pointer is compared against integer zero with <, <=, >, or >=.
- (C++ only) An enumerator and a non-enumerator both appear in a conditional expression.
- (C++ only) Ambiguous virtual bases.
- (C++ only) Subscripting an array that has been declared register.
- (C++ only) Taking the address of a variable that has been declared **register**.
- (C++ only) A base class is not initialized in a derived class's copy constructor.

-Wchar-subscripts

Warn if an array subscript has type char. This is a common cause of error, as programmers often forget that this type is signed on some machines. This warning is enabled by **-Wall**.

-Wcomment

Warn whenever a comment-start sequence /* appears in a /* comment, or whenever a Backslash-Newline appears in a // comment. This warning is enabled by **-Wall**.

-Wno-coverage-mismatch

Warn if feedback profiles do not match when using the **-fprofile-use** option. If a source file is changed between compiling with **-fprofile-gen** and with **-fprofile-use**, the files with the profile feedback can fail to match the source file and GCC cannot use the profile feedback information. By default, this warning is enabled and is treated as an error. **-Wno-coverage-mismatch** can be used to disable the warning or **-Wno-error=coverage-mismatch** can be used to disable the error. Disabling the error for this warning can result in poorly optimized code and is useful only in the case of very

minor changes such as bug fixes to an existing code-base. Completely disabling the warning is not recommended.

-Wno-cpp

(C, Objective-C, C++, Objective-C++ and Fortran only)

Suppress warning messages emitted by #warning directives.

-Wdouble-promotion (C, C++, Objective-C and Objective-C++ only)

Give a warning when a value of type float is implicitly promoted to double. CPUs with a 32-bit "single-precision" floating-point unit implement float in hardware, but emulate double in software. On such a machine, doing computations using double values is much more expensive because of the overhead required for software emulation.

It is easy to accidentally do computations with double because floating-point literals are implicitly of type double. For example, in:

```
float area(float radius)
{
   return 3.14159 * radius * radius;
}
```

the compiler performs the entire computation with double because the floating-point literal is a double.

-Wformat

-Wformat = n

Check calls to printf and scanf, etc., to make sure that the arguments supplied have types appropriate to the format string specified, and that the conversions specified in the format string make sense. This includes standard functions, and others specified by format attributes, in the printf, scanf, strftime and strfmon (an X/Open extension, not in the C standard) families (or other target-specific families). Which functions are checked without format attributes having been specified depends on the standard version selected, and such checks of functions without the attribute specified are disabled by **-ffreestanding** or **-fno-builtin**.

The formats are checked against the format features supported by GNU libc version 2.2. These include all ISO C90 and C99 features, as well as features from the Single Unix Specification and some BSD and GNU extensions. Other library implementations may not support all these features; GCC does not support warning about features that go beyond a particular library's limitations. However, if **-Wpedantic** is used with **-Wformat**, warnings are given about format features not in the selected standard version (but not for strfmon formats, since those are not in any version of the C standard).

-Wformat=1

-Wformat

Option -Wformat is equivalent to -Wformat=1, and -Wno-format is equivalent to -Wformat=0. Since -Wformat also checks for null format arguments for several functions, -Wformat also implies -Wnonnull. Some aspects of this level of format checking can be disabled by the options: -Wno-format-contains-nul, -Wno-format-extra-args, and -Wno-format-zero-length. -Wformat is enabled by -Wall.

-Wno-format-contains-nul

If **-Wformat** is specified, do not warn about format strings that contain NUL bytes.

-Wno-format-extra-args

If **-Wformat** is specified, do not warn about excess arguments to a printf or scanf format function. The C standard specifies that such arguments are ignored.

Where the unused arguments lie between used arguments that are specified with \$ operand number specifications, normally warnings are still given, since the implementation could not know what type to pass to va_arg to skip the unused arguments. However, in the case of scanf formats, this option suppresses the warning if the unused arguments are all pointers, since

the Single Unix Specification says that such unused arguments are allowed.

-Wno-format-zero-length

If **–Wformat** is specified, do not warn about zero-length formats. The C standard specifies that zero-length formats are allowed.

-Wformat=2

Enable **-Wformat** plus additional format checks. Currently equivalent to **-Wformat -Wformat-nonliteral -Wformat-security -Wformat-y2k**.

-Wformat-nonliteral

If **-Wformat** is specified, also warn if the format string is not a string literal and so cannot be checked, unless the format function takes its format arguments as a valist.

-Wformat-security

If **-Wformat** is specified, also warn about uses of format functions that represent possible security problems. At present, this warns about calls to printf and scanf functions where the format string is not a string literal and there are no format arguments, as in printf (foo);. This may be a security hole if the format string came from untrusted input and contains %n. (This is currently a subset of what **-Wformat-nonliteral** warns about, but in future warnings may be added to **-Wformat-security** that are not included in **-Wformat-nonliteral**.)

NOTE: In Ubuntu 8.10 and later versions this option is enabled by default for C, C++, ObjC, ObjC++. To disable, use **-Wno-format-security**, or disable all format warnings with **-Wformat=0**. To make format security warnings fatal, specify **-Werror=format-security**.

-Wformat-y2k

If **-Wformat** is specified, also warn about strftime formats that may yield only a two-digit year.

-Wnonnull

Warn about passing a null pointer for arguments marked as requiring a non-null value by the nonnull function attribute.

-Wnonnull is included in **-Wall** and **-Wformat**. It can be disabled with the **-Wno-nonnull** option.

-Winit-self (C, C++, Objective-C and Objective-C++ only)

Warn about uninitialized variables that are initialized with themselves. Note this option can only be used with the **-Wuninitialized** option.

For example, GCC warns about i being uninitialized in the following snippet only when **-Winit-self** has been specified:

```
int f()
{
  int i = i;
  return i;
}
```

This warning is enabled by -Wall in C++.

-Wimplicit-int (C and Objective-C only)

Warn when a declaration does not specify a type. This warning is enabled by -Wall.

-Wimplicit-function-declaration (C and Objective-C only)

Give a warning whenever a function is used before being declared. In C99 mode (-std=c99 or -std=gnu99), this warning is enabled by default and it is made into an error by -pedantic-errors. This warning is also enabled by -Wall.

-Wimplicit (C and Objective-C only)

Same as -Wimplicit-int and -Wimplicit-function-declaration. This warning is enabled by -Wall.

-Wignored-qualifiers (C and C++ only)

Warn if the return type of a function has a type qualifier such as const. For ISO C such a type qualifier has no effect, since the value returned by a function is not an Ivalue. For C++, the warning is only emitted for scalar types or void. ISO C prohibits qualified void return types on function definitions, so such return types always receive a warning even without this option.

This warning is also enabled by **-Wextra**.

-Wmain

Warn if the type of **main** is suspicious. **main** should be a function with external linkage, returning int, taking either zero arguments, two, or three arguments of appropriate types. This warning is enabled by default in C++ and is enabled by either **-Wall** or **-Wpedantic**.

-Wmissing-braces

Warn if an aggregate or union initializer is not fully bracketed. In the following example, the initializer for **a** is not fully bracketed, but that for **b** is fully bracketed. This warning is enabled by **-Wall** in C.

```
int a[2][2] = { 0, 1, 2, 3 };
int b[2][2] = { { 0, 1 }, { 2, 3 } };
```

This warning is enabled by -Wall.

-Wmissing-include-dirs (C, C++, Objective-C and Objective-C++ only)

Warn if a user-supplied include directory does not exist.

-Wparentheses

Warn if parentheses are omitted in certain contexts, such as when there is an assignment in a context where a truth value is expected, or when operators are nested whose precedence people often get confused about.

Also warn if a comparison like x <= y <= z appears; this is equivalent to (x <= y ? 1 : 0) <= z, which is a different interpretation from that of ordinary mathematical notation.

Also warn about constructions where there may be confusion to which if statement an else branch belongs. Here is an example of such a case:

```
{
  if (a)
    if (b)
    foo ();
  else
    bar ();
}
```

In C/C++, every else branch belongs to the innermost possible if statement, which in this example is if (b). This is often not what the programmer expected, as illustrated in the above example by indentation the programmer chose. When there is the potential for this confusion, GCC issues a warning when this flag is specified. To eliminate the warning, add explicit braces around the innermost if statement so there is no way the else can belong to the enclosing if. The resulting code looks like this:

```
{
    if (a)
        {
            if (b)
            foo ();
            else
            bar ();
    }
}
```

Also warn for dangerous uses of the GNU extension to ?: with omitted middle operand. When the condition in the ?: operator is a boolean expression, the omitted value is always 1. Often programmers expect it to be a value computed inside the conditional expression instead.

This warning is enabled by -Wall.

-Wsequence-point

Warn about code that may have undefined semantics because of violations of sequence point rules in the C and C++ standards.

The C and C++ standards define the order in which expressions in a C/C++ program are evaluated in terms of *sequence points*, which represent a partial ordering between the execution of parts of the program: those executed before the sequence point, and those executed after it. These occur after the evaluation of a full expression (one which is not part of a larger expression), after the evaluation of the first operand of a &&, | |, ? : or , (comma) operator, before a function is called (but after the evaluation of its arguments and the expression denoting the called function), and in certain other places. Other than as expressed by the sequence point rules, the order of evaluation of subexpressions of an expression is not specified. All these rules describe only a partial order rather than a total order, since, for example, if two functions are called within one expression with no sequence point between them, the order in which the functions are called is not specified. However, the standards committee have ruled that function calls do not overlap.

It is not specified when between sequence points modifications to the values of objects take effect. Programs whose behavior depends on this have undefined behavior; the C and C++ standards specify that "Between the previous and next sequence point an object shall have its stored value modified at most once by the evaluation of an expression. Furthermore, the prior value shall be read only to determine the value to be stored." If a program breaks these rules, the results on any particular implementation are entirely unpredictable.

Examples of code with undefined behavior are a = a++i, a[n] = b[n++] and a[i++] = ii. Some more complicated cases are not diagnosed by this option, and it may give an occasional false positive result, but in general it has been found fairly effective at detecting this sort of problem in programs.

The standard is worded confusingly, therefore there is some debate over the precise meaning of the sequence point rules in subtle cases. Links to discussions of the problem, including proposed formal definitions, may be found on the GCC readings page, at http://gcc.gnu.org/readings.html>.

This warning is enabled by -Wall for C and C++.

-Wno-return-local-addr

Do not warn about returning a pointer (or in C++, a reference) to a variable that goes out of scope after the function returns.

-Wreturn-type

Warn whenever a function is defined with a return type that defaults to int. Also warn about any return statement with no return value in a function whose return type is not void (falling off the end of the function body is considered returning without a value), and about a return statement with an expression in a function whose return type is void.

For C++, a function without return type always produces a diagnostic message, even when **-Wno-return-type** is specified. The only exceptions are **main** and functions defined in system headers.

This warning is enabled by **-Wall**.

-Wswitch

Warn whenever a switch statement has an index of enumerated type and lacks a case for one or more of the named codes of that enumeration. (The presence of a default label prevents this warning.) case labels outside the enumeration range also provoke warnings when this option is used (even if there is a default label). This warning is enabled by **-Wall**.

-Wswitch-default

Warn whenever a switch statement does not have a default case.

-Wswitch-enum

Warn whenever a switch statement has an index of enumerated type and lacks a case for one or more of the named codes of that enumeration. case labels outside the enumeration range also provoke warnings when this option is used. The only difference between **-Wswitch** and this option is that this option gives a warning about an omitted enumeration code even if there is a default label.

-Wsync-nand (C and C++ only)

Warn when __sync_fetch_and_nand and __sync_nand_and_fetch built-in functions are used. These functions changed semantics in GCC 4.4.

-Wtrigraphs

Warn if any trigraphs are encountered that might change the meaning of the program (trigraphs within comments are not warned about). This warning is enabled by **-Wall**.

-Wunused-but-set-parameter

Warn whenever a function parameter is assigned to, but otherwise unused (aside from its declaration).

To suppress this warning use the **unused** attribute.

This warning is also enabled by **-Wunused** together with **-Wextra**.

-Wunused-but-set-variable

Warn whenever a local variable is assigned to, but otherwise unused (aside from its declaration). This warning is enabled by **-Wall**.

To suppress this warning use the **unused** attribute.

This warning is also enabled by **-Wunused**, which is enabled by **-Wall**.

-Wunused-function

Warn whenever a static function is declared but not defined or a non-inline static function is unused. This warning is enabled by **-Wall**.

-Wunused-label

Warn whenever a label is declared but not used. This warning is enabled by -Wall.

To suppress this warning use the **unused** attribute.

-Wunused-local-typedefs (C, Objective-C, C++ and Objective-C++ only)

Warn when a typedef locally defined in a function is not used. This warning is enabled by -Wall.

-Wunused-parameter

Warn whenever a function parameter is unused aside from its declaration.

To suppress this warning use the **unused** attribute.

-Wno-unused-result

Do not warn if a caller of a function marked with attribute warn_unused_result does not use its return value. The default is **-Wunused-result**.

-Wunused-variable

Warn whenever a local variable or non-constant static variable is unused aside from its declaration. This warning is enabled by **-Wall**.

To suppress this warning use the **unused** attribute.

-Wunused-value

Warn whenever a statement computes a result that is explicitly not used. To suppress this warning cast the unused expression to **void**. This includes an expression-statement or the left-hand side of a comma expression that contains no side effects. For example, an expression such as x[i,j] causes a warning, while x[(void)i,j] does not.

This warning is enabled by **-Wall**.

-Wunused

All the above -Wunused options combined.

In order to get a warning about an unused function parameter, you must either specify **-Wextra -Wunused** (note that **-Wall** implies **-Wunused**), or separately specify **-Wunused-parameter**.

-Wuninitialized

Warn if an automatic variable is used without first being initialized or if a variable may be clobbered by a setjmp call. In C++, warn if a non-static reference or non-static **const** member appears in a class without constructors.

If you want to warn about code that uses the uninitialized value of the variable in its own initializer, use the **-Winit-self** option.

These warnings occur for individual uninitialized or clobbered elements of structure, union or array variables as well as for variables that are uninitialized or clobbered as a whole. They do not occur for variables or elements declared volatile. Because these warnings depend on optimization, the exact variables or elements for which there are warnings depends on the precise optimization options and version of GCC used.

Note that there may be no warning about a variable that is used only to compute a value that itself is never used, because such computations may be deleted by data flow analysis before the warnings are printed.

-Wmaybe-uninitialized

For an automatic variable, if there exists a path from the function entry to a use of the variable that is initialized, but there exist some other paths for which the variable is not initialized, the compiler emits a warning if it cannot prove the uninitialized paths are not executed at run time. These warnings are made optional because GCC is not smart enough to see all the reasons why the code might be correct in spite of appearing to have an error. Here is one example of how this can happen:

```
{
  int x;
  switch (y)
    {
    case 1: x = 1;
      break;
    case 2: x = 4;
      break;
    case 3: x = 5;
    }
  foo (x);
}
```

If the value of y is always 1, 2 or 3, then x is always initialized, but GCC doesn't know this. To suppress the warning, you need to provide a default case with assert(0) or similar code.

This option also warns when a non-volatile automatic variable might be changed by a call to longjmp. These warnings as well are possible only in optimizing compilation.

The compiler sees only the calls to setjmp. It cannot know where longjmp will be called; in fact, a signal handler could call it at any point in the code. As a result, you may get a warning even when there is in fact no problem because longjmp cannot in fact be called at the place that would cause a problem.

Some spurious warnings can be avoided if you declare all the functions you use that never return as noreturn.

This warning is enabled by -Wall or -Wextra.

-Wunknown-pragmas

Warn when a #pragma directive is encountered that is not understood by GCC. If this command-line option is used, warnings are even issued for unknown pragmas in system header files. This is not the case if the warnings are only enabled by the **-Wall** command-line option.

-Wno-pragmas

Do not warn about misuses of pragmas, such as incorrect parameters, invalid syntax, or conflicts between pragmas. See also **–Wunknown–pragmas**.

-Wstrict-aliasing

This option is only active when **-fstrict-aliasing** is active. It warns about code that might break the strict aliasing rules that the compiler is using for optimization. The warning does not catch all cases, but does attempt to catch the more common pitfalls. It is included in **-Wall**. It is equivalent to **-Wstrict-aliasing=3**

-Wstrict-aliasing=n

This option is only active when **-fstrict-aliasing** is active. It warns about code that might break the strict aliasing rules that the compiler is using for optimization. Higher levels correspond to higher accuracy (fewer false positives). Higher levels also correspond to more effort, similar to the way **-O** works. **-Wstrict-aliasing** is equivalent to **-Wstrict-aliasing=3**.

Level 1: Most aggressive, quick, least accurate. Possibly useful when higher levels do not warn but **-fstrict-aliasing** still breaks the code, as it has very few false negatives. However, it has many false positives. Warns for all pointer conversions between possibly incompatible types, even if never dereferenced. Runs in the front end only.

Level 2: Aggressive, quick, not too precise. May still have many false positives (not as many as level 1 though), and few false negatives (but possibly more than level 1). Unlike level 1, it only warns when an address is taken. Warns about incomplete types. Runs in the front end only.

Level 3 (default for **-Wstrict-aliasing**): Should have very few false positives and few false negatives. Slightly slower than levels 1 or 2 when optimization is enabled. Takes care of the common pun+dereference pattern in the front end: *(int*)&some_float. If optimization is enabled, it also runs in the back end, where it deals with multiple statement cases using flow-sensitive points-to information. Only warns when the converted pointer is dereferenced. Does not warn about incomplete types.

-Wstrict-overflow

-Wstrict-overflow=n

This option is only active when **-fstrict-overflow** is active. It warns about cases where the compiler optimizes based on the assumption that signed overflow does not occur. Note that it does not warn about all cases where the code might overflow: it only warns about cases where the compiler implements some optimization. Thus this warning depends on the optimization level.

An optimization that assumes that signed overflow does not occur is perfectly safe if the values of the variables involved are such that overflow never does, in fact, occur. Therefore this warning can easily give a false positive: a warning about code that is not actually a problem. To help focus on important issues, several warning levels are defined. No warnings are issued for the use of undefined signed

overflow when estimating how many iterations a loop requires, in particular when determining whether a loop will be executed at all.

-Wstrict-overflow=1

Warn about cases that are both questionable and easy to avoid. For example, with **-fstrict-overflow**, the compiler simplifies x + 1 > x to 1. This level of **-Wstrict-overflow** is enabled by **-Wall**; higher levels are not, and must be explicitly requested.

-Wstrict-overflow=2

Also warn about other cases where a comparison is simplified to a constant. For example: abs (x) >= 0. This can only be simplified when **-fstrict-overflow** is in effect, because abs (INT_MIN) overflows to INT_MIN, which is less than zero. **-Wstrict-overflow** (with no level) is the same as **-Wstrict-overflow=2**.

-Wstrict-overflow=3

Also warn about other cases where a comparison is simplified. For example: x + 1 > 1 is simplified to x > 0.

-Wstrict-overflow=4

Also warn about other simplifications not covered by the above cases. For example: (x * 10) / 5 is simplified to x * 2.

-Wstrict-overflow=5

Also warn about cases where the compiler reduces the magnitude of a constant involved in a comparison. For example: x + 2 > y is simplified to x + 1 >= y. This is reported only at the highest warning level because this simplification applies to many comparisons, so this warning level gives a very large number of false positives.

-Wsuggest-attribute=[pure|const|noreturn|format]

Warn for cases where adding an attribute may be beneficial. The attributes currently supported are listed below.

-Wsuggest-attribute=pure

-Wsuggest-attribute=const

-Wsuggest-attribute=noreturn

Warn about functions that might be candidates for attributes pure, const or noreturn. The compiler only warns for functions visible in other compilation units or (in the case of pure and const) if it cannot prove that the function returns normally. A function returns normally if it doesn't contain an infinite loop or return abnormally by throwing, calling abort () or trapping. This analysis requires option **-fipa-pure-const**, which is enabled by default at **-O** and higher. Higher optimization levels improve the accuracy of the analysis.

-Wsuggest-attribute=format

-Wmissing-format-attribute

Warn about function pointers that might be candidates for format attributes. Note these are only possible candidates, not absolute ones. GCC guesses that function pointers with format attributes that are used in assignment, initialization, parameter passing or return statements should have a corresponding format attribute in the resulting type. I.e. the left-hand side of the assignment or initialization, the type of the parameter variable, or the return type of the containing function respectively should also have a format attribute to avoid the warning.

GCC also warns about function definitions that might be candidates for format attributes. Again, these are only possible candidates. GCC guesses that format attributes might be appropriate for any function that calls a function like vprintf or vscanf, but this might not always be the case, and some functions for which format attributes are appropriate may not be detected.

-Warray-bounds

This option is only active when **-ftree-vrp** is active (default for **-O2** and above). It warns about subscripts to arrays that are always out of bounds. This warning is enabled by **-Wall**.

-Wno-div-by-zero

Do not warn about compile-time integer division by zero. Floating-point division by zero is not warned about, as it can be a legitimate way of obtaining infinities and NaNs.

-Wsystem-headers

Print warning messages for constructs found in system header files. Warnings from system headers are normally suppressed, on the assumption that they usually do not indicate real problems and would only make the compiler output harder to read. Using this command-line option tells GCC to emit warnings from system headers as if they occurred in user code. However, note that using **–Wall** in conjunction with this option does *not* warn about unknown pragmas in system headers——for that, **–Wunknown–pragmas** must also be used.

-Wtrampolines

Warn about trampolines generated for pointers to nested functions.

A trampoline is a small piece of data or code that is created at run time on the stack when the address of a nested function is taken, and is used to call the nested function indirectly. For some targets, it is made up of data only and thus requires no special treatment. But, for most targets, it is made up of code and thus requires the stack to be made executable in order for the program to work properly.

-Wfloat-equal

Warn if floating-point values are used in equality comparisons.

The idea behind this is that sometimes it is convenient (for the programmer) to consider floating-point values as approximations to infinitely precise real numbers. If you are doing this, then you need to compute (by analyzing the code, or in some other way) the maximum or likely maximum error that the computation introduces, and allow for it when performing comparisons (and when producing output, but that's a different problem). In particular, instead of testing for equality, you should check to see whether the two values have ranges that overlap; and this is done with the relational operators, so equality comparisons are probably mistaken.

-Wtraditional (C and Objective-C only)

Warn about certain constructs that behave differently in traditional and ISO C. Also warn about ISO C constructs that have no traditional C equivalent, and/or problematic constructs that should be avoided.

- Macro parameters that appear within string literals in the macro body. In traditional C macro replacement takes place within string literals, but in ISO C it does not.
- In traditional C, some preprocessor directives did not exist. Traditional preprocessors only considered a line to be a directive if the # appeared in column 1 on the line. Therefore –Wtraditional warns about directives that traditional C understands but ignores because the # does not appear as the first character on the line. It also suggests you hide directives like #pragma not understood by traditional C by indenting them. Some traditional implementations do not recognize #elif, so this option suggests avoiding it altogether.
- A function-like macro that appears without arguments.
- The unary plus operator.
- The U integer constant suffix, or the F or L floating-point constant suffixes. (Traditional C does support the L suffix on integer constants.) Note, these suffixes appear in macros defined in the system headers of most modern systems, e.g. the _MIN/_MAX macros in limits.h>. Use of these macros in user code might normally lead to spurious warnings, however GCC's integrated preprocessor has enough context to avoid warning in these cases.
- A function declared external in one block and then used after the end of the block.
- A switch statement has an operand of type long.

- A non-static function declaration follows a static one. This construct is not accepted by some traditional C compilers.
- The ISO type of an integer constant has a different width or signedness from its traditional type. This warning is only issued if the base of the constant is ten. I.e. hexadecimal or octal values, which typically represent bit patterns, are not warned about.
- Usage of ISO string concatenation is detected.
- Initialization of automatic aggregates.
- Identifier conflicts with labels. Traditional C lacks a separate namespace for labels.
- Initialization of unions. If the initializer is zero, the warning is omitted. This is done under the
 assumption that the zero initializer in user code appears conditioned on e.g. __STDC__ to avoid
 missing initializer warnings and relies on default initialization to zero in the traditional C case.
- Conversions by prototypes between fixed/floating-point values and vice versa. The absence of
 these prototypes when compiling with traditional C causes serious problems. This is a subset of
 the possible conversion warnings; for the full set use -Wtraditional-conversion.
- Use of ISO C style function definitions. This warning intentionally is *not* issued for prototype declarations or variadic functions because these ISO C features appear in your code when using libiberty's traditional C compatibility macros, PARAMS and VPARAMS. This warning is also bypassed for nested functions because that feature is already a GCC extension and thus not relevant to traditional C compatibility.

-Wtraditional-conversion (C and Objective-C only)

Warn if a prototype causes a type conversion that is different from what would happen to the same argument in the absence of a prototype. This includes conversions of fixed point to floating and vice versa, and conversions changing the width or signedness of a fixed-point argument except when the same as the default promotion.

-Wdeclaration-after-statement (C and Objective-C only)

Warn when a declaration is found after a statement in a block. This construct, known from C++, was introduced with ISO C99 and is by default allowed in GCC. It is not supported by ISO C90 and was not supported by GCC versions before GCC 3.0.

-Wundef

Warn if an undefined identifier is evaluated in an #if directive.

-Wno-endif-labels

Do not warn whenever an #else or an #endif are followed by text.

-Wshadow

Warn whenever a local variable or type declaration shadows another variable, parameter, type, or class member (in C++), or whenever a built-in function is shadowed. Note that in C++, the compiler warns if a local variable shadows an explicit typedef, but not if it shadows a struct/class/enum.

-Wlarger-than=len

Warn whenever an object of larger than *len* bytes is defined.

-Wframe-larger-than=len

Warn if the size of a function frame is larger than *len* bytes. The computation done to determine the stack frame size is approximate and not conservative. The actual requirements may be somewhat greater than *len* even if you do not get a warning. In addition, any space allocated via alloca, variable-length arrays, or related constructs is not included by the compiler when determining whether or not to issue a warning.

-Wno-free-nonheap-object

Do not warn when attempting to free an object that was not allocated on the heap.

-Wstack-usage=len

Warn if the stack usage of a function might be larger than *len* bytes. The computation done to determine the stack usage is conservative. Any space allocated via alloca, variable-length arrays, or related constructs is included by the compiler when determining whether or not to issue a warning.

The message is in keeping with the output of **-fstack-usage**.

• If the stack usage is fully static but exceeds the specified amount, it's:

```
warning: stack usage is 1120 bytes
```

• If the stack usage is (partly) dynamic but bounded, it's:

```
warning: stack usage might be 1648 bytes
```

• If the stack usage is (partly) dynamic and not bounded, it's:

```
warning: stack usage might be unbounded
```

-Wunsafe-loop-optimizations

Warn if the loop cannot be optimized because the compiler cannot assume anything on the bounds of the loop indices. With **-funsafe-loop-optimizations** warn if the compiler makes such assumptions.

-Wno-pedantic-ms-format (MinGW targets only)

When used in combination with **-Wformat** and **-pedantic** without GNU extensions, this option disables the warnings about non-ISO printf / scanf format width specifiers I32, I64, and I used on Windows targets, which depend on the MS runtime.

-Wpointer-arith

Warn about anything that depends on the "size of" a function type or of void. GNU C assigns these types a size of 1, for convenience in calculations with void * pointers and pointers to functions. In C++, warn also when an arithmetic operation involves NULL. This warning is also enabled by **-Wpedantic**.

-Wtype-limits

Warn if a comparison is always true or always false due to the limited range of the data type, but do not warn for constant expressions. For example, warn if an unsigned variable is compared against zero with < or >=. This warning is also enabled by **-Wextra**.

-Wbad-function-cast (C and Objective-C only)

Warn whenever a function call is cast to a non-matching type. For example, warn if int malloc() is cast to anything *.

-Wc++-compat (C and Objective-C only)

Warn about ISO C constructs that are outside of the common subset of ISO C and ISO C++, e.g. request for implicit conversion from void * to a pointer to non-void type.

```
-Wc++11-compat \; (C^{\!_{++}} \text{and Objective--} C^{\!_{++}} \text{only})
```

Warn about C++ constructs whose meaning differs between ISO C++ 1998 and ISO C+2011, e.g., Identifies in ISO G+9

Warn whenever a pointer is cast so as to remove a type qualifier from the target type. For example, warn if a const char * is cast to an ordinary char *.

Also warn when making a cast that introduces a type qualifier in an unsafe way. For example, casting char ** to const char ** is unsafe, as in this example:

```
/* p is char ** value. */
const char **q = (const char **) p;
/* Assignment of readonly string to const char * is OK. */
*q = "string";
/* Now char** pointer points to read-only memory. */
**p = 'b';
```

-Wcast-align

Warn whenever a pointer is cast such that the required alignment of the target is increased. For example, warn if a char * is cast to an int * on machines where integers can only be accessed at two- or four-byte boundaries.

-Wwrite-strings

When compiling C, give string constants the type const char[length] so that copying the address of one into a non-const char * pointer produces a warning. These warnings help you find at compile time code that can try to write into a string constant, but only if you have been very careful about using const in declarations and prototypes. Otherwise, it is just a nuisance. This is why we did not make -Wall request these warnings.

When compiling C++, warn about the deprecated conversion from string literals to char *. This warning is enabled by default for C++ programs.

-Wclobbered

Warn for variables that might be changed by **longjmp** or **vfork**. This warning is also enabled by **-Wextra**.

-Wconversion

Warn for implicit conversions that may alter a value. This includes conversions between real and integer, like abs (x) when x is double; conversions between signed and unsigned, like unsigned ui = -1; and conversions to smaller types, like sqrtf (M_PI) . Do not warn for explicit casts like abs ((int) x) and ui = (unsigned) -1, or if the value is not changed by the conversion like in abs (2.0). Warnings about conversions between signed and unsigned integers can be disabled by using -Wno-sign-conversion.

For C++, also warn for confusing overload resolution for user-defined conversions; and conversions that never use a type conversion operator: conversions to void, the same type, a base class or a reference to them. Warnings about conversions between signed and unsigned integers are disabled by default in C++ unless -Wsign-conversion is explicitly enabled.

-Wno-conversion-null (C++ and Objective-C++ only)

Do not warn for conversions between NULL and non-pointer types. **-Wconversion-null** is enabled by default.

-Wzero-as-null-pointer-constant (C++ and Objective-C++ only)

Warn when a literal '0' is used as null pointer constant. This can be useful to facilitate the conversion to nullptr in C++11.

-Wuseless-cast (C++ and Objective-C++ only)

Warn when an expression is casted to its own type.

-Wempty-body

Warn if an empty body occurs in an **if**, **else** or **do while** statement. This warning is also enabled by **-Wextra**.

-Wenum-compare

Warn about a comparison between values of different enumerated types. In C++ enumeral mismatches in conditional expressions are also diagnosed and the warning is enabled by default. In C this warning is enabled by **-Wall**.

-Wjump-misses-init (C, Objective-C only)

Warn if a goto statement or a switch statement jumps forward across the initialization of a variable, or jumps backward to a label after the variable has been initialized. This only warns about variables that are initialized when they are declared. This warning is only supported for C and Objective-C; in C++ this sort of branch is an error in any case.

-Wjump-misses-init is included in **-Wc++-compat**. It can be disabled with the **-Wno-jump-misses-init** option.

-Wsign-compare

Warn when a comparison between signed and unsigned values could produce an incorrect result when the signed value is converted to unsigned. This warning is also enabled by **-Wextra**; to get the other warnings of **-Wextra** without this warning, use **-Wextra -Wno-sign-compare**.

-Wsign-conversion

Warn for implicit conversions that may change the sign of an integer value, like assigning a signed integer expression to an unsigned integer variable. An explicit cast silences the warning. In C, this option is enabled also by **-Wconversion**.

-Wsizeof-pointer-memaccess

Warn for suspicious length parameters to certain string and memory built-in functions if the argument uses sizeof. This warning warns e.g. about memset (ptr, 0, sizeof (ptr)); if ptr is not an array, but a pointer, and suggests a possible fix, or about memory (&foo, ptr, sizeof (&foo));. This warning is enabled by -Wall.

_Waddress

Warn about suspicious uses of memory addresses. These include using the address of a function in a conditional expression, such as void func(void); if (func), and comparisons against the memory address of a string literal, such as if (x == "abc"). Such uses typically indicate a programmer error: the address of a function always evaluates to true, so their use in a conditional usually indicate that the programmer forgot the parentheses in a function call; and comparisons against string literals result in unspecified behavior and are not portable in C, so they usually indicate that the programmer intended to use stromp. This warning is enabled by **-Wall**.

-Wlogical-op

Warn about suspicious uses of logical operators in expressions. This includes using logical operators in contexts where a bit-wise operator is likely to be expected.

-Waggregate-return

Warn if any functions that return structures or unions are defined or called. (In languages where you can return an array, this also elicits a warning.)

-Wno-aggressive-loop-optimizations

Warn if in a loop with constant number of iterations the compiler detects undefined behavior in some statement during one or more of the iterations.

-Wno-attributes

Do not warn if an unexpected __attribute__ is used, such as unrecognized attributes, function attributes applied to variables, etc. This does not stop errors for incorrect use of supported attributes.

-Wno-builtin-macro-redefined

Do not warn if certain built-in macros are redefined. This suppresses warnings for redefinition of __TIMESTAMP__, __TIME__, __DATE__, __FILE__, and __BASE_FILE__.

-Wstrict-prototypes (C and Objective-C only)

Warn if a function is declared or defined without specifying the argument types. (An old-style function definition is permitted without a warning if preceded by a declaration that specifies the argument types.)

-Wold-style-declaration (C and Objective-C only)

Warn for obsolescent usages, according to the C Standard, in a declaration. For example, warn if storage-class specifiers like static are not the first things in a declaration. This warning is also enabled by **-Wextra**.

-Wold-style-definition (C and Objective-C only)

Warn if an old-style function definition is used. A warning is given even if there is a previous prototype.

-Wmissing-parameter-type (C and Objective-C only)

A function parameter is declared without a type specifier in K&R-style functions:

```
void foo(bar) { }
```

This warning is also enabled by -Wextra.

-Wmissing-prototypes (C and Objective-C only)

Warn if a global function is defined without a previous prototype declaration. This warning is issued even if the definition itself provides a prototype. Use this option to detect global functions that do not have a matching prototype declaration in a header file. This option is not valid for C++ because all function declarations provide prototypes and a non-matching declaration will declare an overload rather than conflict with an earlier declaration. Use **-Wmissing-declarations** to detect missing declarations in C++.

-Wmissing-declarations

Warn if a global function is defined without a previous declaration. Do so even if the definition itself provides a prototype. Use this option to detect global functions that are not declared in header files. In C, no warnings are issued for functions with previous non-prototype declarations; use **-Wmissing-prototype** to detect missing prototypes. In C++, no warnings are issued for function templates, or for inline functions, or for functions in anonymous namespaces.

-Wmissing-field-initializers

Warn if a structure's initializer has some fields missing. For example, the following code causes such a warning, because x . h is implicitly zero:

```
struct s { int f, g, h; };
struct s x = \{3, 4\};
```

This option does not warn about designated initializers, so the following modification does not trigger a warning:

```
struct s { int f, g, h; };
struct s x = { .f = 3, .g = 4 };
```

This warning is included in **-Wextra**. To get other **-Wextra** warnings without this one, use **-Wextra -Wno-missing-field-initializers**.

-Wno-multichar

Do not warn if a multicharacter constant ('FOOF') is used. Usually they indicate a typo in the user's code, as they have implementation-defined values, and should not be used in portable code.

-Wnormalized=<none|id|nfc|nfkc>

In ISO C and ISO C++, two identifiers are different if they are different sequences of characters. However, sometimes when characters outside the basic ASCII character set are used, you can have two different character sequences that look the same. To avoid confusion, the ISO 10646 standard sets out some *normalization rules* which when applied ensure that two sequences that look the same are turned into the same sequence. GCC can warn you if you are using identifiers that have not been normalized; this option controls that warning.

There are four levels of warning supported by GCC. The default is **-Wnormalized=nfc**, which warns about any identifier that is not in the ISO 10646 "C" normalized form, *NFC*. NFC is the recommended form for most uses.

Unfortunately, there are some characters allowed in identifiers by ISO C and ISO C*+that, when turned into NPC, are not allowed in identifiers. That is, there's no way to use these symbols in portable

180 C or Cand have all your identifiers in NPC.—Whormalized-id suppresses the warning for these characters. It is boosed that future versions of the standards involved will correct this, which is why this ontion is not the default.

You can switch the warning off for all characters by writing - Wnormalized=none. You should only do this if you are using some other normalization scheme (like "D"), because otherwise you can easily create bugs that are literally impossible to see

Some characters in 180 1066 have distinct meanings but look identical in some fonts or display methodologies, especially once formatting has been applied. For instance \u207F, "SUPERSCRIPT LATIN SMALL LETTER N", displays just like a regular n that has been placed in a superscript. 180 1066 defines the NFAC normalization scheme to convert all these into a standard form as well, and GCC warns if your code is not in NFAC if you use **—Wnormalized=nfkc**. This warning is comparable to warning about every identifier that contains the letter O because it might be confused with the digit 0, and so is not the default, but may be useful as a local coding convention if the programming environment cannot be fixed to display these characters distinctly.

-Wno-deprecated

Do not warn about usage of deprecated features.

-Wno-deprecated-declarations

Do not warn about uses of functions, variables, and types marked as deprecated by using the deprecated attribute.

-Wno-overflow

Do not warn about compile-time overflow in constant expressions.

-Woverride-init (C and Objective-C only)

Warn if an initialized field without side effects is overridden when using designated initializers.

This warning is included in **-Wextra**. To get other **-Wextra** warnings without this one, use **-Wextra -Wno-override-init**.

-Wpacked

Warn if a structure is given the packed attribute, but the packed attribute has no effect on the layout or size of the structure. Such structures may be mis-aligned for little benefit. For instance, in this code, the variable f.x in struct bar is misaligned even though struct bar does not itself have the packed attribute:

```
struct foo {
  int x;
  char a, b, c, d;
} __attribute__((packed));
struct bar {
  char z;
  struct foo f;
};
```

-Wpacked-bitfield-compat

The 4.1, 4.2 and 4.3 series of GCC ignore the packed attribute on bit-fields of type char. This has been fixed in GCC 4.4 but the change can lead to differences in the structure layout. GCC informs you when the offset of such a field has changed in GCC 4.4. For example there is no longer a 4-bit padding between field a and b in this structure:

```
struct foo
{
  char a:4;
  char b:8;
} __attribute__ ((packed));
```

This warning is enabled by default. Use **-Wno-packed-bitfield-compat** to disable this warning.

-Wpadded

Warn if padding is included in a structure, either to align an element of the structure or to align the whole structure. Sometimes when this happens it is possible to rearrange the fields of the structure to reduce the padding and so make the structure smaller.

-Wredundant-decls

Warn if anything is declared more than once in the same scope, even in cases where multiple declaration is valid and changes nothing.

-Wnested-externs (C and Objective-C only)

Warn if an extern declaration is encountered within a function.

-Wno-inherited-variadic-ctor

Suppress warnings about use of C+11 inheriting constructors when the base class inherited from has a C variadic constructor; the warning is on by default because the ellipsis is not inherited.

-Winline

Warn if a function that is declared as inline cannot be inlined. Even with this option, the compiler does not warn about failures to inline functions declared in system headers.

The compiler uses a variety of heuristics to determine whether or not to inline a function. For example, the compiler takes into account the size of the function being inlined and the amount of inlining that has already been done in the current function. Therefore, seemingly insignificant changes in the source program can cause the warnings produced by **–Winline** to appear or disappear.

-Wno-invalid-offsetof (C++ and Objective-C++ only)

Suppress warnings from applying the **offsetof** macro to a non-POD type. According to the 1998 ISO C++ standard, applying **offsetof** to a non-POD type is undefined. In existing C++ implementations, however, **offsetof** typically gives meaningful results even when applied to certain kinds of non-POD types (such as a simple **struct** that fails to be a POD type only by virtue of having a constructor). This flag is for users who are aware that they are writing nonportable code and who have deliberately chosen to ignore the warning about it.

The restrictions on offsetof may be relaxed in a future version of the C++ standard.

-Wno-int-to-pointer-cast

Suppress warnings from casts to pointer type of an integer of a different size. In C++, casting to a pointer type of smaller size is an error. **Wint-to-pointer-cast** is enabled by default.

-Wno-pointer-to-int-cast (C and Objective-C only)

Suppress warnings from casts from a pointer to an integer type of a different size.

-Winvalid-pch

Warn if a precompiled header is found in the search path but can't be used.

-Wlong-long

Warn if **long long** type is used. This is enabled by either **-Wpedantic** or **-Wtraditional** in ISO C90 and C++98 modes. To inhibit the warning messages, use **-Wno-long-long**.

-Wvariadic-macros

Warn if variadic macros are used in pedantic ISO C90 mode, or the GNU alternate syntax when in pedantic ISO C99 mode. This is default. To inhibit the warning messages, use **-Wno-variadic-macros**.

-Wvarargs

Warn upon questionable usage of the macros used to handle variable arguments like **va_start**. This is default. To inhibit the warning messages, use **–Wno–varargs**.

-Wvector-operation-performance

Warn if vector operation is not implemented via SIMD capabilities of the architecture. Mainly useful for the performance tuning. Vector operation can be implemented piecewise, which means that the scalar operation is performed on every vector element; in parallel, which means that the vector operation is implemented using scalars of wider type, which normally is more performance efficient; and as a single scalar, which means that vector fits into a scalar type.

-Wno-virtual-move-assign

Suppress warnings about inheriting from a virtual base with a non-trivial C++11 move assignment operator. This is dangerous because if the virtual base is reachable along more than one path, it will be moved multiple times, which can mean both objects end up in the moved-from state. If the move assignment operator is written to avoid moving from a moved-from object, this warning can be disabled.

-Wvla

Warn if variable length array is used in the code. **-Wno-vla** prevents the **-Wpedantic** warning of the variable length array.

-Wvolatile-register-var

Warn if a register variable is declared volatile. The volatile modifier does not inhibit all optimizations that may eliminate reads and/or writes to register variables. This warning is enabled by **-Wall**.

-Wdisabled-optimization

Warn if a requested optimization pass is disabled. This warning does not generally indicate that there is anything wrong with your code; it merely indicates that GCC's optimizers are unable to handle the code effectively. Often, the problem is that your code is too big or too complex; GCC refuses to optimize programs when the optimization itself is likely to take inordinate amounts of time.

-Wpointer-sign (C and Objective-C only)

Warn for pointer argument passing or assignment with different signedness. This option is only supported for C and Objective-C. It is implied by **-Wall** and by **-Wpedantic**, which can be disabled with **-Wno-pointer-sign**.

-Wstack-protector

This option is only active when **-fstack-protector** is active. It warns about functions that are not protected against stack smashing.

-Wno-mudflap

Suppress warnings about constructs that cannot be instrumented by **-fmudflap**.

-Woverlength-strings

Warn about string constants that are longer than the "minimum maximum" length specified in the C standard. Modern compilers generally allow string constants that are much longer than the standard's minimum limit, but very portable programs should avoid using longer strings.

The limit applies *after* string constant concatenation, and does not count the trailing NUL. In C90, the limit was 509 characters; in C99, it was raised to 4095. C++98 does not specify a normative minimum maximum, so we do not diagnose overlength strings in C++.

This option is implied by **-Wpedantic**, and can be disabled with **-Wno-overlength-strings**.

-Wunsuffixed-float-constants (C and Objective-C only)

Issue a warning for any floating constant that does not have a suffix. When used together with **-Wsystem-headers** it warns about such constants in system header files. This can be useful when preparing code to use with the FLOAT_CONST_DECIMAL64 pragma from the decimal floating-point extension to C99.

Options for Debugging Your Program or GCC

GCC has various special options that are used for debugging either your program or GCC:

-g Produce debugging information in the operating system's native format (stabs, COFF, XCOFF, or DWARF 2). GDB can work with this debugging information.

On most systems that use stabs format, **–g** enables use of extra debugging information that only GDB can use; this extra information makes debugging work better in GDB but probably makes other debuggers crash or refuse to read the program. If you want to control for certain whether to generate the extra information, use **–gstabs+**, **–gstabs**, **–gxcoff+**, **–gxcoff**, or **–gyms** (see below).

GCC allows you to use $-\mathbf{g}$ with $-\mathbf{O}$. The shortcuts taken by optimized code may occasionally produce surprising results: some variables you declared may not exist at all; flow of control may briefly move where you did not expect it; some statements may not be executed because they compute constant results or their values are already at hand; some statements may execute in different places because they have been moved out of loops.

Nevertheless it proves possible to debug optimized output. This makes it reasonable to use the optimizer for programs that might have bugs.

The following options are useful when GCC is generated with the capability for more than one debugging format.

-gsplit-dwarf

Separate as much dwarf debugging information as possible into a separate output file with the extension .dwo. This option allows the build system to avoid linking files with debug information. To be useful, this option requires a debugger capable of reading .dwo files.

-ggdb

Produce debugging information for use by GDB. This means to use the most expressive format available (DWARF 2, stabs, or the native format if neither of those are supported), including GDB extensions if at all possible.

-gpubnames

Generate dwarf .debug_pubnames and .debug_pubtypes sections.

-gstabs

Produce debugging information in stabs format (if that is supported), without GDB extensions. This is the format used by DBX on most BSD systems. On MIPS, Alpha and System V Release 4 systems this option produces stabs debugging output that is not understood by DBX or SDB. On System V Release 4 systems this option requires the GNU assembler.

-feliminate-unused-debug-symbols

Produce debugging information in stabs format (if that is supported), for only symbols that are actually used.

-femit-class-debug-always

Instead of emitting debugging information for a C++ class in only one object file, emit it in all object files using the class. This option should be used only with debuggers that are unable to handle the way GCC normally emits debugging information for classes because using this option increases the size of debugging information by as much as a factor of two.

-fdebug-types-section

When using DWARF Version 4 or higher, type DIEs can be put into their own .debug_types section instead of making them part of the .debug_info section. It is more efficient to put them in a separate comdat sections since the linker can then remove duplicates. But not all DWARF consumers support .debug_types sections yet and on some objects .debug_types produces larger instead of smaller debugging information.

-gstabs+

Produce debugging information in stabs format (if that is supported), using GNU extensions understood only by the GNU debugger (GDB). The use of these extensions is likely to make other debuggers crash or refuse to read the program.

-gcoff

Produce debugging information in COFF format (if that is supported). This is the format used by SDB on most System V systems prior to System V Release 4.

-gxcoff

Produce debugging information in XCOFF format (if that is supported). This is the format used by the DBX debugger on IBM RS/6000 systems.

-gxcoff+

Produce debugging information in XCOFF format (if that is supported), using GNU extensions understood only by the GNU debugger (GDB). The use of these extensions is likely to make other debuggers crash or refuse to read the program, and may cause assemblers other than the GNU assembler (GAS) to fail with an error.

-gdwarf-version

Produce debugging information in DWARF format (if that is supported). The value of *version* may be either 2, 3 or 4; the default version for most targets is 4.

Note that with DWARF Version 2, some ports require and always use some non-conflicting DWARF 3 extensions in the unwind tables.

Version 4 may require GDB 7.0 and **-fvar-tracking-assignments** for maximum benefit.

-grecord-gcc-switches

This switch causes the command-line options used to invoke the compiler that may affect code generation to be appended to the DW_AT_producer attribute in DWARF debugging information. The options are concatenated with spaces separating them from each other and from the compiler version. See also **-frecord-gcc-switches** for another way of storing compiler options into the object file. This is the default.

-gno-record-gcc-switches

Disallow appending command-line options to the DW_AT_producer attribute in DWARF debugging information.

-gstrict-dwarf

Disallow using extensions of later DWARF standard version than selected with **-gdwarf**-*version*. On most targets using non-conflicting DWARF extensions from later standard versions is allowed.

-gno-strict-dwarf

Allow using extensions of later DWARF standard version than selected with -gdwarf-version.

-gvms

Produce debugging information in Alpha/VMS debug format (if that is supported). This is the format used by DEBUG on Alpha/VMS systems.

- -glevel
- -ggdblevel
- -gstabslevel
- -gcofflevel
- -gxcofflevel
- -gvmslevel

Request debugging information and also use *level* to specify how much information. The default level is 2.

Level 0 produces no debug information at all. Thus, $-\mathbf{g0}$ negates $-\mathbf{g}$.

Level 1 produces minimal information, enough for making backtraces in parts of the program that you don't plan to debug. This includes descriptions of functions and external variables, but no information about local variables and no line numbers.

Level 3 includes extra information, such as all the macro definitions present in the program. Some debuggers support macro expansion when you use -g3.

-gdwarf-2 does not accept a concatenated debug level, because GCC used to support an option **-gdwarf** that meant to generate debug information in version 1 of the DWARF format (which is very different from version 2), and it would have been too confusing. That debug format is long obsolete, but the option cannot be changed now. Instead use an additional **-glevel** option to change the debug level for DWARF.

-gtoggle

Turn off generation of debug info, if leaving out this option generates it, or turn it on at level 2 otherwise. The position of this argument in the command line does not matter; it takes effect after all other options are processed, and it does so only once, no matter how many times it is given. This is mainly intended to be used with **-fcompare-debug**.

-fsanitize=address

Enable AddressSanitizer, a fast memory error detector. Memory access instructions will be instrumented to detect out-of-bounds and use-after-free bugs. See http://code.google.com/p/address-sanitizer/> for more details.

-fsanitize=thread

Enable ThreadSanitizer, a fast data race detector. Memory access instructions will be instrumented to detect data race bugs. See http://code.google.com/p/data-race-test/wiki/ThreadSanitizer for more details.

-fdump-final-insns[=file]

Dump the final internal representation (RTL) to *file*. If the optional argument is omitted (or if *file* is .), the name of the dump file is determined by appending .gkd to the compilation output file name.

-fcompare-debug[=opts]

If no error occurs during compilation, run the compiler a second time, adding *opts* and **-fcompare-debug-second** to the arguments passed to the second compilation. Dump the final

internal representation in both compilations, and print an error if they differ.

If the equal sign is omitted, the default **-gtoggle** is used.

The environment variable GCC_COMPARE_DEBUG, if defined, non-empty and nonzero, implicitly enables **–fcompare–debug**. If GCC_COMPARE_DEBUG is defined to a string starting with a dash, then it is used for *opts*, otherwise the default **–gtoggle** is used.

-fcompare-debug=, with the equal sign but without *opts*, is equivalent to **-fno-compare-debug**, which disables the dumping of the final representation and the second compilation, preventing even **GCC COMPARE DEBUG** from taking effect.

To verify full coverage during **-fcompare-debug** testing, set **GCC_COMPARE_DEBUG** to say **-fcompare-debug-not-overridden**, which GCC rejects as an invalid option in any actual compilation (rather than preprocessing, assembly or linking). To get just a warning, setting **GCC_COMPARE_DEBUG** to **-w%n-fcompare-debug not overridden** will do.

-fcompare-debug-second

This option is implicitly passed to the compiler for the second compilation requested by **–fcompare–debug**, along with options to silence warnings, and omitting other options that would cause side-effect compiler outputs to files or to the standard output. Dump files and preserved temporary files are renamed so as to contain the .gk additional extension during the second compilation, to avoid overwriting those generated by the first.

When this option is passed to the compiler driver, it causes the *first* compilation to be skipped, which makes it useful for little other than debugging the compiler proper.

-feliminate-dwarf2-dups

Compress DWARF 2 debugging information by eliminating duplicated information about each symbol. This option only makes sense when generating DWARF 2 debugging information with **–gdwarf–2**.

-femit-struct-debug-baseonly

Emit debug information for struct-like types only when the base name of the compilation source file matches the base name of file in which the struct is defined.

This option substantially reduces the size of debugging information, but at significant potential loss in type information to the debugger. See **-femit-struct-debug-reduced** for a less aggressive option. See **-femit-struct-debug-detailed** for more detailed control.

This option works only with DWARF 2.

-femit-struct-debug-reduced

Emit debug information for struct-like types only when the base name of the compilation source file matches the base name of file in which the type is defined, unless the struct is a template or defined in a system header.

This option significantly reduces the size of debugging information, with some potential loss in type information to the debugger. See **-femit-struct-debug-baseonly** for a more aggressive option. See **-femit-struct-debug-detailed** for more detailed control.

This option works only with DWARF 2.

-femit-struct-debug-detailed[=spec-list]

Specify the struct-like types for which the compiler generates debug information. The intent is to reduce duplicate struct debug information between different object files within the same program.

This option is a detailed version of **-femit-struct-debug-reduced** and **-femit-struct-debug-baseonly**, which serves for most needs.

A specification has the syntax[dir:|ind:][ord:|gen:](any|sys|base|none)

The optional first word limits the specification to structs that are used directly (**dir:**) or used indirectly (**ind:**). A struct type is used directly when it is the type of a variable, member. Indirect uses arise

through pointers to structs. That is, when use of an incomplete struct is valid, the use is indirect. An example is **struct one direct**; **struct two** * **indirect**;

The optional second word limits the specification to ordinary structs (**ord:**) or generic structs (**gen:**). Generic structs are a bit complicated to explain. For C++, these are non-explicit specializations of template classes, or non-template classes within the above. Other programming languages have generics, but **-femit-struct-debug-detailed** does not yet implement them.

The third word specifies the source files for those structs for which the compiler should emit debug information. The values **none** and **any** have the normal meaning. The value **base** means that the base of name of the file in which the type declaration appears must match the base of the name of the main compilation file. In practice, this means that when compiling *foo.c*, debug information is generated for types declared in that file and *foo.h*, but not other header files. The value **sys** means those types satisfying **base** or declared in system or compiler headers.

You may need to experiment to determine the best settings for your application.

The default is **-femit-struct-debug-detailed=all**.

This option works only with DWARF 2.

-fno-merge-debug-strings

Direct the linker to not merge together strings in the debugging information that are identical in different object files. Merging is not supported by all assemblers or linkers. Merging decreases the size of the debug information in the output file at the cost of increasing link processing time. Merging is enabled by default.

-fdebug-prefix-map=old=new

When compiling files in directory *old*, record debugging information describing them as in *new* instead.

-fno-dwarf2-cfi-asm

Emit DWARF 2 unwind info as compiler generated .eh_frame section instead of using GAS .cfi \star directives.

-p Generate extra code to write profile information suitable for the analysis program prof. You must use this option when compiling the source files you want data about, and you must also use it when linking.

-pg

Generate extra code to write profile information suitable for the analysis program **gprof**. You must use this option when compiling the source files you want data about, and you must also use it when linking.

-Q Makes the compiler print out each function name as it is compiled, and print some statistics about each pass when it finishes.

-ftime-report

Makes the compiler print some statistics about the time consumed by each pass when it finishes.

-fmem-report

Makes the compiler print some statistics about permanent memory allocation when it finishes.

-fmem-report-wpa

Makes the compiler print some statistics about permanent memory allocation for the WPA phase only.

-fpre-ipa-mem-report

-fpost-ipa-mem-report

Makes the compiler print some statistics about permanent memory allocation before or after interprocedural optimization.

-fprofile-report

Makes the compiler print some statistics about consistency of the (estimated) profile and effect of individual passes.

-fstack-usage

Makes the compiler output stack usage information for the program, on a per-function basis. The filename for the dump is made by appending .su to the auxname. auxname is generated from the name of the output file, if explicitly specified and it is not an executable, otherwise it is the basename of the source file. An entry is made up of three fields:

- The name of the function.
- A number of bytes.
- One or more qualifiers: static, dynamic, bounded.

The qualifier static means that the function manipulates the stack statically: a fixed number of bytes are allocated for the frame on function entry and released on function exit; no stack adjustments are otherwise made in the function. The second field is this fixed number of bytes.

The qualifier dynamic means that the function manipulates the stack dynamically: in addition to the static allocation described above, stack adjustments are made in the body of the function, for example to push/pop arguments around function calls. If the qualifier bounded is also present, the amount of these adjustments is bounded at compile time and the second field is an upper bound of the total amount of stack used by the function. If it is not present, the amount of these adjustments is not bounded at compile time and the second field only represents the bounded part.

-fprofile-arcs

Add code so that program flow *arcs* are instrumented. During execution the program records how many times each branch and call is executed and how many times it is taken or returns. When the compiled program exits it saves this data to a file called *auxname.gcda* for each source file. The data may be used for profile-directed optimizations (**-fbranch-probabilities**), or for test coverage analysis (**-ftest-coverage**). Each object file's *auxname* is generated from the name of the output file, if explicitly specified and it is not the final executable, otherwise it is the basename of the source file. In both cases any suffix is removed (e.g. *foo.gcda* for input file *dir/foo.c*, or *dir/foo.gcda* for output file specified as **-o dir/foo.o**).

--coverage

This option is used to compile and link code instrumented for coverage analysis. The option is a synonym for **-fprofile-arcs -ftest-coverage** (when compiling) and **-lgcov** (when linking). See the documentation for those options for more details.

- Compile the source files with -fprofile-arcs plus optimization and code generation options. For
 test coverage analysis, use the additional -ftest-coverage option. You do not need to profile
 every source file in a program.
- Link your object files with **-lgcov** or **-fprofile-arcs** (the latter implies the former).
- Run the program on a representative workload to generate the arc profile information. This may be repeated any number of times. You can run concurrent instances of your program, and provided that the file system supports locking, the data files will be correctly updated. Also fork calls are detected and correctly handled (double counting will not happen).
- For profile-directed optimizations, compile the source files again with the same optimization and code generation options plus **–fbranch–probabilities**.
- For test coverage analysis, use **gcov** to produce human readable information from the .*gcno* and .*gcda* files. Refer to the **gcov** documentation for further information.

With **-fprofile-arcs**, for each function of your program GCC creates a program flow graph, then finds a spanning tree for the graph. Only arcs that are not on the spanning tree have to be instrumented: the compiler adds code to count the number of times that these arcs are executed. When an arc is the only exit or only entrance to a block, the instrumentation code can be added to the block; otherwise, a new basic block must be created to hold the instrumentation code.

-ftest-coverage

Produce a notes file that the **gcov** code-coverage utility can use to show program coverage. Each source file's note file is called *auxname.gcno*. Refer to the **-fprofile-arcs** option above for a description of *auxname* and instructions on how to generate test coverage data. Coverage data matches the source files more closely if you do not optimize.

-fdbg-cnt-list

Print the name and the counter upper bound for all debug counters.

-fdbg-cnt=counter-value-list

Set the internal debug counter upper bound. *counter-value-list* is a comma-separated list of *name:value* pairs which sets the upper bound of each debug counter *name* to *value*. All debug counters have the initial upper bound of UINT_MAX; thus dbg_cnt() returns true always unless the upper bound is set by this option. For example, with -fdbg-cnt=dce:10,tail_call:0, dbg_cnt(dce) returns true only for first 10 invocations.

-fenable-*kind*-*pass*

-fdisable-kind-pass=range-list

This is a set of options that are used to explicitly disable/enable optimization passes. These options are intended for use for debugging GCC. Compiler users should use regular options for enabling/disabling passes instead.

-fdisable-ipa-pass

Disable IPA pass *pass*. *pass* is the pass name. If the same pass is statically invoked in the compiler multiple times, the pass name should be appended with a sequential number starting from 1.

-fdisable-rtl-pass

-fdisable-rtl-pass=range-list

Disable RTL pass *pass*. *pass* is the pass name. If the same pass is statically invoked in the compiler multiple times, the pass name should be appended with a sequential number starting from 1. *range-list* is a comma-separated list of function ranges or assembler names. Each range is a number pair separated by a colon. The range is inclusive in both ends. If the range is trivial, the number pair can be simplified as a single number. If the function's call graph node's *uid* falls within one of the specified ranges, the *pass* is disabled for that function. The *uid* is shown in the function header of a dump file, and the pass names can be dumped by using option **-fdump-passes**.

-fdisable-tree-pass

-fdisable-tree-pass=range-list

Disable tree pass *pass*. See **-fdisable-rtl** for the description of option arguments.

-fenable-ipa-pass

Enable IPA pass *pass*. *pass* is the pass name. If the same pass is statically invoked in the compiler multiple times, the pass name should be appended with a sequential number starting from 1.

-fenable-rtl-pass

-fenable-rtl-pass=range-list

Enable RTL pass pass. See **-fdisable-rtl** for option argument description and examples.

-fenable-tree-pass

-fenable-tree-pass=range-list

Enable tree pass *pass*. See **-fdisable-rtl** for the description of option arguments.

Here are some examples showing uses of these options.

```
# disable ccp1 for all functions
    -fdisable-tree-ccp1
# disable complete unroll for function whose cgraph node uid is 1
    -fenable-tree-cunroll=1
# disable gcse2 for functions at the following ranges [1,1],
# [300,400], and [400,1000]
# disable gcse2 for functions foo and foo2
    -fdisable-rtl-gcse2=foo,foo2
# disable early inlining
    -fdisable-tree-einline
# disable ipa inlining
    -fdisable-ipa-inline
# enable tree full unroll
    -fenable-tree-unroll
```

-dletters

-fdump-rtl-pass

-fdump-rtl-pass=filename

Says to make debugging dumps during compilation at times specified by *letters*. This is used for debugging the RTL-based passes of the compiler. The file names for most of the dumps are made by appending a pass number and a word to the *dumpname*, and the files are created in the directory of the output file. In case of = filename option, the dump is output on the given file instead of the pass numbered dump files. Note that the pass number is computed statically as passes get registered into the pass manager. Thus the numbering is not related to the dynamic order of execution of passes. In particular, a pass installed by a plugin could have a number over 200 even if it executed quite early. *dumpname* is generated from the name of the output file, if explicitly specified and it is not an executable, otherwise it is the basename of the source file. These switches may have different effects when $-\mathbf{E}$ is used for preprocessing.

Debug dumps can be enabled with a **-fdump-rtl** switch or some **-d** option *letters*. Here are the possible letters for use in *pass* and *letters*, and their meanings:

-fdump-rtl-alignments

Dump after branch alignments have been computed.

-fdump-rtl-asmcons

Dump after fixing rtl statements that have unsatisfied in/out constraints.

-fdump-rtl-auto_inc_dec

Dump after auto-inc-dec discovery. This pass is only run on architectures that have auto inc or auto dec instructions.

-fdump-rtl-barriers

Dump after cleaning up the barrier instructions.

-fdump-rtl-bbpart

Dump after partitioning hot and cold basic blocks.

-fdump-rtl-bbro

Dump after block reordering.

-fdump-rtl-btl1

-fdump-rtl-btl2

-fdump-rtl-btl1 and **-fdump-rtl-btl2** enable dumping after the two branch target load optimization passes.

-fdump-rtl-bypass

Dump after jump bypassing and control flow optimizations.

-fdump-rtl-combine

Dump after the RTL instruction combination pass.

-fdump-rtl-compgotos

Dump after duplicating the computed gotos.

-fdump-rtl-ce1

-fdump-rtl-ce2

-fdump-rtl-ce3

-fdump-rtl-ce1, **-fdump-rtl-ce2**, and **-fdump-rtl-ce3** enable dumping after the three if conversion passes.

-fdump-rtl-cprop_hardreg

Dump after hard register copy propagation.

-fdump-rtl-csa

Dump after combining stack adjustments.

-fdump-rtl-cse1

-fdump-rtl-cse2

-fdump-rtl-cse1 and **-fdump-rtl-cse2** enable dumping after the two common subexpression elimination passes.

-fdump-rtl-dce

Dump after the standalone dead code elimination passes.

-fdump-rtl-dbr

Dump after delayed branch scheduling.

-fdump-rtl-dce1

-fdump-rtl-dce2

-fdump-rtl-dce1 and **-fdump-rtl-dce2** enable dumping after the two dead store elimination passes.

-fdump-rtl-eh

Dump after finalization of EH handling code.

-fdump-rtl-eh_ranges

Dump after conversion of EH handling range regions.

-fdump-rtl-expand

Dump after RTL generation.

-fdump-rtl-fwprop1

-fdump-rtl-fwprop2

-fdump-rtl-fwprop1 and **-fdump-rtl-fwprop2** enable dumping after the two forward propagation passes.

-fdump-rtl-gcse1

-fdump-rtl-gcse2

-fdump-rtl-gcse1 and **-fdump-rtl-gcse2** enable dumping after global common subexpression elimination.

-fdump-rtl-init-regs

Dump after the initialization of the registers.

-fdump-rtl-initvals

Dump after the computation of the initial value sets.

-fdump-rtl-into_cfglayout

Dump after converting to cfglayout mode.

-fdump-rtl-ira

Dump after iterated register allocation.

-fdump-rtl-jump

Dump after the second jump optimization.

-fdump-rtl-loop2

-fdump-rtl-loop2 enables dumping after the rtl loop optimization passes.

-fdump-rtl-mach

Dump after performing the machine dependent reorganization pass, if that pass exists.

-fdump-rtl-mode sw

Dump after removing redundant mode switches.

-fdump-rtl-rnreg

Dump after register renumbering.

-fdump-rtl-outof_cfglayout

Dump after converting from cfglayout mode.

-fdump-rtl-peephole2

Dump after the peephole pass.

-fdump-rtl-postreload

Dump after post-reload optimizations.

-fdump-rtl-pro_and_epilogue

Dump after generating the function prologues and epilogues.

-fdump-rtl-regmove

Dump after the register move pass.

-fdump-rtl-sched1

-fdump-rtl-sched2

-fdump-rtl-sched1 and **-fdump-rtl-sched2** enable dumping after the basic block scheduling passes.

-fdump-rtl-see

Dump after sign extension elimination.

-fdump-rtl-seqabstr

Dump after common sequence discovery.

-fdump-rtl-shorten

Dump after shortening branches.

-fdump-rtl-sibling

Dump after sibling call optimizations.

-fdump-rtl-split1

- -fdump-rtl-split2
- -fdump-rtl-split3
- -fdump-rtl-split4
- -fdump-rtl-split5

-fdump-rtl-split1, **-fdump-rtl-split2**, **-fdump-rtl-split3**, **-fdump-rtl-split4** and **-fdump-rtl-split5** enable dumping after five rounds of instruction splitting.

-fdump-rtl-sms

Dump after modulo scheduling. This pass is only run on some architectures.

-fdump-rtl-stack

Dump after conversion from GCC's "flat register file" registers to the x87's stack-like registers. This pass is only run on x86 variants.

-fdump-rtl-subreg1

-fdump-rtl-subreg2

-fdump-rtl-subreg1 and **-fdump-rtl-subreg2** enable dumping after the two subreg expansion passes.

-fdump-rtl-unshare

Dump after all rtl has been unshared.

-fdump-rtl-vartrack

Dump after variable tracking.

-fdump-rtl-vregs

Dump after converting virtual registers to hard registers.

-fdump-rtl-web

Dump after live range splitting.

- -fdump-rtl-regclass
- -fdump-rtl-subregs of mode init
- -fdump-rtl-subregs_of_mode_finish
- -fdump-rtl-dfinit
- -fdump-rtl-dfinish

These dumps are defined but always produce empty files.

-da

-fdump-rtl-all

Produce all the dumps listed above.

-dA

Annotate the assembler output with miscellaneous debugging information.

-dD

Dump all macro definitions, at the end of preprocessing, in addition to normal output.

-dH

Produce a core dump whenever an error occurs.

-dp

Annotate the assembler output with a comment indicating which pattern and alternative is used. The length of each instruction is also printed.

-dP

Dump the RTL in the assembler output as a comment before each instruction. Also turns on **-dp** annotation.

-dx

Just generate RTL for a function instead of compiling it. Usually used with **-fdump-rtl-expand**.

-fdump-noaddr

When doing debugging dumps, suppress address output. This makes it more feasible to use diff on debugging dumps for compiler invocations with different compiler binaries and/or different text / bss / data / heap / stack / dso start locations.

-fdump-unnumbered

When doing debugging dumps, suppress instruction numbers and address output. This makes it more feasible to use diff on debugging dumps for compiler invocations with different options, in particular with and without $-\mathbf{g}$.

-fdump-unnumbered-links

When doing debugging dumps (see $-\mathbf{d}$ option above), suppress instruction numbers for the links to the previous and next instructions in a sequence.

-fdump-translation-unit (C++ only)

-fdump-translation-unit-*options* (C++ only)

Dump a representation of the tree structure for the entire translation unit to a file. The file name is made by appending .tu to the source file name, and the file is created in the same directory as the output file. If the -options form is used, options controls the details of the dump as described for the -fdump-tree options.

-fdump-class-hierarchy (C++ only)

-fdump-class-hierarchy-options (C++ only)

Dump a representation of each class's hierarchy and virtual function table layout to a file. The file name is made by appending .class to the source file name, and the file is created in the same directory as the output file. If the *-options* form is used, *options* controls the details of the dump as described for the **-fdump-tree** options.

-fdump-ipa-switch

Control the dumping at various stages of inter-procedural analysis language tree to a file. The file name is generated by appending a switch specific suffix to the source file name, and the file is created in the same directory as the output file. The following dumps are possible:

all Enables all inter-procedural analysis dumps.

cgraph

Dumps information about call-graph optimization, unused function removal, and inlining decisions.

inline

Dump after function inlining.

–fdump–passes

Dump the list of optimization passes that are turned on and off by the current command-line options.

-fdump-statistics-option

Enable and control dumping of pass statistics in a separate file. The file name is generated by appending a suffix ending in **.statistics** to the source file name, and the file is created in the same directory as the output file. If the *-option* form is used, *-stats* causes counters to be summed over the whole compilation unit while *-details* dumps every event as the passes generate them. The default with no option is to sum counters for each function compiled.

-fdump-tree-switch

- -fdump-tree-switch-options
- **-fdump-tree**-*switch-options=filename*

Control the dumping at various stages of processing the intermediate language tree to a file. The file name is generated by appending a switch-specific suffix to the source file name, and the file is created in the same directory as the output file. In case of *=filename* option, the dump is output on the given file instead of the auto named dump files. If the *-options* form is used, *options* is a list of *-* separated options which control the details of the dump. Not all options are applicable to all dumps; those that are not meaningful are ignored. The following options are available

address

Print the address of each node. Usually this is not meaningful as it changes according to the environment and source file. Its primary use is for tying up a dump file with a debug environment.

asmname

If DECL_ASSEMBLER_NAME has been set for a given decl, use that in the dump instead of DECL_NAME. Its primary use is ease of use working backward from mangled names in the assembly file.

slim

When dumping front-end intermediate representations, inhibit dumping of members of a scope or body of a function merely because that scope has been reached. Only dump such items when they are directly reachable by some other path.

When dumping pretty-printed trees, this option inhibits dumping the bodies of control structures.

When dumping RTL, print the RTL in slim (condensed) form instead of the default LISP-like representation.

raw

Print a raw representation of the tree. By default, trees are pretty-printed into a C-like representation.

details

Enable more detailed dumps (not honored by every dump option). Also include information from the optimization passes.

stats

Enable dumping various statistics about the pass (not honored by every dump option).

blocks

Enable showing basic block boundaries (disabled in raw dumps).

graph

For each of the other indicated dump files (**-fdump-rtl-***pass*), dump a representation of the control flow graph suitable for viewing with GraphViz to *file.passid.pass.dot*. Each function in the file is pretty-printed as a subgraph, so that GraphViz can render them all in a single plot.

This option currently only works for RTL dumps, and the RTL is always dumped in slim form.

vops

Enable showing virtual operands for every statement.

lineno

Enable showing line numbers for statements.

uid Enable showing the unique ID (DECL_UID) for each variable.

verbose

Enable showing the tree dump for each statement.

eh Enable showing the EH region number holding each statement.

scev

Enable showing scalar evolution analysis details.

optimized

Enable showing optimization information (only available in certain passes).

missed

Enable showing missed optimization information (only available in certain passes).

notes

Enable other detailed optimization information (only available in certain passes).

=filename

Instead of an auto named dump file, output into the given file name. The file names *stdout* and *stderr* are treated specially and are considered already open standard streams. For example,

outputs vectorizer dump into *foo.dump*, while the PRE dump is output on to *stderr*. If two conflicting dump filenames are given for the same pass, then the latter option overrides the earlier one.

all Turn on all options, except raw, slim, verbose and lineno.

optall

Turn on all optimization options, i.e., **optimized**, **missed**, and **note**.

The following tree dumps are possible:

original

Dump before any tree based optimization, to file.original.

optimized

Dump after all tree based optimization, to file.optimized.

gimple

Dump each function before and after the gimplification pass to a file. The file name is made by appending *.gimple* to the source file name.

- **cfg** Dump the control flow graph of each function to a file. The file name is made by appending *.cfg* to the source file name.
- **ch** Dump each function after copying loop headers. The file name is made by appending .*ch* to the source file name.
- **ssa** Dump SSA related information to a file. The file name is made by appending .ssa to the source file name.

alias

Dump aliasing information for each function. The file name is made by appending .alias to the source file name.

ccp Dump each function after CCP. The file name is made by appending .ccp to the source file name.

storeccp

Dump each function after STORE-CCP. The file name is made by appending .storeccp to the source file name.

- **pre** Dump trees after partial redundancy elimination. The file name is made by appending .pre to the source file name.
- **fre** Dump trees after full redundancy elimination. The file name is made by appending *.fre* to the source file name.

copyprop

Dump trees after copy propagation. The file name is made by appending .copyprop to the source file name.

store_copyprop

Dump trees after store copy-propagation. The file name is made by appending .store_copyprop to the source file name.

dce Dump each function after dead code elimination. The file name is made by appending .*dce* to the source file name.

mudflap

Dump each function after adding mudflap instrumentation. The file name is made by appending .mudflap to the source file name.

sra Dump each function after performing scalar replacement of aggregates. The file name is made by appending *.sra* to the source file name.

sink

Dump each function after performing code sinking. The file name is made by appending .sink to the source file name.

dom

Dump each function after applying dominator tree optimizations. The file name is made by appending .dom to the source file name.

dse Dump each function after applying dead store elimination. The file name is made by appending .*dse* to the source file name.

phiopt

Dump each function after optimizing PHI nodes into straightline code. The file name is made by appending *phiopt* to the source file name.

forwprop

Dump each function after forward propagating single use variables. The file name is made by appending *forwprop* to the source file name.

copyrename

Dump each function after applying the copy rename optimization. The file name is made by appending .copyrename to the source file name.

nrv Dump each function after applying the named return value optimization on generic trees. The file name is made by appending *.nrv* to the source file name.

vect

Dump each function after applying vectorization of loops. The file name is made by appending .vect to the source file name.

- **slp** Dump each function after applying vectorization of basic blocks. The file name is made by appending *.slp* to the source file name.
- **vrp** Dump each function after Value Range Propagation (VRP). The file name is made by appending .*vrp* to the source file name.
- **all** Enable all the available tree dumps with the flags provided in this option.

-fopt-info

- -fopt-info-options
- -fopt-info-options=filename

Controls optimization dumps from various optimization passes. If the *-options* form is used, *options* is a list of – separated options to select the dump details and optimizations. If *options* is not specified, it defaults to **all** for details and **optall** for optimization groups. If the *filename* is not specified, it defaults to *stderr*. Note that the output *filename* will be overwritten in case of multiple translation units. If a combined output from multiple translation units is desired, *stderr* should be used instead.

The options can be divided into two groups, 1) options describing the verbosity of the dump, and 2) options describing which optimizations should be included. The options from both the groups can be freely mixed as they are non-overlapping. However, in case of any conflicts, the latter options override the earlier options on the command line. Though multiple –fopt–info options are accepted, only one of them can have **=filename**. If other filenames are provided then all but the first one are ignored.

The dump verbosity has the following options

optimized

Print information when an optimization is successfully applied. It is up to a pass to decide which information is relevant. For example, the vectorizer passes print the source location of loops which got successfully vectorized.

missed

Print information about missed optimizations. Individual passes control which information to include in the output. For example,

```
gcc -02 -ftree-vectorize -fopt-info-vec-missed
```

will print information about missed optimization opportunities from vectorization passes on stderr.

note

Print verbose information about optimizations, such as certain transformations, more detailed messages about decisions etc.

all Print detailed optimization information. This includes optimized, missed, and note.

The second set of options describes a group of optimizations and may include one or more of the following.

ipa Enable dumps from all interprocedural optimizations.

loop

Enable dumps from all loop optimizations.

inline

Enable dumps from all inlining optimizations.

vec Enable dumps from all vectorization optimizations.

For example,

outputs missed optimization report from all the passes into missed.all.

As another example,

will output information about missed optimizations as well as optimized locations from all the inlining passes into *inline.txt*.

If the *filename* is provided, then the dumps from all the applicable optimizations are concatenated into the *filename*. Otherwise the dump is output onto *stderr*. If *options* is omitted, it defaults to **all-optall**, which means dump all available optimization info from all the passes. In the following example, all optimization info is output on to *stderr*.

Note that **-fopt-info-vec-missed** behaves the same as **-fopt-info-missed-vec**.

As another example, consider

```
gcc -fopt-info-vec-missed=vec.miss -fopt-info-loop-optimized=loop.opt
```

Here the two output filenames *vec.miss* and *loop.opt* are in conflict since only one output file is allowed. In this case, only the first option takes effect and the subsequent options are ignored. Thus only the *vec.miss* is produced which cotaints dumps from the vectorizer about missed opportunities.

-ftree-vectorizer-verbose=n

This option is deprecated and is implemented in terms of **-fopt-info**. Please use **-fopt-info**-kind form instead, where kind is one of the valid opt-info options. It prints additional optimization information. For n=0 no diagnostic information is reported. If n=1 the vectorizer reports each loop that got vectorized, and the total number of loops that got vectorized. If n=2 the vectorizer reports locations which could not be vectorized and the reasons for those. For any higher verbosity levels all the analysis and transformation information from the vectorizer is reported.

Note that the information output by **-ftree-vectorizer-verbose** option is sent to *stderr*. If the equivalent form **-fopt-info-***options=filename* is used then the output is sent into *filename* instead.

-frandom-seed=string

This option provides a seed that GCC uses in place of random numbers in generating certain symbol names that have to be different in every compiled file. It is also used to place unique stamps in coverage data files and the object files that produce them. You can use the **-frandom-seed** option to produce reproducibly identical object files.

The string should be different for every file you compile.

-fsched-verbose=n

On targets that use instruction scheduling, this option controls the amount of debugging output the scheduler prints. This information is written to standard error, unless **-fdump-rtl-sched1** or **-fdump-rtl-sched2** is specified, in which case it is output to the usual dump listing file, *.sched1* or *.sched2* respectively. However for *n* greater than nine, the output is always printed to standard error.

For *n* greater than zero, **-fsched-verbose** outputs the same information as **-fdump-rtl-sched1** and **-fdump-rtl-sched2**. For *n* greater than one, it also output basic block probabilities, detailed ready list information and unit/insn info. For *n* greater than two, it includes RTL at abort point, control-flow and regions info. And for *n* over four, **-fsched-verbose** also includes dependence info.

-save-temps

-save-temps=cwd

Store the usual "temporary" intermediate files permanently; place them in the current directory and name them based on the source file. Thus, compiling foo.c with $-\mathbf{c}$ —save—temps produces files foo.i and foo.s, as well as foo.o. This creates a preprocessed foo.i output file even though the compiler now normally uses an integrated preprocessor.

When used in combination with the $-\mathbf{x}$ command-line option, $-\mathbf{save-temps}$ is sensible enough to avoid over writing an input source file with the same extension as an intermediate file. The corresponding intermediate file may be obtained by renaming the source file before using $-\mathbf{save-temps}$.

If you invoke GCC in parallel, compiling several different source files that share a common base name in different subdirectories or the same source file compiled for multiple output destinations, it is likely that the different parallel compilers will interfere with each other, and overwrite the temporary files. For instance:

```
gcc -save-temps -o outdir1/foo.o indir1/foo.c&
gcc -save-temps -o outdir2/foo.o indir2/foo.c&
```

may result in foo.i and foo.o being written to simultaneously by both compilers.

-save-temps=obj

Store the usual "temporary" intermediate files permanently. If the $-\mathbf{o}$ option is used, the temporary files are based on the object file. If the $-\mathbf{o}$ option is not used, the $-\mathbf{save-temps=obj}$ switch behaves like $-\mathbf{save-temps}$.

For example:

```
gcc -save-temps=obj -c foo.c
gcc -save-temps=obj -c bar.c -o dir/xbar.o
gcc -save-temps=obj foobar.c -o dir2/yfoobar
```

creates foo.i, foo.s, dir/xbar.i, dir/xbar.s, dir2/yfoobar.i, dir2/yfoobar.s, and dir2/yfoobar.o.

–time[=*file*]

Report the CPU time taken by each subprocess in the compilation sequence. For C source files, this is the compiler proper and assembler (plus the linker if linking is done).

Without the specification of an output file, the output looks like this:

```
# cc1 0.12 0.01
# as 0.00 0.01
```

The first number on each line is the "user time", that is time spent executing the program itself. The second number is "system time", time spent executing operating system routines on behalf of the program. Both numbers are in seconds.

With the specification of an output file, the output is appended to the named file, and it looks like this:

```
0.12 0.01 cc1 <options>
0.00 0.01 as <options>
```

The "user time" and the "system time" are moved before the program name, and the options passed to the program are displayed, so that one can later tell what file was being compiled, and with which options.

-fvar-tracking

Run variable tracking pass. It computes where variables are stored at each position in code. Better debugging information is then generated (if the debugging information format supports this information).

It is enabled by default when compiling with optimization ($-\mathbf{Os}$, $-\mathbf{O}$, $-\mathbf{O2}$, ...), debugging information ($-\mathbf{g}$) and the debug info format supports it.

-fvar-tracking-assignments

Annotate assignments to user variables early in the compilation and attempt to carry the annotations over throughout the compilation all the way to the end, in an attempt to improve debug information while optimizing. Use of **-gdwarf-4** is recommended along with it.

It can be enabled even if var-tracking is disabled, in which case annotations are created and maintained, but discarded at the end.

-fvar-tracking-assignments-toggle

Toggle **-fvar-tracking-assignments**, in the same way that **-gtoggle** toggles **-g**.

-print-file-name=library

Print the full absolute name of the library file *library* that would be used when linking——and don't do anything else. With this option, GCC does not compile or link anything; it just prints the file name.

-print-multi-directory

Print the directory name corresponding to the multilib selected by any other switches present in the command line. This directory is supposed to exist in GCC_EXEC_PREFIX.

-print-multi-lib

Print the mapping from multilib directory names to compiler switches that enable them. The directory name is separated from the switches by ;, and each switch starts with an @ instead of the –, without spaces between multiple switches. This is supposed to ease shell processing.

-print-multi-os-directory

Print the path to OS libraries for the selected multilib, relative to some *lib* subdirectory. If OS libraries are present in the *lib* subdirectory and no multilibs are used, this is usually just., if OS libraries are present in *libsuffix* sibling directories this prints e.g. ../lib64, ../lib or ../lib32, or if OS libraries are present in *lib/subdir* subdirectories it prints e.g. amd64, sparcv9 or ev6.

-print-multiarch

Print the path to OS libraries for the selected multiarch, relative to some *lib* subdirectory.

-print-prog-name=program

Like **-print-file-name**, but searches for a program such as **cpp**.

-print-libgcc-file-name

Same as -print-file-name=libgcc.a.

This is useful when you use **-nostdlib** or **-nodefaultlibs** but you do want to link with *libgcc.a*. You can do:

```
gcc -nostdlib <files>... `gcc -print-libgcc-file-name`
```

-print-search-dirs

Print the name of the configured installation directory and a list of program and library directories **gcc** searches——and don't do anything else.

This is useful when gcc prints the error message installation problem, cannot exec cpp0: No such

file or directory. To resolve this you either need to put *cpp0* and the other compiler components where **gcc** expects to find them, or you can set the environment variable **GCC_EXEC_PREFIX** to the directory where you installed them. Don't forget the trailing /.

-print-sysroot

Print the target sysroot directory that is used during compilation. This is the target sysroot specified either at configure time or using the —sysroot option, possibly with an extra suffix that depends on compilation options. If no target sysroot is specified, the option prints nothing.

-print-sysroot-headers-suffix

Print the suffix added to the target sysroot when searching for headers, or give an error if the compiler is not configured with such a suffix——and don't do anything else.

-dumpmachine

Print the compiler's target machine (for example, i686-pc-linux-gnu)---and don't do anything else.

-dumpversion

Print the compiler version (for example, 3.0)——and don't do anything else.

-dumpspecs

Print the compiler's built-in specs——and don't do anything else. (This is used when GCC itself is being built.)

-fno-eliminate-unused-debug-types

Normally, when producing DWARF 2 output, GCC avoids producing debug symbol output for types that are nowhere used in the source file being compiled. Sometimes it is useful to have GCC emit debugging information for all types declared in a compilation unit, regardless of whether or not they are actually used in that compilation unit, for example if, in the debugger, you want to cast a value to a type that is not actually used in your program (but is declared). More often, however, this results in a significant amount of wasted space.

Options That Control Optimization

These options control various sorts of optimizations.

Without any optimization option, the compiler's goal is to reduce the cost of compilation and to make debugging produce the expected results. Statements are independent: if you stop the program with a breakpoint between statements, you can then assign a new value to any variable or change the program counter to any other statement in the function and get exactly the results you expect from the source code.

Turning on optimization flags makes the compiler attempt to improve the performance and/or code size at the expense of compilation time and possibly the ability to debug the program.

The compiler performs optimization based on the knowledge it has of the program. Compiling multiple files at once to a single output file mode allows the compiler to use information gained from all of the files when compiling each of them.

Not all optimizations are controlled directly by a flag. Only optimizations that have a flag are listed in this section.

Most optimizations are only enabled if an **-O** level is set on the command line. Otherwise they are disabled, even if individual optimization flags are specified.

Depending on the target and how GCC was configured, a slightly different set of optimizations may be enabled at each $-\mathbf{O}$ level than those listed here. You can invoke GCC with $-\mathbf{Q}$ —help=optimizers to find out the exact set of optimizations that are enabled at each level.

-O -O1

Optimize. Optimizing compilation takes somewhat more time, and a lot more memory for a large function.

With **–O**, the compiler tries to reduce code size and execution time, without performing any optimizations that take a great deal of compilation time.

- **-O** turns on the following optimization flags:
- -fauto-inc-dec -fcompare-elim -fcprop-registers -fdce -fdefer-pop -fdelayed-branch -fdse -fguess-branch-probability -fif-conversion2 -fif-conversion -fipa-pure-const -fipa-profile -fipa-reference -fmerge-constants -fsplit-wide-types -ftree-bit-ccp -ftree-builtin-call-dce -ftree-ccp -ftree-ch -ftree-copyrename -ftree-dce -ftree-dominator-opts -ftree-dse -ftree-forwprop -ftree-fre -ftree-phiprop -ftree-slsr -ftree-sra -ftree-pta -ftree-ter -funit-at-a-time
- **-O** also turns on **-fomit-frame-pointer** on machines where doing so does not interfere with debugging.

-02

Optimize even more. GCC performs nearly all supported optimizations that do not involve a space-speed tradeoff. As compared to $-\mathbf{O}$, this option increases both compilation time and the performance of the generated code.

-O2 turns on all optimization flags specified by -O. It also turns on the following optimization flags: -fthread-jumps -falign-functions -falign-jumps -falign-loops -falign-labels -fcaller-saves -fcrossjumping -fcse-follow-jumps -fcse-skip-blocks -fdelete-null-pointer-checks -fdevirtualize -fexpensive-optimizations -fgcse -fgcse-lm -fhoist-adjacent-loads -finline-small-functions -findirect-inlining -fipa-sra -foptimize-sibling-calls -freorder-blocks -freorder-functions -fpartial-inlining -fpeephole2 -fregmove -frerun-cse-after-loop -fsched-interblock -fsched-spec -fschedule-insns -fschedule-insns2 -fstrict-aliasing -fstrict-overflow -ftree-switch-conversion -ftree-tail-merge -ftree-pre -ftree-vrp

Please note the warning under **-fgcse** about invoking **-O2** on programs that use computed gotos.

NOTE: In Ubuntu 8.10 and later versions, **-D_FORTIFY_SOURCE=2** is set by default, and is activated when **-O** is set to 2 or higher. This enables additional compile-time and run-time checks for several libc functions. To disable, specify either **-U_FORTIFY_SOURCE** or **-D_FORTIFY_SOURCE=0**.

-03

Optimize yet more. -O3 turns on all optimizations specified by -O2 and also turns on the -finline-functions, -funswitch-loops, -fpredictive-commoning, -fgcse-after-reload, -ftree-vectorize, -fvect-cost-model, -ftree-partial-pre and -fipa-cp-clone options.

-O0

Reduce compilation time and make debugging produce the expected results. This is the default.

-Os

Optimize for size. **-Os** enables all **-O2** optimizations that do not typically increase code size. It also performs further optimizations designed to reduce code size.

Os disables the following optimization flags: -falign-functions -falign-jumps -falign-loops
 -falign-labels -freorder-blocks -freorder-blocks-and-partition -fprefetch-loop-arrays
 -ftree-vect-loop-version

-Ofast

Disregard strict standards compliance. **–Ofast** enables all **–O3** optimizations. It also enables optimizations that are not valid for all standard-compliant programs. It turns on **–ffast–math** and the Fortran-specific **–fno–protect–parens** and **–fstack–arrays**.

-Og

Optimize debugging experience. **Og** enables optimizations that do not interfere with debugging. It should be the optimization level of choice for the standard edit-compile-debug cycle, offering a reasonable level of optimization while maintaining fast compilation and a good debugging experience.

If you use multiple $-\mathbf{O}$ options, with or without level numbers, the last such option is the one that is effective.

Options of the form -**f** flag specify machine-independent flags. Most flags have both positive and negative forms; the negative form of -**ffoo** is -**fno-foo**. In the table below, only one of the forms is listed——the one you typically use. You can figure out the other form by either removing **no**— or adding it.

The following options control specific optimizations. They are either activated by $-\mathbf{O}$ options or are related to ones that are. You can use the following flags in the rare cases when "fine-tuning" of optimizations to be performed is desired.

-fno-default-inline

Do not make member functions inline by default merely because they are defined inside the class scope (C⁺⁺ only). Otherwise, when you specify **–O**, member functions defined inside class scope are compiled inline by default; i.e., you don't need to add **inline** in front of the member function name.

-fno-defer-pop

Always pop the arguments to each function call as soon as that function returns. For machines that must pop arguments after a function call, the compiler normally lets arguments accumulate on the stack for several function calls and pops them all at once.

Disabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fforward-propagate

Perform a forward propagation pass on RTL. The pass tries to combine two instructions and checks if the result can be simplified. If loop unrolling is active, two passes are performed and the second is scheduled after loop unrolling.

This option is enabled by default at optimization levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-ffp-contract=style

-ffp-contract=off disables floating-point expression contraction. **-ffp-contract=fast** enables floating-point expression contraction such as forming of fused multiply-add operations if the target has native support for them. **-ffp-contract=on** enables floating-point expression contraction if allowed by the language standard. This is currently not implemented and treated equal to **-ffp-contract=off**.

The default is **-ffp-contract=fast**.

-fomit-frame-pointer

Don't keep the frame pointer in a register for functions that don't need one. This avoids the instructions to save, set up and restore frame pointers; it also makes an extra register available in many functions. It also makes debugging impossible on some machines.

On some machines, such as the VAX, this flag has no effect, because the standard calling sequence automatically handles the frame pointer and nothing is saved by pretending it doesn't exist. The machine-description macro FRAME_POINTER_REQUIRED controls whether a target machine supports this flag.

Starting with GCC version 4.6, the default setting (when not optimizing for size) for 32-bit GNU/Linux x86 and 32-bit Darwin x86 targets has been changed to **-fomit-frame-pointer**. The default can be reverted to **-fno-omit-frame-pointer** by configuring GCC with the **--enable-frame-pointer** configure option.

Enabled at levels -O, -O2, -O3, -Os.

-foptimize-sibling-calls

Optimize sibling and tail recursive calls.

Enabled at levels -O2, -O3, -Os.

-fno-inline

Do not expand any functions inline apart from those marked with the always_inline attribute. This is the default when not optimizing.

Single functions can be exempted from inlining by marking them with the noinline attribute.

-finline-small-functions

Integrate functions into their callers when their body is smaller than expected function call code (so overall size of program gets smaller). The compiler heuristically decides which functions are simple enough to be worth integrating in this way. This inlining applies to all functions, even those not declared inline.

Enabled at level -O2.

-findirect-inlining

Inline also indirect calls that are discovered to be known at compile time thanks to previous inlining. This option has any effect only when inlining itself is turned on by the **-finline-functions** or **-finline-small-functions** options.

Enabled at level **-O2**.

-finline-functions

Consider all functions for inlining, even if they are not declared inline. The compiler heuristically decides which functions are worth integrating in this way.

If all calls to a given function are integrated, and the function is declared static, then the function is normally not output as assembler code in its own right.

Enabled at level **–O3**.

-finline-functions-called-once

Consider all static functions called once for inlining into their caller even if they are not marked inline. If a call to a given function is integrated, then the function is not output as assembler code in its own right.

Enabled at levels $-\mathbf{O1}$, $-\mathbf{O2}$, $-\mathbf{O3}$ and $-\mathbf{Os}$.

-fearly-inlining

Inline functions marked by always_inline and functions whose body seems smaller than the function call overhead early before doing **-fprofile-generate** instrumentation and real inlining pass. Doing so makes profiling significantly cheaper and usually inlining faster on programs having large chains of nested wrapper functions.

Enabled by default.

-fipa-sra

Perform interprocedural scalar replacement of aggregates, removal of unused parameters and replacement of parameters passed by reference by parameters passed by value.

Enabled at levels **–O2**, **–O3** and **–Os**.

-finline-limit=n

By default, GCC limits the size of functions that can be inlined. This flag allows coarse control of this limit. *n* is the size of functions that can be inlined in number of pseudo instructions.

Inlining is actually controlled by a number of parameters, which may be specified individually by using **—param** *name=value*. The **—finline—limit=***n* option sets some of these parameters as follows:

max-inline-insns-single

is set to n/2.

max-inline-insns-auto

is set to n/2.

See below for a documentation of the individual parameters controlling inlining and for the defaults of these parameters.

Note: there may be no value to **-finline-limit** that results in default behavior.

Note: pseudo instruction represents, in this particular context, an abstract measurement of function's size. In no way does it represent a count of assembly instructions and as such its exact meaning might

change from one release to an another.

-fno-keep-inline-dllexport

This is a more fine-grained version of **-fkeep-inline-functions**, which applies only to functions that are declared using the dllexport attribute or declspec

-fkeep-inline-functions

In C, emit static functions that are declared inline into the object file, even if the function has been inlined into all of its callers. This switch does not affect functions using the extern inline extension in GNU C90. In C++, emit any and all inline functions into the object file.

-fkeep-static-consts

Emit variables declared static const when optimization isn't turned on, even if the variables aren't referenced.

GCC enables this option by default. If you want to force the compiler to check if a variable is referenced, regardless of whether or not optimization is turned on, use the **-fno-keep-static-consts** option.

-fmerge-constants

Attempt to merge identical constants (string constants and floating-point constants) across compilation units.

This option is the default for optimized compilation if the assembler and linker support it. Use **-fno-merge-constants** to inhibit this behavior.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fmerge-all-constants

Attempt to merge identical constants and identical variables.

This option implies **–fmerge–constants**. In addition to **–fmerge–constants** this considers e.g. even constant initialized arrays or initialized constant variables with integral or floating-point types. Languages like C or C++ require each variable, including multiple instances of the same variable in recursive calls, to have distinct locations, so using this option results in non-conforming behavior.

-fmodulo-sched

Perform swing modulo scheduling immediately before the first scheduling pass. This pass looks at innermost loops and reorders their instructions by overlapping different iterations.

-fmodulo-sched-allow-regmoves

Perform more aggressive SMS-based modulo scheduling with register moves allowed. By setting this flag certain anti-dependences edges are deleted, which triggers the generation of reg-moves based on the life-range analysis. This option is effective only with **-fmodulo-sched** enabled.

-fno-branch-count-reg

Do not use "decrement and branch" instructions on a count register, but instead generate a sequence of instructions that decrement a register, compare it against zero, then branch based upon the result. This option is only meaningful on architectures that support such instructions, which include x86, PowerPC, IA–64 and S/390.

The default is **-fbranch-count-reg**.

-fno-function-cse

Do not put function addresses in registers; make each instruction that calls a constant function contain the function's address explicitly.

This option results in less efficient code, but some strange hacks that alter the assembler output may be confused by the optimizations performed when this option is not used.

The default is **-ffunction-cse**

-fno-zero-initialized-in-bss

If the target supports a BSS section, GCC by default puts variables that are initialized to zero into BSS. This can save space in the resulting code.

This option turns off this behavior because some programs explicitly rely on variables going to the data section——e.g., so that the resulting executable can find the beginning of that section and/or make assumptions based on that.

The default is **-fzero-initialized-in-bss**.

-fmudflap -fmudflapth -fmudflapir

For front-ends that support it (C and C++), instrument all risky pointer/array dereferencing operations, some standard library string/heap functions, and some other associated constructs with range/validity tests. Modules so instrumented should be immune to buffer overflows, invalid heap use, and some other classes of C/C++ programming errors. The instrumentation relies on a separate runtime library (libmudflap), which is linked into a program if **-fmudflap** is given at link time. Run-time behavior of the instrumented program is controlled by the **MUDFLAP_OPTIONS** environment variable. See env MUDFLAP_OPTIONS=-help a.out for its options.

Use **–fmudflapth** instead of **–fmudflap** to compile and to link if your program is multi-threaded. Use **–fmudflapir**, in addition to **–fmudflap** or **–fmudflapth**, if instrumentation should ignore pointer reads. This produces less instrumentation (and therefore faster execution) and still provides some protection against outright memory corrupting writes, but allows erroneously read data to propagate within a program.

-fthread-jumps

Perform optimizations that check to see if a jump branches to a location where another comparison subsumed by the first is found. If so, the first branch is redirected to either the destination of the second branch or a point immediately following it, depending on whether the condition is known to be true or false.

Enabled at levels **-O2**, **-O3**, **-Os**.

-fsplit-wide-types

When using a type that occupies multiple registers, such as long long on a 32-bit system, split the registers apart and allocate them independently. This normally generates better code for those types, but may make debugging more difficult.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fcse-follow-jumps

In common subexpression elimination (CSE), scan through jump instructions when the target of the jump is not reached by any other path. For example, when CSE encounters an if statement with an else clause, CSE follows the jump when the condition tested is false.

Enabled at levels -O2, -O3, -Os.

-fcse-skip-blocks

This is similar to **-fcse-follow-jumps**, but causes CSE to follow jumps that conditionally skip over blocks. When CSE encounters a simple if statement with no else clause, **-fcse-skip-blocks** causes CSE to follow the jump around the body of the if.

Enabled at levels **–O2**, **–O3**, **–Os**.

-frerun-cse-after-loop

Re-run common subexpression elimination after loop optimizations are performed.

Enabled at levels -O2, -O3, -Os.

-fgcse

Perform a global common subexpression elimination pass. This pass also performs global constant and copy propagation.

Note: When compiling a program using computed gotos, a GCC extension, you may get better runtime performance if you disable the global common subexpression elimination pass by adding **-fno-gcse** to the command line.

Enabled at levels **–O2**, **–O3**, **–Os**.

-fgcse-lm

When **-fgcse-lm** is enabled, global common subexpression elimination attempts to move loads that are only killed by stores into themselves. This allows a loop containing a load/store sequence to be changed to a load outside the loop, and a copy/store within the loop.

Enabled by default when **-fgcse** is enabled.

-fgcse-sm

When **-fgcse-sm** is enabled, a store motion pass is run after global common subexpression elimination. This pass attempts to move stores out of loops. When used in conjunction with **-fgcse-lm**, loops containing a load/store sequence can be changed to a load before the loop and a store after the loop.

Not enabled at any optimization level.

-fgcse-las

When **–fgcse–las** is enabled, the global common subexpression elimination pass eliminates redundant loads that come after stores to the same memory location (both partial and full redundancies).

Not enabled at any optimization level.

-fgcse-after-reload

When **-fgcse-after-reload** is enabled, a redundant load elimination pass is performed after reload. The purpose of this pass is to clean up redundant spilling.

-faggressive-loop-optimizations

This option tells the loop optimizer to use language constraints to derive bounds for the number of iterations of a loop. This assumes that loop code does not invoke undefined behavior by for example causing signed integer overflows or out-of-bound array accesses. The bounds for the number of iterations of a loop are used to guide loop unrolling and peeling and loop exit test optimizations. This option is enabled by default.

-funsafe-loop-optimizations

This option tells the loop optimizer to assume that loop indices do not overflow, and that loops with nontrivial exit condition are not infinite. This enables a wider range of loop optimizations even if the loop optimizer itself cannot prove that these assumptions are valid. If you use **-Wunsafe-loop-optimizations**, the compiler warns you if it finds this kind of loop.

-fcrossjumping

Perform cross-jumping transformation. This transformation unifies equivalent code and saves code size. The resulting code may or may not perform better than without cross-jumping.

Enabled at levels -O2, -O3, -Os.

-fauto-inc-dec

Combine increments or decrements of addresses with memory accesses. This pass is always skipped on architectures that do not have instructions to support this. Enabled by default at $-\mathbf{O}$ and higher on architectures that support this.

-fdce

Perform dead code elimination (DCE) on RTL. Enabled by default at **-O** and higher.

-fdse

Perform dead store elimination (DSE) on RTL. Enabled by default at **-O** and higher.

-fif-conversion

Attempt to transform conditional jumps into branch-less equivalents. This includes use of conditional moves, min, max, set flags and abs instructions, and some tricks doable by standard arithmetics. The

use of conditional execution on chips where it is available is controlled by if-conversion2.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fif-conversion2

Use conditional execution (where available) to transform conditional jumps into branch-less equivalents.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fdelete-null-pointer-checks

Assume that programs cannot safely dereference null pointers, and that no code or data element resides there. This enables simple constant folding optimizations at all optimization levels. In addition, other optimization passes in GCC use this flag to control global dataflow analyses that eliminate useless checks for null pointers; these assume that if a pointer is checked after it has already been dereferenced, it cannot be null.

Note however that in some environments this assumption is not true. Use **-fno-delete-null-pointer-checks** to disable this optimization for programs that depend on that behavior.

Some targets, especially embedded ones, disable this option at all levels. Otherwise it is enabled at all levels: $-\mathbf{O0}$, $-\mathbf{O1}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$. Passes that use the information are enabled independently at different optimization levels.

-fdevirtualize

Attempt to convert calls to virtual functions to direct calls. This is done both within a procedure and interprocedurally as part of indirect inlining (-findirect-inlining) and interprocedural constant propagation (-fipa-cp). Enabled at levels -O2, -O3, -Os.

-fexpensive-optimizations

Perform a number of minor optimizations that are relatively expensive.

Enabled at levels -O2, -O3, -Os.

-free

Attempt to remove redundant extension instructions. This is especially helpful for the x86–64 architecture, which implicitly zero-extends in 64-bit registers after writing to their lower 32-bit half.

Enabled for x86 at levels -02, -03.

-foptimize-register-move

-fregmove

Attempt to reassign register numbers in move instructions and as operands of other simple instructions in order to maximize the amount of register tying. This is especially helpful on machines with two-operand instructions.

Note **-fregmove** and **-foptimize-register-move** are the same optimization.

Enabled at levels -O2, -O3, -Os.

-fira-algorithm=algorithm

Use the specified coloring algorithm for the integrated register allocator. The *algorithm* argument can be **priority**, which specifies Chow's priority coloring, or **CB**, which specifies Chaitin-Briggs coloring. Chaitin-Briggs coloring is not implemented for all architectures, but for those targets that do support it, it is the default because it generates better code.

-fira-region=region

Use specified regions for the integrated register allocator. The *region* argument should be one of the following:

all Use all loops as register allocation regions. This can give the best results for machines with a small and/or irregular register set.

mixed

Use all loops except for loops with small register pressure as the regions. This value usually gives the best results in most cases and for most architectures, and is enabled by default when compiling with optimization for speed (-0, -02, ...).

one Use all functions as a single region. This typically results in the smallest code size, and is enabled by default for -Os or -O0.

-fira-hoist-pressure

Use IRA to evaluate register pressure in the code hoisting pass for decisions to hoist expressions. This option usually results in smaller code, but it can slow the compiler down.

This option is enabled at level **–Os** for all targets.

-fira-loop-pressure

Use IRA to evaluate register pressure in loops for decisions to move loop invariants. This option usually results in generation of faster and smaller code on machines with large register files (>= 32 registers), but it can slow the compiler down.

This option is enabled at level **–O3** for some targets.

-fno-ira-share-save-slots

Disable sharing of stack slots used for saving call-used hard registers living through a call. Each hard register gets a separate stack slot, and as a result function stack frames are larger.

-fno-ira-share-spill-slots

Disable sharing of stack slots allocated for pseudo-registers. Each pseudo-register that does not get a hard register gets a separate stack slot, and as a result function stack frames are larger.

-fira-verbose=n

Control the verbosity of the dump file for the integrated register allocator. The default value is 5. If the value n is greater or equal to 10, the dump output is sent to stderr using the same format as n minus 10

-fdelayed-branch

If supported for the target machine, attempt to reorder instructions to exploit instruction slots available after delayed branch instructions.

Enabled at levels -O, -O2, -O3, -Os.

-fschedule-insns

If supported for the target machine, attempt to reorder instructions to eliminate execution stalls due to required data being unavailable. This helps machines that have slow floating point or memory load instructions by allowing other instructions to be issued until the result of the load or floating-point instruction is required.

Enabled at levels **-O2**, **-O3**.

-fschedule-insns2

Similar to **-fschedule-insns**, but requests an additional pass of instruction scheduling after register allocation has been done. This is especially useful on machines with a relatively small number of registers and where memory load instructions take more than one cycle.

Enabled at levels **–O2**, **–O3**, **–Os**.

-fno-sched-interblock

Don't schedule instructions across basic blocks. This is normally enabled by default when scheduling before register allocation, i.e. with **-fschedule-insns** or at **-O2** or higher.

-fno-sched-spec

Don't allow speculative motion of non-load instructions. This is normally enabled by default when scheduling before register allocation, i.e. with -fschedule-insns or at -O2 or higher.

-fsched-pressure

Enable register pressure sensitive insn scheduling before register allocation. This only makes sense when scheduling before register allocation is enabled, i.e. with **-fschedule-insns** or at **-O2** or higher. Usage of this option can improve the generated code and decrease its size by preventing register pressure increase above the number of available hard registers and subsequent spills in register allocation.

-fsched-spec-load

Allow speculative motion of some load instructions. This only makes sense when scheduling before register allocation, i.e. with **-fschedule-insns** or at **-O2** or higher.

-fsched-spec-load-dangerous

Allow speculative motion of more load instructions. This only makes sense when scheduling before register allocation, i.e. with **-fschedule-insns** or at **-O2** or higher.

-fsched-stalled-insns

-fsched-stalled-insns=n

Define how many insns (if any) can be moved prematurely from the queue of stalled insns into the ready list during the second scheduling pass. **-fno-sched-stalled-insns** means that no insns are moved prematurely, **-fsched-stalled-insns=0** means there is no limit on how many queued insns can be moved prematurely. **-fsched-stalled-insns** without a value is equivalent to **-fsched-stalled-insns=1**.

-fsched-stalled-insns-dep

-fsched-stalled-insns-dep=n

Define how many insn groups (cycles) are examined for a dependency on a stalled insn that is a candidate for premature removal from the queue of stalled insns. This has an effect only during the second scheduling pass, and only if **-fsched-stalled-insns** is used. **-fno-sched-stalled-insns-dep** is equivalent to **-fsched-stalled-insns-dep=0**. **-fsched-stalled-insns-dep** without a value is equivalent to **-fsched-stalled-insns-dep=1**.

-fsched2-use-superblocks

When scheduling after register allocation, use superblock scheduling. This allows motion across basic block boundaries, resulting in faster schedules. This option is experimental, as not all machine descriptions used by GCC model the CPU closely enough to avoid unreliable results from the algorithm.

This only makes sense when scheduling after register allocation, i.e. with **-fschedule-insns2** or at **-O2** or higher.

-fsched-group-heuristic

Enable the group heuristic in the scheduler. This heuristic favors the instruction that belongs to a schedule group. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-fsched-critical-path-heuristic

Enable the critical-path heuristic in the scheduler. This heuristic favors instructions on the critical path. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-fsched-spec-insn-heuristic

Enable the speculative instruction heuristic in the scheduler. This heuristic favors speculative instructions with greater dependency weakness. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-fsched-rank-heuristic

Enable the rank heuristic in the scheduler. This heuristic favors the instruction belonging to a basic block with greater size or frequency. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-fsched-last-insn-heuristic

Enable the last-instruction heuristic in the scheduler. This heuristic favors the instruction that is less dependent on the last instruction scheduled. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-fsched-dep-count-heuristic

Enable the dependent-count heuristic in the scheduler. This heuristic favors the instruction that has more instructions depending on it. This is enabled by default when scheduling is enabled, i.e. with **-fschedule-insns** or **-fschedule-insns2** or at **-O2** or higher.

-freschedule-modulo-scheduled-loops

Modulo scheduling is performed before traditional scheduling. If a loop is modulo scheduled, later scheduling passes may change its schedule. Use this option to control that behavior.

-fselective-scheduling

Schedule instructions using selective scheduling algorithm. Selective scheduling runs instead of the first scheduler pass.

-fselective-scheduling2

Schedule instructions using selective scheduling algorithm. Selective scheduling runs instead of the second scheduler pass.

-fsel-sched-pipelining

Enable software pipelining of innermost loops during selective scheduling. This option has no effect unless one of **–fselective–scheduling** or **–fselective–scheduling2** is turned on.

-fsel-sched-pipelining-outer-loops

When pipelining loops during selective scheduling, also pipeline outer loops. This option has no effect unless **–fsel–sched–pipelining** is turned on.

-fshrink-wrap

Emit function prologues only before parts of the function that need it, rather than at the top of the function. This flag is enabled by default at $-\mathbf{O}$ and higher.

-fcaller-saves

Enable allocation of values to registers that are clobbered by function calls, by emitting extra instructions to save and restore the registers around such calls. Such allocation is done only when it seems to result in better code.

This option is always enabled by default on certain machines, usually those which have no call-preserved registers to use instead.

Enabled at levels **-O2**, **-O3**, **-Os**.

-fcombine-stack-adjustments

Tracks stack adjustments (pushes and pops) and stack memory references and then tries to find ways to combine them.

Enabled by default at -O1 and higher.

-fconserve-stack

Attempt to minimize stack usage. The compiler attempts to use less stack space, even if that makes the program slower. This option implies setting the **large-stack-frame** parameter to 100 and the **large-stack-frame-growth** parameter to 400.

-ftree-reassoc

Perform reassociation on trees. This flag is enabled by default at **-O** and higher.

–ftree–pre

Perform partial redundancy elimination (PRE) on trees. This flag is enabled by default at $-\mathbf{O2}$ and $-\mathbf{O3}$.

-ftree-partial-pre

Make partial redundancy elimination (PRE) more aggressive. This flag is enabled by default at -03.

-ftree-forwprop

Perform forward propagation on trees. This flag is enabled by default at **-O** and higher.

-ftree-fre

Perform full redundancy elimination (FRE) on trees. The difference between FRE and PRE is that FRE only considers expressions that are computed on all paths leading to the redundant computation. This analysis is faster than PRE, though it exposes fewer redundancies. This flag is enabled by default at **–O** and higher.

-ftree-phiprop

Perform hoisting of loads from conditional pointers on trees. This pass is enabled by default at **-O** and higher.

-fhoist-adjacent-loads

Speculatively hoist loads from both branches of an if-then-else if the loads are from adjacent locations in the same structure and the target architecture has a conditional move instruction. This flag is enabled by default at $-\mathbf{O2}$ and higher.

-ftree-copy-prop

Perform copy propagation on trees. This pass eliminates unnecessary copy operations. This flag is enabled by default at $-\mathbf{O}$ and higher.

-fipa-pure-const

Discover which functions are pure or constant. Enabled by default at **-O** and higher.

-fipa-reference

Discover which static variables do not escape the compilation unit. Enabled by default at $-\mathbf{0}$ and higher.

-fipa-pta

Perform interprocedural pointer analysis and interprocedural modification and reference analysis. This option can cause excessive memory and compile-time usage on large compilation units. It is not enabled by default at any optimization level.

-fipa-profile

Perform interprocedural profile propagation. The functions called only from cold functions are marked as cold. Also functions executed once (such as cold, noreturn, static constructors or destructors) are identified. Cold functions and loop less parts of functions executed once are then optimized for size. Enabled by default at $-\mathbf{O}$ and higher.

-fipa-cp

Perform interprocedural constant propagation. This optimization analyzes the program to determine when values passed to functions are constants and then optimizes accordingly. This optimization can substantially increase performance if the application has constants passed to functions. This flag is enabled by default at $-\mathbf{O2}$, $-\mathbf{Os}$ and $-\mathbf{O3}$.

-fipa-cp-clone

Perform function cloning to make interprocedural constant propagation stronger. When enabled, interprocedural constant propagation performs function cloning when externally visible function can be called with constant arguments. Because this optimization can create multiple copies of functions, it may significantly increase code size (see **—param ipcp—unit—growth=***value*). This flag is enabled by default at **—O3**.

-ftree-sink

Perform forward store motion on trees. This flag is enabled by default at **-O** and higher.

-ftree-bit-ccp

Perform sparse conditional bit constant propagation on trees and propagate pointer alignment information. This pass only operates on local scalar variables and is enabled by default at $-\mathbf{O}$ and

higher. It requires that **-ftree-ccp** is enabled.

-ftree-ccp

Perform sparse conditional constant propagation (CCP) on trees. This pass only operates on local scalar variables and is enabled by default at $-\mathbf{O}$ and higher.

-ftree-switch-conversion

Perform conversion of simple initializations in a switch to initializations from a scalar array. This flag is enabled by default at $-\mathbf{O2}$ and higher.

-ftree-tail-merge

Look for identical code sequences. When found, replace one with a jump to the other. This optimization is known as tail merging or cross jumping. This flag is enabled by default at **-O2** and higher. The compilation time in this pass can be limited using **max-tail-merge-comparisons** parameter and **max-tail-merge-iterations** parameter.

-ftree-dce

Perform dead code elimination (DCE) on trees. This flag is enabled by default at **-O** and higher.

-ftree-builtin-call-dce

Perform conditional dead code elimination (DCE) for calls to built-in functions that may set errno but are otherwise side-effect free. This flag is enabled by default at $-\mathbf{O2}$ and higher if $-\mathbf{Os}$ is not also specified.

-ftree-dominator-opts

Perform a variety of simple scalar cleanups (constant/copy propagation, redundancy elimination, range propagation and expression simplification) based on a dominator tree traversal. This also performs jump threading (to reduce jumps to jumps). This flag is enabled by default at **–O** and higher.

-ftree-dse

Perform dead store elimination (DSE) on trees. A dead store is a store into a memory location that is later overwritten by another store without any intervening loads. In this case the earlier store can be deleted. This flag is enabled by default at $-\mathbf{O}$ and higher.

-ftree-ch

Perform loop header copying on trees. This is beneficial since it increases effectiveness of code motion optimizations. It also saves one jump. This flag is enabled by default at $-\mathbf{O}$ and higher. It is not enabled for $-\mathbf{O}\mathbf{s}$, since it usually increases code size.

-ftree-loop-optimize

Perform loop optimizations on trees. This flag is enabled by default at **-O** and higher.

-ftree-loop-linear

Perform loop interchange transformations on tree. Same as **-floop-interchange**. To use this code transformation, GCC has to be configured with **--with-ppl** and **--with-cloog** to enable the Graphite loop transformation infrastructure.

-floop-interchange

Perform loop interchange transformations on loops. Interchanging two nested loops switches the inner and outer loops. For example, given a loop like:

```
DO J = 1, M

DO I = 1, N

A(J, I) = A(J, I) * C

ENDDO

ENDDO
```

loop interchange transforms the loop as if it were written:

```
DO I = 1, N
DO J = 1, M
A(J, I) = A(J, I) * C
ENDDO
ENDDO
```

which can be beneficial when N is larger than the caches, because in Fortran, the elements of an array are stored in memory contiguously by column, and the original loop iterates over rows, potentially creating at each access a cache miss. This optimization applies to all the languages supported by GCC and is not limited to Fortran. To use this code transformation, GCC has to be configured with **—with—ppl** and **—with—cloog** to enable the Graphite loop transformation infrastructure.

-floop-strip-mine

Perform loop strip mining transformations on loops. Strip mining splits a loop into two nested loops. The outer loop has strides equal to the strip size and the inner loop has strides of the original loop within a strip. The strip length can be changed using the **loop-block-tile-size** parameter. For example, given a loop like:

```
DO I = 1, N

A(I) = A(I) + C

ENDDO
```

loop strip mining transforms the loop as if it were written:

```
DO II = 1, N, 51

DO I = II, min (II + 50, N)

A(I) = A(I) + C

ENDDO

ENDDO
```

This optimization applies to all the languages supported by GCC and is not limited to Fortran. To use this code transformation, GCC has to be configured with —with—ppl and —with—cloog to enable the Graphite loop transformation infrastructure.

-floop-block

Perform loop blocking transformations on loops. Blocking strip mines each loop in the loop nest such that the memory accesses of the element loops fit inside caches. The strip length can be changed using the **loop-block-tile-size** parameter. For example, given a loop like:

```
DO I = 1, N

DO J = 1, M

A(J, I) = B(I) + C(J)

ENDDO

ENDDO
```

loop blocking transforms the loop as if it were written:

```
DO II = 1, N, 51

DO JJ = 1, M, 51

DO I = II, min (II + 50, N)

DO J = JJ, min (JJ + 50, M)

A(J, I) = B(I) + C(J)

ENDDO

ENDDO

ENDDO

ENDDO

ENDDO

ENDDO
```

which can be beneficial when M is larger than the caches, because the innermost loop iterates over a smaller amount of data which can be kept in the caches. This optimization applies to all the languages supported by GCC and is not limited to Fortran. To use this code transformation, GCC has to be

configured with --with-ppl and --with-cloog to enable the Graphite loop transformation infrastructure.

-fgraphite-identity

Enable the identity transformation for graphite. For every SCoP we generate the polyhedral representation and transform it back to gimple. Using **-fgraphite-identity** we can check the costs or benefits of the GIMPLE -> GRAPHITE -> GIMPLE transformation. Some minimal optimizations are also performed by the code generator CLooG, like index splitting and dead code elimination in loops.

-floop-nest-optimize

Enable the ISL based loop nest optimizer. This is a generic loop nest optimizer based on the Pluto optimization algorithms. It calculates a loop structure optimized for data-locality and parallelism. This option is experimental.

-floop-parallelize-all

Use the Graphite data dependence analysis to identify loops that can be parallelized. Parallelize all the loops that can be analyzed to not contain loop carried dependences without checking that it is profitable to parallelize the loops.

-fcheck-data-deps

Compare the results of several data dependence analyzers. This option is used for debugging the data dependence analyzers.

-ftree-loop-if-convert

Attempt to transform conditional jumps in the innermost loops to branch-less equivalents. The intent is to remove control-flow from the innermost loops in order to improve the ability of the vectorization pass to handle these loops. This is enabled by default if vectorization is enabled.

-ftree-loop-if-convert-stores

Attempt to also if-convert conditional jumps containing memory writes. This transformation can be unsafe for multi-threaded programs as it transforms conditional memory writes into unconditional memory writes. For example,

```
for (i = 0; i < N; i++)
  if (cond)
   A[i] = expr;</pre>
```

is transformed to

```
for (i = 0; i < N; i++)
  A[i] = cond ? expr : A[i];</pre>
```

potentially producing data races.

-ftree-loop-distribution

Perform loop distribution. This flag can improve cache performance on big loop bodies and allow further loop optimizations, like parallelization or vectorization, to take place. For example, the loop

```
DO I = 1, N

A(I) = B(I) + C

D(I) = E(I) * F

ENDDO
```

is transformed to

```
DO I = 1, N

A(I) = B(I) + C

ENDDO

DO I = 1, N

D(I) = E(I) * F

ENDDO
```

-ftree-loop-distribute-patterns

Perform loop distribution of patterns that can be code generated with calls to a library. This flag is enabled by default at -03.

This pass distributes the initialization loops and generates a call to memset zero. For example, the loop

```
DO I = 1, N

A(I) = 0

B(I) = A(I) + I

ENDDO
```

is transformed to

```
DO I = 1, N

A(I) = 0

ENDDO

DO I = 1, N

B(I) = A(I) + I

ENDDO
```

and the initialization loop is transformed into a call to memset zero.

-ftree-loop-im

Perform loop invariant motion on trees. This pass moves only invariants that are hard to handle at RTL level (function calls, operations that expand to nontrivial sequences of insns). With **-funswitch-loops** it also moves operands of conditions that are invariant out of the loop, so that we can use just trivial invariantness analysis in loop unswitching. The pass also includes store motion.

-ftree-loop-ivcanon

Create a canonical counter for number of iterations in loops for which determining number of iterations requires complicated analysis. Later optimizations then may determine the number easily. Useful especially in connection with unrolling.

-fivopts

Perform induction variable optimizations (strength reduction, induction variable merging and induction variable elimination) on trees.

-ftree-parallelize-loops=n

Parallelize loops, i.e., split their iteration space to run in n threads. This is only possible for loops whose iterations are independent and can be arbitrarily reordered. The optimization is only profitable on multiprocessor machines, for loops that are CPU-intensive, rather than constrained e.g. by memory bandwidth. This option implies **–pthread**, and thus is only supported on targets that have support for **–pthread**.

-ftree-pta

Perform function-local points-to analysis on trees. This flag is enabled by default at **O** and higher.

_ftree_sra

Perform scalar replacement of aggregates. This pass replaces structure references with scalars to prevent committing structures to memory too early. This flag is enabled by default at $-\mathbf{O}$ and higher.

-ftree-copyrename

Perform copy renaming on trees. This pass attempts to rename compiler temporaries to other variables at copy locations, usually resulting in variable names which more closely resemble the original variables. This flag is enabled by default at **–O** and higher.

-ftree-coalesce-inlined-vars

Tell the copyrename pass (see **-ftree-copyrename**) to attempt to combine small user-defined variables too, but only if they were inlined from other functions. It is a more limited form of **-ftree-coalesce-vars**. This may harm debug information of such inlined variables, but it will keep variables of the inlined-into function apart from each other, such that they are more likely to contain

the expected values in a debugging session. This was the default in GCC versions older than 4.7.

-ftree-coalesce-vars

Tell the copyrename pass (see **-ftree-copyrename**) to attempt to combine small user-defined variables too, instead of just compiler temporaries. This may severely limit the ability to debug an optimized program compiled with **-fno-var-tracking-assignments**. In the negated form, this flag prevents SSA coalescing of user variables, including inlined ones. This option is enabled by default.

-ftree-ter

Perform temporary expression replacement during the SSA->normal phase. Single use/single def temporaries are replaced at their use location with their defining expression. This results in non-GIMPLE code, but gives the expanders much more complex trees to work on resulting in better RTL generation. This is enabled by default at **-O** and higher.

-ftree-slsr

Perform straight-line strength reduction on trees. This recognizes related expressions involving multiplications and replaces them by less expensive calculations when possible. This is enabled by default at $-\mathbf{O}$ and higher.

-ftree-vectorize

Perform loop vectorization on trees. This flag is enabled by default at -O3.

-ftree-slp-vectorize

Perform basic block vectorization on trees. This flag is enabled by default at **-O3** and when **-ftree-vectorize** is enabled.

-ftree-vect-loop-version

Perform loop versioning when doing loop vectorization on trees. When a loop appears to be vectorizable except that data alignment or data dependence cannot be determined at compile time, then vectorized and non-vectorized versions of the loop are generated along with run-time checks for alignment or dependence to control which version is executed. This option is enabled by default except at level $-\mathbf{Os}$ where it is disabled.

-fvect-cost-model

Enable cost model for vectorization. This option is enabled by default at **-O3**.

-ftree-vrp

Perform Value Range Propagation on trees. This is similar to the constant propagation pass, but instead of values, ranges of values are propagated. This allows the optimizers to remove unnecessary range checks like array bound checks and null pointer checks. This is enabled by default at **-O2** and higher. Null pointer check elimination is only done if **-fdelete-null-pointer-checks** is enabled.

-ftracer

Perform tail duplication to enlarge superblock size. This transformation simplifies the control flow of the function allowing other optimizations to do a better job.

-funroll-loops

Unroll loops whose number of iterations can be determined at compile time or upon entry to the loop. **–funroll–loops** implies **–frerun–cse–after–loop**. This option makes code larger, and may or may not make it run faster.

-funroll-all-loops

Unroll all loops, even if their number of iterations is uncertain when the loop is entered. This usually makes programs run more slowly. **-funroll-all-loops** implies the same options as **-funroll-loops**,

-fsplit-ivs-in-unroller

Enables expression of values of induction variables in later iterations of the unrolled loop using the value in the first iteration. This breaks long dependency chains, thus improving efficiency of the scheduling passes.

A combination of **-fweb** and CSE is often sufficient to obtain the same effect. However, that is not reliable in cases where the loop body is more complicated than a single basic block. It also does not

work at all on some architectures due to restrictions in the CSE pass.

This optimization is enabled by default.

-fvariable-expansion-in-unroller

With this option, the compiler creates multiple copies of some local variables when unrolling a loop, which can result in superior code.

-fpartial-inlining

Inline parts of functions. This option has any effect only when inlining itself is turned on by the **-finline-functions** or **-finline-small-functions** options.

Enabled at level **-O2**.

-fpredictive-commoning

Perform predictive commoning optimization, i.e., reusing computations (especially memory loads and stores) performed in previous iterations of loops.

This option is enabled at level -03.

-fprefetch-loop-arrays

If supported by the target machine, generate instructions to prefetch memory to improve the performance of loops that access large arrays.

This option may generate better or worse code; results are highly dependent on the structure of loops within the source code.

Disabled at level **-Os**.

-fno-peephole

-fno-peephole2

Disable any machine-specific peephole optimizations. The difference between **-fno-peephole** and **-fno-peephole2** is in how they are implemented in the compiler; some targets use one, some use the other, a few use both.

-fpeephole is enabled by default. -fpeephole2 enabled at levels -O2, -O3, -Os.

-fno-guess-branch-probability

Do not guess branch probabilities using heuristics.

GCC uses heuristics to guess branch probabilities if they are not provided by profiling feedback (**-fprofile-arcs**). These heuristics are based on the control flow graph. If some branch probabilities are specified by **__builtin_expect**, then the heuristics are used to guess branch probabilities for the rest of the control flow graph, taking the **__builtin_expect** info into account. The interactions between the heuristics and **__builtin_expect** can be complex, and in some cases, it may be useful to disable the heuristics so that the effects of **__builtin_expect** are easier to understand.

The default is **-fguess-branch-probability** at levels **-O**, **-O2**, **-O3**, **-Os**.

-freorder-blocks

Reorder basic blocks in the compiled function in order to reduce number of taken branches and improve code locality.

Enabled at levels -O2, -O3.

-freorder-blocks-and-partition

In addition to reordering basic blocks in the compiled function, in order to reduce number of taken branches, partitions hot and cold basic blocks into separate sections of the assembly and .o files, to improve paging and cache locality performance.

This optimization is automatically turned off in the presence of exception handling, for linkonce sections, for functions with a user-defined section attribute and on any architecture that does not support named sections.

-freorder-functions

Reorder functions in the object file in order to improve code locality. This is implemented by using special subsections .text.hot for most frequently executed functions and .text.unlikely for unlikely executed functions. Reordering is done by the linker so object file format must support named sections and linker must place them in a reasonable way.

Also profile feedback must be available to make this option effective. See **-fprofile-arcs** for details.

Enabled at levels -O2, -O3, -Os.

-fstrict-aliasing

Allow the compiler to assume the strictest aliasing rules applicable to the language being compiled. For C (and C++), this activates optimizations based on the type of expressions. In particular, an object of one type is assumed never to reside at the same address as an object of a different type, unless the types are almost the same. For example, an unsigned int can alias an int, but not a void* or a double. A character type may alias any other type.

Pay special attention to code like this:

```
union a_union {
  int i;
  double d;
};
int f() {
  union a_union t;
  t.d = 3.0;
  return t.i;
}
```

The practice of reading from a different union member than the one most recently written to (called "type-punning") is common. Even with **-fstrict-aliasing**, type-punning is allowed, provided the memory is accessed through the union type. So, the code above works as expected. However, this code might not:

```
int f() {
  union a_union t;
  int* ip;
  t.d = 3.0;
  ip = &t.i;
  return *ip;
}
```

Similarly, access by taking the address, casting the resulting pointer and dereferencing the result has undefined behavior, even if the cast uses a union type, e.g.:

```
int f() {
  double d = 3.0;
  return ((union a_union *) &d)->i;
}
```

The **-fstrict-aliasing** option is enabled at levels **-O2**, **-O3**, **-Os**.

-fstrict-overflow

Allow the compiler to assume strict signed overflow rules, depending on the language being compiled. For C (and C++) this means that overflow when doing arithmetic with signed numbers is undefined, which means that the compiler may assume that it does not happen. This permits various optimizations. For example, the compiler assumes that an expression like i + 10 > i is always true for signed i. This assumption is only valid if signed overflow is undefined, as the expression is false if i + 10 overflows when using twos complement arithmetic. When this option is in effect any

attempt to determine whether an operation on signed numbers overflows must be written carefully to not actually involve overflow.

This option also allows the compiler to assume strict pointer semantics: given a pointer to an object, if adding an offset to that pointer does not produce a pointer to the same object, the addition is undefined. This permits the compiler to conclude that p + u > p is always true for a pointer p and unsigned integer u. This assumption is only valid because pointer wraparound is undefined, as the expression is false if p + u overflows using twos complement arithmetic.

See also the **-fwrapv** option. Using **-fwrapv** means that integer signed overflow is fully defined: it wraps. When **-fwrapv** is used, there is no difference between **-fstrict-overflow** and **-fno-strict-overflow** for integers. With **-fwrapv** certain types of overflow are permitted. For example, if the compiler gets an overflow when doing arithmetic on constants, the overflowed value can still be used with **-fwrapv**, but not otherwise.

The **-fstrict-overflow** option is enabled at levels **-O2**, **-O3**, **-Os**.

-falign-functions

-falign-functions=n

Align the start of functions to the next power-of-two greater than n, skipping up to n bytes. For instance, **-falign-functions=32** aligns functions to the next 32-byte boundary, but **-falign-functions=24** aligns to the next 32-byte boundary only if this can be done by skipping 23 bytes or less.

-fno-align-functions and **-falign-functions=1** are equivalent and mean that functions are not aligned.

Some assemblers only support this flag when n is a power of two; in that case, it is rounded up.

If n is not specified or is zero, use a machine-dependent default.

Enabled at levels -O2, -O3.

-falign-labels

-falign-labels=n

Align all branch targets to a power-of-two boundary, skipping up to n bytes like **-falign-functions**. This option can easily make code slower, because it must insert dummy operations for when the branch target is reached in the usual flow of the code.

-fno-align-labels and -falign-labels=1 are equivalent and mean that labels are not aligned.

If **-falign-loops** or **-falign-jumps** are applicable and are greater than this value, then their values are used instead.

If n is not specified or is zero, use a machine-dependent default which is very likely to be 1, meaning no alignment.

Enabled at levels -O2, -O3.

-falign-loops

-falign-loops=n

Align loops to a power-of-two boundary, skipping up to n bytes like **-falign-functions**. If the loops are executed many times, this makes up for any execution of the dummy operations.

-fno-align-loops and -falign-loops=1 are equivalent and mean that loops are not aligned.

If n is not specified or is zero, use a machine-dependent default.

Enabled at levels **–O2**, **–O3**.

-falign-jumps

-falign-jumps=n

Align branch targets to a power-of-two boundary, for branch targets where the targets can only be reached by jumping, skipping up to n bytes like **-falign-functions**. In this case, no dummy

operations need be executed.

-fno-align-jumps and -falign-jumps=1 are equivalent and mean that loops are not aligned.

If *n* is not specified or is zero, use a machine-dependent default.

Enabled at levels **–O2**, **–O3**.

-funit-at-a-time

This option is left for compatibility reasons. **-funit-at-a-time** has no effect, while **-fno-unit-at-a-time** implies **-fno-toplevel-reorder** and **-fno-section-anchors**.

Enabled by default.

-fno-toplevel-reorder

Do not reorder top-level functions, variables, and asm statements. Output them in the same order that they appear in the input file. When this option is used, unreferenced static variables are not removed. This option is intended to support existing code that relies on a particular ordering. For new code, it is better to use attributes.

Enabled at level $-\mathbf{O0}$. When disabled explicitly, it also implies $-\mathbf{fno}$ -section-anchors, which is otherwise enabled at $-\mathbf{O0}$ on some targets.

-fweb

Constructs webs as commonly used for register allocation purposes and assign each web individual pseudo register. This allows the register allocation pass to operate on pseudos directly, but also strengthens several other optimization passes, such as CSE, loop optimizer and trivial dead code remover. It can, however, make debugging impossible, since variables no longer stay in a "home register".

Enabled by default with -funroll-loops.

-fwhole-program

Assume that the current compilation unit represents the whole program being compiled. All public functions and variables with the exception of main and those merged by attribute externally_visible become static functions and in effect are optimized more aggressively by interprocedural optimizers.

This option should not be used in combination with -flto. Instead relying on a linker plugin should provide safer and more precise information.

$-\mathbf{flto}[=n]$

This option runs the standard link-time optimizer. When invoked with source code, it generates GIMPLE (one of GCC's internal representations) and writes it to special ELF sections in the object file. When the object files are linked together, all the function bodies are read from these ELF sections and instantiated as if they had been part of the same translation unit.

To use the link-time optimizer, **-flto** needs to be specified at compile time and during the final link. For example:

```
gcc -c -02 -flto foo.c
gcc -c -02 -flto bar.c
gcc -o myprog -flto -02 foo.o bar.o
```

The first two invocations to GCC save a bytecode representation of GIMPLE into special ELF sections inside *foo.o* and *bar.o*. The final invocation reads the GIMPLE bytecode from *foo.o* and *bar.o*, merges the two files into a single internal image, and compiles the result as usual. Since both *foo.o* and *bar.o* are merged into a single image, this causes all the interprocedural analyses and optimizations in GCC to work across the two files as if they were a single one. This means, for example, that the inliner is able to inline functions in *bar.o* into functions in *foo.o* and vice-versa.

Another (simpler) way to enable link-time optimization is:

```
gcc -o myprog -flto -02 foo.c bar.c
```

The above generates bytecode for *foo.c* and *bar.c*, merges them together into a single GIMPLE representation and optimizes them as usual to produce *myprog*.

The only important thing to keep in mind is that to enable link-time optimizations the **-flto** flag needs to be passed to both the compile and the link commands.

To make whole program optimization effective, it is necessary to make certain whole program assumptions. The compiler needs to know what functions and variables can be accessed by libraries and runtime outside of the link-time optimized unit. When supported by the linker, the linker plugin (see **-fuse-linker-plugin**) passes information to the compiler about used and externally visible symbols. When the linker plugin is not available, **-fwhole-program** should be used to allow the compiler to make these assumptions, which leads to more aggressive optimization decisions.

Note that when a file is compiled with **–flto**, the generated object file is larger than a regular object file because it contains GIMPLE bytecodes and the usual final code. This means that object files with LTO information can be linked as normal object files; if **–flto** is not passed to the linker, no interprocedural optimizations are applied.

Additionally, the optimization flags used to compile individual files are not necessarily related to those used at link time. For instance,

```
gcc -c -00 -flto foo.c
gcc -c -00 -flto bar.c
gcc -o myprog -flto -03 foo.o bar.o
```

This produces individual object files with unoptimized assembler code, but the resulting binary myprog is optimized at $-\mathbf{O3}$. If, instead, the final binary is generated without $-\mathbf{flto}$, then myprog is not optimized.

When producing the final binary with **-flto**, GCC only applies link-time optimizations to those files that contain bytecode. Therefore, you can mix and match object files and libraries with GIMPLE bytecodes and final object code. GCC automatically selects which files to optimize in LTO mode and which files to link without further processing.

There are some code generation flags preserved by GCC when generating bytecodes, as they need to be used during the final link stage. Currently, the following options are saved into the GIMPLE bytecode files: **-fPIC**, **-fcommon** and all the **-m** target flags.

At link time, these options are read in and reapplied. Note that the current implementation makes no attempt to recognize conflicting values for these options. If different files have conflicting option values (e.g., one file is compiled with **-fPIC** and another isn't), the compiler simply uses the last value read from the bytecode files. It is recommended, then, that you compile all the files participating in the same link with the same options.

If LTO encounters objects with C linkage declared with incompatible types in separate translation units to be linked together (undefined behavior according to ISO C99 6.2.7), a non-fatal diagnostic may be issued. The behavior is still undefined at run time.

Another feature of LTO is that it is possible to apply interprocedural optimizations on files written in different languages. This requires support in the language front end. Currently, the C, C++ and Fortran front ends are capable of emitting GIMPLE bytecodes, so something like this should work:

```
gcc -c -flto foo.c
g++ -c -flto bar.cc
gfortran -c -flto baz.f90
g++ -o myprog -flto -O3 foo.o bar.o baz.o -lgfortran
```

Notice that the final link is done with **g++** to get the C++ runtime libraries and **-lgfortran** is added to get the Fortran runtime libraries. In general, when mixing languages in LTO mode, you should use the

same link command options as when mixing languages in a regular (non-LTO) compilation; all you need to add is **-flto** to all the compile and link commands.

If object files containing GIMPLE bytecode are stored in a library archive, say *libfoo.a*, it is possible to extract and use them in an LTO link if you are using a linker with plugin support. To enable this feature, use the flag **–fuse–linker–plugin** at link time:

```
gcc -o myprog -02 -flto -fuse-linker-plugin a.o b.o -lfoo
```

With the linker plugin enabled, the linker extracts the needed GIMPLE files from *libfoo.a* and passes them on to the running GCC to make them part of the aggregated GIMPLE image to be optimized.

If you are not using a linker with plugin support and/or do not enable the linker plugin, then the objects inside *libfoo.a* are extracted and linked as usual, but they do not participate in the LTO optimization process.

Link-time optimizations do not require the presence of the whole program to operate. If the program does not require any symbols to be exported, it is possible to combine **-flto** and **-fwhole-program** to allow the interprocedural optimizers to use more aggressive assumptions which may lead to improved optimization opportunities. Use of **-fwhole-program** is not needed when linker plugin is active (see **-fuse-linker-plugin**).

The current implementation of LTO makes no attempt to generate bytecode that is portable between different types of hosts. The bytecode files are versioned and there is a strict version check, so bytecode files generated in one version of GCC will not work with an older/newer version of GCC.

Link-time optimization does not work well with generation of debugging information. Combining **–flto** with **–g** is currently experimental and expected to produce wrong results.

If you specify the optional n, the optimization and code generation done at link time is executed in parallel using n parallel jobs by utilizing an installed **make** program. The environment variable **MAKE** may be used to override the program used. The default value for n is 1.

You can also specify —**fito=jobserver** to use GNU make's job server mode to determine the number of parallel jobs. This is useful when the Makefile calling GCC is already executing in parallel. You must prepend a + to the command recipe in the parent Makefile for this to work. This option likely only works if **MAKE** is GNU make.

This option is disabled by default.

-flto-partition=alg

Specify the partitioning algorithm used by the link-time optimizer. The value is either 1to1 to specify a partitioning mirroring the original source files or balanced to specify partitioning into equally sized chunks (whenever possible) or max to create new partition for every symbol where possible. Specifying none as an algorithm disables partitioning and streaming completely. The default value is balanced. While 1to1 can be used as an workaround for various code ordering issues, the max partitioning is intended for internal testing only.

-flto-compression-level=n

This option specifies the level of compression used for intermediate language written to LTO object files, and is only meaningful in conjunction with LTO mode (**-flto**). Valid values are 0 (no compression) to 9 (maximum compression). Values outside this range are clamped to either 0 or 9. If the option is not given, a default balanced compression setting is used.

-flto-report

Prints a report with internal details on the workings of the link-time optimizer. The contents of this report vary from version to version. It is meant to be useful to GCC developers when processing object files in LTO mode (via **-flto**).

Disabled by default.

-fuse-linker-plugin

Enables the use of a linker plugin during link-time optimization. This option relies on plugin support in the linker, which is available in gold or in GNU ld 2.21 or newer.

This option enables the extraction of object files with GIMPLE bytecode out of library archives. This improves the quality of optimization by exposing more code to the link-time optimizer. This information specifies what symbols can be accessed externally (by non-LTO object or during dynamic linking). Resulting code quality improvements on binaries (and shared libraries that use hidden visibility) are similar to -fwhole-program. See -flto for a description of the effect of this flag and how to use it.

This option is enabled by default when LTO support in GCC is enabled and GCC was configured for use with a linker supporting plugins (GNU ld 2.21 or newer or gold).

-ffat-lto-objects

Fat LTO objects are object files that contain both the intermediate language and the object code. This makes them usable for both LTO linking and normal linking. This option is effective only when compiling with **–flto** and is ignored at link time.

-fno-fat-lto-objects improves compilation time over plain LTO, but requires the complete toolchain to be aware of LTO. It requires a linker with linker plugin support for basic functionality. Additionally, **nm**, **ar** and **ranlib** need to support linker plugins to allow a full-featured build environment (capable of building static libraries etc). GCC provides the **gcc-ar**, **gcc-nm**, **gcc-ranlib** wrappers to pass the right options to these tools. With non fat LTO makefiles need to be modified to use them.

The default is **-ffat-lto-objects** but this default is intended to change in future releases when linker plugin enabled environments become more common.

-fcompare-elim

After register allocation and post-register allocation instruction splitting, identify arithmetic instructions that compute processor flags similar to a comparison operation based on that arithmetic. If possible, eliminate the explicit comparison operation.

This pass only applies to certain targets that cannot explicitly represent the comparison operation before register allocation is complete.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fuse-ld=bfd

Use the **bfd** linker instead of the default linker.

-fuse-ld=gold

Use the **gold** linker instead of the default linker.

-fcprop-registers

After register allocation and post-register allocation instruction splitting, perform a copy-propagation pass to try to reduce scheduling dependencies and occasionally eliminate the copy.

Enabled at levels $-\mathbf{O}$, $-\mathbf{O2}$, $-\mathbf{O3}$, $-\mathbf{Os}$.

-fprofile-correction

Profiles collected using an instrumented binary for multi-threaded programs may be inconsistent due to missed counter updates. When this option is specified, GCC uses heuristics to correct or smooth out such inconsistencies. By default, GCC emits an error message when an inconsistent profile is detected.

-fprofile-dir=path

Set the directory to search for the profile data files in to *path*. This option affects only the profile data generated by **-fprofile-generate**, **-ftest-coverage**, **-fprofile-arcs** and used by **-fprofile-use** and **-fbranch-probabilities** and its related options. Both absolute and relative paths can be used. By default, GCC uses the current directory as *path*, thus the profile data file appears in the same directory as the object file.

-fprofile-generate

-fprofile-generate=*path*

Enable options usually used for instrumenting application to produce profile useful for later recompilation with profile feedback based optimization. You must use **-fprofile-generate** both when compiling and when linking your program.

The following options are enabled: -fprofile-arcs, -fprofile-values, -fvpt.

If path is specified, GCC looks at the path to find the profile feedback data files. See **-fprofile-dir**.

-fprofile-use

-fprofile-use=path

Enable profile feedback directed optimizations, and optimizations generally profitable only with profile feedback available.

The following options are enabled: -fbranch-probabilities, -fvpt, -funroll-loops, -fpeel-loops, -ftracer, -ftree-vectorize, ftree-loop-distribute-patterns

By default, GCC emits an error message if the feedback profiles do not match the source code. This error can be turned into a warning by using **–Wcoverage–mismatch**. Note this may result in poorly optimized code.

If path is specified, GCC looks at the path to find the profile feedback data files. See -fprofile-dir.

The following options control compiler behavior regarding floating-point arithmetic. These options trade off between speed and correctness. All must be specifically enabled.

-ffloat-store

Do not store floating-point variables in registers, and inhibit other options that might change whether a floating-point value is taken from a register or memory.

This option prevents undesirable excess precision on machines such as the 68000 where the floating registers (of the 68881) keep more precision than a double is supposed to have. Similarly for the x86 architecture. For most programs, the excess precision does only good, but a few programs rely on the precise definition of IEEE floating point. Use **-ffloat-store** for such programs, after modifying them to store all pertinent intermediate computations into variables.

-fexcess-precision=style

This option allows further control over excess precision on machines where floating-point registers have more precision than the IEEE float and double types and the processor does not support operations rounding to those types. By default, **-fexcess-precision=fast** is in effect; this means that operations are carried out in the precision of the registers and that it is unpredictable when rounding to the types specified in the source code takes place. When compiling C, if **-fexcess-precision=standard** is specified then excess precision follows the rules specified in ISO C99; in particular, both casts and assignments cause values to be rounded to their semantic types (whereas **-ffloat-store** only affects assignments). This option is enabled by default for C if a strict conformance option such as **-std=c99** is used.

-fexcess-precision=standard is not implemented for languages other than C, and has no effect if **-funsafe-math-optimizations** or **-ffast-math** is specified. On the x86, it also has no effect if **-mfpmath=sse** or **-mfpmath=sse+387** is specified; in the former case, IEEE semantics apply without excess precision, and in the latter, rounding is unpredictable.

-ffast-math

Sets **—fno—math—errno**, **—funsafe—math—optimizations**, **—ffinite—math—only**, **—fno—rounding—math**, **—fno—signaling—nans** and **—fcx—limited—range**.

This option causes the preprocessor macro _ _FAST_MATH_ _ to be defined.

This option is not turned on by any $-\mathbf{O}$ option besides $-\mathbf{Ofast}$ since it can result in incorrect output for programs that depend on an exact implementation of IEEE or ISO rules/specifications for math functions. It may, however, yield faster code for programs that do not require the guarantees of these

specifications.

-fno-math-errno

Do not set errno after calling math functions that are executed with a single instruction, e.g., sqrt. A program that relies on IEEE exceptions for math error handling may want to use this flag for speed while maintaining IEEE arithmetic compatibility.

This option is not turned on by any **-O** option since it can result in incorrect output for programs that depend on an exact implementation of IEEE or ISO rules/specifications for math functions. It may, however, yield faster code for programs that do not require the guarantees of these specifications.

The default is **-fmath-errno**.

On Darwin systems, the math library never sets errno. There is therefore no reason for the compiler to consider the possibility that it might, and **-fno-math-errno** is the default.

-funsafe-math-optimizations

Allow optimizations for floating-point arithmetic that (a) assume that arguments and results are valid and (b) may violate IEEE or ANSI standards. When used at link-time, it may include libraries or startup files that change the default FPU control word or other similar optimizations.

This option is not turned on by any **–O** option since it can result in incorrect output for programs that depend on an exact implementation of IEEE or ISO rules/specifications for math functions. It may, however, yield faster code for programs that do not require the guarantees of these specifications. Enables **–fno–signed–zeros**, **–fno–trapping–math**, **–fassociative–math** and **–freciprocal–math**.

The default is **-fno-unsafe-math-optimizations**.

-fassociative-math

Allow re-association of operands in series of floating-point operations. This violates the ISO C and C+-language standard by possibly changing computation result. NOTE: re-ordering may change the sign of zero as well as ignore NaNs and inhibit or create underflow or overflow (and thus cannot be used on code that relies on rounding behavior like (x + 2**52) - 2**52. May also reorder floating-point comparisons and thus may not be used when ordered comparisons are required. This option requires that both -fno-signed-zeros and -fno-trapping-math be in effect. Moreover, it doesn't make much sense with -frounding-math. For Fortran the option is automatically enabled when both -fno-signed-zeros and -fno-trapping-math are in effect.

The default is **-fno-associative-math**.

-freciprocal-math

Allow the reciprocal of a value to be used instead of dividing by the value if this enables optimizations. For example $x \neq y$ can be replaced with $x \neq (1/y)$, which is useful if (1/y) is subject to common subexpression elimination. Note that this loses precision and increases the number of flops operating on the value.

The default is **-fno-reciprocal-math**.

-ffinite-math-only

Allow optimizations for floating-point arithmetic that assume that arguments and results are not NaNs or +–Infs.

This option is not turned on by any $-\mathbf{O}$ option since it can result in incorrect output for programs that depend on an exact implementation of IEEE or ISO rules/specifications for math functions. It may, however, yield faster code for programs that do not require the guarantees of these specifications.

The default is **-fno-finite-math-only**.

-fno-signed-zeros

Allow optimizations for floating-point arithmetic that ignore the signedness of zero. IEEE arithmetic specifies the behavior of distinct +0.0 and -0.0 values, which then prohibits simplification of expressions such as x+0.0 or 0.0*x (even with **-ffinite-math-only**). This option implies that the sign of a zero result isn't significant.

The default is **-fsigned-zeros**.

-fno-trapping-math

Compile code assuming that floating-point operations cannot generate user-visible traps. These traps include division by zero, overflow, underflow, inexact result and invalid operation. This option requires that **-fno-signaling-nans** be in effect. Setting this option may allow faster code if one relies on "non-stop" IEEE arithmetic, for example.

This option should never be turned on by any **-O** option since it can result in incorrect output for programs that depend on an exact implementation of IEEE or ISO rules/specifications for math functions.

The default is **-ftrapping-math**.

-frounding-math

Disable transformations and optimizations that assume default floating-point rounding behavior. This is round-to-zero for all floating point to integer conversions, and round-to-nearest for all other arithmetic truncations. This option should be specified for programs that change the FP rounding mode dynamically, or that may be executed with a non-default rounding mode. This option disables constant folding of floating-point expressions at compile time (which may be affected by rounding mode) and arithmetic transformations that are unsafe in the presence of sign-dependent rounding modes.

The default is **-fno-rounding-math**.

This option is experimental and does not currently guarantee to disable all GCC optimizations that are affected by rounding mode. Future versions of GCC may provide finer control of this setting using C99's FENV_ACCESS pragma. This command-line option will be used to specify the default state for FENV_ACCESS.

-fsignaling-nans

Compile code assuming that IEEE signaling NaNs may generate user-visible traps during floating-point operations. Setting this option disables optimizations that may change the number of exceptions visible with signaling NaNs. This option implies **-ftrapping-math**.

This option causes the preprocessor macro __SUPPORT_SNAN__ to be defined.

The default is **-fno-signaling-nans**.

This option is experimental and does not currently guarantee to disable all GCC optimizations that affect signaling NaN behavior.

-fsingle-precision-constant

Treat floating-point constants as single precision instead of implicitly converting them to double-precision constants.

-fcx-limited-range

When enabled, this option states that a range reduction step is not needed when performing complex division. Also, there is no checking whether the result of a complex multiplication or division is NaN + I*NaN, with an attempt to rescue the situation in that case. The default is -fno-cx-limited-range, but is enabled by -ffast-math.

This option controls the default setting of the ISO C99 CX_LIMITED_RANGE pragma. Nevertheless, the option applies to all languages.

-fcx-fortran-rules

Complex multiplication and division follow Fortran rules. Range reduction is done as part of complex division, but there is no checking whether the result of a complex multiplication or division is NaN + I*NaN, with an attempt to rescue the situation in that case.

The default is **-fno-cx-fortran-rules**.

The following options control optimizations that may improve performance, but are not enabled by any -O

options. This section includes experimental options that may produce broken code.

-fbranch-probabilities

After running a program compiled with **-fprofile-arcs**, you can compile it a second time using **-fbranch-probabilities**, to improve optimizations based on the number of times each branch was taken. When a program compiled with **-fprofile-arcs** exits, it saves arc execution counts to a file called *sourcename.gcda* for each source file. The information in this data file is very dependent on the structure of the generated code, so you must use the same source code and the same optimization options for both compilations.

With **-fbranch-probabilities**, GCC puts a **REG_BR_PROB** note on each **JUMP_INSN** and **CALL_INSN**. These can be used to improve optimization. Currently, they are only used in one place: in *reorg.c*, instead of guessing which path a branch is most likely to take, the **REG_BR_PROB** values are used to exactly determine which path is taken more often.

-fprofile-values

If combined with **-fprofile-arcs**, it adds code so that some data about values of expressions in the program is gathered.

With **–fbranch–probabilities**, it reads back the data gathered from profiling values of expressions for usage in optimizations.

Enabled with **-fprofile-generate** and **-fprofile-use**.

-fvpt

If combined with **-fprofile-arcs**, this option instructs the compiler to add code to gather information about values of expressions.

With **–fbranch–probabilities**, it reads back the data gathered and actually performs the optimizations based on them. Currently the optimizations include specialization of division operations using the knowledge about the value of the denominator.

-frename-registers

Attempt to avoid false dependencies in scheduled code by making use of registers left over after register allocation. This optimization most benefits processors with lots of registers. Depending on the debug information format adopted by the target, however, it can make debugging impossible, since variables no longer stay in a "home register".

Enabled by default with **-funroll-loops** and **-fpeel-loops**.

-ftracer

Perform tail duplication to enlarge superblock size. This transformation simplifies the control flow of the function allowing other optimizations to do a better job.

Enabled with **-fprofile-use**.

-funroll-loops

Unroll loops whose number of iterations can be determined at compile time or upon entry to the loop. **-funroll-loops** implies **-frerun-cse-after-loop**, **-fweb** and **-frename-registers**. It also turns on complete loop peeling (i.e. complete removal of loops with a small constant number of iterations). This option makes code larger, and may or may not make it run faster.

Enabled with **-fprofile-use**.

-funroll-all-loops

Unroll all loops, even if their number of iterations is uncertain when the loop is entered. This usually makes programs run more slowly. **-funroll-all-loops** implies the same options as **-funroll-loops**.

-fpeel-loops

Peels loops for which there is enough information that they do not roll much (from profile feedback). It also turns on complete loop peeling (i.e. complete removal of loops with small constant number of iterations).

Enabled with -fprofile-use.

-fmove-loop-invariants

Enables the loop invariant motion pass in the RTL loop optimizer. Enabled at level -O1

-funswitch-loops

Move branches with loop invariant conditions out of the loop, with duplicates of the loop on both branches (modified according to result of the condition).

-ffunction-sections

-fdata-sections

Place each function or data item into its own section in the output file if the target supports arbitrary sections. The name of the function or the name of the data item determines the section's name in the output file.

Use these options on systems where the linker can perform optimizations to improve locality of reference in the instruction space. Most systems using the ELF object format and SPARC processors running Solaris 2 have linkers with such optimizations. AIX may have these optimizations in the future.

Only use these options when there are significant benefits from doing so. When you specify these options, the assembler and linker create larger object and executable files and are also slower. You cannot use gprof on all systems if you specify this option, and you may have problems with debugging if you specify both this option and -g.

-fbranch-target-load-optimize

Perform branch target register load optimization before prologue / epilogue threading. The use of target registers can typically be exposed only during reload, thus hoisting loads out of loops and doing inter-block scheduling needs a separate optimization pass.

-fbranch-target-load-optimize2

Perform branch target register load optimization after prologue / epilogue threading.

-fbtr-bb-exclusive

When performing branch target register load optimization, don't reuse branch target registers within any basic block.

-fstack-protector

Emit extra code to check for buffer overflows, such as stack smashing attacks. This is done by adding a guard variable to functions with vulnerable objects. This includes functions that call alloca, and functions with buffers larger than 8 bytes. The guards are initialized when a function is entered and then checked when the function exits. If a guard check fails, an error message is printed and the program exits.

NOTE: In Ubuntu 6.10 and later versions this option is enabled by default for C, C++, ObjC, ObjC++, if none of **-fno-stack-protector**, **-nostdlib**, nor **-ffreestanding** are found.

-fstack-protector-all

Like **–fstack–protector** except that all functions are protected.

-fsection-anchors

Try to reduce the number of symbolic address calculations by using shared "anchor" symbols to address nearby objects. This transformation can help to reduce the number of GOT entries and GOT accesses on some targets.

For example, the implementation of the following function foo:

```
static int a, b, c;
int foo (void) { return a + b + c; }
```

usually calculates the addresses of all three variables, but if you compile it with **–fsection–anchors**, it accesses the variables from a common anchor point instead. The effect is similar to the following pseudocode (which isn't valid C):

```
int foo (void)
{
  register int *xr = &x;
  return xr[&a - &x] + xr[&b - &x] + xr[&c - &x];
}
```

Not all targets support this option.

--param name=value

In some places, GCC uses various constants to control the amount of optimization that is done. For example, GCC does not inline functions that contain more than a certain number of instructions. You can control some of these constants on the command line using the **—param** option.

The names of specific parameters, and the meaning of the values, are tied to the internals of the compiler, and are subject to change without notice in future releases.

In each case, the *value* is an integer. The allowable choices for *name* are:

predictable-branch-outcome

When branch is predicted to be taken with probability lower than this threshold (in percent), then it is considered well predictable. The default is 10.

max-crossjump-edges

The maximum number of incoming edges to consider for cross-jumping. The algorithm used by **–fcrossjumping** is O(N^2) in the number of edges incoming to each block. Increasing values mean more aggressive optimization, making the compilation time increase with probably small improvement in executable size.

min-crossjump-insns

The minimum number of instructions that must be matched at the end of two blocks before cross-jumping is performed on them. This value is ignored in the case where all instructions in the block being cross-jumped from are matched. The default value is 5.

max-grow-copy-bb-insns

The maximum code size expansion factor when copying basic blocks instead of jumping. The expansion is relative to a jump instruction. The default value is 8.

max-goto-duplication-insns

The maximum number of instructions to duplicate to a block that jumps to a computed goto. To avoid $O(N^2)$ behavior in a number of passes, GCC factors computed gotos early in the compilation process, and unfactors them as late as possible. Only computed jumps at the end of a basic blocks with no more than max-goto-duplication-insns are unfactored. The default value is 8.

max-delay-slot-insn-search

The maximum number of instructions to consider when looking for an instruction to fill a delay slot. If more than this arbitrary number of instructions are searched, the time savings from filling the delay slot are minimal, so stop searching. Increasing values mean more aggressive optimization, making the compilation time increase with probably small improvement in execution time.

max-delay-slot-live-search

When trying to fill delay slots, the maximum number of instructions to consider when searching for a block with valid live register information. Increasing this arbitrarily chosen value means more aggressive optimization, increasing the compilation time. This parameter should be removed when the delay slot code is rewritten to maintain the control-flow graph.

max-gcse-memory

The approximate maximum amount of memory that can be allocated in order to perform the global common subexpression elimination optimization. If more memory than specified is required, the optimization is not done.

max-gcse-insertion-ratio

If the ratio of expression insertions to deletions is larger than this value for any expression, then RTL PRE inserts or removes the expression and thus leaves partially redundant computations in the instruction stream. The default value is 20.

max-pending-list-length

The maximum number of pending dependencies scheduling allows before flushing the current state and starting over. Large functions with few branches or calls can create excessively large lists which needlessly consume memory and resources.

max-modulo-backtrack-attempts

The maximum number of backtrack attempts the scheduler should make when modulo scheduling a loop. Larger values can exponentially increase compilation time.

max-inline-insns-single

Several parameters control the tree inliner used in GCC. This number sets the maximum number of instructions (counted in GCC's internal representation) in a single function that the tree inliner considers for inlining. This only affects functions declared inline and methods implemented in a class declaration (C++). The default value is 400.

max-inline-insns-auto

When you use **–finline–functions** (included in **–O3**), a lot of functions that would otherwise not be considered for inlining by the compiler are investigated. To those functions, a different (more restrictive) limit compared to functions declared inline can be applied. The default value is 40.

inline-min-speedup

When estimated performance improvement of caller + callee runtime exceeds this threshold (in precent), the function can be inlined regardless the limit on --param max-inline-insns-single and --param max-inline-insns-auto.

large-function-insns

The limit specifying really large functions. For functions larger than this limit after inlining, inlining is constrained by —**param large-function-growth**. This parameter is useful primarily to avoid extreme compilation time caused by non-linear algorithms used by the back end. The default value is 2700.

large-function-growth

Specifies maximal growth of large function caused by inlining in percents. The default value is 100 which limits large function growth to 2.0 times the original size.

large-unit-insns

The limit specifying large translation unit. Growth caused by inlining of units larger than this limit is limited by —param inline-unit-growth. For small units this might be too tight. For example, consider a unit consisting of function A that is inline and B that just calls A three times. If B is small relative to A, the growth of unit is 300\% and yet such inlining is very sane. For very large units consisting of small inlineable functions, however, the overall unit growth limit is needed to avoid exponential explosion of code size. Thus for smaller units, the size is increased to —param large-unit-insns before applying —param inline-unit-growth. The default is 10000.

inline-unit-growth

Specifies maximal overall growth of the compilation unit caused by inlining. The default value is 30 which limits unit growth to 1.3 times the original size.

ipcp-unit-growth

Specifies maximal overall growth of the compilation unit caused by interprocedural constant propagation. The default value is 10 which limits unit growth to 1.1 times the original size.

large-stack-frame

The limit specifying large stack frames. While inlining the algorithm is trying to not grow past this limit too much. The default value is 256 bytes.

large-stack-frame-growth

Specifies maximal growth of large stack frames caused by inlining in percents. The default value is 1000 which limits large stack frame growth to 11 times the original size.

max-inline-insns-recursive

max-inline-insns-recursive-auto

Specifies the maximum number of instructions an out-of-line copy of a self-recursive inline function can grow into by performing recursive inlining.

For functions declared inline, —param max-inline-insns-recursive is taken into account. For functions not declared inline, recursive inlining happens only when —finline—functions (included in —O3) is enabled and —param max-inline-insns-recursive-auto is used. The default value is 450.

max-inline-recursive-depth

max-inline-recursive-depth-auto

Specifies the maximum recursion depth used for recursive inlining.

For functions declared inline, —param max-inline-recursive-depth is taken into account. For functions not declared inline, recursive inlining happens only when —finline—functions (included in —O3) is enabled and —param max-inline-recursive-depth-auto is used. The default value is 8

min-inline-recursive-probability

Recursive inlining is profitable only for function having deep recursion in average and can hurt for function having little recursion depth by increasing the prologue size or complexity of function body to other optimizers.

When profile feedback is available (see **-fprofile-generate**) the actual recursion depth can be guessed from probability that function recurses via a given call expression. This parameter limits inlining only to call expressions whose probability exceeds the given threshold (in percents). The default value is 10.

early-inlining-insns

Specify growth that the early inliner can make. In effect it increases the amount of inlining for code having a large abstraction penalty. The default value is 10.

max-early-inliner-iterations

max-early-inliner-iterations

Limit of iterations of the early inliner. This basically bounds the number of nested indirect calls the early inliner can resolve. Deeper chains are still handled by late inlining.

comdat-sharing-probability

comdat-sharing-probability

Probability (in percent) that C++ inline function with comdat visibility are shared across multiple compilation units. The default value is 20.

min-vect-loop-bound

The minimum number of iterations under which loops are not vectorized when **-ftree-vectorize** is used. The number of iterations after vectorization needs to be greater than the value specified by this option to allow vectorization. The default value is 0.

gcse-cost-distance-ratio

Scaling factor in calculation of maximum distance an expression can be moved by GCSE optimizations. This is currently supported only in the code hoisting pass. The bigger the ratio, the more aggressive code hoisting is with simple expressions, i.e., the expressions that have cost less than **gcse-unrestricted-cost**. Specifying 0 disables hoisting of simple expressions. The default value is 10.

gcse-unrestricted-cost

Cost, roughly measured as the cost of a single typical machine instruction, at which GCSE optimizations do not constrain the distance an expression can travel. This is currently supported only in the code hoisting pass. The lesser the cost, the more aggressive code hoisting is. Specifying 0 allows all expressions to travel unrestricted distances. The default value is 3.

max-hoist-depth

The depth of search in the dominator tree for expressions to hoist. This is used to avoid quadratic behavior in hoisting algorithm. The value of 0 does not limit on the search, but may slow down compilation of huge functions. The default value is 30.

max-tail-merge-comparisons

The maximum amount of similar bbs to compare a bb with. This is used to avoid quadratic behavior in tree tail merging. The default value is 10.

max-tail-merge-iterations

The maximum amount of iterations of the pass over the function. This is used to limit compilation time in tree tail merging. The default value is 2.

max-unrolled-insns

The maximum number of instructions that a loop may have to be unrolled. If a loop is unrolled, this parameter also determines how many times the loop code is unrolled.

max-average-unrolled-insns

The maximum number of instructions biased by probabilities of their execution that a loop may have to be unrolled. If a loop is unrolled, this parameter also determines how many times the loop code is unrolled.

max-unroll-times

The maximum number of unrollings of a single loop.

max-peeled-insns

The maximum number of instructions that a loop may have to be peeled. If a loop is peeled, this parameter also determines how many times the loop code is peeled.

max-peel-times

The maximum number of peelings of a single loop.

max-peel-branches

The maximum number of branches on the hot path through the peeled sequence.

max-completely-peeled-insns

The maximum number of insns of a completely peeled loop.

max-completely-peel-times

The maximum number of iterations of a loop to be suitable for complete peeling.

max-completely-peel-loop-nest-depth

The maximum depth of a loop nest suitable for complete peeling.

max-unswitch-insns

The maximum number of insns of an unswitched loop.

max-unswitch-level

The maximum number of branches unswitched in a single loop.

lim-expensive

The minimum cost of an expensive expression in the loop invariant motion.

iv-consider-all-candidates-bound

Bound on number of candidates for induction variables, below which all candidates are considered for each use in induction variable optimizations. If there are more candidates than this, only the most relevant ones are considered to avoid quadratic time complexity.

iv-max-considered-uses

The induction variable optimizations give up on loops that contain more induction variable uses.

iv-always-prune-cand-set-bound

If the number of candidates in the set is smaller than this value, always try to remove unnecessary ivs from the set when adding a new one.

scev-max-expr-size

Bound on size of expressions used in the scalar evolutions analyzer. Large expressions slow the analyzer.

scev-max-expr-complexity

Bound on the complexity of the expressions in the scalar evolutions analyzer. Complex expressions slow the analyzer.

omega-max-vars

The maximum number of variables in an Omega constraint system. The default value is 128.

omega-max-geqs

The maximum number of inequalities in an Omega constraint system. The default value is 256.

omega-max-eqs

The maximum number of equalities in an Omega constraint system. The default value is 128.

omega-max-wild-cards

The maximum number of wildcard variables that the Omega solver is able to insert. The default value is 18.

omega-hash-table-size

The size of the hash table in the Omega solver. The default value is 550.

omega-max-keys

The maximal number of keys used by the Omega solver. The default value is 500.

omega-eliminate-redundant-constraints

When set to 1, use expensive methods to eliminate all redundant constraints. The default value is 0

vect-max-version-for-alignment-checks

The maximum number of run-time checks that can be performed when doing loop versioning for alignment in the vectorizer. See option **–ftree–vect–loop–version** for more information.

vect-max-version-for-alias-checks

The maximum number of run-time checks that can be performed when doing loop versioning for alias in the vectorizer. See option **–ftree–vect–loop–version** for more information.

max-iterations-to-track

The maximum number of iterations of a loop the brute-force algorithm for analysis of the number of iterations of the loop tries to evaluate.

hot-bb-count-ws-permille

A basic block profile count is considered hot if it contributes to the given permillage (i.e. 0...1000) of the entire profiled execution.

hot-bb-frequency-fraction

Select fraction of the entry block frequency of executions of basic block in function given basic block needs to have to be considered hot.

max-predicted-iterations

The maximum number of loop iterations we predict statically. This is useful in cases where a function contains a single loop with known bound and another loop with unknown bound. The known number of iterations is predicted correctly, while the unknown number of iterations average to roughly 10. This means that the loop without bounds appears artificially cold relative to the other one.

align-threshold

Select fraction of the maximal frequency of executions of a basic block in a function to align the basic block.

align-loop-iterations

A loop expected to iterate at least the selected number of iterations is aligned.

tracer-dynamic-coverage

tracer-dynamic-coverage-feedback

This value is used to limit superblock formation once the given percentage of executed instructions is covered. This limits unnecessary code size expansion.

The **tracer-dynamic-coverage-feedback** is used only when profile feedback is available. The real profiles (as opposed to statically estimated ones) are much less balanced allowing the threshold to be larger value.

tracer-max-code-growth

Stop tail duplication once code growth has reached given percentage. This is a rather artificial limit, as most of the duplicates are eliminated later in cross jumping, so it may be set to much higher values than is the desired code growth.

tracer-min-branch-ratio

Stop reverse growth when the reverse probability of best edge is less than this threshold (in percent).

tracer-min-branch-ratio

tracer-min-branch-ratio-feedback

Stop forward growth if the best edge has probability lower than this threshold.

Similarly to **tracer-dynamic-coverage** two values are present, one for compilation for profile feedback and one for compilation without. The value for compilation with profile feedback needs to be more conservative (higher) in order to make tracer effective.

max-cse-path-length

The maximum number of basic blocks on path that CSE considers. The default is 10.

max-cse-insns

The maximum number of instructions CSE processes before flushing. The default is 1000.

ggc-min-expand

GCC uses a garbage collector to manage its own memory allocation. This parameter specifies the minimum percentage by which the garbage collector's heap should be allowed to expand between collections. Tuning this may improve compilation speed; it has no effect on code generation.

The default is 30% + 70% * (RAM/1GB) with an upper bound of 100% when RAM >= 1GB. If getrlimit is available, the notion of "RAM" is the smallest of actual RAM and RLIMIT_DATA or RLIMIT_AS. If GCC is not able to calculate RAM on a particular platform, the lower bound of 30% is used. Setting this parameter and **ggc-min-heapsize** to zero causes a full collection to occur at every opportunity. This is extremely slow, but can be useful for debugging.

ggc-min-heapsize

Minimum size of the garbage collector's heap before it begins bothering to collect garbage. The first collection occurs after the heap expands by **ggc-min-expand**% beyond **ggc-min-heapsize**. Again, tuning this may improve compilation speed, and has no effect on code generation.

The default is the smaller of RAM/8, RLIMIT_RSS, or a limit that tries to ensure that RLIMIT_DATA or RLIMIT_AS are not exceeded, but with a lower bound of 4096 (four megabytes) and an upper bound of 131072 (128 megabytes). If GCC is not able to calculate RAM on a particular platform, the lower bound is used. Setting this parameter very large effectively disables garbage collection. Setting this parameter and **ggc-min-expand** to zero causes a full collection to occur at every opportunity.

max-reload-search-insns

The maximum number of instruction reload should look backward for equivalent register. Increasing values mean more aggressive optimization, making the compilation time increase with probably slightly better performance. The default value is 100.

max-cselib-memory-locations

The maximum number of memory locations cselib should take into account. Increasing values mean more aggressive optimization, making the compilation time increase with probably slightly better performance. The default value is 500.

reorder-blocks-duplicate

reorder-blocks-duplicate-feedback

Used by the basic block reordering pass to decide whether to use unconditional branch or duplicate the code on its destination. Code is duplicated when its estimated size is smaller than this value multiplied by the estimated size of unconditional jump in the hot spots of the program.

The **reorder-block-duplicate-feedback** is used only when profile feedback is available. It may be set to higher values than **reorder-block-duplicate** since information about the hot spots is more accurate.

max-sched-ready-insns

The maximum number of instructions ready to be issued the scheduler should consider at any given time during the first scheduling pass. Increasing values mean more thorough searches, making the compilation time increase with probably little benefit. The default value is 100.

max-sched-region-blocks

The maximum number of blocks in a region to be considered for interblock scheduling. The default value is 10.

max-pipeline-region-blocks

The maximum number of blocks in a region to be considered for pipelining in the selective scheduler. The default value is 15.

max-sched-region-insns

The maximum number of insns in a region to be considered for interblock scheduling. The default value is 100.

max-pipeline-region-insns

The maximum number of insns in a region to be considered for pipelining in the selective scheduler. The default value is 200.

min-spec-prob

The minimum probability (in percents) of reaching a source block for interblock speculative scheduling. The default value is 40.

max-sched-extend-regions-iters

The maximum number of iterations through CFG to extend regions. A value of 0 (the default) disables region extensions.

max-sched-insn-conflict-delay

The maximum conflict delay for an insn to be considered for speculative motion. The default value is 3.

sched-spec-prob-cutoff

The minimal probability of speculation success (in percents), so that speculative insns are scheduled. The default value is 40.

sched-spec-state-edge-prob-cutoff

The minimum probability an edge must have for the scheduler to save its state across it. The default value is 10.

sched-mem-true-dep-cost

Minimal distance (in CPU cycles) between store and load targeting same memory locations. The default value is 1.

selsched-max-lookahead

The maximum size of the lookahead window of selective scheduling. It is a depth of search for available instructions. The default value is 50.

selsched-max-sched-times

The maximum number of times that an instruction is scheduled during selective scheduling. This is the limit on the number of iterations through which the instruction may be pipelined. The default value is 2.

selsched-max-insns-to-rename

The maximum number of best instructions in the ready list that are considered for renaming in the selective scheduler. The default value is 2.

sms-min-sc

The minimum value of stage count that swing modulo scheduler generates. The default value is 2.

max-last-value-rtl

The maximum size measured as number of RTLs that can be recorded in an expression in combiner for a pseudo register as last known value of that register. The default is 10000.

integer-share-limit

Small integer constants can use a shared data structure, reducing the compiler's memory usage and increasing its speed. This sets the maximum value of a shared integer constant. The default value is 256.

ssp-buffer-size

The minimum size of buffers (i.e. arrays) that receive stack smashing protection when **-fstack-protection** is used.

This default before Ubuntu 10.10 was "8". Currently it is "4", to increase the number of functions protected by the stack protector.

max-jump-thread-duplication-stmts

Maximum number of statements allowed in a block that needs to be duplicated when threading jumps.

max-fields-for-field-sensitive

Maximum number of fields in a structure treated in a field sensitive manner during pointer analysis. The default is zero for **-O0** and **-O1**, and 100 for **-Os**, **-O2**, and **-O3**.

prefetch-latency

Estimate on average number of instructions that are executed before prefetch finishes. The distance prefetched ahead is proportional to this constant. Increasing this number may also lead to less streams being prefetched (see **simultaneous-prefetches**).

simultaneous-prefetches

Maximum number of prefetches that can run at the same time.

11-cache-line-size

The size of cache line in L1 cache, in bytes.

11-cache-size

The size of L1 cache, in kilobytes.

12-cache-size

The size of L2 cache, in kilobytes.

min-insn-to-prefetch-ratio

The minimum ratio between the number of instructions and the number of prefetches to enable prefetching in a loop.

prefetch-min-insn-to-mem-ratio

The minimum ratio between the number of instructions and the number of memory references to enable prefetching in a loop.

use-canonical-types

Whether the compiler should use the "canonical" type system. By default, this should always be 1, which uses a more efficient internal mechanism for comparing types in C++ and Objective–C++. However, if bugs in the canonical type system are causing compilation failures, set this value to 0 to disable canonical types.

switch-conversion-max-branch-ratio

Switch initialization conversion refuses to create arrays that are bigger than **switch-conversion-max-branch-ratio** times the number of branches in the switch.

max-partial-antic-length

Maximum length of the partial antic set computed during the tree partial redundancy elimination optimization (**-ftree-pre**) when optimizing at **-O3** and above. For some sorts of source code the enhanced partial redundancy elimination optimization can run away, consuming all of the memory available on the host machine. This parameter sets a limit on the length of the sets that are computed, which prevents the runaway behavior. Setting a value of 0 for this parameter allows an unlimited set length.

sccvn-max-scc-size

Maximum size of a strongly connected component (SCC) during SCCVN processing. If this limit is hit, SCCVN processing for the whole function is not done and optimizations depending on it are disabled. The default maximum SCC size is 10000.

sccvn-max-alias-queries-per-access

Maximum number of alias-oracle queries we perform when looking for redundancies for loads and stores. If this limit is hit the search is aborted and the load or store is not considered redundant. The number of queries is algorithmically limited to the number of stores on all paths from the load to the function entry. The default maximum number of queries is 1000.

ira-max-loops-num

IRA uses regional register allocation by default. If a function contains more loops than the number given by this parameter, only at most the given number of the most frequently-executed loops form regions for regional register allocation. The default value of the parameter is 100.

ira-max-conflict-table-size

Although IRA uses a sophisticated algorithm to compress the conflict table, the table can still require excessive amounts of memory for huge functions. If the conflict table for a function could be more than the size in MB given by this parameter, the register allocator instead uses a faster, simpler, and lower-quality algorithm that does not require building a pseudo-register conflict table. The default value of the parameter is 2000.

ira-loop-reserved-regs

IRA can be used to evaluate more accurate register pressure in loops for decisions to move loop invariants (see $-\mathbf{O3}$). The number of available registers reserved for some other purposes is given by this parameter. The default value of the parameter is 2, which is the minimal number of registers needed by typical instructions. This value is the best found from numerous experiments.

loop-invariant-max-bbs-in-loop

Loop invariant motion can be very expensive, both in compilation time and in amount of needed compile-time memory, with very large loops. Loops with more basic blocks than this parameter won't have loop invariant motion optimization performed on them. The default value of the parameter is 1000 for $-\mathbf{O1}$ and 10000 for $-\mathbf{O2}$ and above.

loop-max-datarefs-for-datadeps

Building data dapendencies is expensive for very large loops. This parameter limits the number of data references in loops that are considered for data dependence analysis. These large loops are no handled by the optimizations using loop data dependencies. The default value is 1000.

max-vartrack-size

Sets a maximum number of hash table slots to use during variable tracking dataflow analysis of any function. If this limit is exceeded with variable tracking at assignments enabled, analysis for that function is retried without it, after removing all debug insns from the function. If the limit is exceeded even without debug insns, var tracking analysis is completely disabled for the function. Setting the parameter to zero makes it unlimited.

max-vartrack-expr-depth

Sets a maximum number of recursion levels when attempting to map variable names or debug temporaries to value expressions. This trades compilation time for more complete debug information. If this is set too low, value expressions that are available and could be represented in debug information may end up not being used; setting this higher may enable the compiler to find more complex debug expressions, but compile time and memory use may grow. The default is 12.

min-nondebug-insn-uid

Use uids starting at this parameter for nondebug insns. The range below the parameter is reserved exclusively for debug insns created by **-fvar-tracking-assignments**, but debug insns may get (non-overlapping) uids above it if the reserved range is exhausted.

ipa-sra-ptr-growth-factor

IPA-SRA replaces a pointer to an aggregate with one or more new parameters only when their cumulative size is less or equal to **ipa-sra-ptr-growth-factor** times the size of the original pointer parameter.

tm-max-aggregate-size

When making copies of thread-local variables in a transaction, this parameter specifies the size in bytes after which variables are saved with the logging functions as opposed to save/restore code sequence pairs. This option only applies when using **-fgnu-tm**.

graphite-max-nb-scop-params

To avoid exponential effects in the Graphite loop transforms, the number of parameters in a Static Control Part (SCoP) is bounded. The default value is 10 parameters. A variable whose value is unknown at compilation time and defined outside a SCoP is a parameter of the SCoP.

graphite-max-bbs-per-function

To avoid exponential effects in the detection of SCoPs, the size of the functions analyzed by Graphite is bounded. The default value is 100 basic blocks.

loop-block-tile-size

Loop blocking or strip mining transforms, enabled with **–floop–block** or **–floop–strip–mine**, strip mine each loop in the loop nest by a given number of iterations. The strip length can be changed using the **loop-block-tile-size** parameter. The default value is 51 iterations.

ipa-cp-value-list-size

IPA-CP attempts to track all possible values and types passed to a function's parameter in order to propagate them and perform devirtualization. **ipa-cp-value-list-size** is the maximum number of values and types it stores per one formal parameter of a function.

Ito-partitions

Specify desired number of partitions produced during WHOPR compilation. The number of partitions should exceed the number of CPUs used for compilation. The default value is 32.

Ito-minpartition

Size of minimal partition for WHOPR (in estimated instructions). This prevents expenses of splitting very small programs into too many partitions.

cxx-max-namespaces-for-diagnostic-help

The maximum number of namespaces to consult for suggestions when C++ name lookup fails for an identifier. The default is 1000.

sink-frequency-threshold

The maximum relative execution frequency (in percents) of the target block relative to a statement's original block to allow statement sinking of a statement. Larger numbers result in more aggressive statement sinking. The default value is 75. A small positive adjustment is applied for statements with memory operands as those are even more profitable so sink.

max-stores-to-sink

The maximum number of conditional stores paires that can be sunk. Set to 0 if either vectorization (**-ftree-vectorize**) or if-conversion (**-ftree-loop-if-convert**) is disabled. The default is 2.

allow-load-data-races

Allow optimizers to introduce new data races on loads. Set to 1 to allow, otherwise to 0. This option is enabled by default unless implicitly set by the **-fmemory-model**= option.

allow-store-data-races

Allow optimizers to introduce new data races on stores. Set to 1 to allow, otherwise to 0. This option is enabled by default unless implicitly set by the **-fmemory-model**= option.

allow-packed-load-data-races

Allow optimizers to introduce new data races on packed data loads. Set to 1 to allow, otherwise to 0. This option is enabled by default unless implicitly set by the **-fmemory-model**= option.

allow-packed-store-data-races

Allow optimizers to introduce new data races on packed data stores. Set to 1 to allow, otherwise to 0. This option is enabled by default unless implicitly set by the **-fmemory-model**= option.

case-values-threshold

The smallest number of different values for which it is best to use a jump-table instead of a tree of conditional branches. If the value is 0, use the default for the machine. The default is 0.

tree-reassoc-width

Set the maximum number of instructions executed in parallel in reassociated tree. This parameter overrides target dependent heuristics used by default if has non zero value.

sched-pressure-algorithm

Choose between the two available implementations of **-fsched-pressure**. Algorithm 1 is the original implementation and is the more likely to prevent instructions from being reordered. Algorithm 2 was designed to be a compromise between the relatively conservative approach taken by algorithm 1 and the rather aggressive approach taken by the default scheduler. It relies more heavily on having a regular register file and accurate register pressure classes. See *haifa-sched.c* in the GCC sources for more details.

The default choice depends on the target.

max-slsr-cand-scan

Set the maximum number of existing candidates that will be considered when seeking a basis for a new straight-line strength reduction candidate.

Options Controlling the Preprocessor

These options control the C preprocessor, which is run on each C source file before actual compilation.

If you use the $-\mathbf{E}$ option, nothing is done except preprocessing. Some of these options make sense only together with $-\mathbf{E}$ because they cause the preprocessor output to be unsuitable for actual compilation.

-Wp,option

You can use **-Wp**, option to bypass the compiler driver and pass option directly through to the preprocessor. If option contains commas, it is split into multiple options at the commas. However, many options are modified, translated or interpreted by the compiler driver before being passed to the

preprocessor, and **-Wp** forcibly bypasses this phase. The preprocessor's direct interface is undocumented and subject to change, so whenever possible you should avoid using **-Wp** and let the driver handle the options instead.

-Xpreprocessor option

Pass *option* as an option to the preprocessor. You can use this to supply system-specific preprocessor options that GCC does not recognize.

If you want to pass an option that takes an argument, you must use **-Xpreprocessor** twice, once for the option and once for the argument.

-no-integrated-cpp

Perform preprocessing as a separate pass before compilation. By default, GCC performs preprocessing as an integrated part of input tokenization and parsing. If this option is provided, the appropriate language front end (**cc1**, **cc1plus**, or **cc1obj** for C, C++, and Objective-C, respectively) is instead invoked twice, once for preprocessing only and once for actual compilation of the preprocessed input. This option may be useful in conjunction with the **–B** or **–wrapper** options to specify an alternate preprocessor or perform additional processing of the program source between normal preprocessing and compilation.

−D name

Predefine *name* as a macro, with definition 1.

−D *name=definition*

The contents of *definition* are tokenized and processed as if they appeared during translation phase three in a **#define** directive. In particular, the definition will be truncated by embedded newline characters.

If you are invoking the preprocessor from a shell or shell-like program you may need to use the shell's quoting syntax to protect characters such as spaces that have a meaning in the shell syntax.

If you wish to define a function-like macro on the command line, write its argument list with surrounding parentheses before the equals sign (if any). Parentheses are meaningful to most shells, so you will need to quote the option. With **sh** and **csh**, **-D**'name(args...)=definition' works.

 $-\mathbf{D}$ and $-\mathbf{U}$ options are processed in the order they are given on the command line. All $-\mathbf{imacros}$ file and $-\mathbf{include}$ file options are processed after all $-\mathbf{D}$ and $-\mathbf{U}$ options.

-U name

Cancel any previous definition of *name*, either built in or provided with a $-\mathbf{D}$ option.

-undef

Do not predefine any system-specific or GCC-specific macros. The standard predefined macros remain defined.

−**I** dir

−o file

Write output to *file*. This is the same as specifying *file* as the second non-option argument to **cpp**. **gcc** has a different interpretation of a second non-option argument, so you must use $-\mathbf{o}$ to specify the output file.

-Wall

Turns on all optional warnings which are desirable for normal code. At present this is **–Wcomment**, **–Wtrigraphs**, **–Wmultichar** and a warning about integer promotion causing a change of sign in #if expressions. Note that many of the preprocessor's warnings are on by default and have no options to control them.

-Wcomment

-Wcomments

Warn whenever a comment-start sequence /* appears in a /* comment, or whenever a backslashnewline appears in a // comment. (Both forms have the same effect.)

-Wtrigraphs

Most trigraphs in comments cannot affect the meaning of the program. However, a trigraph that would form an escaped newline (??/ at the end of a line) can, by changing where the comment begins or ends. Therefore, only trigraphs that would form escaped newlines produce warnings inside a comment.

This option is implied by **-Wall**. If **-Wall** is not given, this option is still enabled unless trigraphs are enabled. To get trigraph conversion without warnings, but get the other **-Wall** warnings, use **-trigraphs -Wall -Wno-trigraphs**.

-Wtraditional

Warn about certain constructs that behave differently in traditional and ISO C. Also warn about ISO C constructs that have no traditional C equivalent, and problematic constructs which should be avoided.

-Wundef

Warn whenever an identifier which is not a macro is encountered in an **#if** directive, outside of **defined**. Such identifiers are replaced with zero.

-Wunused-macros

Warn about macros defined in the main file that are unused. A macro is *used* if it is expanded or tested for existence at least once. The preprocessor will also warn if the macro has not been used at the time it is redefined or undefined.

Built-in macros, macros defined on the command line, and macros defined in include files are not warned about.

Note: If a macro is actually used, but only used in skipped conditional blocks, then CPP will report it as unused. To avoid the warning in such a case, you might improve the scope of the macro's definition by, for example, moving it into the first skipped block. Alternatively, you could provide a dummy use with something like:

```
#if defined the_macro_causing_the_warning
#endif
```

-Wendif-labels

Warn whenever an **#else** or an **#endif** are followed by text. This usually happens in code of the form

```
#if FOO
...
#else FOO
...
#endif FOO
```

The second and third FOO should be in comments, but often are not in older programs. This warning is on by default.

-Werror

Make all warnings into hard errors. Source code which triggers warnings will be rejected.

-Wsystem-headers

Issue warnings for code in system headers. These are normally unhelpful in finding bugs in your own code, therefore suppressed. If you are responsible for the system library, you may want to see them.

-w Suppress all warnings, including those which GNU CPP issues by default.

-pedantic

Issue all the mandatory diagnostics listed in the C standard. Some of them are left out by default, since they trigger frequently on harmless code.

-pedantic-errors

Issue all the mandatory diagnostics, and make all mandatory diagnostics into errors. This includes mandatory diagnostics that GCC issues without **–pedantic** but treats as warnings.

$-\mathbf{M}$

Instead of outputting the result of preprocessing, output a rule suitable for **make** describing the dependencies of the main source file. The preprocessor outputs one **make** rule containing the object file name for that source file, a colon, and the names of all the included files, including those coming from **–include** or **–imacros** command line options.

Unless specified explicitly (with **-MT** or **-MQ**), the object file name consists of the name of the source file with any suffix replaced with object file suffix and with any leading directory parts removed. If there are many included files then the rule is split into several lines using \-newline. The rule has no commands.

This option does not suppress the preprocessor's debug output, such as **-dM**. To avoid mixing such debug output with the dependency rules you should explicitly specify the dependency output file with **-MF**, or use an environment variable like **DEPENDENCIES_OUTPUT**. Debug output will still be sent to the regular output stream as normal.

Passing –M to the driver implies –E, and suppresses warnings with an implicit –w.

-MM

Like –M but do not mention header files that are found in system header directories, nor header files that are included, directly or indirectly, from such a header.

This implies that the choice of angle brackets or double quotes in an **#include** directive does not in itself determine whether that header will appear in **-MM** dependency output. This is a slight change in semantics from GCC versions 3.0 and earlier.

-MF file

When used with $-\mathbf{M}$ or $-\mathbf{M}\mathbf{M}$, specifies a file to write the dependencies to. If no $-\mathbf{M}\mathbf{F}$ switch is given the preprocessor sends the rules to the same place it would have sent preprocessed output.

When used with the driver options -MD or -MMD, -MF overrides the default dependency output file.

-MG

In conjunction with an option such as -M requesting dependency generation, -MG assumes missing header files are generated files and adds them to the dependency list without raising an error. The dependency filename is taken directly from the #include directive without prepending any path. -MG also suppresses preprocessed output, as a missing header file renders this useless.

This feature is used in automatic updating of makefiles.

-MP

This option instructs CPP to add a phony target for each dependency other than the main file, causing each to depend on nothing. These dummy rules work around errors **make** gives if you remove header files without updating the *Makefile* to match.

This is typical output:

```
test.o: test.c test.h
test.h:
```

-MT target

Change the target of the rule emitted by dependency generation. By default CPP takes the name of the main input file, deletes any directory components and any file suffix such as .c, and appends the platform's usual object suffix. The result is the target.

An -MT option will set the target to be exactly the string you specify. If you want multiple targets, you can specify them as a single argument to -MT, or use multiple -MT options.

For example, -MT '\$(objpfx)foo.o' might give

```
$(objpfx)foo.o: foo.c
```

-MQ target

Same as -MT, but it quotes any characters which are special to Make. -MQ '\$(objpfx)foo.o' gives

```
$$(objpfx)foo.o: foo.c
```

The default target is automatically quoted, as if it were given with **-MQ**.

-MD

 $-\mathbf{MD}$ is equivalent to $-\mathbf{M}$ $-\mathbf{MF}$ file, except that $-\mathbf{E}$ is not implied. The driver determines file based on whether an $-\mathbf{o}$ option is given. If it is, the driver uses its argument but with a suffix of .d, otherwise it takes the name of the input file, removes any directory components and suffix, and applies a .d suffix.

If -MD is used in conjunction with -E, any -o switch is understood to specify the dependency output file, but if used without -E, each -o is understood to specify a target object file.

Since **–E** is not implied, **–MD** can be used to generate a dependency output file as a side-effect of the compilation process.

-MMD

Like –MD except mention only user header files, not system header files.

-fpch-deps

When using precompiled headers, this flag will cause the dependency-output flags to also list the files from the precompiled header's dependencies. If not specified only the precompiled header would be listed and not the files that were used to create it because those files are not consulted when a precompiled header is used.

-fpch-preprocess

This option allows use of a precompiled header together with **-E**. It inserts a special #pragma, #pragma GCC pch_preprocess "filename" in the output to mark the place where the precompiled header was found, and its *filename*. When **-fpreprocessed** is in use, GCC recognizes this #pragma and loads the PCH.

This option is off by default, because the resulting preprocessed output is only really suitable as input to GCC. It is switched on by **–save–temps**.

You should not write this #pragma in your own code, but it is safe to edit the filename if the PCH file is available in a different location. The filename may be absolute or it may be relative to GCC's current directory.

- -x c
- -x c++

-x objective-c

-x assembler-with-cpp

Specify the source language: C, C++, Objective-C, or assembly. This has nothing to do with standards conformance or extensions; it merely selects which base syntax to expect. If you give none of these options, cpp will deduce the language from the extension of the source file: .c, .cc, .m, or .S. Some other common extensions for C++ and assembly are also recognized. If cpp does not recognize the extension, it will treat the file as C; this is the most generic mode.

Note: Previous versions of cpp accepted a **-lang** option which selected both the language and the standards conformance level. This option has been removed, because it conflicts with the **-l** option.

-std=standard

-ansi

Specify the standard to which the code should conform. Currently CPP knows about C and C++ standards; others may be added in the future.

standard may be one of:

```
c90
c89
iso9899:1990
    The ISO C standard from 1990. c90 is the customary shorthand for this version of the standard.
    The -ansi option is equivalent to -std=c90.
iso9899:199409
    The 1990 C standard, as amended in 1994.
iso9899:1999
c99
iso9899:199x
c9x
    The revised ISO C standard, published in December 1999. Before publication, this was known as
iso9899:2011
c11
c1x
    The revised ISO C standard, published in December 2011. Before publication, this was known as
    C1X.
qnu90
gnu89
    The 1990 C standard plus GNU extensions. This is the default.
gnu99
gnu9x
    The 1999 C standard plus GNU extensions.
qnu11
gnu1x
    The 2011 C standard plus GNU extensions.
c++98
    The 1998 ISO C++ standard plus amendments.
anu++98
   The same as -std=c++98 plus GNU extensions. This is the default for C++ code.
```

-I-

Split the include path. Any directories specified with $-\mathbf{I}$ options before $-\mathbf{I}$ — are searched only for headers requested with #include "file"; they are not searched for #include <file>. If additional directories are specified with $-\mathbf{I}$ options after the $-\mathbf{I}$ —, those directories are searched for all #include directives.

In addition, —I— inhibits the use of the directory of the current file directory as the first search directory for #include "file". This option has been deprecated.

-nostdinc

Do not search the standard system directories for header files. Only the directories you have specified with –**I** options (and the directory of the current file, if appropriate) are searched.

-nostdinc++

Do not search for header files in the C++-specific standard directories, but do still search the other standard directories. (This option is used when building the C++ library.)

-include file

Process *file* as if #include "file" appeared as the first line of the primary source file. However, the first directory searched for *file* is the preprocessor's working directory *instead of* the directory containing the main source file. If not found there, it is searched for in the remainder of the #include "..." search chain as normal.

If multiple **-include** options are given, the files are included in the order they appear on the command line.

-imacros file

Exactly like **-include**, except that any output produced by scanning *file* is thrown away. Macros it defines remain defined. This allows you to acquire all the macros from a header without also processing its declarations.

All files specified by **-imacros** are processed before all files specified by **-include**.

-idirafter dir

Search *dir* for header files, but do it *after* all directories specified with –**I** and the standard system directories have been exhausted. *dir* is treated as a system include directory. If *dir* begins with =, then the = will be replaced by the system that the system and -isystem.

-iprefix prefix

Specify *prefix* as the prefix for subsequent **-iwithprefix** options. If the prefix represents a directory, you should include the final /.

-iwithprefix dir

-iwithprefixbefore dir

Append *dir* to the prefix specified previously with **-iprefix**, and add the resulting directory to the include search path. **-iwithprefixbefore** puts it in the same place **-I** would; **-iwithprefix** puts it where **-idirafter** would.

-isysroot dir

This option is like the —**sysroot** option, but applies only to header files (except for Darwin targets, where it applies to both header files and libraries). See the —**sysroot** option for more information.

-imultilib dir

Use *dir* as a subdirectory of the directory containing target-specific C++ headers.

-isystem dir

Search *dir* for header files, after all directories specified by **–I** but before the standard system directories. Mark it as a system directory, so that it gets the same special treatment as is applied to the standard system directories. If *dir* begins with =, then the = will be replaced by the system to the system directories. If *dir* begins with =, then the = will be replaced by the system to the system directories.

-iquote dir

Search *dir* only for header files requested with #include "file"; they are not searched for #include <file>, before all directories specified by -I and before the standard system directories. If *dir* begins with =, then the = will be replaced by the system prefix; see --systoot and -isystoot.

-fdirectives-only

When preprocessing, handle directives, but do not expand macros.

The option's behavior depends on the **–E** and **–fpreprocessed** options.

With $-\mathbf{E}$, preprocessing is limited to the handling of directives such as #define, #ifdef, and #error. Other preprocessor operations, such as macro expansion and trigraph conversion are not performed. In addition, the $-\mathbf{dD}$ option is implicitly enabled.

With **-fpreprocessed**, predefinition of command line and most builtin macros is disabled. Macros such as __LINE__, which are contextually dependent, are handled normally. This enables compilation of files previously preprocessed with -E -fdirectives-only.

With both $-\mathbf{E}$ and $-\mathbf{fpreprocessed}$, the rules for $-\mathbf{fpreprocessed}$ take precedence. This enables full preprocessing of files previously preprocessed with $-\mathbf{E}$ $-\mathbf{fdirectives-only}$.

-fdollars-in-identifiers

Accept \$ in identifiers.

-fextended-identifiers

Accept universal character names in identifiers. This option is experimental; in a future version of GCC, it will be enabled by default for C99 and C++.

-fno-canonical-system-headers

When preprocessing, do not shorten system header paths with canonicalization.

-fpreprocessed

Indicate to the preprocessor that the input file has already been preprocessed. This suppresses things like macro expansion, trigraph conversion, escaped newline splicing, and processing of most directives. The preprocessor still recognizes and removes comments, so that you can pass a file preprocessed with $-\mathbf{C}$ to the compiler without problems. In this mode the integrated preprocessor is little more than a tokenizer for the front ends.

-fpreprocessed is implicit if the input file has one of the extensions **.i**, **.ii** or **.mi**. These are the extensions that GCC uses for preprocessed files created by **-save-temps**.

-ftabstop=width

Set the distance between tab stops. This helps the preprocessor report correct column numbers in warnings or errors, even if tabs appear on the line. If the value is less than 1 or greater than 100, the option is ignored. The default is 8.

-fdebug-cpp

This option is only useful for debugging GCC. When used with **–E**, dumps debugging information about location maps. Every token in the output is preceded by the dump of the map its location belongs to. The dump of the map holding the location of a token would be:

```
{"P":F</file/path>;"F":F</includer/path>;"L":<line_num>;"C":<col_num>;"S'
```

When used without **–E**, this option has no effect.

-ftrack-macro-expansion[=level]

Track locations of tokens across macro expansions. This allows the compiler to emit diagnostic about the current macro expansion stack when a compilation error occurs in a macro expansion. Using this option makes the preprocessor and the compiler consume more memory. The *level* parameter can be used to choose the level of precision of token location tracking thus decreasing the memory consumption if necessary. Value **0** of *level* de-activates this option just as if no **-ftrack-macro-expansion** was present on the command line. Value **1** tracks tokens locations in a degraded mode for the sake of minimal memory overhead. In this mode all tokens resulting from the expansion of an argument of a function-like macro have the same location. Value **2** tracks tokens locations completely. This value is the most memory hungry. When this option is given no argument, the default parameter value is **2**.

Note that -ftrack-macro-expansion=2 is activated by default.

-fexec-charset=charset

Set the execution character set, used for string and character constants. The default is UTF-8. *charset* can be any encoding supported by the system's iconv library routine.

-fwide-exec-charset=charset

Set the wide execution character set, used for wide string and character constants. The default is UTF-32 or UTF-16, whichever corresponds to the width of wchar_t. As with **-fexec-charset**, charset can be any encoding supported by the system's iconv library routine; however, you will have problems with encodings that do not fit exactly in wchar_t.

-finput-charset=charset

Set the input character set, used for translation from the character set of the input file to the source character set used by GCC. If the locale does not specify, or GCC cannot get this information from the locale, the default is UTF-8. This can be overridden by either the locale or this command line option. Currently the command line option takes precedence if there's a conflict. *charset* can be any encoding supported by the system's iconv library routine.

-fworking-directory

Enable generation of linemarkers in the preprocessor output that will let the compiler know the current working directory at the time of preprocessing. When this option is enabled, the preprocessor will emit, after the initial linemarker, a second linemarker with the current working directory followed by two slashes. GCC will use this directory, when it's present in the preprocessed input, as the directory emitted as the current working directory in some debugging information formats. This option is implicitly enabled if debugging information is enabled, but this can be inhibited with the negated form **–fno–working–directory**. If the **–P** flag is present in the command line, this option has no effect, since no #line directives are emitted whatsoever.

-fno-show-column

Do not print column numbers in diagnostics. This may be necessary if diagnostics are being scanned by a program that does not understand the column numbers, such as **dejagnu**.

-A predicate=answer

Make an assertion with the predicate *predicate* and answer *answer*. This form is preferred to the older form **–A** *predicate*(*answer*), which is still supported, because it does not use shell special characters.

-A -predicate=answer

Cancel an assertion with the predicate *predicate* and answer *answer*.

-dCHARS

CHARS is a sequence of one or more of the following characters, and must not be preceded by a space. Other characters are interpreted by the compiler proper, or reserved for future versions of GCC, and so are silently ignored. If you specify characters whose behavior conflicts, the result is undefined.

M Instead of the normal output, generate a list of **#define** directives for all the macros defined during the execution of the preprocessor, including predefined macros. This gives you a way of finding out what is predefined in your version of the preprocessor. Assuming you have no file *foo.h*, the command

```
touch foo.h; cpp -dM foo.h
```

will show all the predefined macros.

If you use -dM without the -E option, -dM is interpreted as a synonym for -fdump-rtl-mach.

- **D** Like **M** except in two respects: it does *not* include the predefined macros, and it outputs *both* the #define directives and the result of preprocessing. Both kinds of output go to the standard output file.
- **N** Like **D**, but emit only the macro names, not their expansions.
- I Output **#include** directives in addition to the result of preprocessing.
- U Like **D** except that only macros that are expanded, or whose definedness is tested in preprocessor directives, are output; the output is delayed until the use or test of the macro; and **#undef** directives are also output for macros tested but undefined at the time.
- **-P** Inhibit generation of linemarkers in the output from the preprocessor. This might be useful when running the preprocessor on something that is not C code, and will be sent to a program which might be confused by the linemarkers.
- -C Do not discard comments. All comments are passed through to the output file, except for comments in processed directives, which are deleted along with the directive.

You should be prepared for side effects when using $-\mathbf{C}$; it causes the preprocessor to treat comments as tokens in their own right. For example, comments appearing at the start of what would be a directive line have the effect of turning that line into an ordinary source line, since the first token on the line is no longer a #.

-CC

Do not discard comments, including during macro expansion. This is like $-\mathbf{C}$, except that comments contained within macros are also passed through to the output file where the macro is expanded.

In addition to the side-effects of the **-C** option, the **-CC** option causes all C++-style comments inside a macro to be converted to C-style comments. This is to prevent later use of that macro from inadvertently commenting out the remainder of the source line.

The **-CC** option is generally used to support lint comments.

-traditional-cpp

Try to imitate the behavior of old-fashioned C preprocessors, as opposed to ISO C preprocessors.

-trigraphs

Process trigraph sequences. These are three-character sequences, all starting with ??, that are defined by ISO C to stand for single characters. For example, ??/ stands for \, so '??/n' is a character constant for a newline. By default, GCC ignores trigraphs, but in standard-conforming modes it converts them. See the -std and -ansi options.

The nine trigraphs and their replacements are

```
Trigraph: ??( ??) ??< ??> ??= ??/ ??' ??! ??-
Replacement: [ ] { } # \ ^ | ~
```

-remap

Enable special code to work around file systems which only permit very short file names, such as MS-DOS.

--help

--target-help

Print text describing all the command line options instead of preprocessing anything.

- -v Verbose mode. Print out GNU CPP's version number at the beginning of execution, and report the final form of the include path.

-version

--version

Print out GNU CPP's version number. With one dash, proceed to preprocess as normal. With two dashes, exit immediately.

Passing Options to the Assembler

You can pass options to the assembler.

-Wa, option

Pass *option* as an option to the assembler. If *option* contains commas, it is split into multiple options at the commas.

-Xassembler option

Pass option as an option to the assembler. You can use this to supply system-specific assembler options that GCC does not recognize.

If you want to pass an option that takes an argument, you must use **-Xassembler** twice, once for the option and once for the argument.

Options for Linking

These options come into play when the compiler links object files into an executable output file. They are meaningless if the compiler is not doing a link step.

object-file-name

A file name that does not end in a special recognized suffix is considered to name an object file or library. (Object files are distinguished from libraries by the linker according to the file contents.) If linking is done, these object files are used as input to the linker.

-c

-S

-E If any of these options is used, then the linker is not run, and object file names should not be used as arguments.

-llibrary

-l library

Search the library named *library* when linking. (The second alternative with the library as a separate argument is only for POSIX compliance and is not recommended.)

It makes a difference where in the command you write this option; the linker searches and processes libraries and object files in the order they are specified. Thus, **foo.o** –**lz bar.o** searches library **z** after file *foo.o* but before *bar.o*. If *bar.o* refers to functions in **z**, those functions may not be loaded.

The linker searches a standard list of directories for the library, which is actually a file named *liblibrary.a*. The linker then uses this file as if it had been specified precisely by name.

The directories searched include several standard system directories plus any that you specify with -L.

Normally the files found this way are library files——archive files whose members are object files. The linker handles an archive file by scanning through it for members which define symbols that have so far been referenced but not defined. But if the file that is found is an ordinary object file, it is linked in the usual fashion. The only difference between using an —I option and specifying a file name is that —I surrounds *library* with **lib** and .a and searches several directories.

-lobjc

You need this special case of the -l option in order to link an Objective-C or Objective-C++ program.

-nostartfiles

Do not use the standard system startup files when linking. The standard system libraries are used normally, unless **–nostdlib** or **–nodefaultlibs** is used.

-nodefaultlibs

Do not use the standard system libraries when linking. Only the libraries you specify are passed to the linker, and options specifying linkage of the system libraries, such as <code>-static-libgcc</code> or <code>-shared-libgcc</code>, are ignored. The standard startup files are used normally, unless <code>-nostartfiles</code> is used.

The compiler may generate calls to memcmp, memset, memcpy and memmove. These entries are usually resolved by entries in libc. These entry points should be supplied through some other mechanism when this option is specified.

-nostdlib

Do not use the standard system startup files or libraries when linking. No startup files and only the libraries you specify are passed to the linker, and options specifying linkage of the system libraries, such as -static-libgcc or -shared-libgcc, are ignored.

The compiler may generate calls to memcmp, memset, memcpy and memmove. These entries are usually resolved by entries in libc. These entry points should be supplied through some other mechanism when this option is specified.

One of the standard libraries bypassed by **-nostdlib** and **-nodefaultlibs** is *libgcc.a*, a library of internal subroutines which GCC uses to overcome shortcomings of particular machines, or special needs for some languages.

In most cases, you need *libgcc.a* even when you want to avoid other standard libraries. In other words, when you specify **–nostdlib** or **–nodefaultlibs** you should usually specify **–lgcc** as well. This ensures that you have no unresolved references to internal GCC library subroutines. (An example of such an internal subroutine is **__main**, used to ensure C++ constructors are called.)

-pie

Produce a position independent executable on targets that support it. For predictable results, you must also specify the same set of options used for compilation (**-fpie**, **-fPIE**, or model suboptions) when you specify this linker option.

-rdynamic

Pass the flag **-export-dynamic** to the ELF linker, on targets that support it. This instructs the linker to add all symbols, not only used ones, to the dynamic symbol table. This option is needed for some uses of dlopen or to allow obtaining backtraces from within a program.

-s Remove all symbol table and relocation information from the executable.

-static

On systems that support dynamic linking, this prevents linking with the shared libraries. On other systems, this option has no effect.

-shared

Produce a shared object which can then be linked with other objects to form an executable. Not all systems support this option. For predictable results, you must also specify the same set of options used for compilation (**-fpic**, **-fPIC**, or model suboptions) when you specify this linker option.[1]

-shared-libgcc

-static-libgcc

On systems that provide *libgcc* as a shared library, these options force the use of either the shared or static version, respectively. If no shared version of *libgcc* was built when the compiler was configured, these options have no effect.

There are several situations in which an application should use the shared *libgcc* instead of the static version. The most common of these is when the application wishes to throw and catch exceptions across different shared libraries. In that case, each of the libraries as well as the application itself should use the shared *libgcc*.

Therefore, the G++ and GCJ drivers automatically add **-shared-libgcc** whenever you build a shared library or a main executable, because C++ and Java programs typically use exceptions, so this is the right thing to do.

If, instead, you use the GCC driver to create shared libraries, you may find that they are not always linked with the shared *libgcc*. If GCC finds, at its configuration time, that you have a non-GNU linker or a GNU linker that does not support option —**eh-frame-hdr**, it links the shared version of *libgcc* into shared libraries by default. Otherwise, it takes advantage of the linker and optimizes away the linking with the shared version of *libgcc*, linking with the static version of *libgcc* by default. This allows exceptions to propagate through such shared libraries, without incurring relocation costs at library load time.

However, if a library or main executable is supposed to throw or catch exceptions, you must link it using the G++ or GCJ driver, as appropriate for the languages used in the program, or using the option **-shared-libgcc**, such that it is linked with the shared *libgcc*.

-static-libasan

When the **-fsanitize=address** option is used to link a program, the GCC driver automatically links against **libasan**. If *libasan* is available as a shared library, and the **-static** option is not used, then this links against the shared version of *libasan*. The **-static-libasan** option directs the GCC driver to link *libasan* statically, without necessarily linking other libraries statically.

-static-libtsan

When the **-fsanitize=thread** option is used to link a program, the GCC driver automatically links against **libtsan**. If *libtsan* is available as a shared library, and the **-static** option is not used, then this links against the shared version of *libtsan*. The **-static-libtsan** option directs the GCC driver to link *libtsan* statically, without necessarily linking other libraries statically.

-static-libstdc++

When the $\mathbf{g}++$ program is used to link a C++ program, it normally automatically links against $\mathbf{libstdc}++$. If libstdc++ is available as a shared library, and the $-\mathbf{static}$ option is not used, then this links against the shared version of libstdc++. That is normally fine. However, it is sometimes useful to freeze the version of libstdc++ used by the program without going all the way to a fully static link. The $-\mathbf{static}-\mathbf{libstdc}++$ option directs the $\mathbf{g}++$ driver to link libstdc++ statically, without necessarily linking other libraries statically.

-symbolic

Bind references to global symbols when building a shared object. Warn about any unresolved references (unless overridden by the link editor option **–Xlinker –z –Xlinker defs**). Only a few systems support this option.

-T script

Use *script* as the linker script. This option is supported by most systems using the GNU linker. On some targets, such as bare-board targets without an operating system, the $-\mathbf{T}$ option may be required when linking to avoid references to undefined symbols.

-Xlinker option

Pass *option* as an option to the linker. You can use this to supply system-specific linker options that GCC does not recognize.

If you want to pass an option that takes a separate argument, you must use **-Xlinker** twice, once for the option and once for the argument. For example, to pass **-assert definitions**, you must write **-Xlinker -assert -Xlinker definitions**. It does not work to write **-Xlinker "-assert definitions"**, because this passes the entire string as a single argument, which is not what the linker expects.

When using the GNU linker, it is usually more convenient to pass arguments to linker options using the *option=value* syntax than as separate arguments. For example, you can specify **-Xlinker -Map=output.map** rather than **-Xlinker -Map -Xlinker output.map**. Other linkers may not support this syntax for command-line options.

-Wl,option

Pass *option* as an option to the linker. If *option* contains commas, it is split into multiple options at the commas. You can use this syntax to pass an argument to the option. For example, **-Wl,-Map,output.map** passes **-Map output.map** to the linker. When using the GNU linker, you can also get the same effect with **-Wl,-Map=output.map**.

NOTE: In Ubuntu 8.10 and later versions, for LDFLAGS, the option **-Wl,-z,relro** is used. To disable, use **-Wl,-z,norelro**.

−**u** symbol

Pretend the symbol *symbol* is undefined, to force linking of library modules to define it. You can use **–u** multiple times with different symbols to force loading of additional library modules.

Options for Directory Search

These options specify directories to search for header files, for libraries and for parts of the compiler:

-Idir

Add the directory *dir* to the head of the list of directories to be searched for header files. This can be used to override a system header file, substituting your own version, since these directories are searched before the system header file directories. However, you should not use this option to add directories that contain vendor-supplied system header files (use **-isystem** for that). If you use more than one **-I** option, the directories are scanned in left-to-right order; the standard system directories come after.

If a standard system include directory, or a directory specified with **–isystem**, is also specified with **–I**, the **–I** option is ignored. The directory is still searched but as a system directory at its normal position in the system include chain. This is to ensure that GCC's procedure to fix buggy system headers and the ordering for the include_next directive are not inadvertently changed. If you really need to change the search order for system directories, use the **–nostdinc** and/or **–isystem** options.

-iplugindir=dir

Set the directory to search for plugins that are passed by **-fplugin**=*name* instead of **-fplugin**=*path*/*name*.**so**. This option is not meant to be used by the user, but only passed by the driver.

-iquotedir

Add the directory *dir* to the head of the list of directories to be searched for header files only for the case of **#include** '*file*'; they are not searched for **#include** <*file*>, otherwise just like –**I**.

-Ldir

Add directory *dir* to the list of directories to be searched for **-1**.

-**B**prefix

This option specifies where to find the executables, libraries, include files, and data files of the compiler itself.

The compiler driver program runs one or more of the subprograms **cpp**, **cc1**, **as** and **ld**. It tries *prefix* as a prefix for each program it tries to run, both with and without *machinelversionl*.

For each subprogram to be run, the compiler driver first tries the $-\mathbf{B}$ prefix, if any. If that name is not found, or if $-\mathbf{B}$ is not specified, the driver tries two standard prefixes, /usr/lib/gcc/ and /usr/local/lib/gcc/. If neither of those results in a file name that is found, the unmodified program name is searched for using the directories specified in your **PATH** environment variable.

The compiler checks to see if the path provided by the $-\mathbf{B}$ refers to a directory, and if necessary it adds a directory separator character at the end of the path.

−B prefixes that effectively specify directory names also apply to libraries in the linker, because the compiler translates these options into **−L** options for the linker. They also apply to includes files in the preprocessor, because the compiler translates these options into **−isystem** options for the preprocessor. In this case, the compiler appends **include** to the prefix.

The runtime support file libgcc.a can also be searched for using the $-\mathbf{B}$ prefix, if needed. If it is not found there, the two standard prefixes above are tried, and that is all. The file is left out of the link if it is not found by those means.

Another way to specify a prefix much like the -B prefix is to use the environment variable GCC EXEC PREFIX.

As a special kludge, if the path provided by $-\mathbf{B}$ is [dir/]stageN/, where N is a number in the range 0 to 9, then it is replaced by [dir/]include. This is to help with boot-strapping the compiler.

-specs=file

Process *file* after the compiler reads in the standard *specs* file, in order to override the defaults which the **gcc** driver program uses when determining what switches to pass to **cc1**, **cc1plus**, **as**, **ld**, etc. More than one **-specs**=*file* can be specified on the command line, and they are processed in order, from left to right.

--sysroot=dir

Use *dir* as the logical root directory for headers and libraries. For example, if the compiler normally searches for headers in /usr/include and libraries in /usr/lib, it instead searches dir/usr/include and dir/usr/lib.

If you use both this option and the **-isysroot** option, then the **--sysroot** option applies to libraries, but the **-isysroot** option applies to header files.

The GNU linker (beginning with version 2.16) has the necessary support for this option. If your linker does not support this option, the header file aspect of —**sysroot** still works, but the library aspect does not.

--no-sysroot-suffix

For some targets, a suffix is added to the root directory specified with —-sysroot, depending on the other options used, so that headers may for example be found in dir/suffix/usr/include instead of dir/usr/include. This option disables the addition of such a suffix.

-I-

This option has been deprecated. Please use **-iquote** instead for **-I** directories before the **-I**- and remove the **-I**-. Any directories you specify with **-I** options before the **-I**- option are searched only for the case of **#include** "*file*"; they are not searched for **#include** <*file*>.

If additional directories are specified with $-\mathbf{I}$ options after the $-\mathbf{I}$ -, these directories are searched for all **#include** directives. (Ordinarily *all* $-\mathbf{I}$ directories are used this way.)

In addition, the $-\mathbf{I}$ - option inhibits the use of the current directory (where the current input file came from) as the first search directory for **#include** "*file*". There is no way to override this effect of $-\mathbf{I}$ -. With $-\mathbf{I}$. you can specify searching the directory that is current when the compiler is invoked. That is not exactly the same as what the preprocessor does by default, but it is often satisfactory.

-I- does not inhibit the use of the standard system directories for header files. Thus, -I- and -nostdinc are independent.

Specifying Target Machine and Compiler Version

The usual way to run GCC is to run the executable called **gcc**, or *machine***–gcc** when cross-compiling, or *machine***–gcc**-*version* to run a version other than the one that was installed last.

Hardware Models and Configurations

Each target machine types can have its own special options, starting with -m, to choose among various hardware models or configurations——for example, 68010 vs 68020, floating coprocessor or none. A single installed version of the compiler can compile for any model or configuration, according to the options specified.

Some configurations of the compiler also support additional special options, usually for compatibility with other compilers on the same platform.

AArch64 Options

These options are defined for AArch64 implementations:

-mbig-endian

Generate big-endian code. This is the default when GCC is configured for an aarch64_be-*-* target.

-mgeneral-regs-only

Generate code which uses only the general registers.

-mlittle-endian

Generate little-endian code. This is the default when GCC is configured for an **aarch64**_*-* but not an **aarch64**_be-*-* target.

-mcmodel=tiny

Generate code for the tiny code model. The program and its statically defined symbols must be within 1GB of each other. Pointers are 64 bits. Programs can be statically or dynamically linked. This model is not fully implemented and mostly treated as **small**.

-mcmodel=small

Generate code for the small code model. The program and its statically defined symbols must be within 4GB of each other. Pointers are 64 bits. Programs can be statically or dynamically linked. This is the default code model.

-mcmodel=large

Generate code for the large code model. This makes no assumptions about addresses and sizes of sections. Pointers are 64 bits. Programs can be statically linked only.

-mstrict-align

Do not assume that unaligned memory references will be handled by the system.

-momit-leaf-frame-pointer

-mno-omit-leaf-frame-pointer

Omit or keep the frame pointer in leaf functions. The former behaviour is the default.

-mtls-dialect=desc

Use TLS descriptors as the thread-local storage mechanism for dynamic accesses of TLS variables. This is the default.

-mtls-dialect=traditional

Use traditional TLS as the thread-local storage mechanism for dynamic accesses of TLS variables.

-mfix-cortex-a53-835769

-mno-fix-cortex-a53-835769

Enable or disable the workaround for the ARM Cortex-A53 erratum number 835769. This will involve inserting a NOP instruction between memory instructions and 64-bit integer multiply-accumulate instructions.

-march=name

Specify the name of the target architecture, optionally suffixed by one or more feature modifiers. This option has the form $-\mathbf{march} = arch\{+[\mathbf{no}]feature\}^*$, where the only value for arch is $\mathbf{armv8} - \mathbf{a}$. The possible values for feature are documented in the sub-section below.

Where conflicting feature modifiers are specified, the right-most feature is used.

GCC uses this name to determine what kind of instructions it can emit when generating assembly code. This option can be used in conjunction with or instead of the **-mcpu**= option.

-mcpu=name

Specify the name of the target processor, optionally suffixed by one or more feature modifiers. This option has the form $-\mathbf{mcpu} = cpu\{+[\mathbf{no}]feature\}^*$, where the possible values for cpu are **generic**, **large**. The possible values for feature are documented in the sub-section below.

Where conflicting feature modifiers are specified, the right-most feature is used.

GCC uses this name to determine what kind of instructions it can emit when generating assembly code.

-mtune=name

Specify the name of the processor to tune the performance for. The code will be tuned as if the target processor were of the type specified in this option, but still using instructions compatible with the target processor specified by a **-mcpu**= option. This option cannot be suffixed by feature modifiers.

-march and -mcpu feature modifiers

Feature modifiers used with **-march** and **-mcpu** can be one the following:

crypto

Enable Crypto extension. This implies Advanced SIMD is enabled.

fp Enable floating-point instructions.

simd

Enable Advanced SIMD instructions. This implies floating-point instructions are enabled. This is the default for all current possible values for options **–march** and **–mcpu**=.

Adapteva Epiphany Options

These -m options are defined for Adapteva Epiphany:

-mhalf-reg-file

Don't allocate any register in the range r32...r63. That allows code to run on hardware variants that lack these registers.

-mprefer-short-insn-regs

Preferrentially allocate registers that allow short instruction generation. This can result in increased instruction count, so this may either reduce or increase overall code size.

-mbranch-cost=num

Set the cost of branches to roughly *num* "simple" instructions. This cost is only a heuristic and is not guaranteed to produce consistent results across releases.

-mcmove

Enable the generation of conditional moves.

-mnops=num

Emit *num* NOPs before every other generated instruction.

-mno-soft-cmpsf

For single-precision floating-point comparisons, emit an fsub instruction and test the flags. This is faster than a software comparison, but can get incorrect results in the presence of NaNs, or when two different small numbers are compared such that their difference is calculated as zero. The default is **-msoft-cmpsf**, which uses slower, but IEEE-compliant, software comparisons.

-mstack-offset=num

Set the offset between the top of the stack and the stack pointer. E.g., a value of 8 means that the eight bytes in the range sp+0...sp+7 can be used by leaf functions without stack allocation. Values other than 8 or 16 are untested and unlikely to work. Note also that this option changes the ABI; compiling a program with a different stack offset than the libraries have been compiled with generally does not work. This option can be useful if you want to evaluate if a different stack offset would give you better code, but to actually use a different stack offset to build working programs, it is recommended to configure the toolchain with the appropriate —with—stack—offset=num option.

-mno-round-nearest

Make the scheduler assume that the rounding mode has been set to truncating. The default is **-mround-nearest**.

-mlong-calls

If not otherwise specified by an attribute, assume all calls might be beyond the offset range of the b / bl instructions, and therefore load the function address into a register before performing a (otherwise direct) call. This is the default.

-mshort-calls

If not otherwise specified by an attribute, assume all direct calls are in the range of the b / bl instructions, so use these instructions for direct calls. The default is **-mlong-calls**.

-msmall16

Assume addresses can be loaded as 16-bit unsigned values. This does not apply to function addresses for which **-mlong-calls** semantics are in effect.

-mfp-mode=mode

Set the prevailing mode of the floating-point unit. This determines the floating-point mode that is provided and expected at function call and return time. Making this mode match the mode you predominantly need at function start can make your programs smaller and faster by avoiding unnecessary mode switches.

mode can be set to one the following values:

caller

Any mode at function entry is valid, and retained or restored when the function returns, and when it calls other functions. This mode is useful for compiling libraries or other compilation units you might want to incorporate into different programs with different prevailing FPU modes, and the convenience of being able to use a single object file outweighs the size and speed overhead for any extra mode switching that might be needed, compared with what would be needed with a more specific choice of prevailing FPU mode.

truncate

This is the mode used for floating-point calculations with truncating (i.e. round towards zero) rounding mode. That includes conversion from floating point to integer.

round-nearest

This is the mode used for floating-point calculations with round-to-nearest-or-even rounding mode.

int This is the mode used to perform integer calculations in the FPU, e.g. integer multiply, or integer multiply-and-accumulate.

The default is **-mfp-mode=caller**

-mnosplit-lohi

-mno-postinc

-mno-postmodify

Code generation tweaks that disable, respectively, splitting of 32-bit loads, generation of post-increment addresses, and generation of post-modify addresses. The defaults are **msplit-lohi**, **-mpost-inc**, and **-mpost-modify**.

-mnovect-double

Change the preferred SIMD mode to SImode. The default is **-mvect-double**, which uses DImode as preferred SIMD mode.

-max-vect-align=num

The maximum alignment for SIMD vector mode types. *num* may be 4 or 8. The default is 8. Note that this is an ABI change, even though many library function interfaces are unaffected if they don't use SIMD vector modes in places that affect size and/or alignment of relevant types.

-msplit-vecmove-early

Split vector moves into single word moves before reload. In theory this can give better register allocation, but so far the reverse seems to be generally the case.

-m1reg-reg

Specify a register to hold the constant -1, which makes loading small negative constants and certain bitmasks faster. Allowable values for *reg* are **r43** and **r63**, which specify use of that register as a fixed register, and **none**, which means that no register is used for this purpose. The default is **-m1reg-none**.

ARM Options

These -m options are defined for Advanced RISC Machines (ARM) architectures:

-mabi=name

Generate code for the specified ABI. Permissible values are: apcs-gnu, atpcs, aapcs, aapcs-linux and iwmmxt.

-mapcs-frame

Generate a stack frame that is compliant with the ARM Procedure Call Standard for all functions, even if this is not strictly necessary for correct execution of the code. Specifying **–fomit–frame–pointer** with this option causes the stack frames not to be generated for leaf functions. The default is **–mno–apcs–frame**.

-mapcs

This is a synonym for **-mapcs-frame**.

-mthumb-interwork

Generate code that supports calling between the ARM and Thumb instruction sets. Without this option, on pre-v5 architectures, the two instruction sets cannot be reliably used inside one program. The default is **-mno-thumb-interwork**, since slightly larger code is generated when **-mthumb-interwork** is specified. In AAPCS configurations this option is meaningless.

-mno-sched-prolog

Prevent the reordering of instructions in the function prologue, or the merging of those instruction with the instructions in the function's body. This means that all functions start with a recognizable set of instructions (or in fact one of a choice from a small set of different function prologues), and this information can be used to locate the start of functions inside an executable piece of code. The default is **-msched-prolog**.

-mfloat-abi=name

Specifies which floating-point ABI to use. Permissible values are: soft, softfp and hard.

Specifying **soft** causes GCC to generate output containing library calls for floating-point operations. **softfp** allows the generation of code using hardware floating-point instructions, but still uses the soft-float calling conventions. **hard** allows generation of floating-point instructions and uses FPU-specific calling conventions.

The default depends on the specific target configuration. Note that the hard-float and soft-float ABIs are not link-compatible; you must compile your entire program with the same ABI, and link with a compatible set of libraries.

-mlittle-endian

Generate code for a processor running in little-endian mode. This is the default for all standard configurations.

-mbig-endian

Generate code for a processor running in big-endian mode; the default is to compile code for a little-endian processor.

-mwords-little-endian

This option only applies when generating code for big-endian processors. Generate code for a little-endian word order but a big-endian byte order. That is, a byte order of the form **32107654**. Note: this option should only be used if you require compatibility with code for big-endian ARM processors generated by versions of the compiler prior to 2.8. This option is now deprecated.

-march=name

This specifies the name of the target ARM architecture. GCC uses this name to determine what kind of instructions it can emit when generating assembly code. This option can be used in conjunction with or instead of the -mcpu= option. Permissible names are: armv2, armv2a, armv3, armv3m, armv4, armv4t, armv5, armv5t, armv5e, armv5te, armv6t, armv6j, armv6t2, armv6zk, armv6-m, armv7, armv7-a, armv7-r, armv7-m, armv7e-m armv8-a, iwmmxt, iwmmxt2, ep9312.

-march=native causes the compiler to auto-detect the architecture of the build computer. At present, this feature is only supported on GNU/Linux, and not all architectures are recognized. If the auto-detect is unsuccessful the option has no effect.

-mtune=name

This option specifies the name of the target ARM processor for which GCC should tune the performance of the code. For some ARM implementations better performance can be obtained by using this option. Permissible names are: arm2, arm250, arm3, arm6, arm60, arm600, arm610, arm620, arm7, arm7m, arm7d, arm7dm, arm7di, arm7dmi, arm70, arm700, arm700i, arm710, arm710c, arm7100, arm720, arm7500, arm7500fe, arm7tdmi, arm7tdmi—s, arm710t, arm720t, arm740t, strongarm, strongarm110, strongarm1100, strongarm1110, arm8, arm810, arm9, arm9e, arm920, arm920t, arm922t, arm946e—s, arm966e—s, arm968e—s, arm926ej—s, arm940t, arm9tdmi, arm10tdmi, arm1020t, arm1026ej—s, arm10e, arm1020e, arm1022e, arm1136j—s, arm1136jf—s, mpcore, mpcorenovfp, arm1156t2—s, arm1156t2f—s, arm1176jz—s, arm1176jzf—s, cortex—a5, cortex—a7, cortex—a8, cortex—a9, cortex—a15, cortex—r4, cortex—r4f, cortex—r5, cortex—m4, cortex—m3, cortex—m1, cortex—m0, cortex—m0plus, marvell—pj4, xscale, iwmmxt, iwmmxt2, ep9312, fa526, fa626, fa606te, fa626te, fmp626, fa726te.

-mtune=generic–*arch* specifies that GCC should tune the performance for a blend of processors within architecture *arch*. The aim is to generate code that run well on the current most popular processors, balancing between optimizations that benefit some CPUs in the range, and avoiding performance pitfalls of other CPUs. The effects of this option may change in future GCC versions as CPU models come and go.

-mtune=native causes the compiler to auto-detect the CPU of the build computer. At present, this feature is only supported on GNU/Linux, and not all architectures are recognized. If the auto-detect is

unsuccessful the option has no effect.

-mcpu=*name*

This specifies the name of the target ARM processor. GCC uses this name to derive the name of the target ARM architecture (as if specified by **-march**) and the ARM processor type for which to tune for performance (as if specified by **-mtune**). Where this option is used in conjunction with **-march** or **-mtune**, those options take precedence over the appropriate part of this option.

Permissible names for this option are the same as those for -mtune.

-mcpu=generic-*arch* is also permissible, and is equivalent to **-march**=*arch* **-mtune**=**generic**-*arch*. See **-mtune** for more information.

-mcpu=native causes the compiler to auto-detect the CPU of the build computer. At present, this feature is only supported on GNU/Linux, and not all architectures are recognized. If the auto-detect is unsuccessful the option has no effect.

-mfpu=name

This specifies what floating-point hardware (or hardware emulation) is available on the target. Permissible names are: vfp, vfpv3, vfpv3-fp16, vfpv3-d16, vfpv3-d16-fp16, vfpv3xd, vfpv3xd-fp16, neon, neon-fp16, vfpv4, vfpv4-d16, fpv4-sp-d16, neon-vfpv4, fp-armv8, neon-fp-armv8, and crypto-neon-fp-armv8.

If **-msoft-float** is specified this specifies the format of floating-point values.

If the selected floating-point hardware includes the NEON extension (e.g. **-mfpu=neon**), note that floating-point operations are not generated by GCC's auto-vectorization pass unless **-funsafe-math-optimizations** is also specified. This is because NEON hardware does not fully implement the IEEE 754 standard for floating-point arithmetic (in particular denormal values are treated as zero), so the use of NEON instructions may lead to a loss of precision.

-mfp16-format=name

Specify the format of the __fp16 half-precision floating-point type. Permissible names are **none**, **ieee**, and **alternative**; the default is **none**, in which case the __fp16 type is not defined.

-mstructure-size-boundary=n

The sizes of all structures and unions are rounded up to a multiple of the number of bits set by this option. Permissible values are 8, 32 and 64. The default value varies for different toolchains. For the COFF targeted toolchain the default value is 8. A value of 64 is only allowed if the underlying ABI supports it.

Specifying a larger number can produce faster, more efficient code, but can also increase the size of the program. Different values are potentially incompatible. Code compiled with one value cannot necessarily expect to work with code or libraries compiled with another value, if they exchange information using structures or unions.

-mabort-on-noreturn

Generate a call to the function abort at the end of a noreturn function. It is executed if the function tries to return.

-mlong-calls

-mno-long-calls

Tells the compiler to perform function calls by first loading the address of the function into a register and then performing a subroutine call on this register. This switch is needed if the target function lies outside of the 64–megabyte addressing range of the offset-based version of subroutine call instruction.

Even if this switch is enabled, not all function calls are turned into long calls. The heuristic is that static functions, functions that have the **short-call** attribute, functions that are inside the scope of a **#pragma no_long_calls** directive, and functions whose definitions have already been compiled within the current compilation unit are not turned into long calls. The exceptions to this rule are that weak function definitions, functions with the **long-call** attribute or the **section** attribute, and functions that are within the scope of a **#pragma long_calls** directive are always turned into long calls.

This feature is not enabled by default. Specifying **-mno-long-calls** restores the default behavior, as does placing the function calls within the scope of a **#pragma long_calls_off** directive. Note these switches have no effect on how the compiler generates code to handle function calls via function pointers.

-msingle-pic-base

Treat the register used for PIC addressing as read-only, rather than loading it in the prologue for each function. The runtime system is responsible for initializing this register with an appropriate value before execution begins.

-mpic-register=reg

Specify the register to be used for PIC addressing. For standard PIC base case, the default will be any suitable register determined by compiler. For single PIC base case, the default is **R9** if target is EABI based or stack-checking is enabled, otherwise the default is **R10**.

-mpoke-function-name

Write the name of each function into the text section, directly preceding the function prologue. The generated code is similar to this:

```
t0
    .ascii "arm_poke_function_name", 0
    .align
t1
    .word 0xff000000 + (t1 - t0)
arm_poke_function_name
    mov    ip, sp
    stmfd    sp!, {fp, ip, lr, pc}
    sub     fp, ip, #4
```

When performing a stack backtrace, code can inspect the value of pc stored at fp + 0. If the trace function then looks at location pc - 12 and the top 8 bits are set, then we know that there is a function name embedded immediately preceding this location and has length (pc[-3]) & 0xff000000.

-mthumb

-marm

Select between generating code that executes in ARM and Thumb states. The default for most configurations is to generate code that executes in ARM state, but the default can be changed by configuring GCC with the —with—mode=state configure option.

-mtpcs-frame

Generate a stack frame that is compliant with the Thumb Procedure Call Standard for all non-leaf functions. (A leaf function is one that does not call any other functions.) The default is **-mno-tpcs-frame**.

-mtpcs-leaf-frame

Generate a stack frame that is compliant with the Thumb Procedure Call Standard for all leaf functions. (A leaf function is one that does not call any other functions.) The default is **-mno-apcs-leaf-frame**.

-mcallee-super-interworking

Gives all externally visible functions in the file being compiled an ARM instruction set header which switches to Thumb mode before executing the rest of the function. This allows these functions to be called from non-interworking code. This option is not valid in AAPCS configurations because interworking is enabled by default.

-mcaller-super-interworking

Allows calls via function pointers (including virtual functions) to execute correctly regardless of whether the target code has been compiled for interworking or not. There is a small overhead in the cost of executing a function pointer if this option is enabled. This option is not valid in AAPCS

configurations because interworking is enabled by default.

-mtp=name

Specify the access model for the thread local storage pointer. The valid models are **soft**, which generates calls to __aeabi_read_tp, **cp15**, which fetches the thread pointer from cp15 directly (supported in the arm6k architecture), and **auto**, which uses the best available method for the selected processor. The default setting is **auto**.

-mtls-dialect=dialect

Specify the dialect to use for accessing thread local storage. Two *dialects* are supported——**gnu** and **gnu2**. The **gnu** dialect selects the original GNU scheme for supporting local and global dynamic TLS models. The **gnu2** dialect selects the GNU descriptor scheme, which provides better performance for shared libraries. The GNU descriptor scheme is compatible with the original scheme, but does require new assembler, linker and library support. Initial and local exec TLS models are unaffected by this option and always use the original scheme.

-mword-relocations

Only generate absolute relocations on word-sized values (i.e. R_ARM_ABS32). This is enabled by default on targets (uClinux, SymbianOS) where the runtime loader imposes this restriction, and when **-fpic** or **-fPIC** is specified.

-mfix-cortex-m3-ldrd

Some Cortex-M3 cores can cause data corruption when ldrd instructions with overlapping destination and base registers are used. This option avoids generating these instructions. This option is enabled by default when **-mcpu=cortex-m3** is specified.

-munaligned-access

-mno-unaligned-access

Enables (or disables) reading and writing of 16– and 32– bit values from addresses that are not 16– or 32– bit aligned. By default unaligned access is disabled for all pre–ARMv6 and all ARMv6–M architectures, and enabled for all other architectures. If unaligned access is not enabled then words in packed data structures will be accessed a byte at a time.

The ARM attribute Tag_CPU_unaligned_access will be set in the generated object file to either true or false, depending upon the setting of this option. If unaligned access is enabled then the preprocessor symbol __ARM_FEATURE_UNALIGNED will also be defined.

AVR Options

These options are defined for AVR implementations:

-mmcu=mcu

Specify Atmel AVR instruction set architectures (ISA) or MCU type.

The default for this option is@tie{}avr2.

GCC supports the following AVR devices and ISAs:

avr2

"Classic" devices with up to $8@tie{}$ KiB of program memory. $mcu@tie{}$ = attiny22, attiny26, at90c8534, at90s2313, at90s2323, at90s2333, at90s2343, at90s4414, at90s4433, at90s4434, at90s8515, at90s8535.

avr25

"Classic" devices with up to 8@tie{}KiB of program memory and with the MOVW instruction. mcu@tie{}= ata5272, ata6289, attiny13, attiny13a, attiny2313, attiny2313a, attiny24, attiny24a, attiny25, attiny261, attiny261a, attiny43u, attiny4313, attiny44, attiny44a, attiny45, attiny461, attiny461a, attiny48, attiny84, attiny84a, attiny85, attiny861, attiny861a, attiny87, attiny88, at86rf401.

avr3

"Classic" devices with 16@tie{}KiB up to 64@tie{}KiB of program memory. mcu@tie{}= at43usb355, at76c711.

avr31

"Classic" devices with 128@tie{}KiB of program memory. $mcu@tie{}$ = atmega103, at43usb320.

avr35

"Classic" devices with 16@tie{}KiB up to 64@tie{}KiB of program memory and with the MOVW instruction. mcu@tie{}= ata5505, atmega16u2, atmega32u2, atmega8u2, attiny1634, attiny167, at90usb162, at90usb82.

avr4

"Enhanced" devices with up to 8@tie{}KiB of program memory. mcu@tie{}= ata6285, ata6286, atmega48, atmega48a, atmega48p, atmega48pa, atmega8, atmega8a, atmega8hva, atmega8515, atmega8535, atmega88, atmega88a, atmega88p, atmega88pa, at90pwm1, at90pwm2, at90pwm2b, at90pwm3b, at90pwm81.

avr5

"Enhanced" devices with 16@tie{}KiB up to 64@tie{}KiB of program memory. mcu@tie{}= ata5790n, ata5795, atmega16, atmega16a, atmegal6hva2, atmegal6hvb, atmegal6hvbrevb, atmegal6ml, atmegal6u4, atmega161, atmega162, atmega163, atmega164a, atmega164p, atmega164pa, atmega165, atmega165a, atmega165p, atmega165pa, atmega168, atmega168a, atmega168p, atmega168pa, atmega169, atmega169a, atmega169p, atmega169pa, atmega26hvg, atmega32, atmega32a, atmega32c1, atmega32hvb, atmega32hvbrevb, atmega32m1, atmega32u4, atmega32u6, atmega323, atmega324a, atmega324p, atmega324pa, atmega325a, atmega325a, atmega325p, atmega3250a, atmega3250p, atmega3250pa, atmega3250, atmega328, atmega328p, atmega329, atmega329a, atmega329p, atmega329pa, atmega3290, atmega3290a, atmega3290p, atmega3290pa, atmega406, atmega48hvf, atmega64, atmega64a, atmega64c1, atmega64hve, atmega64m1, atmega64rfa2, atmega64rfr2, atmega640, atmega644, atmega644a, atmega644p, atmega644pa, atmega645, atmega645a, atmega645p, atmega6450, atmega6450p, atmega649, atmega6450a, atmega649a, atmega649p, atmega6490, atmega6490a, atmega6490p, at90can32, at90can64, at90pwm161, at90pwm216, at90pwm316, at90scr100, at90usb646, at90usb647, at94k, m3000.

avr51

"Enhanced" devices with 128@tie{}KiB of program memory. mcu@tie{}= atmega128, atmega128a, atmega128rfa1, atmega1280, atmega1281, atmega1284, atmega1284p, at90can128, at90usb1286, at90usb1287.

avr6

"Enhanced" devices with 3-byte PC, i.e. with more than $128@tie{}$ KiB of program memory. $mcu@tie{}$ = atmega2560, atmega2561.

avrxmega2

"XMEGA" devices with more than $8@tie{KiB}$ and up to $64@tie{KiB}$ of program memory. $mcu@tie{}$ = atmxt112s1, atmxt224, atmxt224e, atmxt336s, atxmega16a4, atxmega16a4u, atxmega16c4, atxmega16c4, atxmega16c1, atxmega32a4, atxmega32a4u, atxmega32c4, atxmega32c4, atxmega32c5, atxmega32x1.

avrxmega4

"XMEGA" devices with more than 64@tie{}KiB and up to 128@tie{}KiB of program memory. mcu@tie{}= atxmega64a3, atxmega64a3u, atxmega64a4u, atxmega64b1,

atxmega64b3, atxmega64c3, atxmega64d3, atxmega64d4.

avrxmega5

"XMEGA" devices with more than $64@tie{}$ KiB and up to $128@tie{}$ KiB of program memory and more than $64@tie{}$ KiB of RAM. $mcu@tie{}$ = atxmega64a1, atxmega64a1u.

avrxmega6

"XMEGA" devices with more than 128@tie{}KiB of program memory. mcu@tie{}= atmxt540s, atmxt540sreva, atxmega128a3, atxmega128a3u, atxmega128b1, atxmega128b3, atxmega128c3, atxmega128d3, atxmega128d4, atxmega192a3, atxmega192a3u, atxmega192c3, atxmega192d3, atxmega256a3b, atxmega256a3bu, atxmega256a3bu, atxmega256c3, atxmega256d3, atxmega384c3, atxmega384c3.

avrxmega7

"XMEGA" devices with more than 128@tie{}KiB of program memory and more than 64@tie{}KiB of RAM. mcu@tie{}= atxmega128a1, atxmega128a1u, atxmega128a4u.

avr1

This ISA is implemented by the minimal AVR core and supported for assembler only. $mcu@tie\{\}=$ attiny11, attiny12, attiny15, attiny28, at90s1200.

-maccumulate-args

Accumulate outgoing function arguments and acquire/release the needed stack space for outgoing function arguments once in function prologue/epilogue. Without this option, outgoing arguments are pushed before calling a function and popped afterwards.

Popping the arguments after the function call can be expensive on AVR so that accumulating the stack space might lead to smaller executables because arguments need not to be removed from the stack after such a function call.

This option can lead to reduced code size for functions that perform several calls to functions that get their arguments on the stack like calls to printf-like functions.

-mbranch-cost=cost

Set the branch costs for conditional branch instructions to *cost*. Reasonable values for *cost* are small, non-negative integers. The default branch cost is 0.

-mcall-prologues

Functions prologues/epilogues are expanded as calls to appropriate subroutines. Code size is smaller.

-mint8

Assume int to be 8-bit integer. This affects the sizes of all types: a char is 1 byte, an int is 1 byte, a long is 2 bytes, and long long is 4 bytes. Please note that this option does not conform to the C standards, but it results in smaller code size.

-mno-interrupts

Generated code is not compatible with hardware interrupts. Code size is smaller.

-mrelax

Try to replace CALL resp. JMP instruction by the shorter RCALL resp. RJMP instruction if applicable. Setting -mrelax just adds the --relax option to the linker command line when the linker is called.

Jump relaxing is performed by the linker because jump offsets are not known before code is located. Therefore, the assembler code generated by the compiler is the same, but the instructions in the executable may differ from instructions in the assembler code.

Relaxing must be turned on if linker stubs are needed, see the section on EIND and linker stubs below.

-msp8

Treat the stack pointer register as an 8-bit register, i.e. assume the high byte of the stack pointer is zero. In general, you don't need to set this option by hand.

This option is used internally by the compiler to select and build multilibs for architectures avr2 and avr25. These architectures mix devices with and without SPH. For any setting other than -mmcu=avr2 or -mmcu=avr25 the compiler driver will add or remove this option from the compiler proper's command line, because the compiler then knows if the device or architecture has an 8-bit stack pointer and thus no SPH register or not.

-mstrict-X

Use address register X in a way proposed by the hardware. This means that X is only used in indirect, post-increment or pre-decrement addressing.

Without this option, the X register may be used in the same way as Y or Z which then is emulated by additional instructions. For example, loading a value with X+const addressing with a small nonnegative const < 64 to a register *Rn* is performed as

-mtiny-stack

Only change the lower 8@tie{}bits of the stack pointer.

-Waddr-space-convert

Warn about conversions between address spaces in the case where the resulting address space is not contained in the incoming address space.

EIND and Devices with more than 128 Ki Bytes of Flash

Pointers in the implementation are 16@tie{}bits wide. The address of a function or label is represented as word address so that indirect jumps and calls can target any code address in the range of 64@tie{}Ki words.

In order to facilitate indirect jump on devices with more than 128@tie{}Ki bytes of program memory space, there is a special function register called EIND that serves as most significant part of the target address when EICALL or EIJMP instructions are used.

Indirect jumps and calls on these devices are handled as follows by the compiler and are subject to some limitations:

- The compiler never sets EIND.
- The compiler uses EIND implicitely in EICALL/EIJMP instructions or might read EIND directly in order to emulate an indirect call/jump by means of a RET instruction.
- The compiler assumes that EIND never changes during the startup code or during the application. In particular, EIND is not saved/restored in function or interrupt service routine prologue/epilogue.
- For indirect calls to functions and computed goto, the linker generates *stubs*. Stubs are jump pads sometimes also called *trampolines*. Thus, the indirect call/jump jumps to such a stub. The stub contains a direct jump to the desired address.
- Linker relaxation must be turned on so that the linker will generate the stubs correctly an all situaltion. See the compiler option -mrelax and the linler option --relax. There are corner cases where the linker is supposed to generate stubs but aborts without relaxation and without a helpful error message.
- The default linker script is arranged for code with EIND = 0. If code is supposed to work for a setup with EIND != 0, a custom linker script has to be used in order to place the sections whose name start with .trampolines into the segment where EIND points to.
- The startup code from libgcc never sets EIND. Notice that startup code is a blend of code from libgcc and AVR-LibC. For the impact of AVR-LibC on EIND, see the AVR-LibC user manual (http://nongnu.org/avr-libc/user-manual/).
- It is legitimate for user-specific startup code to set up EIND early, for example by means of initialization code located in section .init3. Such code runs prior to general startup code that

initializes RAM and calls constructors, but after the bit of startup code from AVR-LibC that sets EIND to the segment where the vector table is located.

The __trampolines_start symbol is defined in the linker script.

- Stubs are generated automatically by the linker if the following two conditions are met:
 - -<The address of a label is taken by means of the gs modifier> (short for *generate stubs*) like so:

```
LDI r24, lo8(gs(<func>))
LDI r25, hi8(gs(<func>))
```

- -<The final location of that label is in a code segment> outside the segment where the stubs are located.
- The compiler emits such gs modifiers for code labels in the following situations:
 - -< Taking address of a function or code label.>
 - -<Computed goto.>
 - -<If prologue-save function is used, see -mcall-prologues> command-line option.
 - -<Switch/case dispatch tables. If you do not want such dispatch> tables you can specify the -fno-jump-tables command-line option.
 - -<C and C++ constructors/destructors called during startup/shutdown.>
 - -<If the tools hit a gs() modifier explained above.>
- Jumping to non-symbolic addresses like so is *not* supported:

```
int main (void)
{
    /* Call function at word address 0x2 */
    return ((int(*)(void)) 0x2)();
}
```

Instead, a stub has to be set up, i.e. the function has to be called through a symbol (func_4 in the example):

```
int main (void)
{
    extern int func_4 (void);

    /* Call function at byte address 0x4 */
    return func_4();
}
```

and the application be linked with -Wl,--defsym,func_4=0x4. Alternatively, func_4 can be defined in the linker script.

Handling of the RAMPD, RAMPX, RAMPY and RAMPZ Special Function Registers

Some AVR devices support memories larger than the 64@tie{}KiB range that can be accessed with 16-bit

pointers. To access memory locations outside this 64@tie{}KiB range, the contentent of a RAMP register is used as high part of the address: The X, Y, Z address register is concatenated with the RAMPX, RAMPY, RAMPZ special function register, respectively, to get a wide address. Similarly, RAMPD is used together with direct addressing.

- The startup code initializes the RAMP special function registers with zero.
- If a AVR Named Address Spaces,named address space other than generic or __flash is used, then RAMPZ is set as needed before the operation.
- If the device supports RAM larger than 64@tie{KiB} and the compiler needs to change RAMPZ to accomplish an operation, RAMPZ is reset to zero after the operation.
- If the device comes with a specific RAMP register, the ISR prologue/epilogue saves/restores that SFR and initializes it with zero in case the ISR code might (implicitly) use it.
- RAM larger than 64@tie{KiB} is not supported by GCC for AVR targets. If you use inline assembler
 to read from locations outside the 16-bit address range and change one of the RAMP registers, you
 must reset it to zero after the access.

AVR Built-in Macros

GCC defines several built-in macros so that the user code can test for the presence or absence of features. Almost any of the following built-in macros are deduced from device capabilities and thus triggered by the -mmcu= command-line option.

For even more AVR-specific built-in macros see AVR Named Address Spaces and AVR Built-in Functions.

```
__AVR_ARCH__
```

Build-in macro that resolves to a decimal number that identifies the architecture and depends on the -mmcu=mcu option. Possible values are:

```
2, 25, 3, 31, 35, 4, 5, 51, 6, 102, 104, 105, 106, 107
```

for mcu=avr2, avr25, avr3, avr31, avr35, avr4, avr5, avr51, avr6, avrxmega2, avrxmega4, avrxmega5, avrxmega6, avrxmega7, respectively. If mcu specifies a device, this built-in macro is set accordingly. For example, with -mmcu=atmega8 the macro will be defined to 4.

```
__AVR_Device__
```

Setting -mmcu=device defines this built-in macro which reflects the device's name. For example, -mmcu=atmega8 defines the built-in macro __AVR_ATmega8__, -mmcu=attiny261a defines __AVR_ATtiny261A__, etc.

The built-in macros' names follow the scheme __AVR_Device_ where Device is the device name as from the AVR user manual. The difference between Device in the built-in macro and device in _mmcu=device is that the latter is always lowercase.

If device is not a device but only a core architecture like avr51, this macro will not be defined.

```
__AVR_XMEGA__
The device / architecture belongs to the XMEGA family of devices.

__AVR_HAVE_ELPM__
The device has the the ELPM instruction.

__AVR_HAVE_ELPMX__
The device has the ELPM Rn, Z and ELPM Rn, Z+ instructions.

__AVR_HAVE_MOVW__
```

gcc-4.8 2015-06-23 132

The device has the MOVW instruction to perform 16-bit register-register moves.

```
__AVR_HAVE_LPMX__
    The device has the LPM Rn, Z and LPM Rn, Z+ instructions.
__AVR_HAVE_MUL__
    The device has a hardware multiplier.
AVR HAVE JMP CALL
    The device has the JMP and CALL instructions. This is the case for devices with at least 16@tie{}KiB
    of program memory.
__AVR_HAVE_EIJMP_EICALL__
__AVR_3_BYTE_PC__
    The device has the EIJMP and EICALL instructions. This is the case for devices with more than
    128@tie{}KiB of program memory. This also means that the program counter (PC) is 3@tie{}bytes
    wide.
__AVR_2_BYTE_PC__
    The program counter (PC) is 2@tie{}bytes wide. This is the case for devices with up to 128@tie{}KiB
    of program memory.
__AVR_HAVE_8BIT_SP__
__AVR_HAVE_16BIT_SP__
    The stack pointer (SP) register is treated as 8-bit respectively 16-bit register by the compiler. The
    definition of these macros is affected by -mtiny-stack.
__AVR_HAVE_SPH__
__AVR_SP8__
    The device has the SPH (high part of stack pointer) special function register or has an 8-bit stack
    pointer, respectively. The definition of these macros is affected by -mmcu= and in the cases of
    -mmcu=avr2 and -mmcu=avr25 also by -msp8.
AVR HAVE RAMPD
__AVR_HAVE_RAMPX__
__AVR_HAVE_RAMPY__
__AVR_HAVE_RAMPZ__
    The device has the RAMPD, RAMPY, RAMPY, RAMPZ special function register, respectively.
__NO_INTERRUPTS__
    This macro reflects the -mno-interrupts command line option.
__AVR_ERRATA_SKIP__
__AVR_ERRATA_SKIP_JMP_CALL__
    Some AVR devices (AT90S8515, ATmega103) must not skip 32-bit instructions because of a hardware
    erratum. Skip instructions are SBRS, SBRC, SBIS, SBIC and CPSE. The second macro is only
    defined if __AVR_HAVE_JMP_CALL_ _ is also set.
__AVR_SFR_OFFSET__=offset
    Instructions that can address I/O special function registers directly like IN, OUT, SBI, etc. may use a
    different address as if addressed by an instruction to access RAM like LD or STS. This offset depends
    on the device architecture and has to be subtracted from the RAM address in order to get the respective
    I/O@tie{}address.
__WITH_AVRLIBC__
    The compiler is configured to be used together with AVR-Libc. See the --with-avrlibc
```

Blackfin Options

-mcpu=cpu[-sirevision]

configure option.

Specifies the name of the target Blackfin processor. Currently, *cpu* can be one of **bf512**, **bf514**, **bf516**, **bf518**, **bf522**, **bf523**, **bf524**, **bf525**, **bf526**, **bf527**, **bf531**, **bf532**, **bf533**, **bf534**, **bf536**, **bf537**, **bf538**, **bf539**, **bf542**, **bf544**, **bf547**, **bf548**, **bf549**, **bf542m**, **bf544m**, **bf547m**, **bf548m**, **bf549m**, **bf561**,

bf592.

The optional *sirevision* specifies the silicon revision of the target Blackfin processor. Any workarounds available for the targeted silicon revision are enabled. If *sirevision* is **none**, no workarounds are enabled. If *sirevision* is **any**, all workarounds for the targeted processor are enabled. The __SILICON_REVISION__ macro is defined to two hexadecimal digits representing the major and minor numbers in the silicon revision. If *sirevision* is **none**, the __SILICON_REVISION__ is not defined. If *sirevision* is **any**, the __SILICON_REVISION__ is defined to be 0xffff. If this optional *sirevision* is not used, GCC assumes the latest known silicon revision of the targeted Blackfin processor.

GCC defines a preprocessor macro for the specified *cpu*. For the **bfin-elf** toolchain, this option causes the hardware BSP provided by libgloss to be linked in if **-msim** is not given.

Without this option, **bf532** is used as the processor by default.

Note that support for **bf561** is incomplete. For **bf561**, only the preprocessor macro is defined.

-msim

Specifies that the program will be run on the simulator. This causes the simulator BSP provided by libgloss to be linked in. This option has effect only for **bfin-elf** toolchain. Certain other options, such as **-mid-shared-library** and **-mfdpic**, imply **-msim**.

-momit-leaf-frame-pointer

Don't keep the frame pointer in a register for leaf functions. This avoids the instructions to save, set up and restore frame pointers and makes an extra register available in leaf functions. The option **–fomit–frame–pointer** removes the frame pointer for all functions, which might make debugging harder.

-mspecld-anomaly

When enabled, the compiler ensures that the generated code does not contain speculative loads after jump instructions. If this option is used, __WORKAROUND_SPECULATIVE_LOADS is defined.

-mno-specld-anomaly

Don't generate extra code to prevent speculative loads from occurring.

-mcsync-anomaly

When enabled, the compiler ensures that the generated code does not contain CSYNC or SSYNC instructions too soon after conditional branches. If this option is used, __WORKAROUND_SPECULATIVE_SYNCS is defined.

-mno-csync-anomaly

Don't generate extra code to prevent CSYNC or SSYNC instructions from occurring too soon after a conditional branch.

-mlow-64k

When enabled, the compiler is free to take advantage of the knowledge that the entire program fits into the low 64k of memory.

-mno-low-64k

Assume that the program is arbitrarily large. This is the default.

-mstack-check-l1

Do stack checking using information placed into L1 scratchpad memory by the uClinux kernel.

-mid-shared-library

Generate code that supports shared libraries via the library ID method. This allows for execute in place and shared libraries in an environment without virtual memory management. This option implies **-fPIC**. With a **bfin-elf** target, this option implies **-msim**.

-mno-id-shared-library

Generate code that doesn't assume ID-based shared libraries are being used. This is the default.

-mleaf-id-shared-library

Generate code that supports shared libraries via the library ID method, but assumes that this library or executable won't link against any other ID shared libraries. That allows the compiler to use faster code for jumps and calls.

-mno-leaf-id-shared-library

Do not assume that the code being compiled won't link against any ID shared libraries. Slower code is generated for jump and call insns.

-mshared-library-id=n

Specifies the identification number of the ID-based shared library being compiled. Specifying a value of 0 generates more compact code; specifying other values forces the allocation of that number to the current library but is no more space— or time-efficient than omitting this option.

-msep-data

Generate code that allows the data segment to be located in a different area of memory from the text segment. This allows for execute in place in an environment without virtual memory management by eliminating relocations against the text section.

-mno-sep-data

Generate code that assumes that the data segment follows the text segment. This is the default.

-mlong-calls

-mno-long-calls

Tells the compiler to perform function calls by first loading the address of the function into a register and then performing a subroutine call on this register. This switch is needed if the target function lies outside of the 24-bit addressing range of the offset-based version of subroutine call instruction.

This feature is not enabled by default. Specifying **-mno-long-calls** restores the default behavior. Note these switches have no effect on how the compiler generates code to handle function calls via function pointers.

-mfast-fp

Link with the fast floating-point library. This library relaxes some of the IEEE floating-point standard's rules for checking inputs against Not-a-Number (NAN), in the interest of performance.

_minline_plf

Enable inlining of PLT entries in function calls to functions that are not known to bind locally. It has no effect without **-mfdpic**.

-mmulticore

Build a standalone application for multicore Blackfin processors. This option causes proper start files and link scripts supporting multicore to be used, and defines the macro __BFIN_MULTICORE. It can only be used with -mcpu=bf561[-sirevision].

This option can be used with **-mcorea** or **-mcoreb**, which selects the one-application-per-core programming model. Without **-mcorea** or **-mcoreb**, the single-application/dual-core programming model is used. In this model, the main function of Core B should be named as coreb_main.

If this option is not used, the single-core application programming model is used.

-mcorea

Build a standalone application for Core A of BF561 when using the one-application-per-core programming model. Proper start files and link scripts are used to support Core A, and the macro __BFIN_COREA is defined. This option can only be used in conjunction with **-mmulticore**.

-mcoreb

Build a standalone application for Core B of BF561 when using the one-application-per-core programming model. Proper start files and link scripts are used to support Core B, and the macro __BFIN_COREB is defined. When this option is used, coreb_main should be used instead of main. This option can only be used in conjunction with -mmulticore.

-msdram

Build a standalone application for SDRAM. Proper start files and link scripts are used to put the application into SDRAM, and the macro __BFIN_SDRAM is defined. The loader should initialize SDRAM before loading the application.

-micplb

Assume that ICPLBs are enabled at run time. This has an effect on certain anomaly workarounds. For Linux targets, the default is to assume ICPLBs are enabled; for standalone applications the default is off.

C6X Options

-march=name

This specifies the name of the target architecture. GCC uses this name to determine what kind of instructions it can emit when generating assembly code. Permissible names are: c62x, c64x, c64x+, c67x, c67x+, c67x+, c674x.

-mbig-endian

Generate code for a big-endian target.

-mlittle-endian

Generate code for a little-endian target. This is the default.

-msim

Choose startup files and linker script suitable for the simulator.

-msdata=default

Put small global and static data in the **.neardata** section, which is pointed to by register B14. Put small uninitialized global and static data in the **.bss** section, which is adjacent to the **.neardata** section. Put small read-only data into the **.rodata** section. The corresponding sections used for large pieces of data are **.fardata**, **.far** and **.const**.

-msdata=all

Put all data, not just small objects, into the sections reserved for small data, and use addressing relative to the B14 register to access them.

-msdata=none

Make no use of the sections reserved for small data, and use absolute addresses to access all data. Put all initialized global and static data in the **.fardata** section, and all uninitialized data in the **.far** section. Put all constant data into the **.const** section.

CRIS Options

These options are defined specifically for the CRIS ports.

-march=architecture-type

-mcpu=architecture-type

Generate code for the specified architecture. The choices for *architecture-type* are **v3**, **v8** and **v10** for respectively ETRAX 4, ETRAX 100, and ETRAX 100 LX. Default is **v0** except for cris-axis-linux-gnu, where the default is **v10**.

-mtune=architecture-type

Tune to *architecture-type* everything applicable about the generated code, except for the ABI and the set of available instructions. The choices for *architecture-type* are the same as for **—march=** *architecture-type*.

-mmax-stack-frame=n

Warn when the stack frame of a function exceeds n bytes.

-metrax4

-metrax100

The options -metrax4 and -metrax100 are synonyms for -march=v3 and -march=v8 respectively.

-mmul-bug-workaround

-mno-mul-bug-workaround

Work around a bug in the muls and mulu instructions for CPU models where it applies. This option is active by default.

-mpdebug

Enable CRIS-specific verbose debug-related information in the assembly code. This option also has the effect of turning off the #NO_APP formatted-code indicator to the assembler at the beginning of the assembly file.

-mcc-init

Do not use condition-code results from previous instruction; always emit compare and test instructions before use of condition codes.

-mno-side-effects

Do not emit instructions with side effects in addressing modes other than post-increment.

- -mstack-align
- -mno-stack-align
- -mdata-align
- -mno-data-align
- -mconst-align
- -mno-const-align

These options (**no**– options) arrange (eliminate arrangements) for the stack frame, individual data and constants to be aligned for the maximum single data access size for the chosen CPU model. The default is to arrange for 32–bit alignment. ABI details such as structure layout are not affected by these options.

-m32-bit

-m16-bit

-m8-bit

Similar to the stack- data- and const-align options above, these options arrange for stack frame, writable data and constants to all be 32-bit, 16-bit or 8-bit aligned. The default is 32-bit alignment.

-mno-prologue-epilogue

-mprologue-epilogue

With **-mno-prologue-epilogue**, the normal function prologue and epilogue which set up the stack frame are omitted and no return instructions or return sequences are generated in the code. Use this option only together with visual inspection of the compiled code: no warnings or errors are generated when call-saved registers must be saved, or storage for local variables needs to be allocated.

-mno-gotplt

-mgotplt

With **-fpic** and **-fPIC**, don't generate (do generate) instruction sequences that load addresses for functions from the PLT part of the GOT rather than (traditional on other architectures) calls to the PLT. The default is **-mgotplt**.

-melf

Legacy no-op option only recognized with the cris-axis-elf and cris-axis-linux-gnu targets.

-mlinux

Legacy no-op option only recognized with the cris-axis-linux-gnu target.

-sim

This option, recognized for the cris-axis-elf, arranges to link with input-output functions from a simulator library. Code, initialized data and zero-initialized data are allocated consecutively.

-sim2

Like **–sim**, but pass linker options to locate initialized data at 0x40000000 and zero-initialized data at 0x80000000.

CR16 Options

These options are defined specifically for the CR16 ports.

-mmag

Enable the use of multiply-accumulate instructions. Disabled by default.

-mcr16cplus

-mcr16c

Generate code for CR16C or CR16C+ architecture, CR16C+ architecture is default.

-msim

Links the library libsim which is in compatible with simulator. Applicable to ELF compiler only.

-mint32

Choose integer type as 32-bit wide.

-mbit-ops

Generates sbit/cbit instructions for bit manipulations.

-mdata-model=model

Choose a data model. The choices for *model* are **near**, **far** or **medium**. **medium** is default. However, **far** is not valid with **-mcr16c**, as the CR16C architecture does not support the far data model.

Darwin Options

These options are defined for all architectures running the Darwin operating system.

FSF GCC on Darwin does not create "fat" object files; it creates an object file for the single architecture that GCC was built to target. Apple's GCC on Darwin does create "fat" files if multiple **–arch** options are used; it does so by running the compiler or linker multiple times and joining the results together with *lipo*.

The subtype of the file created (like **ppc7400** or **ppc970** or **i686**) is determined by the flags that specify the ISA that GCC is targeting, like **-mcpu** or **-march**. The **-force_cpusubtype_ALL** option can be used to override this.

The Darwin tools vary in their behavior when presented with an ISA mismatch. The assembler, *as*, only permits instructions to be used that are valid for the subtype of the file it is generating, so you cannot put 64—bit instructions in a **ppc750** object file. The linker for shared libraries, */usr/bin/libtool*, fails and prints an error if asked to create a shared library with a less restrictive subtype than its input files (for instance, trying to put a **ppc970** object file in a **ppc7400** library). The linker for executables, **ld**, quietly gives the executable the most restrictive subtype of any of its input files.

-Fdir

Add the framework directory *dir* to the head of the list of directories to be searched for header files. These directories are interleaved with those specified by **–I** options and are scanned in a left-to-right order.

A framework directory is a directory with frameworks in it. A framework is a directory with a *Headers* and/or *PrivateHeaders* directory contained directly in it that ends in *.framework*. The name of a framework is the name of this directory excluding the *.framework*. Headers associated with the framework are found in one of those two directories, with *Headers* being searched first. A subframework is a framework directory that is in a framework's *Frameworks* directory. Includes of subframework headers can only appear in a header of a framework that contains the subframework, or in a sibling subframework header. Two subframeworks are siblings if they occur in the same framework. A subframework should not have the same name as a framework; a warning is issued if this is violated. Currently a subframework cannot have subframeworks; in the future, the mechanism may be extended to support this. The standard frameworks can be found in */System/Library/Frameworks* and */Library/Frameworks*. An example include looks like #include <Framework/header.h>, where *Framework* denotes the name of the framework and *headerh* is found in the *PrivateHeaders* or *Headers* directory.

-iframeworkdir

Like -F except the directory is a treated as a system directory. The main difference between this -iframework and -F is that with -iframework the compiler does not warn about constructs

contained within header files found via dir. This option is valid only for the C family of languages.

-gused

Emit debugging information for symbols that are used. For stabs debugging format, this enables **-feliminate-unused-debug-symbols**. This is by default ON.

-gfull

Emit debugging information for all symbols and types.

-mmacosx-version-min=version

The earliest version of MacOS X that this executable will run on is *version*. Typical values of *version* include 10.1, 10.2, and 10.3.9.

If the compiler was built to use the system's headers by default, then the default for this option is the system version on which the compiler is running, otherwise the default is to make choices that are compatible with as many systems and code bases as possible.

-mkernel

Enable kernel development mode. The **-mkernel** option sets **-static**, **-fno-common**, **-fno-use-cxa-atexit**, **-fno-exceptions**, **-fno-non-call-exceptions**, **-fapple-kext**, **-fno-weak** and **-fno-rtti** where applicable. This mode also sets **-mno-altivec**, **-msoft-float**, **-fno-builtin** and **-mlong-branch** for PowerPC targets.

-mone-byte-bool

Override the defaults for **bool** so that **sizeof(bool)==1**. By default **sizeof(bool)** is **4** when compiling for Darwin/PowerPC and **1** when compiling for Darwin/x86, so this option has no effect on x86.

Warning: The **-mone-byte-bool** switch causes GCC to generate code that is not binary compatible with code generated without that switch. Using this switch may require recompiling all other modules in a program, including system libraries. Use this switch to conform to a non-default data model.

-mfix-and-continue

-ffix-and-continue

-findirect-data

Generate code suitable for fast turnaround development, such as to allow GDB to dynamically load . o files into already-running programs. **-findirect-data** and **-ffix-and-continue** are provided for backwards compatibility.

-all load

Loads all members of static archive libraries. See man ld(1) for more information.

-arch errors fatal

Cause the errors having to do with files that have the wrong architecture to be fatal.

-bind_at_load

Causes the output file to be marked such that the dynamic linker will bind all undefined references when the file is loaded or launched.

-bundle

Produce a Mach-o bundle format file. See man ld(1) for more information.

-bundle loader executable

This option specifies the *executable* that will load the build output file being linked. See man ld(1) for more information.

-dynamiclib

When passed this option, GCC produces a dynamic library instead of an executable when linking, using the Darwin *libtool* command.

-force_cpusubtype_ALL

This causes GCC's output file to have the *ALL* subtype, instead of one controlled by the **-mcpu** or **-march** option.

- -allowable_client client_name
- -client_name
- -compatibility_version
- -current_version
- -dead strip
- -dependency-file
- -dylib_file
- $-dylinker_install_name$
- -dynamic
- $-exported_symbols_list$
- -filelist
- -flat_namespace
- -force_flat_namespace
- -headerpad_max_install_names
- -image_base
- -init
- -install_name
- -keep_private_externs
- $-multi_module$
- -multiply_defined
- -multiply_defined_unused
- -noall load
- -no_dead_strip_inits_and_terms
- -nofixprebinding
- -nomultidefs
- -noprebind
- -noseglinkedit
- -pagezero_size
- -prebind
- $-prebind_all_two level_modules$
- -private bundle
- -read_only_relocs
- -sectalign
- -sectobjectsymbols
- -whyload
- -seg1addr
- -sectcreate
- -sectobjectsymbols
- -sectorder
- -segaddr
- -segs_read_only_addr
- -segs_read_write_addr
- -seg_addr_table
- -seg_addr_table_filename
- -seglinkedit
- -segprot
- $-segs_read_only_addr$
- -segs_read_write_addr
- -single module
- -static
- -sub_library
- -sub_umbrella

- -twolevel_namespace
- -umbrella
- -undefined
- -unexported_symbols_list
- -weak reference mismatches
- -whatsloaded

These options are passed to the Darwin linker. The Darwin linker man page describes them in detail.

DEC Alpha Options

These -m options are defined for the DEC Alpha implementations:

-mno-soft-float

-msoft-float

Use (do not use) the hardware floating-point instructions for floating-point operations. When **-msoft-float** is specified, functions in *libgcc.a* are used to perform floating-point operations. Unless they are replaced by routines that emulate the floating-point operations, or compiled in such a way as to call such emulations routines, these routines issue floating-point operations. If you are compiling for an Alpha without floating-point operations, you must ensure that the library is built so as not to call them.

Note that Alpha implementations without floating-point operations are required to have floating-point registers.

-mfp-reg

-mno-fp-regs

Generate code that uses (does not use) the floating-point register set. **-mno-fp-regs** implies **-msoft-float**. If the floating-point register set is not used, floating-point operands are passed in integer registers as if they were integers and floating-point results are passed in \$0 instead of \$£0. This is a non-standard calling sequence, so any function with a floating-point argument or return value called by code compiled with **-mno-fp-regs** must also be compiled with that option.

A typical use of this option is building a kernel that does not use, and hence need not save and restore, any floating-point registers.

-mieee

The Alpha architecture implements floating-point hardware optimized for maximum performance. It is mostly compliant with the IEEE floating-point standard. However, for full compliance, software assistance is required. This option generates code fully IEEE-compliant code *except* that the *inexact-flag* is not maintained (see below). If this option is turned on, the preprocessor macro _IEEE_FP is defined during compilation. The resulting code is less efficient but is able to correctly support denormalized numbers and exceptional IEEE values such as not-a-number and plus/minus infinity. Other Alpha compilers call this option **–ieee_with_no_inexact**.

-mieee-with-inexact

This is like **-mieee** except the generated code also maintains the IEEE *inexact-flag*. Turning on this option causes the generated code to implement fully-compliant IEEE math. In addition to <code>_IEEE_FP</code>, <code>_IEEE_FP</code>_EXACT is defined as a preprocessor macro. On some Alpha implementations the resulting code may execute significantly slower than the code generated by default. Since there is very little code that depends on the <code>inexact-flag</code>, you should normally not specify this option. Other Alpha compilers call this option <code>-ieee_with_inexact</code>.

-mfp-trap-mode=trap-mode

This option controls what floating-point related traps are enabled. Other Alpha compilers call this option **–fptm** *trap-mode*. The trap mode can be set to one of four values:

- **n** This is the default (normal) setting. The only traps that are enabled are the ones that cannot be disabled in software (e.g., division by zero trap).
- **u** In addition to the traps enabled by **n**, underflow traps are enabled as well.

- **su** Like **u**, but the instructions are marked to be safe for software completion (see Alpha architecture manual for details).
- **sui** Like **su**, but inexact traps are enabled as well.

-mfp-rounding-mode=rounding-mode

Selects the IEEE rounding mode. Other Alpha compilers call this option **–fprm** *rounding-mode*. The *rounding-mode* can be one of:

- n Normal IEEE rounding mode. Floating-point numbers are rounded towards the nearest machine number or towards the even machine number in case of a tie.
- m Round towards minus infinity.
- c Chopped rounding mode. Floating-point numbers are rounded towards zero.
- **d** Dynamic rounding mode. A field in the floating-point control register (*fpcr*, see Alpha architecture reference manual) controls the rounding mode in effect. The C library initializes this register for rounding towards plus infinity. Thus, unless your program modifies the *fpcr*, **d** corresponds to round towards plus infinity.

-mtrap-precision=trap-precision

In the Alpha architecture, floating-point traps are imprecise. This means without software assistance it is impossible to recover from a floating trap and program execution normally needs to be terminated. GCC can generate code that can assist operating system trap handlers in determining the exact location that caused a floating-point trap. Depending on the requirements of an application, different levels of precisions can be selected:

- **p** Program precision. This option is the default and means a trap handler can only identify which program caused a floating-point exception.
- **f** Function precision. The trap handler can determine the function that caused a floating-point exception.
- i Instruction precision. The trap handler can determine the exact instruction that caused a floating-point exception.

Other Alpha compilers provide the equivalent options called **-scope_safe** and **-resumption_safe**.

-mieee-conformant

This option marks the generated code as IEEE conformant. You must not use this option unless you also specify **-mtrap-precision=i** and either **-mfp-trap-mode=su** or **-mfp-trap-mode=sui**. Its only effect is to emit the line **.eflag 48** in the function prologue of the generated assembly file.

-mbuild-constants

Normally GCC examines a 32- or 64-bit integer constant to see if it can construct it from smaller constants in two or three instructions. If it cannot, it outputs the constant as a literal and generates code to load it from the data segment at run time.

Use this option to require GCC to construct *all* integer constants using code, even if it takes more instructions (the maximum is six).

You typically use this option to build a shared library dynamic loader. Itself a shared library, it must relocate itself in memory before it can find the variables and constants in its own data segment.

- -mbwx
- -mno-bwx
- -mcix
- -mno-cix
- -mfix
- -mno-fix
- -mmax

-mno-max

Indicate whether GCC should generate code to use the optional BWX, CIX, FIX and MAX instruction sets. The default is to use the instruction sets supported by the CPU type specified via **-mcpu=** option or that of the CPU on which GCC was built if none is specified.

-mfloat-vax

-mfloat-ieee

Generate code that uses (does not use) VAX F and G floating-point arithmetic instead of IEEE single and double precision.

-mexplicit-relocs

-mno-explicit-relocs

Older Alpha assemblers provided no way to generate symbol relocations except via assembler macros. Use of these macros does not allow optimal instruction scheduling. GNU binutils as of version 2.12 supports a new syntax that allows the compiler to explicitly mark which relocations should apply to which instructions. This option is mostly useful for debugging, as GCC detects the capabilities of the assembler when it is built and sets the default accordingly.

-msmall-data

-mlarge-data

When **-mexplicit-relocs** is in effect, static data is accessed via *gp-relative* relocations. When **-msmall-data** is used, objects 8 bytes long or smaller are placed in a *small data area* (the .sdata and .sbss sections) and are accessed via 16-bit relocations off of the \$gp register. This limits the size of the small data area to 64KB, but allows the variables to be directly accessed via a single instruction.

The default is **-mlarge-data**. With this option the data area is limited to just below 2GB. Programs that require more than 2GB of data must use malloc or mmap to allocate the data in the heap instead of in the program's data segment.

When generating code for shared libraries, **-fpic** implies **-msmall-data** and **-fPIC** implies **-mlarge-data**.

-msmall-text

-mlarge-text

When **-msmall-text** is used, the compiler assumes that the code of the entire program (or shared library) fits in 4MB, and is thus reachable with a branch instruction. When **-msmall-data** is used, the compiler can assume that all local symbols share the same \$gp value, and thus reduce the number of instructions required for a function call from 4 to 1.

The default is **-mlarge-text**.

$-mcpu=cpu_type$

Set the instruction set and instruction scheduling parameters for machine type *cpu_type*. You can specify either the **EV** style name or the corresponding chip number. GCC supports scheduling parameters for the EV4, EV5 and EV6 family of processors and chooses the default values for the instruction set from the processor you specify. If you do not specify a processor type, GCC defaults to the processor on which the compiler was built.

Supported values for *cpu_type* are

ev4 ev45

21064

Schedules as an EV4 and has no instruction set extensions.

ev5 21164

Schedules as an EV5 and has no instruction set extensions.

ev56

21164a

Schedules as an EV5 and supports the BWX extension.

pca56

21164pc

21164PC

Schedules as an EV5 and supports the BWX and MAX extensions.

ev6

21264

Schedules as an EV6 and supports the BWX, FIX, and MAX extensions.

ev67

21264a

Schedules as an EV6 and supports the BWX, CIX, FIX, and MAX extensions.

Native toolchains also support the value **native**, which selects the best architecture option for the host processor. **–mcpu=native** has no effect if GCC does not recognize the processor.

-mtune=cpu_type

Set only the instruction scheduling parameters for machine type *cpu_type*. The instruction set is not changed.

Native toolchains also support the value **native**, which selects the best architecture option for the host processor. **—mtune=native** has no effect if GCC does not recognize the processor.

-mmemory-latency=time

Sets the latency the scheduler should assume for typical memory references as seen by the application. This number is highly dependent on the memory access patterns used by the application and the size of the external cache on the machine.

Valid options for time are

number

A decimal number representing clock cycles.

L1

L2

L3

main

The compiler contains estimates of the number of clock cycles for "typical" EV4 & EV5 hardware for the Level 1, 2 & 3 caches (also called Dcache, Scache, and Bcache), as well as to main memory. Note that L3 is only valid for EV5.

FR30 Options

These options are defined specifically for the FR30 port.

-msmall-model

Use the small address space model. This can produce smaller code, but it does assume that all symbolic values and addresses fit into a 20-bit range.

-mno-lsim

Assume that runtime support has been provided and so there is no need to include the simulator library (*libsim.a*) on the linker command line.

FRV Options

-mgpr-32

Only use the first 32 general-purpose registers.

-mgpr-64

Use all 64 general-purpose registers.

-mfpr-32

Use only the first 32 floating-point registers.

-mfpr-64

Use all 64 floating-point registers.

-mhard-float

Use hardware instructions for floating-point operations.

-msoft-float

Use library routines for floating-point operations.

-malloc-cc

Dynamically allocate condition code registers.

-mfixed-cc

Do not try to dynamically allocate condition code registers, only use icc0 and fcc0.

-mdword

Change ABI to use double word insns.

-mno-dword

Do not use double word instructions.

-mdouble

Use floating-point double instructions.

-mno-double

Do not use floating-point double instructions.

-mmedia

Use media instructions.

-mno-media

Do not use media instructions.

-mmuladd

Use multiply and add/subtract instructions.

-mno-muladd

Do not use multiply and add/subtract instructions.

-mfdpic

Select the FDPIC ABI, which uses function descriptors to represent pointers to functions. Without any PIC/PIE—related options, it implies **–fPIE**. With **–fpic** or **–fpie**, it assumes GOT entries and small data are within a 12—bit range from the GOT base address; with **–fPIC** or **–fPIE**, GOT offsets are computed with 32 bits. With a **bfin-elf** target, this option implies **–msim**.

-minline-plt

Enable inlining of PLT entries in function calls to functions that are not known to bind locally. It has no effect without **-mfdpic**. It's enabled by default if optimizing for speed and compiling for shared libraries (i.e., **-fPIC** or **-fpic**), or when an optimization option such as **-O3** or above is present in the command line.

-mTLS

Assume a large TLS segment when generating thread-local code.

-mtls

Do not assume a large TLS segment when generating thread-local code.

-mgprel-ro

Enable the use of GPREL relocations in the FDPIC ABI for data that is known to be in read-only sections. It's enabled by default, except for **-fpic** or **-fpie**: even though it may help make the global

offset table smaller, it trades 1 instruction for 4. With **-fPIC** or **-fPIE**, it trades 3 instructions for 4, one of which may be shared by multiple symbols, and it avoids the need for a GOT entry for the referenced symbol, so it's more likely to be a win. If it is not, **-mno-gprel-ro** can be used to disable it.

-multilib-library-pic

Link with the (library, not FD) pic libraries. It's implied by **-mlibrary-pic**, as well as by **-fPIC** and **-fpic** without **-mfdpic**. You should never have to use it explicitly.

-mlinked-fp

Follow the EABI requirement of always creating a frame pointer whenever a stack frame is allocated. This option is enabled by default and can be disabled with **-mno-linked-fp**.

-mlong-calls

Use indirect addressing to call functions outside the current compilation unit. This allows the functions to be placed anywhere within the 32-bit address space.

-malign-labels

Try to align labels to an 8-byte boundary by inserting NOPs into the previous packet. This option only has an effect when VLIW packing is enabled. It doesn't create new packets; it merely adds NOPs to existing ones.

-mlibrary-pic

Generate position-independent EABI code.

-macc-4

Use only the first four media accumulator registers.

-macc-8

Use all eight media accumulator registers.

-mpack

Pack VLIW instructions.

-mno-pack

Do not pack VLIW instructions.

-mno-eflags

Do not mark ABI switches in e_flags.

-mcond-move

Enable the use of conditional-move instructions (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-cond-move

Disable the use of conditional-move instructions.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mscc

Enable the use of conditional set instructions (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-scc

Disable the use of conditional set instructions.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mcond-exec

Enable the use of conditional execution (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-cond-exec

Disable the use of conditional execution.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mvliw-branch

Run a pass to pack branches into VLIW instructions (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-vliw-branch

Do not run a pass to pack branches into VLIW instructions.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mmulti-cond-exec

Enable optimization of && and | | in conditional execution (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-multi-cond-exec

Disable optimization of && and | | in conditional execution.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mnested-cond-exec

Enable nested conditional execution optimizations (default).

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-mno-nested-cond-exec

Disable nested conditional execution optimizations.

This switch is mainly for debugging the compiler and will likely be removed in a future version.

-moptimize-membar

This switch removes redundant membar instructions from the compiler-generated code. It is enabled by default.

-mno-optimize-membar

This switch disables the automatic removal of redundant membar instructions from the generated code.

-mtomcat-stats

Cause gas to print out tomcat statistics.

-mcpu=cpu

Select the processor type for which to generate code. Possible values are frv, fr550, tomcat, fr500, fr450, fr400, fr400, fr300 and simple.

GNU/Linux Options

These -m options are defined for GNU/Linux targets:

-mglibc

Use the GNU C library. This is the default except on *-*-linux-*uclibc* and *-*-linux-*android* targets.

-muclibc

Use uClibc C library. This is the default on *-*-linux-*uclibc* targets.

-mbionic

Use Bionic C library. This is the default on *-*-linux-*android* targets.

-mandroid

Compile code compatible with Android platform. This is the default on *-*-linux-*android* targets.

When compiling, this option enables **-mbionic**, **-fPIC**, **-fno-exceptions** and **-fno-rtti** by default. When linking, this option makes the GCC driver pass Android-specific options to the linker. Finally, this option causes the preprocessor macro __ANDROID__ to be defined.

-tno-android-cc

Disable compilation effects of **-mandroid**, i.e., do not enable **-mbionic**, **-fPIC**, **-fno-exceptions** and **-fno-rtti** by default.

-tno-android-ld

Disable linking effects of -mandroid, i.e., pass standard Linux linking options to the linker.

H8/300 Options

These **-m** options are defined for the H8/300 implementations:

-mrelax

Shorten some address references at link time, when possible; uses the linker option -relax.

-mh

Generate code for the H8/300H.

-ms

Generate code for the H8S.

-mn

Generate code for the H8S and H8/300H in the normal mode. This switch must be used either with **-mh** or **-ms**.

-ms2600

Generate code for the H8S/2600. This switch must be used with -ms.

-mexr

Extended registers are stored on stack before execution of function with monitor attribute. Default option is **–mexr**. This option is valid only for H8S targets.

-mno-exr

Extended registers are not stored on stack before execution of function with monitor attribute. Default option is **-mno-exr**. This option is valid only for H8S targets.

-mint32

Make int data 32 bits by default.

-malign-300

On the H8/300H and H8S, use the same alignment rules as for the H8/300. The default for the H8/300H and H8S is to align longs and floats on 4-byte boundaries. **-malign-300** causes them to be aligned on 2-byte boundaries. This option has no effect on the H8/300.

HPPA Options

These -m options are defined for the HPPA family of computers:

-march=*architecture-type*

Generate code for the specified architecture. The choices for *architecture-type* are **1.0** for PA 1.0, **1.1** for PA 1.1, and **2.0** for PA 2.0 processors. Refer to /usr/lib/sched.models on an HP-UX system to determine the proper architecture option for your machine. Code compiled for lower numbered architectures runs on higher numbered architectures, but not the other way around.

```
-mpa-risc-1-0
```

-mpa-risc-1-1

-mpa-risc-2-0

Synonyms for **-march=1.0**, **-march=1.1**, and **-march=2.0** respectively.

-mbig-switch

Generate code suitable for big switch tables. Use this option only if the assembler/linker complain about out-of-range branches within a switch table.

-mjump-in-delay

Fill delay slots of function calls with unconditional jump instructions by modifying the return pointer for the function call to be the target of the conditional jump.

-mdisable-fpregs

Prevent floating-point registers from being used in any manner. This is necessary for compiling kernels that perform lazy context switching of floating-point registers. If you use this option and attempt to perform floating-point operations, the compiler aborts.

-mdisable-indexing

Prevent the compiler from using indexing address modes. This avoids some rather obscure problems when compiling MIG generated code under MACH.

-mno-space-regs

Generate code that assumes the target has no space registers. This allows GCC to generate faster indirect calls and use unscaled index address modes.

Such code is suitable for level 0 PA systems and kernels.

-mfast-indirect-calls

Generate code that assumes calls never cross space boundaries. This allows GCC to emit code that performs faster indirect calls.

This option does not work in the presence of shared libraries or nested functions.

-mfixed-range=register-range

Generate code treating the given register range as fixed registers. A fixed register is one that the register allocator cannot use. This is useful when compiling kernel code. A register range is specified as two registers separated by a dash. Multiple register ranges can be specified separated by a comma.

-mlong-load-store

Generate 3-instruction load and store sequences as sometimes required by the HP-UX 10 linker. This is equivalent to the +**k** option to the HP compilers.

-mportable-runtime

Use the portable calling conventions proposed by HP for ELF systems.

-mgas

Enable the use of assembler directives only GAS understands.

-mschedule=cpu-type

Schedule code according to the constraints for the machine type *cpu-type*. The choices for *cpu-type* are **700 7100**, **7100LC**, **7200**, **7300** and **8000**. Refer to /usr/lib/sched.models on an HP-UX system to determine the proper scheduling option for your machine. The default scheduling is **8000**.

-mlinker-opt

Enable the optimization pass in the HP-UX linker. Note this makes symbolic debugging impossible. It also triggers a bug in the HP-UX 8 and HP-UX 9 linkers in which they give bogus error messages when linking some programs.

-msoft-float

Generate output containing library calls for floating point. **Warning:** the requisite libraries are not available for all HPPA targets. Normally the facilities of the machine's usual C compiler are used, but this cannot be done directly in cross-compilation. You must make your own arrangements to provide suitable library functions for cross-compilation.

-msoft-float changes the calling convention in the output file; therefore, it is only useful if you compile *all* of a program with this option. In particular, you need to compile *libgcc.a*, the library that comes with GCC, with **-msoft-float** in order for this to work.

-msio

Generate the predefine, _SIO, for server IO. The default is **-mwsio**. This generates the predefines, __hp9000s700, __hp9000s700__ and _WSIO, for workstation IO. These options are available

under HP-UX and HI-UX.

-mgnu-ld

Use options specific to GNU **ld**. This passes **-shared** to **ld** when building a shared library. It is the default when GCC is configured, explicitly or implicitly, with the GNU linker. This option does not affect which **ld** is called; it only changes what parameters are passed to that **ld**. The **ld** that is called is determined by the **--with-ld** configure option, GCC's program search path, and finally by the user's **PATH**. The linker used by GCC can be printed using **which 'gcc -print-prog-name=ld'**. This option is only available on the 64-bit HP-UX GCC, i.e. configured with **hppa*64*-*-hpux***.

-mhp-ld

Use options specific to HP ld. This passes -b to ld when building a shared library and passes +Accept TypeMismatch to ld on all links. It is the default when GCC is configured, explicitly or implicitly, with the HP linker. This option does not affect which ld is called; it only changes what parameters are passed to that ld. The ld that is called is determined by the --with-ld configure option, GCC's program search path, and finally by the user's PATH. The linker used by GCC can be printed using which 'gcc -print-prog-name=ld'. This option is only available on the 64-bit HP-UX GCC, i.e. configured with hppa*64*-*-hpux*.

-mlong-calls

Generate code that uses long call sequences. This ensures that a call is always able to reach linker generated stubs. The default is to generate long calls only when the distance from the call site to the beginning of the function or translation unit, as the case may be, exceeds a predefined limit set by the branch type being used. The limits for normal calls are 7,600,000 and 240,000 bytes, respectively for the PA 2.0 and PA 1.X architectures. Sibcalls are always limited at 240,000 bytes.

Distances are measured from the beginning of functions when using the **-ffunction-sections** option, or when using the **-mgas** and **-mno-portable-runtime** options together under HP-UX with the SOM linker.

It is normally not desirable to use this option as it degrades performance. However, it may be useful in large applications, particularly when partial linking is used to build the application.

The types of long calls used depends on the capabilities of the assembler and linker, and the type of code being generated. The impact on systems that support long absolute calls, and long pic symbol-difference or pc-relative calls should be relatively small. However, an indirect call is used on 32-bit ELF systems in pic code and it is quite long.

-munix=unix-std

Generate compiler predefines and select a startfile for the specified UNIX standard. The choices for *unix-std* are **93**, **95** and **98**. **93** is supported on all HP-UX versions. **95** is available on HP-UX 10.10 and later. **98** is available on HP-UX 11.11 and later. The default values are **93** for HP-UX 10.00, **95** for HP-UX 10.10 though to 11.00, and **98** for HP-UX 11.11 and later.

-munix=93 provides the same predefines as GCC 3.3 and 3.4. -munix=95 provides additional predefines for XOPEN_UNIX and _XOPEN_SOURCE_EXTENDED, and the startfile unix95.o. -munix=98 provides additional predefines for _XOPEN_UNIX, _XOPEN_SOURCE_EXTENDED, _INCLUDE__STDC_A1_SOURCE and _INCLUDE_XOPEN_SOURCE_500, and the startfile unix98.o.

It is *important* to note that this option changes the interfaces for various library routines. It also affects the operational behavior of the C library. Thus, *extreme* care is needed in using this option.

Library code that is intended to operate with more than one UNIX standard must test, set and restore the variable __xpg4_extended_mask as appropriate. Most GNU software doesn't provide this capability.

-nolibdld

Suppress the generation of link options to search libdld.sl when the **-static** option is specified on HP-UX 10 and later.

gcc-4.8 2015-06-23 150

-static

The HP-UX implementation of setlocale in libc has a dependency on libdld.sl. There isn't an archive version of libdld.sl. Thus, when the **-static** option is specified, special link options are needed to resolve this dependency.

On HP-UX 10 and later, the GCC driver adds the necessary options to link with libdld.sl when the **-static** option is specified. This causes the resulting binary to be dynamic. On the 64-bit port, the linkers generate dynamic binaries by default in any case. The **-nolibdld** option can be used to prevent the GCC driver from adding these link options.

_threads

Add support for multithreading with the *dce thread* library under HP-UX. This option sets flags for both the preprocessor and linker.

Intel 386 and AMD x86-64 Options

These **-m** options are defined for the i386 and x86–64 family of computers:

-march=cpu-type

Generate instructions for the machine type *cpu-type*. In contrast to **-mtune**=*cpu-type*, which merely tunes the generated code for the specified *cpu-type*, **-march**=*cpu-type* allows GCC to generate code that may not run at all on processors other than the one indicated. Specifying **-march**=*cpu-type* implies **-mtune**=*cpu-type*.

The choices for *cpu-type* are:

native

This selects the CPU to generate code for at compilation time by determining the processor type of the compiling machine. Using **-march=native** enables all instruction subsets supported by the local machine (hence the result might not run on different machines). Using **-mtune=native** produces code optimized for the local machine under the constraints of the selected instruction set.

i386

Original Intel i386 CPU.

i486

Intel i486 CPU. (No scheduling is implemented for this chip.)

i586

pentium

Intel Pentium CPU with no MMX support.

pentium-mmx

Intel Pentium MMX CPU, based on Pentium core with MMX instruction set support.

pentiumpro

Intel Pentium Pro CPU.

i686

When used with **-march**, the Pentium Pro instruction set is used, so the code runs on all i686 family chips. When used with **-mtune**, it has the same meaning as **generic**.

pentium2

Intel Pentium II CPU, based on Pentium Pro core with MMX instruction set support.

pentium3

pentium3m

Intel Pentium III CPU, based on Pentium Pro core with MMX and SSE instruction set support.

pentium-m

Intel Pentium M; low-power version of Intel Pentium III CPU with MMX, SSE and SSE2 instruction set support. Used by Centrino notebooks.

pentium4

pentium4m

Intel Pentium 4 CPU with MMX, SSE and SSE2 instruction set support.

prescott

Improved version of Intel Pentium 4 CPU with MMX, SSE, SSE2 and SSE3 instruction set support.

nocona

Improved version of Intel Pentium 4 CPU with 64-bit extensions, MMX, SSE, SSE2 and SSE3 instruction set support.

core2

Intel Core 2 CPU with 64-bit extensions, MMX, SSE, SSE2, SSE3 and SSSE3 instruction set support.

corei7

Intel Core i7 CPU with 64-bit extensions, MMX, SSE, SSE2, SSE3, SSE3, SSE4.1 and SSE4.2 instruction set support.

corei7-avx

Intel Core i7 CPU with 64-bit extensions, MMX, SSE, SSE2, SSE3, SSSE3, SSE4.1, SSE4.2, AVX, AES and PCLMUL instruction set support.

core-avx-i

Intel Core CPU with 64-bit extensions, MMX, SSE, SSE2, SSE3, SSSE3, SSE4.1, SSE4.2, AVX, AES, PCLMUL, FSGSBASE, RDRND and F16C instruction set support.

core-avx2

Intel Core CPU with 64-bit extensions, MOVBE, MMX, SSE, SSE2, SSE3, SSSE3, SSE4.1, SSE4.2, AVX, AVX2, AES, PCLMUL, FSGSBASE, RDRND, FMA, BMI, BMI2 and F16C instruction set support.

atom

Intel Atom CPU with 64-bit extensions, MOVBE, MMX, SSE, SSE2, SSE3 and SSSE3 instruction set support.

k6 AMD K6 CPU with MMX instruction set support.

k6-2

k6-3

Improved versions of AMD K6 CPU with MMX and 3DNow! instruction set support.

athlon

athlon-tbird

AMD Athlon CPU with MMX, 3dNOW!, enhanced 3DNow! and SSE prefetch instructions support.

athlon-4

athlon-xp

athlon-mp

Improved AMD Athlon CPU with MMX, 3DNow!, enhanced 3DNow! and full SSE instruction set support.

k8

opteron

athlon64

athlon-fx

Processors based on the AMD K8 core with x86–64 instruction set support, including the AMD Opteron, Athlon 64, and Athlon 64 FX processors. (This supersets MMX, SSE, SSE2, 3DNow!, enhanced 3DNow! and 64–bit instruction set extensions.)

k8-sse3

opteron-sse3

athlon64-sse3

Improved versions of AMD K8 cores with SSE3 instruction set support.

amdfam10

barcelona

CPUs based on AMD Family 10h cores with x86–64 instruction set support. (This supersets MMX, SSE, SSE2, SSE3, SSE4A, 3DNow!, enhanced 3DNow!, ABM and 64-bit instruction set extensions.)

bdver1

CPUs based on AMD Family 15h cores with x86–64 instruction set support. (This supersets FMA4, AVX, XOP, LWP, AES, PCL_MUL, CX16, MMX, SSE, SSE2, SSE3, SSE4A, SSSE3, SSE4.1, SSE4.2, ABM and 64–bit instruction set extensions.)

bdver2

AMD Family 15h core based CPUs with x86–64 instruction set support. (This supersets BMI, TBM, F16C, FMA, AVX, XOP, LWP, AES, PCL_MUL, CX16, MMX, SSE, SSE2, SSE3, SSE4A, SSSE3, SSE4.1, SSE4.2, ABM and 64–bit instruction set extensions.)

bdver3

AMD Family 15h core based CPUs with x86–64 instruction set support. (This supersets BMI, TBM, F16C, FMA, AVX, XOP, LWP, AES, PCL_MUL, CX16, MMX, SSE, SSE2, SSE3, SSE4A, SSSE3, SSE4.1, SSE4.2, ABM and 64–bit instruction set extensions.

btver1

CPUs based on AMD Family 14h cores with x86–64 instruction set support. (This supersets MMX, SSE, SSE2, SSE3, SSE3, SSE4A, CX16, ABM and 64–bit instruction set extensions.)

btver2

CPUs based on AMD Family 16h cores with x86–64 instruction set support. This includes MOVBE, F16C, BMI, AVX, PCL_MUL, AES, SSE4.2, SSE4.1, CX16, ABM, SSE4A, SSSE3, SSE2, SSE, MMX and 64-bit instruction set extensions.

winchip-c6

IDT WinChip C6 CPU, dealt in same way as i486 with additional MMX instruction set support.

winchip2

IDT WinChip 2 CPU, dealt in same way as i486 with additional MMX and 3DNow! instruction set support.

c3 VIA C3 CPU with MMX and 3DNow! instruction set support. (No scheduling is implemented for this chip.)

c3-2

VIA C3-2 (Nehemiah/C5XL) CPU with MMX and SSE instruction set support. (No scheduling is implemented for this chip.)

geode

AMD Geode embedded processor with MMX and 3DNow! instruction set support.

-mtune=cpu-type

Tune to *cpu-type* everything applicable about the generated code, except for the ABI and the set of available instructions. While picking a specific *cpu-type* schedules things appropriately for that particular chip, the compiler does not generate any code that cannot run on the default machine type unless you use a **-march**=*cpu-type* option. For example, if GCC is configured for i686-pc-linux-gnu then **-mtune**=**pentium4** generates code that is tuned for Pentium 4 but still runs on i686 machines.

The choices for *cpu-type* are the same as for **-march**. In addition, **-mtune** supports an extra choice for *cpu-type*:

generic

Produce code optimized for the most common IA32/AMD64/EM64T processors. If you know the CPU on which your code will run, then you should use the corresponding **-mtune** or **-march** option instead of **-mtune=generic**. But, if you do not know exactly what CPU users of your application will have, then you should use this option.

As new processors are deployed in the marketplace, the behavior of this option will change. Therefore, if you upgrade to a newer version of GCC, code generation controlled by this option will change to reflect the processors that are most common at the time that version of GCC is released.

There is no **-march=generic** option because **-march** indicates the instruction set the compiler can use, and there is no generic instruction set applicable to all processors. In contrast, **-mtune** indicates the processor (or, in this case, collection of processors) for which the code is optimized.

-mcpu=cpu-type

A deprecated synonym for **-mtune**.

-mfpmath=unit

Generate floating-point arithmetic for selected unit *unit*. The choices for *unit* are:

387 Use the standard 387 floating-point coprocessor present on the majority of chips and emulated otherwise. Code compiled with this option runs almost everywhere. The temporary results are computed in 80-bit precision instead of the precision specified by the type, resulting in slightly different results compared to most of other chips. See **-ffloat-store** for more detailed description.

This is the default choice for i386 compiler.

sse Use scalar floating-point instructions present in the SSE instruction set. This instruction set is supported by Pentium III and newer chips, and in the AMD line by Athlon–4, Athlon XP and Athlon MP chips. The earlier version of the SSE instruction set supports only single-precision arithmetic, thus the double and extended-precision arithmetic are still done using 387. A later version, present only in Pentium 4 and AMD x86–64 chips, supports double-precision arithmetic too.

For the i386 compiler, you must use **-march**=*cpu*-*type*, **-msse** or **-msse2** switches to enable SSE extensions and make this option effective. For the x86–64 compiler, these extensions are enabled by default.

The resulting code should be considerably faster in the majority of cases and avoid the numerical instability problems of 387 code, but may break some existing code that expects temporaries to be 80 bits.

This is the default choice for the x86–64 compiler.

```
sse,387
sse+387
both
```

Attempt to utilize both instruction sets at once. This effectively doubles the amount of available registers, and on chips with separate execution units for 387 and SSE the execution resources too. Use this option with care, as it is still experimental, because the GCC register allocator does not model separate functional units well, resulting in unstable performance.

-masm=dialect

Output assembly instructions using selected *dialect*. Supported choices are **intel** or **att** (the default). Darwin does not support **intel**.

```
-mieee-fp
```

-mno-ieee-fp

Control whether or not the compiler uses IEEE floating-point comparisons. These correctly handle the case where the result of a comparison is unordered.

-msoft-float

Generate output containing library calls for floating point.

Warning: the requisite libraries are not part of GCC. Normally the facilities of the machine's usual C compiler are used, but this can't be done directly in cross-compilation. You must make your own arrangements to provide suitable library functions for cross-compilation.

On machines where a function returns floating-point results in the 80387 register stack, some floating-point opcodes may be emitted even if **-msoft-float** is used.

-mno-fp-ret-in-387

Do not use the FPU registers for return values of functions.

The usual calling convention has functions return values of types float and double in an FPU register, even if there is no FPU. The idea is that the operating system should emulate an FPU.

The option -mno-fp-ret-in-387 causes such values to be returned in ordinary CPU registers instead.

-mno-fancy-math-387

Some 387 emulators do not support the sin, cos and sqrt instructions for the 387. Specify this option to avoid generating those instructions. This option is the default on FreeBSD, OpenBSD and NetBSD. This option is overridden when **-march** indicates that the target CPU always has an FPU and so the instruction does not need emulation. These instructions are not generated unless you also use the **-funsafe-math-optimizations** switch.

-malign-double

-mno-align-double

Control whether GCC aligns double, long double, and long long variables on a two-word boundary or a one-word boundary. Aligning double variables on a two-word boundary produces code that runs somewhat faster on a Pentium at the expense of more memory.

On x86–64, **-malign-double** is enabled by default.

Warning: if you use the **-malign-double** switch, structures containing the above types are aligned differently than the published application binary interface specifications for the 386 and are not binary compatible with structures in code compiled without that switch.

-m96bit-long-double

-m128bit-long-double

These switches control the size of long double type. The i386 application binary interface specifies the size to be 96 bits, so **-m96bit-long-double** is the default in 32-bit mode.

Modern architectures (Pentium and newer) prefer long double to be aligned to an 8- or 16-byte boundary. In arrays or structures conforming to the ABI, this is not possible. So specifying **-m128bit-long-double** aligns long double to a 16-byte boundary by padding the long double with an additional 32-bit zero.

In the x86–64 compiler, **-m128bit-long-double** is the default choice as its ABI specifies that long double is aligned on 16-byte boundary.

Notice that neither of these options enable any extra precision over the x87 standard of 80 bits for a long double.

Warning: if you override the default value for your target ABI, this changes the size of structures and arrays containing long double variables, as well as modifying the function calling convention for functions taking long double. Hence they are not binary-compatible with code compiled without that switch.

-mlong-double-64

-mlong-double-80

These switches control the size of long double type. A size of 64 bits makes the long double type equivalent to the double type. This is the default for Bionic C library.

Warning: if you override the default value for your target ABI, this changes the size of structures and arrays containing long double variables, as well as modifying the function calling convention for functions taking long double. Hence they are not binary-compatible with code compiled without that switch.

-mlarge-data-threshold=threshold

When **–mcmodel=medium** is specified, data objects larger than *threshold* are placed in the large data section. This value must be the same across all objects linked into the binary, and defaults to 65535.

-mrtd

Use a different function-calling convention, in which functions that take a fixed number of arguments return with the ret num instruction, which pops their arguments while returning. This saves one instruction in the caller since there is no need to pop the arguments there.

You can specify that an individual function is called with this calling sequence with the function attribute **stdcall**. You can also override the **-mrtd** option by using the function attribute **cdecl**.

Warning: this calling convention is incompatible with the one normally used on Unix, so you cannot use it if you need to call libraries compiled with the Unix compiler.

Also, you must provide function prototypes for all functions that take variable numbers of arguments (including printf); otherwise incorrect code is generated for calls to those functions.

In addition, seriously incorrect code results if you call a function with too many arguments. (Normally, extra arguments are harmlessly ignored.)

-mregparm=num

Control how many registers are used to pass integer arguments. By default, no registers are used to pass arguments, and at most 3 registers can be used. You can control this behavior for a specific function by using the function attribute **regparm**.

Warning: if you use this switch, and *num* is nonzero, then you must build all modules with the same value, including any libraries. This includes the system libraries and startup modules.

-msseregparm

Use SSE register passing conventions for float and double arguments and return values. You can control this behavior for a specific function by using the function attribute **sseregparm**.

Warning: if you use this switch then you must build all modules with the same value, including any libraries. This includes the system libraries and startup modules.

-mvect8-ret-in-mem

Return 8-byte vectors in memory instead of MMX registers. This is the default on Solaris@tie{}8 and 9 and VxWorks to match the ABI of the Sun Studio compilers until version 12. Later compiler versions (starting with Studio 12 Update@tie{}1) follow the ABI used by other x86 targets, which is the default on Solaris@tie{}10 and later. *Only* use this option if you need to remain compatible with existing code produced by those previous compiler versions or older versions of GCC.

-mpc32

-mpc64

-mpc80

Set 80387 floating-point precision to 32, 64 or 80 bits. When **-mpc32** is specified, the significands of results of floating-point operations are rounded to 24 bits (single precision); **-mpc64** rounds the significands of results of floating-point operations to 53 bits (double precision) and **-mpc80** rounds the significands of results of floating-point operations to 64 bits (extended double precision), which is the default. When this option is used, floating-point operations in higher precisions are not available to the programmer without setting the FPU control word explicitly.

Setting the rounding of floating-point operations to less than the default 80 bits can speed some programs by 2% or more. Note that some mathematical libraries assume that extended-precision (80-bit) floating-point operations are enabled by default; routines in such libraries could suffer significant loss of accuracy, typically through so-called "catastrophic cancellation", when this option

is used to set the precision to less than extended precision.

-mstackrealign

Realign the stack at entry. On the Intel x86, the **-mstackrealign** option generates an alternate prologue and epilogue that realigns the run-time stack if necessary. This supports mixing legacy codes that keep 4-byte stack alignment with modern codes that keep 16-byte stack alignment for SSE compatibility. See also the attribute force_align_arg_pointer, applicable to individual functions.

-mpreferred-stack-boundary = num

Attempt to keep the stack boundary aligned to a 2 raised to *num* byte boundary. If **-mpreferred-stack-boundary** is not specified, the default is 4 (16 bytes or 128 bits).

Warning: When generating code for the x86–64 architecture with SSE extensions disabled, **—mpreferred—stack—boundary=3** can be used to keep the stack boundary aligned to 8 byte boundary. Since x86–64 ABI require 16 byte stack alignment, this is ABI incompatible and intended to be used in controlled environment where stack space is important limitation. This option will lead to wrong code when functions compiled with 16 byte stack alignment (such as functions from a standard library) are called with misaligned stack. In this case, SSE instructions may lead to misaligned memory access traps. In addition, variable arguments will be handled incorrectly for 16 byte aligned objects (including x87 long double and __int128), leading to wrong results. You must build all modules with **—mpreferred—stack—boundary=3**, including any libraries. This includes the system libraries and startup modules.

-mincoming-stack-boundary=num

Assume the incoming stack is aligned to a 2 raised to *num* byte boundary. If **-mincoming-stack-boundary** is not specified, the one specified by **-mpreferred-stack-boundary** is used.

On Pentium and Pentium Pro, double and long double values should be aligned to an 8-byte boundary (see **-malign-double**) or suffer significant run time performance penalties. On Pentium III, the Streaming SIMD Extension (SSE) data type __m128 may not work properly if it is not 16-byte aligned.

To ensure proper alignment of this values on the stack, the stack boundary must be as aligned as that required by any value stored on the stack. Further, every function must be generated such that it keeps the stack aligned. Thus calling a function compiled with a higher preferred stack boundary from a function compiled with a lower preferred stack boundary most likely misaligns the stack. It is recommended that libraries that use callbacks always use the default setting.

This extra alignment does consume extra stack space, and generally increases code size. Code that is sensitive to stack space usage, such as embedded systems and operating system kernels, may want to reduce the preferred alignment to **-mpreferred-stack-boundary=2**.

- -mmmx
- -mno-mmx
- -msse
- -mno-sse
- -msse2
- -mno-sse2
- -msse3
- -mno-sse3
- -mssse3
- -mno-ssse3
- -msse4.1
- -mno-sse4.1
- -msse4.2

- -mno-sse4.2
- -msse4
- -mno-sse4
- -mavx
- -mno-avx
- -mavx2
- -mno-avx2
- -maes
- -mno-aes
- -mpclmul
- -mno-pclmul
- -mfsgsbase
- -mno-fsgsbase
- -mrdrnd
- -mno-rdrnd
- -mf16c
- -mno-f16c
- -mfma
- -mno-fma
- -msse4a
- -mno-sse4a
- -mfma4
- -mno-fma4
- -mxop
- -mno-xop
- -mlwp
- -mno-lwp
- -m3dnow
- -mno-3dnow
- -mpopent
- -mno-popent
- -mabm
- -mno-abm
- -mbmi
- -mbmi2
- -mno-bmi
- -mno-bmi2
- -mlzcnt
- -mno-lzcnt
- -mrtm
- -mtbm
- -mno-tbm

These switches enable or disable the use of instructions in the MMX, SSE, SSE2, SSE3, SSSE3, SSE4.1, AVX, AVX2, AES, PCLMUL, FSGSBASE, RDRND, F16C, FMA, SSE4A, FMA4, XOP, LWP, ABM, BMI, BMI2, LZCNT, RTM or 3DNow! extended instruction sets. These extensions are also available as built-in functions: see **X86 Built-in Functions**, for details of the functions enabled and disabled by these switches.

To generate SSE/SSE2 instructions automatically from floating-point code (as opposed to 387 instructions), see **-mfpmath=sse**.

GCC depresses SSEx instructions when **-mavx** is used. Instead, it generates new AVX instructions or AVX equivalence for all SSEx instructions when needed.

These options enable GCC to use these extended instructions in generated code, even without **-mfpmath=sse**. Applications that perform run-time CPU detection must compile separate files for

each supported architecture, using the appropriate flags. In particular, the file containing the CPU detection code should be compiled without these options.

-mcld

This option instructs GCC to emit a cld instruction in the prologue of functions that use string instructions. String instructions depend on the DF flag to select between autoincrement or autodecrement mode. While the ABI specifies the DF flag to be cleared on function entry, some operating systems violate this specification by not clearing the DF flag in their exception dispatchers. The exception handler can be invoked with the DF flag set, which leads to wrong direction mode when string instructions are used. This option can be enabled by default on 32-bit x86 targets by configuring GCC with the **--enable-cld** configure option. Generation of cld instructions can be suppressed with the **-mno-cld** compiler option in this case.

-mvzeroupper

This option instructs GCC to emit a vzeroupper instruction before a transfer of control flow out of the function to minimize the AVX to SSE transition penalty as well as remove unnecessary zeroupper intrinsics.

-mprefer-avx128

This option instructs GCC to use 128-bit AVX instructions instead of 256-bit AVX instructions in the auto-vectorizer.

-mcx16

This option enables GCC to generate CMPXCHG16B instructions. CMPXCHG16B allows for atomic operations on 128-bit double quadword (or oword) data types. This is useful for high-resolution counters that can be updated by multiple processors (or cores). This instruction is generated as part of atomic built-in functions: see __sync Builtins or __atomic Builtins for details.

-msahf

This option enables generation of SAHF instructions in 64-bit code. Early Intel Pentium 4 CPUs with Intel 64 support, prior to the introduction of Pentium 4 G1 step in December 2005, lacked the LAHF and SAHF instructions which were supported by AMD64. These are load and store instructions, respectively, for certain status flags. In 64-bit mode, the SAHF instruction is used to optimize fmod, drem, and remainder built-in functions; see **Other Builtins** for details.

-mmovbe

This option enables use of the movbe instruction to implement __builtin_bswap32 and __builtin_bswap64.

-mcrc32

```
This option enables built-in functions __builtin_ia32_crc32qi, __builtin_ia32_crc32hi, __builtin_ia32_crc32hi and __builtin_ia32_crc32di to generate the crc32 machine instruction.
```

-mrecip

This option enables use of RCPSS and RSQRTSS instructions (and their vectorized variants RCPPS and RSQRTPS) with an additional Newton-Raphson step to increase precision instead of DIVSS and SQRTSS (and their vectorized variants) for single-precision floating-point arguments. These instructions are generated only when **-funsafe-math-optimizations** is enabled together with **-finite-math-only** and **-fno-trapping-math**. Note that while the throughput of the sequence is higher than the throughput of the non-reciprocal instruction, the precision of the sequence can be decreased by up to 2 ulp (i.e. the inverse of 1.0 equals 0.99999994).

Note that GCC implements 1.0f/sqrtf(x) in terms of RSQRTSS (or RSQRTPS) already with **-ffast-math** (or the above option combination), and doesn't need **-mrecip**.

Also note that GCC emits the above sequence with additional Newton-Raphson step for vectorized single-float division and vectorized sqrtf(x) already with **-ffast-math** (or the above option combination), and doesn't need **-mrecip**.

-mrecip=opt

This option controls which reciprocal estimate instructions may be used. *opt* is a comma-separated list of options, which may be preceded by a ! to invert the option:

all Enable all estimate instructions.

default

Enable the default instructions, equivalent to -mrecip.

none

Disable all estimate instructions, equivalent to **-mno-recip**.

div Enable the approximation for scalar division.

vec-div

Enable the approximation for vectorized division.

sqrt

Enable the approximation for scalar square root.

vec-sqrt

Enable the approximation for vectorized square root.

So, for example, -mrecip=all,!sqrt enables all of the reciprocal approximations, except for square root.

-mveclibabi=type

Specifies the ABI type to use for vectorizing intrinsics using an external library. Supported values for *type* are **svml** for the Intel short vector math library and **acml** for the AMD math core library. To use this option, both **-ftree-vectorize** and **-funsafe-math-optimizations** have to be enabled, and an SVML or ACML ABI-compatible library must be specified at link time.

GCC currently emits calls to vmldExp2, vmldLn2, vmldLog102, vmldLog102, vmldPow2, vmldTanh2, vmldTanh2, vmldAtanh2, vmldAtanh2, vmldCbrt2, vmldSinh2, vmldSinh2, vmldAsinh2, vmldAsinh2, vmldCosh2, vmldAcosh2, vmldAcosh2, vmldAcosh2, vmldAcosh2, vmlsExp4, vmlsLn4, vmlsLog104, vmlsLog104, vmlsPow4, vmlsTanh4, vmlsTanh4, vmlsAtanh4, vmlsCbrt4, vmlsSinh4, vmlsSinh4, vmlsAsinh4, vmlsAsinh4, vmlsAcosh4, vmlsCosh4, vmlsAcosh4 and vmlsAcosh4 for corresponding function type when -mveclibabi=svml is used, and __vrd2_sin, __vrd2_cos, __vrd2_exp, __vrd2_log, __vrd2_log2, __vrd2_log10, __vrs4_sinf, __vrs4_cosf, __vrs4_expf, __vrs4_log1, __vrs4_log10 and __vrs4_powf for the corresponding function type when -mveclibabi=acml is used.

-mabi=name

Generate code for the specified calling convention. Permissible values are **sysv** for the ABI used on GNU/Linux and other systems, and **ms** for the Microsoft ABI. The default is to use the Microsoft ABI when targeting Microsoft Windows and the SysV ABI on all other systems. You can control this behavior for a specific function by using the function attribute **ms_abi/sysv_abi**.

-mtls-dialect=type

Generate code to access thread-local storage using the **gnu** or **gnu2** conventions. **gnu** is the conservative default; **gnu2** is more efficient, but it may add compile— and run-time requirements that cannot be satisfied on all systems.

-mpush-args

-mno-push-args

Use PUSH operations to store outgoing parameters. This method is shorter and usually equally fast as method using SUB/MOV operations and is enabled by default. In some cases disabling it may improve performance because of improved scheduling and reduced dependencies.

-maccumulate-outgoing-args

If enabled, the maximum amount of space required for outgoing arguments is computed in the function prologue. This is faster on most modern CPUs because of reduced dependencies, improved

scheduling and reduced stack usage when the preferred stack boundary is not equal to 2. The drawback is a notable increase in code size. This switch implies **-mno-push-args**.

-mthreads

Support thread-safe exception handling on MinGW. Programs that rely on thread-safe exception handling must compile and link all code with the **-mthreads** option. When compiling, **-mthreads** defines -D_MT; when linking, it links in a special thread helper library **-lmingwthrd** which cleans up per-thread exception-handling data.

-mno-align-stringops

Do not align the destination of inlined string operations. This switch reduces code size and improves performance in case the destination is already aligned, but GCC doesn't know about it.

-minline-all-stringops

By default GCC inlines string operations only when the destination is known to be aligned to least a 4-byte boundary. This enables more inlining and increases code size, but may improve performance of code that depends on fast memcpy, strlen, and memset for short lengths.

-minline-stringops-dynamically

For string operations of unknown size, use run-time checks with inline code for small blocks and a library call for large blocks.

-mstringop-strategy=alg

Override the internal decision heuristic for the particular algorithm to use for inlining string operations. The allowed values for *alg* are:

rep_byte rep_4byte rep_8byte

Expand using i386 rep prefix of the specified size.

byte_loop loop

unrolled_loop

Expand into an inline loop.

libcall

Always use a library call.

-momit-leaf-frame-pointer

Don't keep the frame pointer in a register for leaf functions. This avoids the instructions to save, set up, and restore frame pointers and makes an extra register available in leaf functions. The option **-fomit-leaf-frame-pointer** removes the frame pointer for leaf functions, which might make debugging harder.

-mtls-direct-seg-refs

-mno-tls-direct-seg-refs

Controls whether TLS variables may be accessed with offsets from the TLS segment register (*gs for 32-bit, *fs for 64-bit), or whether the thread base pointer must be added. Whether or not this is valid depends on the operating system, and whether it maps the segment to cover the entire TLS area.

For systems that use the GNU C Library, the default is on.

-msse2avx

-mno-sse2avx

Specify that the assembler should encode SSE instructions with VEX prefix. The option **-mavx** turns this on by default.

-mfentry

-mno-fentry

If profiling is active (**-pg**), put the profiling counter call before the prologue. Note: On x86 architectures the attribute ms_hook_prologue isn't possible at the moment for **-mfentry** and **-pg**.

-m8bit-idiv

-mno-8bit-idiv

On some processors, like Intel Atom, 8-bit unsigned integer divide is much faster than 32-bit/64-bit integer divide. This option generates a run-time check. If both dividend and divisor are within range of 0 to 255, 8-bit unsigned integer divide is used instead of 32-bit/64-bit integer divide.

-mavx256-split-unaligned-load

-mavx256-split-unaligned-store

Split 32-byte AVX unaligned load and store.

These -m switches are supported in addition to the above on x86-64 processors in 64-bit environments.

-m32

-m64

-mx32

Generate code for a 32-bit or 64-bit environment. The **-m32** option sets int, long, and pointer types to 32 bits, and generates code that runs on any i386 system.

The **-m64** option sets int to 32 bits and long and pointer types to 64 bits, and generates code for the x86-64 architecture. For Darwin only the **-m64** option also turns off the **-fno-pic** and **-mdynamic-no-pic** options.

The -mx32 option sets int, long, and pointer types to 32 bits, and generates code for the x86-64 architecture.

-mno-red-zone

Do not use a so-called "red zone" for x86–64 code. The red zone is mandated by the x86–64 ABI; it is a 128-byte area beyond the location of the stack pointer that is not modified by signal or interrupt handlers and therefore can be used for temporary data without adjusting the stack pointer. The flag **-mno-red-zone** disables this red zone.

-mcmodel=small

Generate code for the small code model: the program and its symbols must be linked in the lower 2 GB of the address space. Pointers are 64 bits. Programs can be statically or dynamically linked. This is the default code model.

-mcmodel=kernel

Generate code for the kernel code model. The kernel runs in the negative 2 GB of the address space. This model has to be used for Linux kernel code.

-mcmodel=medium

Generate code for the medium model: the program is linked in the lower 2 GB of the address space. Small symbols are also placed there. Symbols with sizes larger than **-mlarge-data-threshold** are put into large data or BSS sections and can be located above 2GB. Programs can be statically or dynamically linked.

-mcmodel=large

Generate code for the large model. This model makes no assumptions about addresses and sizes of sections.

-maddress-mode=long

Generate code for long address mode. This is only supported for 64-bit and x32 environments. It is the default address mode for 64-bit environments.

-maddress-mode=short

Generate code for short address mode. This is only supported for 32-bit and x32 environments. It is the default address mode for 32-bit and x32 environments.

i386 and x86-64 Windows Options

These additional options are available for Microsoft Windows targets:

-mconsole

This option specifies that a console application is to be generated, by instructing the linker to set the PE header subsystem type required for console applications. This option is available for Cygwin and MinGW targets and is enabled by default on those targets.

-mdll

This option is available for Cygwin and MinGW targets. It specifies that a DLL——a dynamic link library——is to be generated, enabling the selection of the required runtime startup object and entry point.

-mnop-fun-dllimport

This option is available for Cygwin and MinGW targets. It specifies that the dllimport attribute should be ignored.

-mthread

This option is available for MinGW targets. It specifies that MinGW-specific thread support is to be used.

-municode

This option is available for MinGW-w64 targets. It causes the UNICODE preprocessor macro to be predefined, and chooses Unicode-capable runtime startup code.

-mwin32

This option is available for Cygwin and MinGW targets. It specifies that the typical Microsoft Windows predefined macros are to be set in the pre-processor, but does not influence the choice of runtime library/startup code.

-mwindows

This option is available for Cygwin and MinGW targets. It specifies that a GUI application is to be generated by instructing the linker to set the PE header subsystem type appropriately.

-fno-set-stack-executable

This option is available for MinGW targets. It specifies that the executable flag for the stack used by nested functions isn't set. This is necessary for binaries running in kernel mode of Microsoft Windows, as there the User32 API, which is used to set executable privileges, isn't available.

-fwritable-relocated-rdata

This option is available for MinGW and Cygwin targets. It specifies that relocated-data in read-only section is put into .data section. This is a necessary for older runtimes not supporting modification of .rdata sections for pseudo-relocation.

-mpe-aligned-commons

This option is available for Cygwin and MinGW targets. It specifies that the GNU extension to the PE file format that permits the correct alignment of COMMON variables should be used when generating code. It is enabled by default if GCC detects that the target assembler found during configuration supports the feature.

See also under **i386 and x86–64 Options** for standard options.

IA-64 Options

These are the **-m** options defined for the Intel IA-64 architecture.

-mbig-endian

Generate code for a big-endian target. This is the default for HP-UX.

_mlittle_endian

Generate code for a little-endian target. This is the default for AIX5 and GNU/Linux.

-mgnu-as

-mno-gnu-as

Generate (or don't) code for the GNU assembler. This is the default.

-mgnu-ld

-mno-gnu-ld

Generate (or don't) code for the GNU linker. This is the default.

-mno-pic

Generate code that does not use a global pointer register. The result is not position independent code, and violates the IA-64 ABI.

-mvolatile-asm-stop

-mno-volatile-asm-stop

Generate (or don't) a stop bit immediately before and after volatile asm statements.

-mregister-names

-mno-register-names

Generate (or don't) in, loc, and out register names for the stacked registers. This may make assembler output more readable.

-mno-sdata

-msdata

Disable (or enable) optimizations that use the small data section. This may be useful for working around optimizer bugs.

-mconstant-gp

Generate code that uses a single constant global pointer value. This is useful when compiling kernel code.

-mauto-pic

Generate code that is self-relocatable. This implies **-mconstant-gp**. This is useful when compiling firmware code.

-minline-float-divide-min-latency

Generate code for inline divides of floating-point values using the minimum latency algorithm.

-minline-float-divide-max-throughput

Generate code for inline divides of floating-point values using the maximum throughput algorithm.

-mno-inline-float-divide

Do not generate inline code for divides of floating-point values.

-minline-int-divide-min-latency

Generate code for inline divides of integer values using the minimum latency algorithm.

-minline-int-divide-max-throughput

Generate code for inline divides of integer values using the maximum throughput algorithm.

-mno-inline-int-divide

Do not generate inline code for divides of integer values.

-minline-sqrt-min-latency

Generate code for inline square roots using the minimum latency algorithm.

-minline-sqrt-max-throughput

Generate code for inline square roots using the maximum throughput algorithm.

-mno-inline-sqrt

Do not generate inline code for sqrt.

-mfused-madd

-mno-fused-madd

Do (don't) generate code that uses the fused multiply/add or multiply/subtract instructions. The default is to use these instructions.

-mno-dwarf2-asm

-mdwarf2-asm Don't (or do)

Don't (or do) generate assembler code for the DWARF 2 line number debugging info. This may be useful when not using the GNU assembler.

-mearly-stop-bits

-mno-early-stop-bits

Allow stop bits to be placed earlier than immediately preceding the instruction that triggered the stop bit. This can improve instruction scheduling, but does not always do so.

-mfixed-range=register-range

Generate code treating the given register range as fixed registers. A fixed register is one that the register allocator cannot use. This is useful when compiling kernel code. A register range is specified as two registers separated by a dash. Multiple register ranges can be specified separated by a comma.

-mtls-size=tls-size

Specify bit size of immediate TLS offsets. Valid values are 14, 22, and 64.

-mtune=cpu-type

Tune the instruction scheduling for a particular CPU, Valid values are **itanium**, **itanium**, **merced**, **itanium**, and **mckinley**.

-milp32

-mlp64

Generate code for a 32-bit or 64-bit environment. The 32-bit environment sets int, long and pointer to 32 bits. The 64-bit environment sets int to 32 bits and long and pointer to 64 bits. These are HP-UX specific flags.

-mno-sched-br-data-spec

-msched-br-data-spec

(Dis/En)able data speculative scheduling before reload. This results in generation of ld.a instructions and the corresponding check instructions (ld.c/chk.a). The default is 'disable'.

-msched-ar-data-spec

-mno-sched-ar-data-spec

(En/Dis)able data speculative scheduling after reload. This results in generation of ld.a instructions and the corresponding check instructions (ld.c/chk.a). The default is 'enable'.

-mno-sched-control-spec

-msched-control-spec

(Dis/En)able control speculative scheduling. This feature is available only during region scheduling (i.e. before reload). This results in generation of the ld.s instructions and the corresponding check instructions chk.s. The default is 'disable'.

-msched-br-in-data-spec

-mno-sched-br-in-data-spec

(En/Dis)able speculative scheduling of the instructions that are dependent on the data speculative loads before reload. This is effective only with **-msched-br-data-spec** enabled. The default is 'enable'.

-msched-ar-in-data-spec

-mno-sched-ar-in-data-spec

(En/Dis)able speculative scheduling of the instructions that are dependent on the data speculative loads after reload. This is effective only with **-msched-ar-data-spec** enabled. The default is 'enable'.

-msched-in-control-spec

-mno-sched-in-control-spec

(En/Dis)able speculative scheduling of the instructions that are dependent on the control speculative loads. This is effective only with **-msched-control-spec** enabled. The default is 'enable'.

-mno-sched-prefer-non-data-spec-insns

-msched-prefer-non-data-spec-insns

If enabled, data-speculative instructions are chosen for schedule only if there are no other choices at the moment. This makes the use of the data speculation much more conservative. The default is 'disable'.

-mno-sched-prefer-non-control-spec-insns

-msched-prefer-non-control-spec-insns

If enabled, control-speculative instructions are chosen for schedule only if there are no other choices at the moment. This makes the use of the control speculation much more conservative. The default is 'disable'.

-mno-sched-count-spec-in-critical-path

-msched-count-spec-in-critical-path

If enabled, speculative dependencies are considered during computation of the instructions priorities. This makes the use of the speculation a bit more conservative. The default is 'disable'.

-msched-spec-ldc

Use a simple data speculation check. This option is on by default.

-msched-control-spec-ldc

Use a simple check for control speculation. This option is on by default.

-msched-stop-bits-after-every-cycle

Place a stop bit after every cycle when scheduling. This option is on by default.

-msched-fp-mem-deps-zero-cost

Assume that floating-point stores and loads are not likely to cause a conflict when placed into the same instruction group. This option is disabled by default.

-msel-sched-dont-check-control-spec

Generate checks for control speculation in selective scheduling. This flag is disabled by default.

-msched-max-memory-insns=max-insns

Limit on the number of memory insns per instruction group, giving lower priority to subsequent memory insns attempting to schedule in the same instruction group. Frequently useful to prevent cache bank conflicts. The default value is 1.

-msched-max-memory-insns-hard-limit

Makes the limit specified by **msched-max-memory-insns** a hard limit, disallowing more than that number in an instruction group. Otherwise, the limit is "soft", meaning that non-memory operations are preferred when the limit is reached, but memory operations may still be scheduled.

LM32 Options

These -m options are defined for the LatticeMico32 architecture:

-mbarrel-shift-enabled

Enable barrel-shift instructions.

-mdivide-enabled

Enable divide and modulus instructions.

-mmultiply-enabled

Enable multiply instructions.

-msign-extend-enabled

Enable sign extend instructions.

-muser-enabled

Enable user-defined instructions.

M32C Options

-mcpu=name

Select the CPU for which code is generated. *name* may be one of **r8c** for the R8C/Tiny series, **m16c** for the M16C (up to /60) series, **m32cm** for the M16C/80 series, or **m32c** for the M32C/80 series.

-msim

Specifies that the program will be run on the simulator. This causes an alternate runtime library to be linked in which supports, for example, file I/O. You must not use this option when generating programs that will run on real hardware; you must provide your own runtime library for whatever I/O functions are needed.

-memregs=number

Specifies the number of memory-based pseudo-registers GCC uses during code generation. These pseudo-registers are used like real registers, so there is a tradeoff between GCC's ability to fit the code into available registers, and the performance penalty of using memory instead of registers. Note that all modules in a program must be compiled with the same value for this option. Because of that, you must not use this option with GCC's default runtime libraries.

M32R/D Options

These -m options are defined for Renesas M32R/D architectures:

-m32r2

Generate code for the M32R/2.

-m32rx

Generate code for the M32R/X.

-m32r

Generate code for the M32R. This is the default.

-mmodel=small

Assume all objects live in the lower 16MB of memory (so that their addresses can be loaded with the 1d24 instruction), and assume all subroutines are reachable with the b1 instruction. This is the default

The addressability of a particular object can be set with the model attribute.

-mmodel=medium

Assume objects may be anywhere in the 32-bit address space (the compiler generates seth/add3 instructions to load their addresses), and assume all subroutines are reachable with the bl instruction.

-mmodel=large

Assume objects may be anywhere in the 32-bit address space (the compiler generates seth/add3 instructions to load their addresses), and assume subroutines may not be reachable with the b1 instruction (the compiler generates the much slower seth/add3/j1 instruction sequence).

-msdata=none

Disable use of the small data area. Variables are put into one of .data, .bss, or .rodata (unless the section attribute has been specified). This is the default.

The small data area consists of sections **.sdata** and **.sbss**. Objects may be explicitly put in the small data area with the section attribute using one of these sections.

-msdata=sdata

Put small global and static data in the small data area, but do not generate special code to reference them

-msdata=use

Put small global and static data in the small data area, and generate special instructions to reference them.

−G *num*

Put global and static objects less than or equal to *num* bytes into the small data or BSS sections instead of the normal data or BSS sections. The default value of *num* is 8. The **-msdata** option must be set to one of **sdata** or **use** for this option to have any effect.

All modules should be compiled with the same **-G** *num* value. Compiling with different values of *num* may or may not work; if it doesn't the linker gives an error message——incorrect code is not

generated.

-mdebug

Makes the M32R-specific code in the compiler display some statistics that might help in debugging programs.

-malign-loops

Align all loops to a 32-byte boundary.

-mno-align-loops

Do not enforce a 32-byte alignment for loops. This is the default.

-missue-rate=number

Issue *number* instructions per cycle. *number* can only be 1 or 2.

-mbranch-cost=number

number can only be 1 or 2. If it is 1 then branches are preferred over conditional code, if it is 2, then the opposite applies.

-mflush-trap=number

Specifies the trap number to use to flush the cache. The default is 12. Valid numbers are between 0 and 15 inclusive.

-mno-flush-trap

Specifies that the cache cannot be flushed by using a trap.

-mflush-func=name

Specifies the name of the operating system function to call to flush the cache. The default is _flush_cache, but a function call is only used if a trap is not available.

-mno-flush-func

Indicates that there is no OS function for flushing the cache.

M680x0 Options

These are the -m options defined for M680x0 and ColdFire processors. The default settings depend on which architecture was selected when the compiler was configured; the defaults for the most common choices are given below.

-march=arch

Generate code for a specific M680x0 or ColdFire instruction set architecture. Permissible values of *arch* for M680x0 architectures are: **68000**, **68010**, **68020**, **68030**, **68040**, **68060** and **cpu32**. ColdFire architectures are selected according to Freescale's ISA classification and the permissible values are: **isaa**, **isaaplus**, **isab** and **isac**.

GCC defines a macro __mcfarch__ whenever it is generating code for a ColdFire target. The arch in this macro is one of the -march arguments given above.

When used together, **-march** and **-mtune** select code that runs on a family of similar processors but that is optimized for a particular microarchitecture.

−mcpu=*cpu*

Generate code for a specific M680x0 or ColdFire processor. The M680x0 *cpus* are: **68000**, **68010**, **68020**, **68030**, **68040**, **68060**, **68302**, **68332** and **cpu32**. The ColdFire *cpus* are given by the table below, which also classifies the CPUs into families:

Family: -mcpu arguments

51 : 51 51ac 51ag 51cn 51em 51je 51jf 51jg 51jm 51mm 51qe 51qm

5206 : 5202 5204 5206

5206e : 5206e 5208 : 5207 5208 5211a : 5210a 5211a 5213 : 5211 5212 5213 5216 : 5214 5216

52235 : 52230 52231 52232 52233 52234 52235

5225 : 5224 5225

52259 : 52252 52254 52255 52256 52258 52259

5235 : 5232 5233 5234 5235 523x

5249 : 5249 5250 : 5250 5271 : 5270 5271 5272 : 5272 5275 : 5274 5275

5282 : 5280 5281 5282 528x

53017 : 53011 53012 53013 53014 53015 53016 53017

5307:5307

5329 : 5327 5328 5329 532x 5373 : 5372 5373 537x

5407:5407

5475 : 5470 5471 5472 5473 5474 5475 547x 5480 5481 5482 5483 5484 5485

-mcpu=cpu overrides -march=arch if arch is compatible with cpu. Other combinations of -mcpu and -march are rejected.

GCC defines the macro __mcf_cpu_cpu when ColdFire target cpu is selected. It also defines __mcf_family_family, where the value of family is given by the table above.

-mtune=tune

Tune the code for a particular microarchitecture within the constraints set by **-march** and **-mcpu**. The M680x0 microarchitectures are: **68000**, **68010**, **68020**, **68030**, **68040**, **68060** and **cpu32**. The ColdFire microarchitectures are: **cfv1**, **cfv2**, **cfv3**, **cfv4** and **cfv4e**.

You can also use **-mtune=68020-40** for code that needs to run relatively well on 68020, 68030 and 68040 targets. **-mtune=68020-60** is similar but includes 68060 targets as well. These two options select the same tuning decisions as **-m68020-40** and **-m68020-60** respectively.

GCC defines the macros __mcarch and __mcarch__ when tuning for 680x0 architecture arch. It also defines mcarch unless either -ansi or a non-GNU -std option is used. If GCC is tuning for a range of architectures, as selected by -mtune=68020-40 or -mtune=68020-60, it defines the macros for every architecture in the range.

GCC also defines the macro __muarch__ when tuning for ColdFire microarchitecture uarch, where uarch is one of the arguments given above.

-m68000

-mc68000

Generate output for a 68000. This is the default when the compiler is configured for 68000–based systems. It is equivalent to **–march=68000**.

Use this option for microcontrollers with a 68000 or EC000 core, including the 68008, 68302, 68306, 68307, 68322, 68328 and 68356.

-m68010

Generate output for a 68010. This is the default when the compiler is configured for 68010–based systems. It is equivalent to **-march=68010**.

-m68020

-mc68020

Generate output for a 68020. This is the default when the compiler is configured for 68020-based systems. It is equivalent to **-march=68020**.

-m68030

Generate output for a 68030. This is the default when the compiler is configured for 68030–based systems. It is equivalent to **-march=68030**.

-m68040

Generate output for a 68040. This is the default when the compiler is configured for 68040–based systems. It is equivalent to **-march=68040**.

This option inhibits the use of 68881/68882 instructions that have to be emulated by software on the 68040. Use this option if your 68040 does not have code to emulate those instructions.

-m68060

Generate output for a 68060. This is the default when the compiler is configured for 68060–based systems. It is equivalent to **-march=68060**.

This option inhibits the use of 68020 and 68881/68882 instructions that have to be emulated by software on the 68060. Use this option if your 68060 does not have code to emulate those instructions.

-mcpu32

Generate output for a CPU32. This is the default when the compiler is configured for CPU32-based systems. It is equivalent to **-march=cpu32**.

Use this option for microcontrollers with a CPU32 or CPU32+ core, including the 68330, 68331, 68332, 68333, 68334, 68340, 68341, 68349 and 68360.

-m5200

Generate output for a 520X ColdFire CPU. This is the default when the compiler is configured for 520X-based systems. It is equivalent to **-mcpu=5206**, and is now deprecated in favor of that option.

Use this option for microcontroller with a 5200 core, including the MCF5202, MCF5203, MCF5204 and MCF5206.

-m5206e

Generate output for a 5206e ColdFire CPU. The option is now deprecated in favor of the equivalent **-mcpu=5206e**.

-m528x

Generate output for a member of the ColdFire 528X family. The option is now deprecated in favor of the equivalent -mcpu=528x.

-m5307

Generate output for a ColdFire 5307 CPU. The option is now deprecated in favor of the equivalent **-mcpu=5307**.

-m5407

Generate output for a ColdFire 5407 CPU. The option is now deprecated in favor of the equivalent -mcpu=5407.

-mcfv4e

Generate output for a ColdFire V4e family CPU (e.g. 547x/548x). This includes use of hardware floating-point instructions. The option is equivalent to **-mcpu=547x**, and is now deprecated in favor of that option.

-m68020-40

Generate output for a 68040, without using any of the new instructions. This results in code that can run relatively efficiently on either a 68020/68881 or a 68030 or a 68040. The generated code does use the 68881 instructions that are emulated on the 68040.

The option is equivalent to -march=68020 -mtune=68020-40.

-m68020-60

Generate output for a 68060, without using any of the new instructions. This results in code that can run relatively efficiently on either a 68020/68881 or a 68030 or a 68040. The generated code does use

the 68881 instructions that are emulated on the 68060.

The option is equivalent to -march=68020 -mtune=68020-60.

-mhard-float

-m68881

Generate floating-point instructions. This is the default for 68020 and above, and for ColdFire devices that have an FPU. It defines the macro __HAVE_68881__ on M680x0 targets and __mcffpu__ on ColdFire targets.

-msoft-float

Do not generate floating-point instructions; use library calls instead. This is the default for 68000, 68010, and 68832 targets. It is also the default for ColdFire devices that have no FPU.

-mdiv

-mno-div

Generate (do not generate) ColdFire hardware divide and remainder instructions. If **-march** is used without **-mcpu**, the default is "on" for ColdFire architectures and "off" for M680x0 architectures. Otherwise, the default is taken from the target CPU (either the default CPU, or the one specified by **-mcpu**). For example, the default is "off" for **-mcpu=5206** and "on" for **-mcpu=5206e**.

GCC defines the macro __mcfhwdiv__ when this option is enabled.

-mshort

Consider type int to be 16 bits wide, like short int. Additionally, parameters passed on the stack are also aligned to a 16-bit boundary even on targets whose API mandates promotion to 32-bit.

-mno-short

Do not consider type int to be 16 bits wide. This is the default.

-mnobitfield

-mno-bitfield

Do not use the bit-field instructions. The **-m68000**, **-mcpu32** and **-m5200** options imply **-mnobitfield**.

-mbitfield

Do use the bit-field instructions. The -m68020 option implies -mbitfield. This is the default if you use a configuration designed for a 68020.

-mrtd

Use a different function-calling convention, in which functions that take a fixed number of arguments return with the rtd instruction, which pops their arguments while returning. This saves one instruction in the caller since there is no need to pop the arguments there.

This calling convention is incompatible with the one normally used on Unix, so you cannot use it if you need to call libraries compiled with the Unix compiler.

Also, you must provide function prototypes for all functions that take variable numbers of arguments (including printf); otherwise incorrect code is generated for calls to those functions.

In addition, seriously incorrect code results if you call a function with too many arguments. (Normally, extra arguments are harmlessly ignored.)

The rtd instruction is supported by the 68010, 68020, 68030, 68040, 68060 and CPU32 processors, but not by the 68000 or 5200.

_mno_rtd

Do not use the calling conventions selected by -mrtd. This is the default.

-malign-int

-mno-align-int

Control whether GCC aligns int, long, long long, float, double, and long double variables on a 32-bit boundary (-malign-int) or a 16-bit boundary (-mno-align-int). Aligning

variables on 32-bit boundaries produces code that runs somewhat faster on processors with 32-bit busses at the expense of more memory.

Warning: if you use the **-malign-int** switch, GCC aligns structures containing the above types differently than most published application binary interface specifications for the m68k.

-mpcrel

Use the pc-relative addressing mode of the 68000 directly, instead of using a global offset table. At present, this option implies **–fpic**, allowing at most a 16–bit offset for pc-relative addressing. **–fPIC** is not presently supported with **–mpcrel**, though this could be supported for 68020 and higher processors.

-mno-strict-align

-mstrict-align

Do not (do) assume that unaligned memory references are handled by the system.

-msep-data

Generate code that allows the data segment to be located in a different area of memory from the text segment. This allows for execute-in-place in an environment without virtual memory management. This option implies **-fPIC**.

-mno-sep-data

Generate code that assumes that the data segment follows the text segment. This is the default.

-mid-shared-library

Generate code that supports shared libraries via the library ID method. This allows for execute-inplace and shared libraries in an environment without virtual memory management. This option implies **-fPIC**.

-mno-id-shared-library

Generate code that doesn't assume ID-based shared libraries are being used. This is the default.

-mshared-library-id=n

Specifies the identification number of the ID-based shared library being compiled. Specifying a value of 0 generates more compact code; specifying other values forces the allocation of that number to the current library, but is no more space— or time-efficient than omitting this option.

-mxgot

-mno-xgot

When generating position-independent code for ColdFire, generate code that works if the GOT has more than 8192 entries. This code is larger and slower than code generated without this option. On M680x0 processors, this option is not needed; **-fPIC** suffices.

GCC normally uses a single instruction to load values from the GOT. While this is relatively efficient, it only works if the GOT is smaller than about 64k. Anything larger causes the linker to report an error such as:

```
relocation truncated to fit: R_68K_GOT160 foobar
```

If this happens, you should recompile your code with **-mxgot**. It should then work with very large GOTs. However, code generated with **-mxgot** is less efficient, since it takes 4 instructions to fetch the value of a global symbol.

Note that some linkers, including newer versions of the GNU linker, can create multiple GOTs and sort GOT entries. If you have such a linker, you should only need to use **-mxgot** when compiling a single object file that accesses more than 8192 GOT entries. Very few do.

These options have no effect unless GCC is generating position-independent code.

MCore Options

These are the **-m** options defined for the Motorola M*Core processors.

-mhardlit

-mno-hardlit

Inline constants into the code stream if it can be done in two instructions or less.

-mdiv

-mno-div

Use the divide instruction. (Enabled by default).

-mrelax-immediate

-mno-relax-immediate

Allow arbitrary-sized immediates in bit operations.

-mwide-bitfields

-mno-wide-bitfields

Always treat bit-fields as int-sized.

-m4byte-functions

-mno-4byte-functions

Force all functions to be aligned to a 4-byte boundary.

-mcallgraph-data

-mno-callgraph-data

Emit callgraph information.

-mslow-bytes

-mno-slow-bytes

Prefer word access when reading byte quantities.

-mlittle-endian

-mbig-endian

Generate code for a little-endian target.

-m210

-m340

Generate code for the 210 processor.

-mno-lsim

Assume that runtime support has been provided and so omit the simulator library (*libsim.a*) from the linker command line.

-mstack-increment=size

Set the maximum amount for a single stack increment operation. Large values can increase the speed of programs that contain functions that need a large amount of stack space, but they can also trigger a segmentation fault if the stack is extended too much. The default value is 0x1000.

MeP Options

-mabsdiff

Enables the abs instruction, which is the absolute difference between two registers.

-mall-opts

Enables all the optional instructions——average, multiply, divide, bit operations, leading zero, absolute difference, min/max, clip, and saturation.

-maverage

Enables the ave instruction, which computes the average of two registers.

-mbased=n

Variables of size n bytes or smaller are placed in the .based section by default. Based variables use the p register as a base register, and there is a 128-byte limit to the .based section.

-mbitops

Enables the bit operation instructions——bit test (btstm), set (bsetm), clear (bclrm), invert (bnotm), and test-and-set (tas).

-mc=*name*

Selects which section constant data is placed in. *name* may be tiny, near, or far.

-mclip

Enables the clip instruction. Note that -mclip is not useful unless you also provide -mminmax.

-mconfig=name

Selects one of the built-in core configurations. Each MeP chip has one or more modules in it; each module has a core CPU and a variety of coprocessors, optional instructions, and peripherals. The MeP-Integrator tool, not part of GCC, provides these configurations through this option; using this option is the same as using all the corresponding command-line options. The default configuration is default.

-mcop

Enables the coprocessor instructions. By default, this is a 32-bit coprocessor. Note that the coprocessor is normally enabled via the -mconfig= option.

-mcop32

Enables the 32-bit coprocessor's instructions.

-mcop64

Enables the 64-bit coprocessor's instructions.

-mivc2

Enables IVC2 scheduling. IVC2 is a 64-bit VLIW coprocessor.

-mdc

Causes constant variables to be placed in the .near section.

-mdiv

Enables the div and divu instructions.

-meb

Generate big-endian code.

-mel

Generate little-endian code.

-mio-volatile

Tells the compiler that any variable marked with the io attribute is to be considered volatile.

-ml

Causes variables to be assigned to the .far section by default.

-mleadz

Enables the leadz (leading zero) instruction.

-mm

Causes variables to be assigned to the .near section by default.

-mminmax

Enables the min and max instructions.

-mmult

Enables the multiplication and multiply-accumulate instructions.

-mno-opts

Disables all the optional instructions enabled by -mall-opts.

-mrepeat

Enables the repeat and erepeat instructions, used for low-overhead looping.

-ms

Causes all variables to default to the .tiny section. Note that there is a 65536-byte limit to this section. Accesses to these variables use the %gp base register.

-msatur

Enables the saturation instructions. Note that the compiler does not currently generate these itself, but this option is included for compatibility with other tools, like as.

-msdram

Link the SDRAM-based runtime instead of the default ROM-based runtime.

-msim

Link the simulator runtime libraries.

-msimnovec

Link the simulator runtime libraries, excluding built-in support for reset and exception vectors and tables.

-mtf

Causes all functions to default to the .far section. Without this option, functions default to the .near section.

-mtinv=n

Variables that are n bytes or smaller are allocated to the .tiny section. These variables use the \$gp base register. The default for this option is 4, but note that there's a 65536-byte limit to the .tiny section.

MicroBlaze Options

-msoft-float

Use software emulation for floating point (default).

-mhard-float

Use hardware floating-point instructions.

-mmemcpy

Do not optimize block moves, use memcpy.

-mno-clearbss

This option is deprecated. Use **-fno-zero-initialized-in-bss** instead.

-mcpu=cpu-type

Use features of, and schedule code for, the given CPU. Supported values are in the format **v***X***.***YY***.***Z*, where *X* is a major version, *YY* is the minor version, and *Z* is compatibility code. Example values are **v3.00.a**, **v4.00.b**, **v5.00.a**, **v5.00.b**, **v5.00.b**, **v6.00.a**.

-mxl-soft-mul

Use software multiply emulation (default).

-mxl-soft-div

Use software emulation for divides (default).

-mxl-barrel-shift

Use the hardware barrel shifter.

-mxl-pattern-compare

Use pattern compare instructions.

-msmall-divides

Use table lookup optimization for small signed integer divisions.

-mxl-stack-check

This option is deprecated. Use **-fstack-check** instead.

-mxl-gp-opt

Use GP-relative .sdata/.sbss sections.

-mxl-multiply-high

Use multiply high instructions for high part of 32x32 multiply.

-mxl-float-convert

Use hardware floating-point conversion instructions.

-mxl-float-sqrt

Use hardware floating-point square root instruction.

-mbig-endian

Generate code for a big-endian target.

-mlittle-endian

Generate code for a little-endian target.

-mxl-reorder

Use reorder instructions (swap and byte reversed load/store).

-mxl-mode-app-model

Select application model app-model. Valid models are

executable

normal executable (default), uses startup code crt0.o.

xmdstub

for use with Xilinx Microprocessor Debugger (XMD) based software intrusive debug agent called xmdstub. This uses startup file *crt1.o* and sets the start address of the program to 0x800.

bootstrap

for applications that are loaded using a bootloader. This model uses startup file *crt2.o* which does not contain a processor reset vector handler. This is suitable for transferring control on a processor reset to the bootloader rather than the application.

novectors

for applications that do not require any of the MicroBlaze vectors. This option may be useful for applications running within a monitoring application. This model uses *crt3.o* as a startup file.

Option **-xl-mode**-app-model is a deprecated alias for **-mxl-mode**-app-model.

MIPS Options

-EB

Generate big-endian code.

-EL

Generate little-endian code. This is the default for **mips*el-*-*** configurations.

-march=arch

Generate code that runs on *arch*, which can be the name of a generic MIPS ISA, or the name of a particular processor. The ISA names are: mips1, mips2, mips3, mips4, mips32, mips32r2, mips64 and mips64r2. The processor names are: 4kc, 4km, 4kp, 4ksc, 4kec, 4kem, 4kep, 4ksd, 5kc, 5kf, 20kc, 24kc, 24kf2_1, 24kf1_1, 24kec, 24kef2_1, 24kef1_1, 34kc, 34kf2_1, 34kf1_1, 34kn, 74kc, 74kf2_1, 74kf1_1, 74kf3_2, 1004kc, 1004kf2_1, 1004kf1_1, loongson2e, loongson2f, loongson3a, m4k, octeon, octeon+, octeon2, orion, r2000, r3000, r3900, r4000, r4400, r4600, r4650, r4700, r6000, r8000, rm7000, rm9000, r10000, r12000, r14000, r16000, sb1, sr71000, vr4100, vr4111, vr4120, vr4130, vr4300, vr5000, vr5400, vr5500, xlr and xlp. The special value from-abi selects the most compatible architecture for the selected ABI (that is, mips1 for 32-bit ABIs and mips3 for 64-bit ABIs).

The native Linux/GNU toolchain also supports the value **native**, which selects the best architecture option for the host processor. **–march=native** has no effect if GCC does not recognize the processor.

In processor names, a final 000 can be abbreviated as **k** (for example, -march=r2k). Prefixes are optional, and vr may be written r.

Names of the form $n\mathbf{f2}_{-1}$ refer to processors with FPUs clocked at half the rate of the core, names of the form $n\mathbf{f1}_{-1}$ refer to processors with FPUs clocked at the same rate as the core, and names of the

form $nf3_2$ refer to processors with FPUs clocked a ratio of 3:2 with respect to the core. For compatibility reasons, nf is accepted as a synonym for $nf2_1$ while nx and bfx are accepted as synonyms for $nf1_1$.

GCC defines two macros based on the value of this option. The first is _MIPS_ARCH, which gives the name of target architecture, as a string. The second has the form _MIPS_ARCH_foo, where foo is the capitalized value of _MIPS_ARCH. For example, -march=r2000 sets _MIPS_ARCH to "r2000" and defines the macro _MIPS_ARCH_R2000.

Note that the _MIPS_ARCH macro uses the processor names given above. In other words, it has the full prefix and does not abbreviate 000 as k. In the case of from-abi, the macro names the resolved architecture (either "mips1" or "mips3"). It names the default architecture when no -march option is given.

-mtune=arch

Optimize for *arch*. Among other things, this option controls the way instructions are scheduled, and the perceived cost of arithmetic operations. The list of *arch* values is the same as for **–march**.

When this option is not used, GCC optimizes for the processor specified by **-march**. By using **-march** and **-mtune** together, it is possible to generate code that runs on a family of processors, but optimize the code for one particular member of that family.

-mtune defines the macros **_MIPS_TUNE** and **_MIPS_TUNE**_*foo*, which work in the same way as the **-march** ones described above.

-mips1

Equivalent to **-march=mips1**.

-mips2

Equivalent to -march=mips2.

-mips3

Equivalent to **-march=mips3**.

-mips4

Equivalent to -march=mips4.

-mips32

Equivalent to **-march=mips32**.

-mips32r2

Equivalent to **-march=mips32r2**.

-mips64

Equivalent to -march=mips64.

-mips64r2

Equivalent to -march=mips64r2.

-mips16

-mno-mips16

Generate (do not generate) MIPS16 code. If GCC is targeting a MIPS32 or MIPS64 architecture, it makes use of the MIPS16e ASE.

MIPS16 code generation can also be controlled on a per-function basis by means of mips16 and nomips16 attributes.

-mflip-mips16

Generate MIPS16 code on alternating functions. This option is provided for regression testing of mixed MIPS16/non-MIPS16 code generation, and is not intended for ordinary use in compiling user code.

-minterlink-mips16

-mno-interlink-mips16

Require (do not require) that non-MIPS16 code be link-compatible with MIPS16 code.

For example, non–MIPS16 code cannot jump directly to MIPS16 code; it must either use a call or an indirect jump. **–minterlink–mips16** therefore disables direct jumps unless GCC knows that the target of the jump is not MIPS16.

- -mabi=32
- -mabi=o64
- -mabi=n32
- -mabi=64
- -mabi=eabi

Generate code for the given ABI.

Note that the EABI has a 32-bit and a 64-bit variant. GCC normally generates 64-bit code when you select a 64-bit architecture, but you can use **-mgp32** to get 32-bit code instead.

For information about the O64 ABI, see http://gcc.gnu.org/projects/mipso64-abi.html>.

GCC supports a variant of the o32 ABI in which floating-point registers are 64 rather than 32 bits wide. You can select this combination with **-mabi=32 -mfp64**. This ABI relies on the mthcl and mfhcl instructions and is therefore only supported for MIPS32R2 processors.

The register assignments for arguments and return values remain the same, but each scalar value is passed in a single 64-bit register rather than a pair of 32-bit registers. For example, scalar floating-point values are returned in \$£0 only, not a \$£0/\$£1 pair. The set of call-saved registers also remains the same, but all 64 bits are saved.

-mabicalls

-mno-abicalls

Generate (do not generate) code that is suitable for SVR4–style dynamic objects. **–mabicalls** is the default for SVR4–based systems.

-mshared

-mno-shared

Generate (do not generate) code that is fully position-independent, and that can therefore be linked into shared libraries. This option only affects **–mabicalls**.

All **-mabicalls** code has traditionally been position-independent, regardless of options like **-fPIC** and **-fpic**. However, as an extension, the GNU toolchain allows executables to use absolute accesses for locally-binding symbols. It can also use shorter GP initialization sequences and generate direct calls to locally-defined functions. This mode is selected by **-mno-shared**.

-mno-shared depends on binutils 2.16 or higher and generates objects that can only be linked by the GNU linker. However, the option does not affect the ABI of the final executable; it only affects the ABI of relocatable objects. Using **-mno-shared** generally makes executables both smaller and quicker.

-mshared is the default.

-mplt

-mno-plt

Assume (do not assume) that the static and dynamic linkers support PLTs and copy relocations. This option only affects **-mno-shared -mabicalls**. For the n64 ABI, this option has no effect without **-msym32**.

You can make **-mplt** the default by configuring GCC with **--with-mips-plt**. The default is **-mno-plt** otherwise.

-mxgot

-mno-xgot

Lift (do not lift) the usual restrictions on the size of the global offset table.

GCC normally uses a single instruction to load values from the GOT. While this is relatively efficient, it only works if the GOT is smaller than about 64k. Anything larger causes the linker to report an error such as:

```
relocation truncated to fit: R_MIPS_GOT16 foobar
```

If this happens, you should recompile your code with **-mxgot**. This works with very large GOTs, although the code is also less efficient, since it takes three instructions to fetch the value of a global symbol.

Note that some linkers can create multiple GOTs. If you have such a linker, you should only need to use **-mxgot** when a single object file accesses more than 64k's worth of GOT entries. Very few do.

These options have no effect unless GCC is generating position independent code.

-mgp32

Assume that general-purpose registers are 32 bits wide.

-mgp64

Assume that general-purpose registers are 64 bits wide.

-mfp32

Assume that floating-point registers are 32 bits wide.

-mfp64

Assume that floating-point registers are 64 bits wide.

-mhard-float

Use floating-point coprocessor instructions.

-msoft-float

Do not use floating-point coprocessor instructions. Implement floating-point calculations using library calls instead.

-mno-float

Equivalent to **-msoft-float**, but additionally asserts that the program being compiled does not perform any floating-point operations. This option is presently supported only by some bare-metal MIPS configurations, where it may select a special set of libraries that lack all floating-point support (including, for example, the floating-point printf formats). If code compiled with -mno-float accidentally contains floating-point operations, it is likely to suffer a link-time or run-time failure.

-msingle-float

Assume that the floating-point coprocessor only supports single-precision operations.

-mdouble-float

Assume that the floating-point coprocessor supports double-precision operations. This is the default.

-mllsc

-mno-llsc

Use (do not use) **ll**, **sc**, and **sync** instructions to implement atomic memory built-in functions. When neither option is specified, GCC uses the instructions if the target architecture supports them.

-mllsc is useful if the runtime environment can emulate the instructions and -mno-llsc can be useful when compiling for nonstandard ISAs. You can make either option the default by configuring GCC with --with-llsc and --without-llsc respectively. --with-llsc is the default for some configurations; see the installation documentation for details.

-mdsp

-mno-dsp

Use (do not use) revision 1 of the MIPS DSP ASE.

This option defines the preprocessor macro __mips_dsp. It also defines __mips_dsp_rev to 1.

-mdspr2

-mno-dspr2

Use (do not use) revision 2 of the MIPS DSP ASE.

This option defines the preprocessor macros __mips_dsp and __mips_dspr2. It also defines __mips_dsp_rev to 2.

-msmartmips

-mno-smartmips

Use (do not use) the MIPS SmartMIPS ASE.

-mpaired-single

-mno-paired-single

Use (do not use) paired-single floating-point instructions.

This option requires hardware floating-point support to be enabled.

-mdmx

-mno-mdmx

Use (do not use) MIPS Digital Media Extension instructions. This option can only be used when generating 64-bit code and requires hardware floating-point support to be enabled.

-mips3d

-mno-mips3d

Use (do not use) the MIPS-3D ASE. The option -mips3d implies -mpaired-single.

-mmt

-mno-mt

Use (do not use) MT Multithreading instructions.

-mmcu

-mno-mcu

Use (do not use) the MIPS MCU ASE instructions.

-mlong64

Force long types to be 64 bits wide. See **-mlong32** for an explanation of the default and the way that the pointer size is determined.

-mlong32

Force long, int, and pointer types to be 32 bits wide.

The default size of ints, longs and pointers depends on the ABI. All the supported ABIs use 32-bit ints. The n64 ABI uses 64-bit longs, as does the 64-bit EABI; the others use 32-bit longs. Pointers are the same size as longs, or the same size as integer registers, whichever is smaller.

-msym32

-mno-sym32

Assume (do not assume) that all symbols have 32-bit values, regardless of the selected ABI. This option is useful in combination with **-mabi=64** and **-mno-abicalls** because it allows GCC to generate shorter and faster references to symbolic addresses.

$-\mathbf{G}$ num

Put definitions of externally-visible data in a small data section if that data is no bigger than *num* bytes. GCC can then generate more efficient accesses to the data; see **-mgpopt** for details.

The default $-\mathbf{G}$ option depends on the configuration.

-mlocal-sdata

-mno-local-sdata

Extend (do not extend) the $-\mathbf{G}$ behavior to local data too, such as to static variables in C. $-\mathbf{mlocal}$ -sdata is the default for all configurations.

If the linker complains that an application is using too much small data, you might want to try rebuilding the less performance-critical parts with **-mno-local-sdata**. You might also want to build large libraries with **-mno-local-sdata**, so that the libraries leave more room for the main program.

-mextern-sdata

-mno-extern-sdata

Assume (do not assume) that externally-defined data is in a small data section if the size of that data is within the **-G** limit. **-mextern-sdata** is the default for all configurations.

If you compile a module Mod with -mextern-sdata -G num -mgpopt, and Mod references a variable Var that is no bigger than num bytes, you must make sure that Var is placed in a small data section. If Var is defined by another module, you must either compile that module with a high-enough -G setting or attach a section attribute to Var's definition. If Var is common, you must link the application with a high-enough -G setting.

The easiest way of satisfying these restrictions is to compile and link every module with the same $-\mathbf{G}$ option. However, you may wish to build a library that supports several different small data limits. You can do this by compiling the library with the highest supported $-\mathbf{G}$ setting and additionally using $-\mathbf{mno}-\mathbf{extern}-\mathbf{sdata}$ to stop the library from making assumptions about externally-defined data.

-mgpopt

-mno-gpopt

Use (do not use) GP-relative accesses for symbols that are known to be in a small data section; see **-G**, **-mlocal-sdata** and **-mextern-sdata**. **-mgpopt** is the default for all configurations.

-mno-gpopt is useful for cases where the gp register might not hold the value of gp. For example, if the code is part of a library that might be used in a boot monitor, programs that call boot monitor routines pass an unknown value in gp. (In such situations, the boot monitor itself is usually compiled with G0.)

-mno-gpopt implies -mno-local-sdata and -mno-extern-sdata.

-membedded-data

-mno-embedded-data

Allocate variables to the read-only data section first if possible, then next in the small data section if possible, otherwise in data. This gives slightly slower code than the default, but reduces the amount of RAM required when executing, and thus may be preferred for some embedded systems.

-muninit-const-in-rodata

-mno-uninit-const-in-rodata

Put uninitialized const variables in the read-only data section. This option is only meaningful in conjunction with **-membedded-data**.

-mcode-readable=setting

Specify whether GCC may generate code that reads from executable sections. There are three possible settings:

-mcode-readable=yes

Instructions may freely access executable sections. This is the default setting.

-mcode-readable=pcrel

MIPS16 PC-relative load instructions can access executable sections, but other instructions must not do so. This option is useful on 4KSc and 4KSd processors when the code TLBs have the Read Inhibit bit set. It is also useful on processors that can be configured to have a dual instruction/data SRAM interface and that, like the M4K, automatically redirect PC-relative loads to the instruction RAM.

-mcode-readable=no

Instructions must not access executable sections. This option can be useful on targets that are configured to have a dual instruction/data SRAM interface but that (unlike the M4K) do not automatically redirect PC-relative loads to the instruction RAM.

-msplit-addresses

-mno-split-addresses

Enable (disable) use of the %hi() and %lo() assembler relocation operators. This option has been superseded by **-mexplicit-relocs** but is retained for backwards compatibility.

-mexplicit-relocs

-mno-explicit-relocs

Use (do not use) assembler relocation operators when dealing with symbolic addresses. The alternative, selected by **-mno-explicit-relocs**, is to use assembler macros instead.

-mexplicit-relocs is the default if GCC was configured to use an assembler that supports relocation operators.

-mcheck-zero-division

-mno-check-zero-division

Trap (do not trap) on integer division by zero.

The default is -mcheck-zero-division.

-mdivide-traps

-mdivide-breaks

MIPS systems check for division by zero by generating either a conditional trap or a break instruction. Using traps results in smaller code, but is only supported on MIPS II and later. Also, some versions of the Linux kernel have a bug that prevents trap from generating the proper signal (SIGFPE). Use **-mdivide-traps** to allow conditional traps on architectures that support them and **-mdivide-breaks** to force the use of breaks.

The default is usually **-mdivide-traps**, but this can be overridden at configure time using **--with-divide=breaks**. Divide-by-zero checks can be completely disabled using **-mno-check-zero-division**.

-mmemcpy

-mno-memcpy

Force (do not force) the use of memcpy() for non-trivial block moves. The default is **-mno-memcpy**, which allows GCC to inline most constant-sized copies.

-mlong-calls

-mno-long-calls

Disable (do not disable) use of the jal instruction. Calling functions using jal is more efficient but requires the caller and callee to be in the same 256 megabyte segment.

This option has no effect on abicalls code. The default is **-mno-long-calls**.

-mmad

-mno-mad

Enable (disable) use of the mad, madu and mul instructions, as provided by the R4650 ISA.

-mfused-madd

-mno-fused-madd

Enable (disable) use of the floating-point multiply-accumulate instructions, when they are available. The default is **-mfused-madd**.

On the R8000 CPU when multiply-accumulate instructions are used, the intermediate product is calculated to infinite precision and is not subject to the FCSR Flush to Zero bit. This may be undesirable in some circumstances. On other processors the result is numerically identical to the equivalent computation using separate multiply, add, subtract and negate instructions.

-nocpp

Tell the MIPS assembler to not run its preprocessor over user assembler files (with a .s suffix) when assembling them.

-mfix-24k

-mno-fix-24k

Work around the 24K E48 (lost data on stores during refill) errata. The workarounds are implemented by the assembler rather than by GCC.

-mfix-r4000

-mno-fix-r4000

Work around certain R4000 CPU errata:

- A double-word or a variable shift may give an incorrect result if executed immediately after starting an integer division.
- A double-word or a variable shift may give an incorrect result if executed while an integer multiplication is in progress.
- An integer division may give an incorrect result if started in a delay slot of a taken branch or a jump.

-mfix-r4400

-mno-fix-r4400

Work around certain R4400 CPU errata:

 A double-word or a variable shift may give an incorrect result if executed immediately after starting an integer division.

-mfix-r10000

-mno-fix-r10000

Work around certain R10000 errata:

 11/sc sequences may not behave atomically on revisions prior to 3.0. They may deadlock on revisions 2.6 and earlier.

This option can only be used if the target architecture supports branch-likely instructions. -mfix-r10000 is the default when -march=r10000 is used; -mno-fix-r10000 is the default otherwise.

-mfix-vr4120

-mno-fix-vr4120

Work around certain VR4120 errata:

- dmultu does not always produce the correct result.
- div and ddiv do not always produce the correct result if one of the operands is negative.

The workarounds for the division errata rely on special functions in *libgcc.a*. At present, these functions are only provided by the mips64vr*-elf configurations.

Other VR4120 errata require a NOP to be inserted between certain pairs of instructions. These errata are handled by the assembler, not by GCC itself.

-mfix-vr4130

Work around the VR4130 mflo/mfhi errata. The workarounds are implemented by the assembler rather than by GCC, although GCC avoids using mflo and mfhi if the VR4130 macc, macchi, dmacc and dmacchi instructions are available instead.

-mfix-sb1

-mno-fix-sb1

Work around certain SB-1 CPU core errata. (This flag currently works around the SB-1 revision 2 "F1" and "F2" floating-point errata.)

-mr10k-cache-barrier=setting

Specify whether GCC should insert cache barriers to avoid the side-effects of speculation on R10K processors.

In common with many processors, the R10K tries to predict the outcome of a conditional branch and

speculatively executes instructions from the "taken" branch. It later aborts these instructions if the predicted outcome is wrong. However, on the R10K, even aborted instructions can have side effects.

This problem only affects kernel stores and, depending on the system, kernel loads. As an example, a speculatively-executed store may load the target memory into cache and mark the cache line as dirty, even if the store itself is later aborted. If a DMA operation writes to the same area of memory before the "dirty" line is flushed, the cached data overwrites the DMA-ed data. See the R10K processor manual for a full description, including other potential problems.

One workaround is to insert cache barrier instructions before every memory access that might be speculatively executed and that might have side effects even if aborted. -mr10k-cache-barrier=setting controls GCC's implementation of this workaround. It assumes that aborted accesses to any byte in the following regions does not have side effects:

- 1. the memory occupied by the current function's stack frame;
- 2. the memory occupied by an incoming stack argument;
- 3. the memory occupied by an object with a link-time-constant address.

It is the kernel's responsibility to ensure that speculative accesses to these regions are indeed safe.

If the input program contains a function declaration such as:

```
void foo (void);
```

then the implementation of foo must allow j foo and jal foo to be executed speculatively. GCC honors this restriction for functions it compiles itself. It expects non-GCC functions (such as handwritten assembly code) to do the same.

The option has three forms:

-mr10k-cache-barrier=load-store

Insert a cache barrier before a load or store that might be speculatively executed and that might have side effects even if aborted.

-mr10k-cache-barrier=store

Insert a cache barrier before a store that might be speculatively executed and that might have side effects even if aborted.

-mr10k-cache-barrier=none

Disable the insertion of cache barriers. This is the default setting.

-mflush-func=func

-mno-flush-func

Specifies the function to call to flush the I and D caches, or to not call any such function. If called, the function must take the same arguments as the common $_{\tt flush_func}()$, that is, the address of the memory range for which the cache is being flushed, the size of the memory range, and the number 3 (to flush both caches). The default depends on the target GCC was configured for, but commonly is either $_{\tt flush_func}$ or $_{\tt cpu_flush}$.

mbranch-cost=num

Set the cost of branches to roughly *num* "simple" instructions. This cost is only a heuristic and is not guaranteed to produce consistent results across releases. A zero cost redundantly selects the default, which is based on the **–mtune** setting.

-mbranch-likely

-mno-branch-likely

Enable or disable use of Branch Likely instructions, regardless of the default for the selected architecture. By default, Branch Likely instructions may be generated if they are supported by the selected architecture. An exception is for the MIPS32 and MIPS64 architectures and processors that implement those architectures; for those, Branch Likely instructions are not be generated by default because the MIPS32 and MIPS64 architectures specifically deprecate their use.

-mfp-exceptions

-mno-fp-exceptions

Specifies whether FP exceptions are enabled. This affects how FP instructions are scheduled for some processors. The default is that FP exceptions are enabled.

For instance, on the SB-1, if FP exceptions are disabled, and we are emitting 64-bit code, then we can use both FP pipes. Otherwise, we can only use one FP pipe.

-mvr4130-align

-mno-vr4130-align

The VR4130 pipeline is two-way superscalar, but can only issue two instructions together if the first one is 8-byte aligned. When this option is enabled, GCC aligns pairs of instructions that it thinks should execute in parallel.

This option only has an effect when optimizing for the VR4130. It normally makes code faster, but at the expense of making it bigger. It is enabled by default at optimization level **–O3**.

-msynci

-mno-synci

Enable (disable) generation of synci instructions on architectures that support it. The synci instructions (if enabled) are generated when __builtin___clear_cache() is compiled.

This option defaults to -mno-synci, but the default can be overridden by configuring with --with-synci.

When compiling code for single processor systems, it is generally safe to use synci. However, on many multi-core (SMP) systems, it does not invalidate the instruction caches on all cores and may lead to undefined behavior.

-mrelax-pic-calls

-mno-relax-pic-calls

Try to turn PIC calls that are normally dispatched via register \$25 into direct calls. This is only possible if the linker can resolve the destination at link-time and if the destination is within range for a direct call.

-mrelax-pic-calls is the default if GCC was configured to use an assembler and a linker that support the .reloc assembly directive and -mexplicit-relocs is in effect. With -mno-explicit-relocs, this optimization can be performed by the assembler and the linker alone without help from the compiler.

-mmcount-ra-address

-mno-mcount-ra-address

Emit (do not emit) code that allows _mcount to modify the calling function's return address. When enabled, this option extends the usual _mcount interface with a new *ra-address* parameter, which has type intptr_t * and is passed in register \$12. _mcount can then modify the return address by doing both of the following:

- Returning the new address in register \$31.
- Storing the new address in *ra-address, if ra-address is nonnull.

The default is **-mno-mcount-ra-address**.

MMIX Options

These options are defined for the MMIX:

-mlibfuncs

-mno-libfuncs

Specify that intrinsic library functions are being compiled, passing all values in registers, no matter the size.

-mepsilon

-mno-epsilon

Generate floating-point comparison instructions that compare with respect to the rE epsilon register.

-mabi=mmixware

-mabi=gnu

Generate code that passes function parameters and return values that (in the called function) are seen as registers \$0 and up, as opposed to the GNU ABI which uses global registers \$231 and up.

-mzero-extend

-mno-zero-extend

When reading data from memory in sizes shorter than 64 bits, use (do not use) zero-extending load instructions by default, rather than sign-extending ones.

-mknuthdiv

-mno-knuthdiv

Make the result of a division yielding a remainder have the same sign as the divisor. With the default, **-mno-knuthdiv**, the sign of the remainder follows the sign of the dividend. Both methods are arithmetically valid, the latter being almost exclusively used.

-mtoplevel-symbols

-mno-toplevel-symbols

Prepend (do not prepend) a: to all global symbols, so the assembly code can be used with the PREFIX assembly directive.

-melf

Generate an executable in the ELF format, rather than the default **mmo** format used by the **mmix** simulator.

-mbranch-predict

-mno-branch-predict

Use (do not use) the probable-branch instructions, when static branch prediction indicates a probable branch.

-mbase-addresses

-mno-base-addresses

Generate (do not generate) code that uses *base addresses*. Using a base address automatically generates a request (handled by the assembler and the linker) for a constant to be set up in a global register. The register is used for one or more base address requests within the range 0 to 255 from the value held in the register. The generally leads to short and fast code, but the number of different data items that can be addressed is limited. This means that a program that uses lots of static data may require **-mno-base-addresses**.

-msingle-exit

-mno-single-exit

Force (do not force) generated code to have a single exit point in each function.

MN10300 Options

These **-m** options are defined for Matsushita MN10300 architectures:

-mmult-bug

Generate code to avoid bugs in the multiply instructions for the MN10300 processors. This is the default.

-mno-mult-bug

Do not generate code to avoid bugs in the multiply instructions for the MN10300 processors.

-mam33

Generate code using features specific to the AM33 processor.

-mno-am33

Do not generate code using features specific to the AM33 processor. This is the default.

-mam33-2

Generate code using features specific to the AM33/2.0 processor.

-mam34

Generate code using features specific to the AM34 processor.

-mtune=cpu-type

Use the timing characteristics of the indicated CPU type when scheduling instructions. This does not change the targeted processor type. The CPU type must be one of mn10300, am33, am33-2 or am34.

-mreturn-pointer-on-d0

When generating a function that returns a pointer, return the pointer in both a0 and d0. Otherwise, the pointer is returned only in a0, and attempts to call such functions without a prototype result in errors. Note that this option is on by default; use **-mno-return-pointer-on-d0** to disable it.

-mno-crt0

Do not link in the C run-time initialization object file.

-mrelax

Indicate to the linker that it should perform a relaxation optimization pass to shorten branches, calls and absolute memory addresses. This option only has an effect when used on the command line for the final link step.

This option makes symbolic debugging impossible.

-mliw

Allow the compiler to generate *Long Instruction Word* instructions if the target is the **AM33** or later. This is the default. This option defines the preprocessor macro __**LIW**__.

-mnoliw

Do not allow the compiler to generate *Long Instruction Word* instructions. This option defines the preprocessor macro __NO_LIW__.

-msetlb

Allow the compiler to generate the *SETLB* and *Lcc* instructions if the target is the **AM33** or later. This is the default. This option defines the preprocessor macro __**SETLB**__.

-mnosetlb

Do not allow the compiler to generate *SETLB* or *Lcc* instructions. This option defines the preprocessor macro __NO_SETLB__.

Moxie Options

-meb

Generate big-endian code. This is the default for **moxie**-*-* configurations.

-mel

Generate little-endian code.

-mno-crt0

Do not link in the C run-time initialization object file.

PDP-11 Options

These options are defined for the PDP-11:

-mfpu

Use hardware FPP floating point. This is the default. (FIS floating point on the PDP-11/40 is not supported.)

-msoft-float

Do not use hardware floating point.

-mac0

Return floating-point results in ac0 (fr0 in Unix assembler syntax).

-mno-ac0

Return floating-point results in memory. This is the default.

-m40

Generate code for a PDP-11/40.

-m45

Generate code for a PDP-11/45. This is the default.

-m10

Generate code for a PDP-11/10.

-mbcopy-builtin

Use inline movmemhi patterns for copying memory. This is the default.

-mbcopy

Do not use inline movmemhi patterns for copying memory.

-mint16

-mno-int32

Use 16-bit int. This is the default.

-mint32

-mno-int16

Use 32-bit int.

-mfloat64

-mno-float32

Use 64-bit float. This is the default.

-mfloat32

-mno-float64

Use 32-bit float.

-mabshi

Use abshi2 pattern. This is the default.

-mno-abshi

Do not use abshi2 pattern.

-mbranch-expensive

Pretend that branches are expensive. This is for experimenting with code generation only.

-mbranch-cheap

Do not pretend that branches are expensive. This is the default.

-munix-asm

Use Unix assembler syntax. This is the default when configured for **pdp11**-*-**bsd**.

-mdec-asm

Use DEC assembler syntax. This is the default when configured for any PDP-11 target other than **pdp11-*-bsd**.

picoChip Options

These **-m** options are defined for picoChip implementations:

-mae=*ae_type*

Set the instruction set, register set, and instruction scheduling parameters for array element type ae_type . Supported values for ae_type are ANY, MUL, and MAC.

-mae=ANY selects a completely generic AE type. Code generated with this option runs on any of the other AE types. The code is not as efficient as it would be if compiled for a specific AE type, and some

types of operation (e.g., multiplication) do not work properly on all types of AE.

-mae=MUL selects a MUL AE type. This is the most useful AE type for compiled code, and is the default.

-mae=MAC selects a DSP-style MAC AE. Code compiled with this option may suffer from poor performance of byte (char) manipulation, since the DSP AE does not provide hardware support for byte load/stores.

-msymbol-as-address

Enable the compiler to directly use a symbol name as an address in a load/store instruction, without first loading it into a register. Typically, the use of this option generates larger programs, which run faster than when the option isn't used. However, the results vary from program to program, so it is left as a user option, rather than being permanently enabled.

-mno-inefficient-warnings

Disables warnings about the generation of inefficient code. These warnings can be generated, for example, when compiling code that performs byte-level memory operations on the MAC AE type. The MAC AE has no hardware support for byte-level memory operations, so all byte load/stores must be synthesized from word load/store operations. This is inefficient and a warning is generated to indicate that you should rewrite the code to avoid byte operations, or to target an AE type that has the necessary hardware support. This option disables these warnings.

PowerPC Options

These are listed under

RL78 Options

-msim

Links in additional target libraries to support operation within a simulator.

- -mmul=none
- -mmul=g13
- -mmul=rl78

Specifies the type of hardware multiplication support to be used. The default is none, which uses software multiplication functions. The g13 option is for the hardware multiply/divide peripheral only on the RL78/G13 targets. The r178 option is for the standard hardware multiplication defined in the RL78 software manual.

IBM RS/6000 and PowerPC Options

These -m options are defined for the IBM RS/6000 and PowerPC:

- -mpowerpc-gpopt
- -mno-powerpc-gpopt
- -mpowerpc-gfxopt
- -mno-powerpc-gfxopt
- -mpowerpc64
- -mno-powerpc64
- -mmfcrf
- -mno-mfcrf
- -mpopentb
- -mno-popentb
- -mpopentd
- -mno-popentd
- -mfprnd
- -mno-fprnd
- -mcmpb

- -mno-cmpb
- -mmfpgpr
- -mno-mfpgpr
- -mhard-dfp
- -mno-hard-dfp

You use these options to specify which instructions are available on the processor you are using. The default value of these options is determined when configuring GCC. Specifying the -mcpu=cpu_type overrides the specification of these options. We recommend you use the -mcpu=cpu_type option rather than the options listed above.

Specifying **-mpowerpc-gpopt** allows GCC to use the optional PowerPC architecture instructions in the General Purpose group, including floating-point square root. Specifying **-mpowerpc-gfxopt** allows GCC to use the optional PowerPC architecture instructions in the Graphics group, including floating-point select.

The -mmfcrf option allows GCC to generate the move from condition register field instruction implemented on the POWER4 processor and other processors that support the PowerPC V2.01 architecture. The -mpopcntb option allows GCC to generate the popcount and double-precision FP reciprocal estimate instruction implemented on the POWER5 processor and other processors that support the PowerPC V2.02 architecture. The -mpopcntd option allows GCC to generate the popcount instruction implemented on the POWER7 processor and other processors that support the PowerPC V2.06 architecture. The -mfprnd option allows GCC to generate the FP round to integer instructions implemented on the POWER5+ processor and other processors that support the PowerPC V2.03 architecture. The -mcmpb option allows GCC to generate the compare bytes instruction implemented on the POWER6 processor and other processors that support the PowerPC V2.05 architecture. The -mmfpgpr option allows GCC to generate the FP move to/from general-purpose register instructions implemented on the POWER6X processor and other processors that support the extended PowerPC V2.05 architecture. The -mhard-dfp option allows GCC to generate the decimal floating-point instructions implemented on some POWER processors.

The **-mpowerpc64** option allows GCC to generate the additional 64-bit instructions that are found in the full PowerPC64 architecture and to treat GPRs as 64-bit, doubleword quantities. GCC defaults to **-mno-powerpc64**.

-mcpu=cpu_type

Set architecture type, register usage, and instruction scheduling parameters for machine type *cpu_type*. Supported values for *cpu_type* are 401, 403, 405, 405fp, 440, 440fp, 464, 464fp, 476, 476fp, 505, 601, 602, 603, 603e, 604, 604e, 620, 630, 740, 7400, 7450, 750, 801, 821, 823, 860, 970, 8540, a2, e300c2, e300c3, e500mc, e500mc64, e5500, e6500, ec603e, G3, G4, G5, titan, power3, power4, power5, power5+, power6, power6x, power7, power8, powerpc, powerpc64, powerpc64le, and rs64.

-mcpu=powerpc, **-mcpu=powerpc64**, and **-mcpu=powerpc64le** specify pure 32-bit PowerPC (either endian), 64-bit big endian PowerPC and 64-bit little endian PowerPC architecture machine types, with an appropriate, generic processor model assumed for scheduling purposes.

The other options specify a specific processor. Code generated under those options runs best on that processor, and may not run at all on others.

The **-mcpu** options automatically enable or disable the following options:

-maltivec -mfprnd -mhard-float -mmfcrf -mmultiple -mpopentb -mpopentd
 -mpowerpc64 -mpowerpc-gpopt -mpowerpc-gfxopt -msingle-float -mdouble-float
 -msimple-fpu -mstring -mmulhw -mdlmzb -mmfpgpr -mvsx -mcrypto -mdirect-move
 -mpower8-fusion -mpower8-vector -mquad-memory -mquad-memory-atomic

The particular options set for any particular CPU varies between compiler versions, depending on what setting seems to produce optimal code for that CPU; it doesn't necessarily reflect the actual hardware's capabilities. If you wish to set an individual option to a particular value, you may specify it after the **-mcpu** option, like **-mcpu=970 -mno-altivec**.

On AIX, the **-maltivec** and **-mpowerpc64** options are not enabled or disabled by the **-mcpu** option at present because AIX does not have full support for these options. You may still enable or disable them individually if you're sure it'll work in your environment.

-mtune=cpu_type

Set the instruction scheduling parameters for machine type *cpu_type*, but do not set the architecture type or register usage, as **-mcpu**=*cpu_type* does. The same values for *cpu_type* are used for **-mtune** as for **-mcpu**. If both are specified, the code generated uses the architecture and registers set by **-mcpu**, but the scheduling parameters set by **-mtune**.

-mcmodel=small

Generate PowerPC64 code for the small model: The TOC is limited to 64k.

-mcmodel=medium

Generate PowerPC64 code for the medium model: The TOC and other static data may be up to a total of 4G in size.

-mcmodel=large

Generate PowerPC64 code for the large model: The TOC may be up to 4G in size. Other data and code is only limited by the 64-bit address space.

-maltivec

-mno-altivec

Generate code that uses (does not use) AltiVec instructions, and also enable the use of built-in functions that allow more direct access to the AltiVec instruction set. You may also need to set **-mabi=altivec** to adjust the current ABI with AltiVec ABI enhancements.

When **-maltivec** is used, rather than **-maltivec=le** or **-maltivec=be**, the element order for Altivec intrinsics such as vec_splat, vec_extract, and vec_insert will match array element order corresponding to the endianness of the target. That is, element zero identifies the leftmost element in a vector register when targeting a big-endian platform, and identifies the rightmost element in a vector register when targeting a little-endian platform.

-maltivec=be

Generate Altivec instructions using big-endian element order, regardless of whether the target is big-or little-endian. This is the default when targeting a big-endian platform.

The element order is used to interpret element numbers in Altivec intrinsics such as vec_splat, vec_extract, and vec_insert. By default, these will match array element order corresponding to the endianness for the target.

-maltivec=le

Generate Altivec instructions using little-endian element order, regardless of whether the target is big—or little-endian. This is the default when targeting a little-endian platform. This option is currently ignored when targeting a big-endian platform.

The element order is used to interpret element numbers in Altivec intrinsics such as vec_splat, vec_extract, and vec_insert. By default, these will match array element order corresponding to the endianness for the target.

-myrsaye

-mno-vrsave

Generate VRSAVE instructions when generating AltiVec code.

-mgen-cell-microcode

Generate Cell microcode instructions.

-mwarn-cell-microcode

Warn when a Cell microcode instruction is emitted. An example of a Cell microcode instruction is a variable shift.

-msecure-plt

Generate code that allows **ld** and **ld.so** to build executables and shared libraries with non-executable .plt and .got sections. This is a PowerPC 32-bit SYSV ABI option.

-mbss-plt

Generate code that uses a BSS .plt section that **ld.so** fills in, and requires .plt and .got sections that are both writable and executable. This is a PowerPC 32-bit SYSV ABI option.

-misel

-mno-isel

This switch enables or disables the generation of ISEL instructions.

-misel=ves/no

This switch has been deprecated. Use **-misel** and **-mno-isel** instead.

-mspe

-mno-spe

This switch enables or disables the generation of SPE simd instructions.

-mpaired

-mno-paired

This switch enables or disables the generation of PAIRED simd instructions.

-mspe=yes/no

This option has been deprecated. Use -mspe and -mno-spe instead.

-mvsx

-mno-vsx

Generate code that uses (does not use) vector/scalar (VSX) instructions, and also enable the use of built-in functions that allow more direct access to the VSX instruction set.

-mcrypto

-mno-crypto

Enable the use (disable) of the built-in functions that allow direct access to the cryptographic instructions that were added in version 2.07 of the PowerPC ISA.

-mdirect-move

-mno-direct-move

Generate code that uses (does not use) the instructions to move data between the general purpose registers and the vector/scalar (VSX) registers that were added in version 2.07 of the PowerPC ISA.

-mpower8-fusion

-mno-power8-fusion

Generate code that keeps (does not keeps) some integer operations adjacent so that the instructions can be fused together on power8 and later processors.

-mpower8-vector

-mno-power8-vector

Generate code that uses (does not use) the vector and scalar instructions that were added in version 2.07 of the PowerPC ISA. Also enable the use of built-in functions that allow more direct access to the vector instructions.

-mquad-memory

-mno-quad-memory

Generate code that uses (does not use) the non-atomic quad word memory instructions. The **-mquad-memory** option requires use of 64-bit mode.

-mquad-memory-atomic

-mno-quad-memory-atomic

Generate code that uses (does not use) the atomic quad word memory instructions. The **-mquad-memory-atomic** option requires use of 64-bit mode.

-mfloat-gprs=yes/single/double/no

-mfloat-gprs

This switch enables or disables the generation of floating-point operations on the general-purpose registers for architectures that support it.

The argument yes or single enables the use of single-precision floating-point operations.

The argument *double* enables the use of single and double-precision floating-point operations.

The argument *no* disables floating-point operations on the general-purpose registers.

This option is currently only available on the MPC854x.

-m32

-m64

Generate code for 32-bit or 64-bit environments of Darwin and SVR4 targets (including GNU/Linux). The 32-bit environment sets int, long and pointer to 32 bits and generates code that runs on any PowerPC variant. The 64-bit environment sets int to 32 bits and long and pointer to 64 bits, and generates code for PowerPC64, as for **-mpowerpc64**.

-mfull-toc

- -mno-fp-in-toc
- -mno-sum-in-toc
- -mminimal-toc

Modify generation of the TOC (Table Of Contents), which is created for every executable file. The **-mfull-toc** option is selected by default. In that case, GCC allocates at least one TOC entry for each unique non-automatic variable reference in your program. GCC also places floating-point constants in the TOC. However, only 16,384 entries are available in the TOC.

If you receive a linker error message that saying you have overflowed the available TOC space, you can reduce the amount of TOC space used with the **-mno-fp-in-toc** and **-mno-sum-in-toc** options. **-mno-fp-in-toc** prevents GCC from putting floating-point constants in the TOC and **-mno-sum-in-toc** forces GCC to generate code to calculate the sum of an address and a constant at run time instead of putting that sum into the TOC. You may specify one or both of these options. Each causes GCC to produce very slightly slower and larger code at the expense of conserving TOC space.

If you still run out of space in the TOC even when you specify both of these options, specify **-mminimal-toc** instead. This option causes GCC to make only one TOC entry for every file. When you specify this option, GCC produces code that is slower and larger but which uses extremely little TOC space. You may wish to use this option only on files that contain less frequently-executed code.

-maix64

-maix32

Enable 64-bit AIX ABI and calling convention: 64-bit pointers, 64-bit long type, and the infrastructure needed to support them. Specifying -maix64 implies -mpowerpc64, while -maix32 disables the 64-bit ABI and implies -mno-powerpc64. GCC defaults to -maix32.

-mxl-compat

-mno-xl-compat

Produce code that conforms more closely to IBM XL compiler semantics when using AIX-compatible ABI. Pass floating-point arguments to prototyped functions beyond the register save area (RSA) on the stack in addition to argument FPRs. Do not assume that most significant double in 128-bit long double value is properly rounded when comparing values and converting to double. Use XL symbol names for long double support routines.

The AIX calling convention was extended but not initially documented to handle an obscure K&R C case of calling a function that takes the address of its arguments with fewer arguments than declared. IBM XL compilers access floating-point arguments that do not fit in the RSA from the stack when a subroutine is compiled without optimization. Because always storing floating-point arguments on the stack is inefficient and rarely needed, this option is not enabled by default and only is necessary when

calling subroutines compiled by IBM XL compilers without optimization.

-mpe

Support *IBM RS/6000 SP Parallel Environment* (PE). Link an application written to use message passing with special startup code to enable the application to run. The system must have PE installed in the standard location (/usr/lpp/ppe.poe/), or the specs file must be overridden with the -specs= option to specify the appropriate directory location. The Parallel Environment does not support threads, so the -mpe option and the -pthread option are incompatible.

-malign-natural

-malign-power

On AIX, 32-bit Darwin, and 64-bit PowerPC GNU/Linux, the option **-malign-natural** overrides the ABI-defined alignment of larger types, such as floating-point doubles, on their natural size-based boundary. The option **-malign-power** instructs GCC to follow the ABI-specified alignment rules. GCC defaults to the standard alignment defined in the ABI.

On 64-bit Darwin, natural alignment is the default, and **-malign-power** is not supported.

-msoft-float

-mhard-float

Generate code that does not use (uses) the floating-point register set. Software floating-point emulation is provided if you use the **-msoft-float** option, and pass the option to GCC when linking.

-msingle-float

-mdouble-float

Generate code for single— or double-precision floating-point operations. **-mdouble-float** implies **-msingle-float**.

-msimple-fpu

Do not generate sqrt and div instructions for hardware floating-point unit.

-mfpu=name

Specify type of floating-point unit. Valid values for *name* are **sp_lite** (equivalent to **-msingle-float -msimple-fpu**), **dp_lite** (equivalent to **-mdouble-float -msimple-fpu**), **sp_full** (equivalent to **-mdouble-float**).

-mxilinx-fpu

Perform optimizations for the floating-point unit on Xilinx PPC 405/440.

-mmultiple

-mno-multiple

Generate code that uses (does not use) the load multiple word instructions and the store multiple word instructions. These instructions are generated by default on POWER systems, and not generated on PowerPC systems. Do not use **-mmultiple** on little-endian PowerPC systems, since those instructions do not work when the processor is in little-endian mode. The exceptions are PPC740 and PPC750 which permit these instructions in little-endian mode.

-mstring

-mno-string

Generate code that uses (does not use) the load string instructions and the store string word instructions to save multiple registers and do small block moves. These instructions are generated by default on POWER systems, and not generated on PowerPC systems. Do not use **-mstring** on little-endian PowerPC systems, since those instructions do not work when the processor is in little-endian mode. The exceptions are PPC740 and PPC750 which permit these instructions in little-endian mode.

-mupdate

-mno-update

Generate code that uses (does not use) the load or store instructions that update the base register to the address of the calculated memory location. These instructions are generated by default. If you use **-mno-update**, there is a small window between the time that the stack pointer is updated and the address of the previous frame is stored, which means code that walks the stack frame across interrupts

or signals may get corrupted data.

-mavoid-indexed-addresses

-mno-avoid-indexed-addresses

Generate code that tries to avoid (not avoid) the use of indexed load or store instructions. These instructions can incur a performance penalty on Power6 processors in certain situations, such as when stepping through large arrays that cross a 16M boundary. This option is enabled by default when targeting Power6 and disabled otherwise.

-mfused-madd

-mno-fused-madd

Generate code that uses (does not use) the floating-point multiply and accumulate instructions. These instructions are generated by default if hardware floating point is used. The machine-dependent **-mfused-madd** option is now mapped to the machine-independent **-ffp-contract=fast** option, and **-mno-fused-madd** is mapped to **-ffp-contract=off**.

-mmulhw

-mno-mulhw

Generate code that uses (does not use) the half-word multiply and multiply-accumulate instructions on the IBM 405, 440, 464 and 476 processors. These instructions are generated by default when targeting those processors.

-mdlmzb

-mno-dlmzb

Generate code that uses (does not use) the string-search **dlmzb** instruction on the IBM 405, 440, 464 and 476 processors. This instruction is generated by default when targeting those processors.

-mno-bit-align

-mbit-align

On System V.4 and embedded PowerPC systems do not (do) force structures and unions that contain bit-fields to be aligned to the base type of the bit-field.

For example, by default a structure containing nothing but 8 unsigned bit-fields of length 1 is aligned to a 4-byte boundary and has a size of 4 bytes. By using **-mno-bit-align**, the structure is aligned to a 1-byte boundary and is 1 byte in size.

-mno-strict-align

-mstrict-align

On System V.4 and embedded PowerPC systems do not (do) assume that unaligned memory references are handled by the system.

-mrelocatable

-mno-relocatable

Generate code that allows (does not allow) a static executable to be relocated to a different address at run time. A simple embedded PowerPC system loader should relocate the entire contents of .got2 and 4-byte locations listed in the .fixup section, a table of 32-bit addresses generated by this option. For this to work, all objects linked together must be compiled with -mrelocatable or -mrelocatable-lib. -mrelocatable code aligns the stack to an 8-byte boundary.

-mrelocatable-lib

-mno-relocatable-lib

Like -mrelocatable, -mrelocatable-lib generates a .fixup section to allow static executables to be relocated at run time, but -mrelocatable-lib does not use the smaller stack alignment of -mrelocatable. Objects compiled with -mrelocatable-lib may be linked with objects compiled with any combination of the -mrelocatable options.

-mno-toc

-mtoc

On System V.4 and embedded PowerPC systems do not (do) assume that register 2 contains a pointer to a global area pointing to the addresses used in the program.

-mlittle

-mlittle-endian

On System V.4 and embedded PowerPC systems compile code for the processor in little-endian mode. The **-mlittle-endian** option is the same as **-mlittle**.

-mbig

-mbig-endian

On System V.4 and embedded PowerPC systems compile code for the processor in big-endian mode. The **-mbig-endian** option is the same as **-mbig**.

-mdynamic-no-pic

On Darwin and Mac OS X systems, compile code so that it is not relocatable, but that its external references are relocatable. The resulting code is suitable for applications, but not shared libraries.

-msingle-pic-base

Treat the register used for PIC addressing as read-only, rather than loading it in the prologue for each function. The runtime system is responsible for initializing this register with an appropriate value before execution begins.

-mprioritize-restricted-insns=priority

This option controls the priority that is assigned to dispatch-slot restricted instructions during the second scheduling pass. The argument *priority* takes the value **0**, **1**, or **2** to assign no, highest, or second-highest (respectively) priority to dispatch-slot restricted instructions.

-msched-costly-dep=dependence_type

This option controls which dependences are considered costly by the target during instruction scheduling. The argument *dependence_type* takes one of the following values:

no No dependence is costly.

all All dependences are costly.

true_store_to_load

A true dependence from store to load is costly.

store_to_load

Any dependence from store to load is costly.

number

Any dependence for which the latency is greater than or equal to *number* is costly.

-minsert-sched-nops=scheme

This option controls which NOP insertion scheme is used during the second scheduling pass. The argument *scheme* takes one of the following values:

no Don't insert NOPs.

pad

Pad with NOPs any dispatch group that has vacant issue slots, according to the scheduler's grouping.

regroup_exact

Insert NOPs to force costly dependent insns into separate groups. Insert exactly as many NOPs as needed to force an insn to a new group, according to the estimated processor grouping.

number

Insert NOPs to force costly dependent insns into separate groups. Insert *number* NOPs to force an insn to a new group.

-mcall-sysv

On System V.4 and embedded PowerPC systems compile code using calling conventions that adhere to the March 1995 draft of the System V Application Binary Interface, PowerPC processor supplement. This is the default unless you configured GCC using **powerpc-*-eabiaix**.

-mcall-sysv-eabi

-mcall-eabi

Specify both **-mcall-sysv** and **-meabi** options.

-mcall-sysv-noeabi

Specify both **-mcall-sysv** and **-mno-eabi** options.

-mcall-aixdesc

On System V.4 and embedded PowerPC systems compile code for the AIX operating system.

-mcall-linux

On System V.4 and embedded PowerPC systems compile code for the Linux-based GNU system.

-mcall-freebsd

On System V.4 and embedded PowerPC systems compile code for the FreeBSD operating system.

-mcall-netbsd

On System V.4 and embedded PowerPC systems compile code for the NetBSD operating system.

-mcall-openbsd

On System V.4 and embedded PowerPC systems compile code for the OpenBSD operating system.

-maix-struct-return

Return all structures in memory (as specified by the AIX ABI).

-msvr4-struct-return

Return structures smaller than 8 bytes in registers (as specified by the SVR4 ABI).

-mabi=abi-type

Extend the current ABI with a particular extension, or remove such extension. Valid values are *altivec*, *no-altivec*, *spe*, *no-spe*, *ibmlongdouble*, *ieeelongdouble*, *elfv1*, *elfv2*.

-mabi=spe

Extend the current ABI with SPE ABI extensions. This does not change the default ABI, instead it adds the SPE ABI extensions to the current ABI.

-mabi=no-spe

Disable Book-E SPE ABI extensions for the current ABI.

-mabi=ibmlongdouble

Change the current ABI to use IBM extended-precision long double. This is a PowerPC 32-bit SYSV ABI option.

-mabi=ieeelongdouble

Change the current ABI to use IEEE extended-precision long double. This is a PowerPC 32-bit Linux ABI option.

-mabi=elfv1

Change the current ABI to use the ELFv1 ABI. This is the default ABI for big-endian PowerPC 64-bit Linux. Overriding the default ABI requires special system support and is likely to fail in spectacular ways.

-mabi=elfv2

Change the current ABI to use the ELFv2 ABI. This is the default ABI for little-endian PowerPC 64-bit Linux. Overriding the default ABI requires special system support and is likely to fail in spectacular ways.

-mprototype

-mno-prototype

On System V.4 and embedded PowerPC systems assume that all calls to variable argument functions are properly prototyped. Otherwise, the compiler must insert an instruction before every non-prototyped call to set or clear bit 6 of the condition code register (*CR*) to indicate whether floating-point values are passed in the floating-point registers in case the function takes variable arguments. With **-mprototype**, only calls to prototyped variable argument functions set or clear the bit.

-msim

On embedded PowerPC systems, assume that the startup module is called sim-crt0.o and that the standard C libraries are libsim.a and libc.a. This is the default for **powerpc-*-eabisim** configurations.

-mmvme

On embedded PowerPC systems, assume that the startup module is called *crt0.o* and the standard C libraries are *libmvme.a* and *libc.a*.

-mads

On embedded PowerPC systems, assume that the startup module is called *crt0.o* and the standard C libraries are *libads.a* and *libc.a*.

-myellowknife

On embedded PowerPC systems, assume that the startup module is called *crt0.o* and the standard C libraries are *libyk.a* and *libc.a*.

-mvxworks

On System V.4 and embedded PowerPC systems, specify that you are compiling for a VxWorks system.

-memb

On embedded PowerPC systems, set the *PPC_EMB* bit in the ELF flags header to indicate that **eabi** extended relocations are used.

-meabi

-mno-eabi

On System V.4 and embedded PowerPC systems do (do not) adhere to the Embedded Applications Binary Interface (EABI), which is a set of modifications to the System V.4 specifications. Selecting **-meabi** means that the stack is aligned to an 8-byte boundary, a function __eabi is called from main to set up the EABI environment, and the **-msdata** option can use both r2 and r13 to point to two separate small data areas. Selecting **-mno-eabi** means that the stack is aligned to a 16-byte boundary, no EABI initialization function is called from main, and the **-msdata** option only uses r13 to point to a single small data area. The **-meabi** option is on by default if you configured GCC using one of the **powerpc*-*-eabi*** options.

-msdata=eabi

On System V.4 and embedded PowerPC systems, put small initialized const global and static data in the .sdata2 section, which is pointed to by register r2. Put small initialized non-const global and static data in the .sdata section, which is pointed to by register r13. Put small uninitialized global and static data in the .sbss section, which is adjacent to the .sdata section. The -msdata=eabi option is incompatible with the -mrelocatable option. The -msdata=eabi option also sets the -memb option.

-msdata=sysv

On System V.4 and embedded PowerPC systems, put small global and static data in the **.sdata** section, which is pointed to by register r13. Put small uninitialized global and static data in the **.sbss** section, which is adjacent to the **.sdata** section. The **-msdata=sysv** option is incompatible with the **-mrelocatable** option.

-msdata=default

-msdata

On System V.4 and embedded PowerPC systems, if **-meabi** is used, compile code the same as **-msdata=eabi**, otherwise compile code the same as **-msdata=sysv**.

-msdata=data

On System V.4 and embedded PowerPC systems, put small global data in the **.sdata** section. Put small uninitialized global data in the **.sbss** section. Do not use register r13 to address small data however. This is the default behavior unless other **-msdata** options are used.

-msdata=none

-mno-sdata

On embedded PowerPC systems, put all initialized global and static data in the .data section, and all uninitialized data in the .bss section.

-mblock-move-inline-limit=num

Inline all block moves (such as calls to memcpy or structure copies) less than or equal to *num* bytes. The minimum value for *num* is 32 bytes on 32-bit targets and 64 bytes on 64-bit targets. The default value is target-specific.

-G num

On embedded PowerPC systems, put global and static items less than or equal to *num* bytes into the small data or BSS sections instead of the normal data or BSS section. By default, *num* is 8. The **-G** *num* switch is also passed to the linker. All modules should be compiled with the same **-G** *num* value.

-mregnames

-mno-regnames

On System V.4 and embedded PowerPC systems do (do not) emit register names in the assembly language output using symbolic forms.

-mlongcall

-mno-longcall

By default assume that all calls are far away so that a longer and more expensive calling sequence is required. This is required for calls farther than 32 megabytes (33,554,432 bytes) from the current location. A short call is generated if the compiler knows the call cannot be that far away. This setting can be overridden by the shortcall function attribute, or by #pragma longcall(0).

Some linkers are capable of detecting out-of-range calls and generating glue code on the fly. On these systems, long calls are unnecessary and generate slower code. As of this writing, the AIX linker can do this, as can the GNU linker for PowerPC/64. It is planned to add this feature to the GNU linker for 32–bit PowerPC systems as well.

On Darwin/PPC systems, #pragma longcall generates jbsr callee, L42, plus a branch island (glue code). The two target addresses represent the callee and the branch island. The Darwin/PPC linker prefers the first address and generates a bl callee if the PPC bl instruction reaches the callee directly; otherwise, the linker generates bl L42 to call the branch island. The branch island is appended to the body of the calling function; it computes the full 32-bit address of the callee and jumps to it.

On Mach-O (Darwin) systems, this option directs the compiler emit to the glue for every direct call, and the Darwin linker decides whether to use or discard it.

In the future, GCC may ignore all longcall specifications when the linker is known to generate glue.

-mtls-markers

-mno-tls-markers

Mark (do not mark) calls to __tls_get_addr with a relocation specifying the function argument. The relocation allows the linker to reliably associate function call with argument setup instructions for TLS optimization, which in turn allows GCC to better schedule the sequence.

-pthread

Adds support for multithreading with the *pthreads* library. This option sets flags for both the preprocessor and linker.

-mrecip

-mno-recip

This option enables use of the reciprocal estimate and reciprocal square root estimate instructions with additional Newton-Raphson steps to increase precision instead of doing a divide or square root and divide for floating-point arguments. You should use the **-ffast-math** option when using **-mrecip** (or at least **-funsafe-math-optimizations**, **-finite-math-only**, **-freciprocal-math** and **-fno-trapping-math**). Note that while the throughput of the sequence is generally higher than the

throughput of the non-reciprocal instruction, the precision of the sequence can be decreased by up to 2 ulp (i.e. the inverse of 1.0 equals 0.99999994) for reciprocal square roots.

-mrecip=opt

This option controls which reciprocal estimate instructions may be used. *opt* is a comma-separated list of options, which may be preceded by a ! to invert the option: all: enable all estimate instructions, default: enable the default instructions, equivalent to **-mrecip**, none: disable all estimate instructions, equivalent to **-mno-recip**; div: enable the reciprocal approximation instructions for both single and double precision; divf: enable the single-precision reciprocal approximation instructions; rsqrt: enable the reciprocal square root approximation instructions for both single and double precision; rsqrtf: enable the single-precision reciprocal square root approximation instructions; rsqrtf: enable the double-precision reciprocal square root approximation instructions;

So, for example, **-mrecip=all,!rsqrtd** enables all of the reciprocal estimate instructions, except for the FRSQRTE, XSRSQRTEDP, and XVRSQRTEDP instructions which handle the double-precision reciprocal square root calculations.

-mrecip-precision

-mno-recip-precision

Assume (do not assume) that the reciprocal estimate instructions provide higher-precision estimates than is mandated by the PowerPC ABI. Selecting **-mcpu=power6**, **-mcpu=power7** or **-mcpu=power8** automatically selects **-mrecip-precision**. The double-precision square root estimate instructions are not generated by default on low-precision machines, since they do not provide an estimate that converges after three steps.

-mveclibabi=type

Specifies the ABI type to use for vectorizing intrinsics using an external library. The only type supported at present is mass, which specifies to use IBM's Mathematical Acceleration Subsystem (MASS) libraries for vectorizing intrinsics using external libraries. GCC currently emits calls to acosd2, acosf4, acoshd2, acoshf4, asind2, asinf4, asinhd2, asinhf4, atan2d2, atan2f4, atand2, atanf4, atanhd2, atanhf4, cbrtd2, cbrtf4, cosd2, cosf4, coshd2, coshf4, erfcd2, erfcf4, erfd2, erff4, exp2d2, exp2f4, expd2, expf4, expm1d2, expm1f4, hypotd2, hypotf4, lgammad2, lgammaf4, log10d2, log10f4, log1pd2, log1pf4, log2d2, log2f4, logd2, logf4, powd2, powf4, sind2, sinf4, sinhd2, sinhf4, sqrtd2, sqrtf4, tand2, tanf4, tanhd2, and tanhf4 when generating code for power7. Both -ftree-vectorize and -funsafe-math-optimizations must also be enabled. The MASS libraries must be specified at link time.

-mfriz

-mno-friz

Generate (do not generate) the friz instruction when the **-funsafe-math-optimizations** option is used to optimize rounding of floating-point values to 64-bit integer and back to floating point. The friz instruction does not return the same value if the floating-point number is too large to fit in an integer.

-mpointers-to-nested-functions

-mno-pointers-to-nested-functions

Generate (do not generate) code to load up the static chain register (r11) when calling through a pointer on AIX and 64-bit Linux systems where a function pointer points to a 3-word descriptor giving the function address, TOC value to be loaded in register r2, and static chain value to be loaded in register r11. The **-mpointers-to-nested-functions** is on by default. You cannot call through pointers to nested functions or pointers to functions compiled in other languages that use the static chain if you use the **-mno-pointers-to-nested-functions**.

-msave-toc-indirect

-mno-save-toc-indirect

Generate (do not generate) code to save the TOC value in the reserved stack location in the function prologue if the function calls through a pointer on AIX and 64-bit Linux systems. If the TOC value is

gcc-4.8 2015-06-23 200

not saved in the prologue, it is saved just before the call through the pointer. The **-mno-save-toc-indirect** option is the default.

-mcompat-align-parm

-mno-compat-align-parm

Generate (do not generate) code to pass structure parameters with a maximum alignment of 64 bits, for compatibility with older versions of GCC.

Older versions of GCC (prior to 4.9.0) incorrectly did not align a structure parameter on a 128-bit boundary when that structure contained a member requiring 128-bit alignment. This is corrected in more recent versions of GCC. This option may be used to generate code that is compatible with functions compiled with older versions of GCC.

In this version of the compiler, the **-mcompat-align-parm** is the default, except when using the Linux ELFv2 ABI.

RX Options

These command-line options are defined for RX targets:

-m64bit-doubles

-m32bit-doubles

Make the double data type be 64 bits (-m64bit-doubles) or 32 bits (-m32bit-doubles) in size. The default is -m32bit-doubles. *Note* RX floating-point hardware only works on 32-bit values, which is why the default is -m32bit-doubles.

-fpu

-nofpu

Enables (**-fpu**) or disables (**-nofpu**) the use of RX floating-point hardware. The default is enabled for the *RX600* series and disabled for the *RX200* series.

Floating-point instructions are only generated for 32-bit floating-point values, however, so the FPU hardware is not used for doubles if the **-m64bit-doubles** option is used.

Note If the **-fpu** option is enabled then **-funsafe-math-optimizations** is also enabled automatically. This is because the RX FPU instructions are themselves unsafe.

-mcpu=name

Selects the type of RX CPU to be targeted. Currently three types are supported, the generic *RX600* and *RX200* series hardware and the specific *RX610* CPU. The default is *RX600*.

The only difference between RX600 and RX610 is that the RX610 does not support the MVTIPL instruction.

The RX200 series does not have a hardware floating-point unit and so **-nofpu** is enabled by default when this type is selected.

-mbig-endian-data

-mlittle-endian-data

Store data (but not code) in the big-endian format. The default is **-mlittle-endian-data**, i.e. to store data in the little-endian format.

-msmall-data-limit=N

Specifies the maximum size in bytes of global and static variables which can be placed into the small data area. Using the small data area can lead to smaller and faster code, but the size of area is limited and it is up to the programmer to ensure that the area does not overflow. Also when the small data area is used one of the RX's registers (usually r13) is reserved for use pointing to this area, so it is no longer available for use by the compiler. This could result in slower and/or larger code if variables are pushed onto the stack instead of being held in this register.

Note, common variables (variables that have not been initialized) and constants are not placed into the small data area as they are assigned to other sections in the output executable.

The default value is zero, which disables this feature. Note, this feature is not enabled by default with higher optimization levels (**-O2** etc) because of the potentially detrimental effects of reserving a register. It is up to the programmer to experiment and discover whether this feature is of benefit to their program. See the description of the **-mpid** option for a description of how the actual register to hold the small data area pointer is chosen.

-msim

-mno-sim

Use the simulator runtime. The default is to use the libgloss board-specific runtime.

-mas100-syntax

-mno-as100-syntax

When generating assembler output use a syntax that is compatible with Renesas's AS100 assembler. This syntax can also be handled by the GAS assembler, but it has some restrictions so it is not generated by default.

-mmax-constant-size=N

Specifies the maximum size, in bytes, of a constant that can be used as an operand in a RX instruction. Although the RX instruction set does allow constants of up to 4 bytes in length to be used in instructions, a longer value equates to a longer instruction. Thus in some circumstances it can be beneficial to restrict the size of constants that are used in instructions. Constants that are too big are instead placed into a constant pool and referenced via register indirection.

The value N can be between 0 and 4. A value of 0 (the default) or 4 means that constants of any size are allowed.

-mrelax

Enable linker relaxation. Linker relaxation is a process whereby the linker attempts to reduce the size of a program by finding shorter versions of various instructions. Disabled by default.

-mint-register=N

Specify the number of registers to reserve for fast interrupt handler functions. The value N can be between 0 and 4. A value of 1 means that register r13 is reserved for the exclusive use of fast interrupt handlers. A value of 2 reserves r13 and r12. A value of 3 reserves r13, r12 and r11, and a value of 4 reserves r13 through r10. A value of 0, the default, does not reserve any registers.

-msave-acc-in-interrupts

Specifies that interrupt handler functions should preserve the accumulator register. This is only necessary if normal code might use the accumulator register, for example because it performs 64-bit multiplications. The default is to ignore the accumulator as this makes the interrupt handlers faster.

-mpid

-mno-pid

Enables the generation of position independent data. When enabled any access to constant data is done via an offset from a base address held in a register. This allows the location of constant data to be determined at run time without requiring the executable to be relocated, which is a benefit to embedded applications with tight memory constraints. Data that can be modified is not affected by this option.

Note, using this feature reserves a register, usually r13, for the constant data base address. This can result in slower and/or larger code, especially in complicated functions.

The actual register chosen to hold the constant data base address depends upon whether the **-msmall-data-limit** and/or the **-mint-register** command-line options are enabled. Starting with register r13 and proceeding downwards, registers are allocated first to satisfy the requirements of **-mint-register**, then **-mpid** and finally **-msmall-data-limit**. Thus it is possible for the small data area register to be r8 if both **-mint-register=4** and **-mpid** are specified on the command line.

By default this feature is not enabled. The default can be restored via the **-mno-pid** command-line option.

gcc-4.8 2015-06-23 202

-mno-warn-multiple-fast-interrupts

-mwarn-multiple-fast-interrupts

Prevents GCC from issuing a warning message if it finds more than one fast interrupt handler when it is compiling a file. The default is to issue a warning for each extra fast interrupt handler found, as the RX only supports one such interrupt.

Note: The generic GCC command-line option -ffixed-reg has special significance to the RX port when used with the interrupt function attribute. This attribute indicates a function intended to process fast interrupts. GCC ensures that it only uses the registers r10, r11, r12 and/or r13 and only provided that the normal use of the corresponding registers have been restricted via the -ffixed-reg or -mint-register command-line options.

S/390 and zSeries Options

These are the **-m** options defined for the S/390 and zSeries architecture.

-mhard-float

-msoft-float

Use (do not use) the hardware floating-point instructions and registers for floating-point operations. When **-msoft-float** is specified, functions in *libgcc.a* are used to perform floating-point operations. When **-mhard-float** is specified, the compiler generates IEEE floating-point instructions. This is the default.

-mhard-dfp

-mno-hard-dfp

Use (do not use) the hardware decimal-floating-point instructions for decimal-floating-point operations. When **-mno-hard-dfp** is specified, functions in *libgcc.a* are used to perform decimal-floating-point operations. When **-mhard-dfp** is specified, the compiler generates decimal-floating-point hardware instructions. This is the default for **-march=z9-ec** or higher.

-mlong-double-64

-mlong-double-128

These switches control the size of long double type. A size of 64 bits makes the long double type equivalent to the double type. This is the default.

-mbackchain

-mno-backchain

Store (do not store) the address of the caller's frame as backchain pointer into the callee's stack frame. A backchain may be needed to allow debugging using tools that do not understand DWARF 2 call frame information. When **-mno-packed-stack** is in effect, the backchain pointer is stored at the bottom of the stack frame; when **-mpacked-stack** is in effect, the backchain is placed into the topmost word of the 96/160 byte register save area.

In general, code compiled with **-mbackchain** is call-compatible with code compiled with **-mmo-backchain**; however, use of the backchain for debugging purposes usually requires that the whole binary is built with **-mbackchain**. Note that the combination of **-mbackchain**, **-mpacked-stack** and **-mhard-float** is not supported. In order to build a linux kernel use **-msoft-float**.

The default is to not maintain the backchain.

-mpacked-stack

-mno-packed-stack

Use (do not use) the packed stack layout. When **-mno-packed-stack** is specified, the compiler uses the all fields of the 96/160 byte register save area only for their default purpose; unused fields still take up stack space. When **-mpacked-stack** is specified, register save slots are densely packed at the top of the register save area; unused space is reused for other purposes, allowing for more efficient use of the available stack space. However, when **-mbackchain** is also in effect, the topmost word of the save area is always used to store the backchain, and the return address register is always saved two words below the backchain.

gcc-4.8 2015-06-23 203

As long as the stack frame backchain is not used, code generated with **-mpacked-stack** is call-compatible with code generated with **-mno-packed-stack**. Note that some non-FSF releases of GCC 2.95 for S/390 or zSeries generated code that uses the stack frame backchain at run time, not just for debugging purposes. Such code is not call-compatible with code compiled with **-mpacked-stack**. Also, note that the combination of **-mbackchain**, **-mpacked-stack** and **-mhard-float** is not supported. In order to build a linux kernel use **-msoft-float**.

The default is to not use the packed stack layout.

-msmall-exec

-mno-small-exec

Generate (or do not generate) code using the bras instruction to do subroutine calls. This only works reliably if the total executable size does not exceed 64k. The default is to use the basr instruction instead, which does not have this limitation.

-m64

-m31

When -m31 is specified, generate code compliant to the GNU/Linux for S/390 ABI. When -m64 is specified, generate code compliant to the GNU/Linux for zSeries ABI. This allows GCC in particular to generate 64-bit instructions. For the s390 targets, the default is -m31, while the s390x targets default to -m64.

-mzarch

-mesa

When **-mzarch** is specified, generate code using the instructions available on z/Architecture. When **-mesa** is specified, generate code using the instructions available on ESA/390. Note that **-mesa** is not possible with **-m64**. When generating code compliant to the GNU/Linux for S/390 ABI, the default is **-mesa**. When generating code compliant to the GNU/Linux for zSeries ABI, the default is **-mzarch**.

-mmvcle

-mno-mvcle

Generate (or do not generate) code using the mvcle instruction to perform block moves. When **-mno-mvcle** is specified, use a mvc loop instead. This is the default unless optimizing for size.

-mdebug

-mno-debug

Print (or do not print) additional debug information when compiling. The default is to not print debug information.

-march=cpu-type

Generate code that runs on *cpu-type*, which is the name of a system representing a certain processor type. Possible values for *cpu-type* are **g5**, **g6**, **z900**, **z990**, **z9–109**, **z9–ec**, **z10**, **z196**, and **zEC12**. When generating code using the instructions available on z/Architecture, the default is **–march=z900**. Otherwise, the default is **–march=g5**.

-mtune=cpu-type

Tune to *cpu-type* everything applicable about the generated code, except for the ABI and the set of available instructions. The list of *cpu-type* values is the same as for **-march**. The default is the value used for **-march**.

-mtpf-trace

-mno-tpf-trace

Generate code that adds (does not add) in TPF OS specific branches to trace routines in the operating system. This option is off by default, even when compiling for the TPF OS.

-mfused-madd

-mno-fused-madd

Generate code that uses (does not use) the floating-point multiply and accumulate instructions. These instructions are generated by default if hardware floating point is used.

-mwarn-framesize=framesize

Emit a warning if the current function exceeds the given frame size. Because this is a compile-time check it doesn't need to be a real problem when the program runs. It is intended to identify functions that most probably cause a stack overflow. It is useful to be used in an environment with limited stack size e.g. the linux kernel.

-mwarn-dynamicstack

Emit a warning if the function calls alloca or uses dynamically-sized arrays. This is generally a bad idea with a limited stack size.

-mstack-guard=stack-guard

-mstack-size=stack-size

If these options are provided the S/390 back end emits additional instructions in the function prologue that trigger a trap if the stack size is *stack-guard* bytes above the *stack-size* (remember that the stack on S/390 grows downward). If the *stack-guard* option is omitted the smallest power of 2 larger than the frame size of the compiled function is chosen. These options are intended to be used to help debugging stack overflow problems. The additionally emitted code causes only little overhead and hence can also be used in production-like systems without greater performance degradation. The given values have to be exact powers of 2 and *stack-size* has to be greater than *stack-guard* without exceeding 64k. In order to be efficient the extra code makes the assumption that the stack starts at an address aligned to the value given by *stack-size*. The *stack-guard* option can only be used in conjunction with *stack-size*.

-**mhotpatch**=*pre-halfwords*, *post-halfwords*

If the hotpatch option is enabled, a "hot-patching" function prologue is generated for all functions in the compilation unit. The funtion label is prepended with the given number of two-byte NOP instructions (*pre-halfwords*, maximum 1000000). After the label, 2 * *post-halfwords* bytes are appended, using the largest NOP like instructions the architecture allows (maximum 1000000).

If both arguments are zero, hotpatching is disabled.

This option can be overridden for individual functions with the hotpatch attribute.

Score Options

These options are defined for Score implementations:

_meh

Compile code for big-endian mode. This is the default.

-mel

Compile code for little-endian mode.

-mnhwloop

Disable generation of bcnz instructions.

-muls

Enable generation of unaligned load and store instructions.

-mmac

Enable the use of multiply-accumulate instructions. Disabled by default.

-mscore5

Specify the SCORE5 as the target architecture.

-mscore5u

Specify the SCORE5U of the target architecture.

-mscore7

Specify the SCORE7 as the target architecture. This is the default.

-mscore7d

Specify the SCORE7D as the target architecture.

SH Options

These **-m** options are defined for the SH implementations:

-m1

Generate code for the SH1.

-m2

Generate code for the SH2.

-m2e

Generate code for the SH2e.

-m2a-nofpu

Generate code for the SH2a without FPU, or for a SH2a-FPU in such a way that the floating-point unit is not used.

-m2a-single-only

Generate code for the SH2a-FPU, in such a way that no double-precision floating-point operations are used

-m2a-single

Generate code for the SH2a-FPU assuming the floating-point unit is in single-precision mode by default.

-m2a

Generate code for the SH2a-FPU assuming the floating-point unit is in double-precision mode by default.

-m3

Generate code for the SH3.

-m3e

Generate code for the SH3e.

-m4-nofpu

Generate code for the SH4 without a floating-point unit.

-m4-single-only

Generate code for the SH4 with a floating-point unit that only supports single-precision arithmetic.

-m4-single

Generate code for the SH4 assuming the floating-point unit is in single-precision mode by default.

-m4

Generate code for the SH4.

-m4-100

Generate code for SH4-100.

-m4-100-nofpu

Generate code for SH4–100 in such a way that the floating-point unit is not used.

-m4-100-single

Generate code for SH4-100 assuming the floating-point unit is in single-precision mode by default.

-m4-100-single-only

Generate code for SH4-100 in such a way that no double-precision floating-point operations are used.

-m4-200

Generate code for SH4-200.

-m4-200-nofpu

Generate code for SH4-200 without in such a way that the floating-point unit is not used.

-m4-200-single

Generate code for SH4-200 assuming the floating-point unit is in single-precision mode by default.

-m4-200-single-only

Generate code for SH4-200 in such a way that no double-precision floating-point operations are used.

-m4-300

Generate code for SH4-300.

-m4-300-nofpu

Generate code for SH4-300 without in such a way that the floating-point unit is not used.

-m4-300-single

Generate code for SH4-300 in such a way that no double-precision floating-point operations are used.

-m4-300-single-only

Generate code for SH4-300 in such a way that no double-precision floating-point operations are used.

-m4-340

Generate code for SH4-340 (no MMU, no FPU).

-m4-500

Generate code for SH4–500 (no FPU). Passes **–isa=sh4–nofpu** to the assembler.

-m4a-nofpu

Generate code for the SH4al-dsp, or for a SH4a in such a way that the floating-point unit is not used.

-m4a-single-only

Generate code for the SH4a, in such a way that no double-precision floating-point operations are used.

-m4a-single

Generate code for the SH4a assuming the floating-point unit is in single-precision mode by default.

-m4a

Generate code for the SH4a.

-m4al

Same as **-m4a-nofpu**, except that it implicitly passes **-dsp** to the assembler. GCC doesn't generate any DSP instructions at the moment.

-m5-32media

Generate 32-bit code for SHmedia.

-m5-32media-nofpu

Generate 32-bit code for SHmedia in such a way that the floating-point unit is not used.

-m5-64media

Generate 64-bit code for SHmedia.

-m5-64media-nofpu

Generate 64-bit code for SHmedia in such a way that the floating-point unit is not used.

-m5-compact

Generate code for SHcompact.

-m5-compact-nofpu

Generate code for SHcompact in such a way that the floating-point unit is not used.

-mb

Compile code for the processor in big-endian mode.

-ml

Compile code for the processor in little-endian mode.

-mdalign

Align doubles at 64-bit boundaries. Note that this changes the calling conventions, and thus some functions from the standard C library do not work unless you recompile it first with **-mdalign**.

-mrelax

Shorten some address references at link time, when possible; uses the linker option -relax.

-mbigtable

Use 32-bit offsets in switch tables. The default is to use 16-bit offsets.

-mbitops

Enable the use of bit manipulation instructions on SH2A.

-mfmovd

Enable the use of the instruction fmovd. Check -mdalign for alignment constraints.

-mrenesas

Comply with the calling conventions defined by Renesas.

-mno-renesas

Comply with the calling conventions defined for GCC before the Renesas conventions were available. This option is the default for all targets of the SH toolchain.

-mnomacsave

Mark the MAC register as call-clobbered, even if -mrenesas is given.

-mieee

-mno-ieee

Control the IEEE compliance of floating-point comparisons, which affects the handling of cases where the result of a comparison is unordered. By default **-mieee** is implicitly enabled. If **-ffinite-math-only** is enabled **-mno-ieee** is implicitly set, which results in faster floating-point greater-equal and less-equal comparisons. The implicit settings can be overridden by specifying either **-mieee** or **-mno-ieee**.

-minline-ic invalidate

Inline code to invalidate instruction cache entries after setting up nested function trampolines. This option has no effect if **-musermode** is in effect and the selected code generation option (e.g. **-m4**) does not allow the use of the <code>icbi</code> instruction. If the selected code generation option does not allow the use of the <code>icbi</code> instruction, and **-musermode** is not in effect, the inlined code manipulates the instruction cache address array directly with an associative write. This not only requires privileged mode at run time, but it also fails if the cache line had been mapped via the TLB and has become unmapped.

-misize

Dump instruction size and location in the assembly code.

-mpadstruct

This option is deprecated. It pads structures to multiple of 4 bytes, which is incompatible with the SH ABI

-matomic-model=model

Sets the model of atomic operations and additional parameters as a comma separated list. For details on the atomic built-in functions see **__atomic Builtins**. The following models and parameters are supported:

none

Disable compiler generated atomic sequences and emit library calls for atomic operations. This is the default if the target is not $sh^*-*-linux^*$.

soft-gusa

Generate GNU/Linux compatible gUSA software atomic sequences for the atomic built-in functions. The generated atomic sequences require additional support from the interrupt/exception handling code of the system and are only suitable for SH3* and SH4* single-core systems. This option is enabled by default when the target is sh*-*-linux* and SH3* or SH4*. When the target is SH4A, this option will also partially utilize the hardware atomic instructions movli.l and movco.l to create more efficient code, unless **strict** is specified.

soft-tcb

Generate software atomic sequences that use a variable in the thread control block. This is a variation of the gUSA sequences which can also be used on SH1* and SH2* targets. The generated atomic sequences require additional support from the interrupt/exception handling code of the system and are only suitable for single-core systems. When using this model, the **gbr-offset**= parameter has to be specified as well.

soft-imask

Generate software atomic sequences that temporarily disable interrupts by setting SR.IMASK = 1111. This model works only when the program runs in privileged mode and is only suitable for single-core systems. Additional support from the interrupt/exception handling code of the system is not required. This model is enabled by default when the target is sh*-*-linux* and SH1* or SH2*.

hard-llcs

Generate hardware atomic sequences using the movli.1 and movco.1 instructions only. This is only available on SH4A and is suitable for multi-core systems. Since the hardware instructions support only 32 bit atomic variables access to 8 or 16 bit variables is emulated with 32 bit accesses. Code compiled with this option will also be compatible with other software atomic model interrupt/exception handling systems if executed on an SH4A system. Additional support from the interrupt/exception handling code of the system is not required for this model.

gbr-offset=

This parameter specifies the offset in bytes of the variable in the thread control block structure that should be used by the generated atomic sequences when the **soft-tcb** model has been selected. For other models this parameter is ignored. The specified value must be an integer multiple of four and in the range 0–1020.

strict

This parameter prevents mixed usage of multiple atomic models, even though they would be compatible, and will make the compiler generate atomic sequences of the specified model only.

-mtas

Generate the tas.b opcode for __atomic_test_and_set. Notice that depending on the particular hardware and software configuration this can degrade overall performance due to the operand cache line flushes that are implied by the tas.b instruction. On multi-core SH4A processors the tas.b instruction must be used with caution since it can result in data corruption for certain cache configurations.

-mprefergot

When generating position-independent code, emit function calls using the Global Offset Table instead of the Procedure Linkage Table.

-musermode

-mno-usermode

Don't allow (allow) the compiler generating privileged mode code. Specifying **-musermode** also implies **-mno-inline-ic_invalidate** if the inlined code would not work in user mode. **-musermode** is the default when the target is sh*-*-linux*. If the target is SH1* or SH2* **-musermode** has no effect, since there is no user mode.

-multcost=number

Set the cost to assume for a multiply insn.

_mdiv=strateov

Set the division strategy to be used for integer division operations. For SHmedia *strategy* can be one of:

fp Performs the operation in floating point. This has a very high latency, but needs only a few instructions, so it might be a good choice if your code has enough easily-exploitable ILP to allow the compiler to schedule the floating-point instructions together with other instructions. Division

by zero causes a floating-point exception.

inv Uses integer operations to calculate the inverse of the divisor, and then multiplies the dividend with the inverse. This strategy allows CSE and hoisting of the inverse calculation. Division by zero calculates an unspecified result, but does not trap.

inv:minlat

A variant of **inv** where, if no CSE or hoisting opportunities have been found, or if the entire operation has been hoisted to the same place, the last stages of the inverse calculation are intertwined with the final multiply to reduce the overall latency, at the expense of using a few more instructions, and thus offering fewer scheduling opportunities with other code.

call Calls a library function that usually implements the **inv:minlat** strategy. This gives high code density for m5-*media-nofpu compilations.

call2

Uses a different entry point of the same library function, where it assumes that a pointer to a lookup table has already been set up, which exposes the pointer load to CSE and code hoisting optimizations.

inv:call inv:call2

inv:fp

Use the **inv** algorithm for initial code generation, but if the code stays unoptimized, revert to the **call**, **call2**, or **fp** strategies, respectively. Note that the potentially-trapping side effect of division by zero is carried by a separate instruction, so it is possible that all the integer instructions are hoisted out, but the marker for the side effect stays where it is. A recombination to floating-point operations or a call is not possible in that case.

inv20u inv20l

Variants of the **inv:minlat** strategy. In the case that the inverse calculation is not separated from the multiply, they speed up division where the dividend fits into 20 bits (plus sign where applicable) by inserting a test to skip a number of operations in this case; this test slows down the case of larger dividends. **inv20u** assumes the case of a such a small dividend to be unlikely, and **inv20l** assumes it to be likely.

For targets other than SHmedia *strategy* can be one of:

call-div1

Calls a library function that uses the single-step division instruction div1 to perform the operation. Division by zero calculates an unspecified result and does not trap. This is the default except for SH4, SH2A and SHcompact.

call-fp

Calls a library function that performs the operation in double precision floating point. Division by zero causes a floating-point exception. This is the default for SHcompact with FPU. Specifying this for targets that do not have a double precision FPU will default to call-div1.

call-table

Calls a library function that uses a lookup table for small divisors and the div1 instruction with case distinction for larger divisors. Division by zero calculates an unspecified result and does not trap. This is the default for SH4. Specifying this for targets that do not have dynamic shift instructions will default to call-div1.

When a division strategy has not been specified the default strategy will be selected based on the current target. For SH2A the default strategy is to use the divs and divu instructions instead of library function calls.

-maccumulate-outgoing-args

Reserve space once for outgoing arguments in the function prologue rather than around each call. Generally beneficial for performance and size. Also needed for unwinding to avoid changing the stack frame around conditional code.

-mdivsi3 libfunc=name

Set the name of the library function used for 32-bit signed division to *name*. This only affects the name used in the **call** and **inv:call** division strategies, and the compiler still expects the same sets of input/output/clobbered registers as if this option were not present.

-mfixed-range=register-range

Generate code treating the given register range as fixed registers. A fixed register is one that the register allocator can not use. This is useful when compiling kernel code. A register range is specified as two registers separated by a dash. Multiple register ranges can be specified separated by a comma.

-mindexed-addressing

Enable the use of the indexed addressing mode for SHmedia32/SHcompact. This is only safe if the hardware and/or OS implement 32-bit wrap-around semantics for the indexed addressing mode. The architecture allows the implementation of processors with 64-bit MMU, which the OS could use to get 32-bit addressing, but since no current hardware implementation supports this or any other way to make the indexed addressing mode safe to use in the 32-bit ABI, the default is **-mno-indexed-addressing**.

-mgettrcost=number

Set the cost assumed for the gettr instruction to *number*. The default is 2 if **-mpt-fixed** is in effect, 100 otherwise.

-mpt-fixed

Assume pt* instructions won't trap. This generally generates better-scheduled code, but is unsafe on current hardware. The current architecture definition says that ptabs and ptrel trap when the target anded with 3 is 3. This has the unintentional effect of making it unsafe to schedule these instructions before a branch, or hoist them out of a loop. For example, __do_global_ctors, a part of *libgec* that runs constructors at program startup, calls functions in a list which is delimited by -1. With the -mpt-fixed option, the ptabs is done before testing against -1. That means that all the constructors run a bit more quickly, but when the loop comes to the end of the list, the program crashes because ptabs loads -1 into a target register.

Since this option is unsafe for any hardware implementing the current architecture specification, the default is **-mno-pt-fixed**. Unless specified explicitly with **-mgettrcost**, **-mno-pt-fixed** also implies **-mgettrcost=100**; this deters register allocation from using target registers for storing ordinary integers.

-minvalid-symbols

Assume symbols might be invalid. Ordinary function symbols generated by the compiler are always valid to load with movi/shori/ptabs or movi/shori/ptrel, but with assembler and/or linker tricks it is possible to generate symbols that cause ptabs or ptrel to trap. This option is only meaningful when **-mno-pt-fixed** is in effect. It prevents cross-basic-block CSE, hoisting and most scheduling of symbol loads. The default is **-mno-invalid-symbols**.

-mbranch-cost=num

Assume *num* to be the cost for a branch instruction. Higher numbers make the compiler try to generate more branch-free code if possible. If not specified the value is selected depending on the processor type that is being compiled for.

-mzdcbranch

-mno-zdcbranch

Assume (do not assume) that zero displacement conditional branch instructions bt and bf are fast. If **-mzdcbranch** is specified, the compiler will try to prefer zero displacement branch code sequences. This is enabled by default when generating code for SH4 and SH4A. It can be explicitly disabled by specifying **-mno-zdcbranch**.

gcc-4.8 2015-06-23 211

-mcbranchdi

Enable the cbranchdi4 instruction pattern.

-mcmpeqdi

Emit the cmpeqdi_t instruction pattern even when -mcbranchdi is in effect.

-mfused-madd

-mno-fused-madd

Generate code that uses (does not use) the floating-point multiply and accumulate instructions. These instructions are generated by default if hardware floating point is used. The machine-dependent **-mfused-madd** option is now mapped to the machine-independent **-ffp-contract=fast** option, and **-mno-fused-madd** is mapped to **-ffp-contract=off**.

-mfsca

-mno-fsca

Allow or disallow the compiler to emit the fsca instruction for sine and cosine approximations. The option -mfsca must be used in combination with -funsafe-math-optimizations. It is enabled by default when generating code for SH4A. Using -mno-fsca disables sine and cosine approximations even if -funsafe-math-optimizations is in effect.

-mfsrra

-mno-fsrra

Allow or disallow the compiler to emit the fsrra instruction for reciprocal square root approximations. The option -mfsrra must be used in combination with -funsafe-math-optimizations and -ffinite-math-only. It is enabled by default when generating code for SH4A. Using -mno-fsrra disables reciprocal square root approximations even if -funsafe-math-optimizations and -ffinite-math-only are in effect.

-mpretend-cmove

Prefer zero-displacement conditional branches for conditional move instruction patterns. This can result in faster code on the SH4 processor.

Solaris 2 Options

These -m options are supported on Solaris 2:

-mimpure-text

-mimpure-text, used in addition to **-shared**, tells the compiler to not pass **-z text** to the linker when linking a shared object. Using this option, you can link position-dependent code into a shared object.

-mimpure-text suppresses the "relocations remain against allocatable but non-writable sections" linker error message. However, the necessary relocations trigger copy-on-write, and the shared object is not actually shared across processes. Instead of using **-mimpure-text**, you should compile all source code with **-fpic** or **-fPIC**.

These switches are supported in addition to the above on Solaris 2:

-pthreads

Add support for multithreading using the POSIX threads library. This option sets flags for both the preprocessor and linker. This option does not affect the thread safety of object code produced by the compiler or that of libraries supplied with it.

-pthread

This is a synonym for **-pthreads**.

SPARC Options

These -m options are supported on the SPARC:

-mno-app-regs

-mapp-regs

Specify **-mapp-regs** to generate output using the global registers 2 through 4, which the SPARC SVR4 ABI reserves for applications. Like the global register 1, each global register 2 through 4 is then

treated as an allocable register that is clobbered by function calls. This is the default.

To be fully SVR4 ABI-compliant at the cost of some performance loss, specify **-mno-app-regs**. You should compile libraries and system software with this option.

-mflat

-mno-flat

With **-mflat**, the compiler does not generate save/restore instructions and uses a "flat" or single register window model. This model is compatible with the regular register window model. The local registers and the input registers (0--5) are still treated as "call-saved" registers and are saved on the stack as needed.

With **-mno-flat** (the default), the compiler generates save/restore instructions (except for leaf functions). This is the normal operating mode.

-mfpu

-mhard-float

Generate output containing floating-point instructions. This is the default.

-mno-fpu

-msoft-float

Generate output containing library calls for floating point. **Warning:** the requisite libraries are not available for all SPARC targets. Normally the facilities of the machine's usual C compiler are used, but this cannot be done directly in cross-compilation. You must make your own arrangements to provide suitable library functions for cross-compilation. The embedded targets **sparc-*-aout** and **sparclite-*-*** do provide software floating-point support.

-msoft-float changes the calling convention in the output file; therefore, it is only useful if you compile *all* of a program with this option. In particular, you need to compile *libgcc.a*, the library that comes with GCC, with **-msoft-float** in order for this to work.

-mhard-quad-float

Generate output containing quad-word (long double) floating-point instructions.

-msoft-quad-float

Generate output containing library calls for quad-word (long double) floating-point instructions. The functions called are those specified in the SPARC ABI. This is the default.

As of this writing, there are no SPARC implementations that have hardware support for the quad-word floating-point instructions. They all invoke a trap handler for one of these instructions, and then the trap handler emulates the effect of the instruction. Because of the trap handler overhead, this is much slower than calling the ABI library routines. Thus the **-msoft-quad-float** option is the default.

-mno-unaligned-doubles

-munaligned-doubles

Assume that doubles have 8-byte alignment. This is the default.

With **-munaligned-doubles**, GCC assumes that doubles have 8-byte alignment only if they are contained in another type, or if they have an absolute address. Otherwise, it assumes they have 4-byte alignment. Specifying this option avoids some rare compatibility problems with code generated by other compilers. It is not the default because it results in a performance loss, especially for floating-point code.

-muser-mode

-mno-user-mode

Do not generate code that can only run in supervisor mode. This is relevant only for the casa instruction emitted for the LEON3 processor. The default is **-mno-user-mode**.

-mno-faster-structs

-mfaster-structs

With **-mfaster-structs**, the compiler assumes that structures should have 8-byte alignment. This enables the use of pairs of 1dd and std instructions for copies in structure assignment, in place of

twice as many 1d and st pairs. However, the use of this changed alignment directly violates the SPARC ABI. Thus, it's intended only for use on targets where the developer acknowledges that their resulting code is not directly in line with the rules of the ABI.

```
-mcpu=cpu_type
```

Set the instruction set, register set, and instruction scheduling parameters for machine type *cpu_type*. Supported values for *cpu_type* are **v7**, **cypress**, **v8**, **supersparc**, **hypersparc**, **leon**, **leon3**, **leon3v7**, **sparclite**, **f930**, **f934**, **sparclite86x**, **sparclet**, **tsc701**, **v9**, **ultrasparc**, **ultrasparc3**, **niagara**, **niagara2**, **niagara3** and **niagara4**.

Native Solaris and GNU/Linux toolchains also support the value **native**, which selects the best architecture option for the host processor. **–mcpu=native** has no effect if GCC does not recognize the processor.

Default instruction scheduling parameters are used for values that select an architecture and not an implementation. These are v7, v8, sparclite, sparclet, v9.

Here is a list of each supported architecture and their supported implementations.

```
v7 cypress, leon3v7
v8 supersparc, hypersparc, leon, leon3
sparclite
f930, f934, sparclite86x
sparclet
tsc701
```

v9 ultrasparc, ultrasparc3, niagara, niagara2, niagara3, niagara4

By default (unless configured otherwise), GCC generates code for the V7 variant of the SPARC architecture. With **-mcpu=cypress**, the compiler additionally optimizes it for the Cypress CY7C602 chip, as used in the SPARCStation/SPARCServer 3xx series. This is also appropriate for the older SPARCStation 1, 2, IPX etc.

With **-mcpu=v8**, GCC generates code for the V8 variant of the SPARC architecture. The only difference from V7 code is that the compiler emits the integer multiply and integer divide instructions which exist in SPARC-V8 but not in SPARC-V7. With **-mcpu=supersparc**, the compiler additionally optimizes it for the SuperSPARC chip, as used in the SPARCStation 10, 1000 and 2000 series.

With -mcpu=sparclite, GCC generates code for the SPARClite variant of the SPARC architecture. This adds the integer multiply, integer divide step and scan (ffs) instructions which exist in SPARClite but not in SPARC-V7. With -mcpu=f930, the compiler additionally optimizes it for the Fujitsu MB86930 chip, which is the original SPARClite, with no FPU. With -mcpu=f934, the compiler additionally optimizes it for the Fujitsu MB86934 chip, which is the more recent SPARClite with FPU.

With **-mcpu=sparclet**, GCC generates code for the SPARClet variant of the SPARC architecture. This adds the integer multiply, multiply/accumulate, integer divide step and scan (ffs) instructions which exist in SPARClet but not in SPARC-V7. With **-mcpu=tsc701**, the compiler additionally optimizes it for the TEMIC SPARClet chip.

With -mcpu=v9, GCC generates code for the V9 variant of the SPARC architecture. This adds 64-bit integer and floating-point move instructions, 3 additional floating-point condition code registers and conditional move instructions. With -mcpu=ultrasparc, the compiler additionally optimizes it for the Sun UltraSPARC I/II/IIi chips. With -mcpu=ultrasparc3, the compiler additionally optimizes it for Sun UltraSPARC TI chips. With -mcpu=niagara, the compiler additionally optimizes it for Sun UltraSPARC T2 chips. With -mcpu=niagara3, the compiler additionally optimizes it for Sun UltraSPARC T3 chips. With -mcpu=niagara4, the compiler additionally optimizes it for Sun UltraSPARC T3 chips. With -mcpu=niagara4, the compiler additionally optimizes it for Sun UltraSPARC T4 chips.

-mtune=cpu_type

Set the instruction scheduling parameters for machine type *cpu_type*, but do not set the instruction set or register set that the option **-mcpu**=*cpu_type* does.

The same values for -mcpu=cpu_type can be used for -mtune=cpu_type, but the only useful values are those that select a particular CPU implementation. Those are cypress, supersparc, hypersparc, leon, leon3, leon3v7, f930, f934, sparclite86x, tsc701, ultrasparc, ultrasparc3, niagara, niagara2, niagara3 and niagara4. With native Solaris and GNU/Linux toolchains, native can also be used.

-mv8plus

-mno-v8plus

With **-mv8plus**, GCC generates code for the SPARC-V8+ ABI. The difference from the V8 ABI is that the global and out registers are considered 64 bits wide. This is enabled by default on Solaris in 32-bit mode for all SPARC-V9 processors.

-mvis

-mno-vis

With **-mvis**, GCC generates code that takes advantage of the UltraSPARC Visual Instruction Set extensions. The default is **-mno-vis**.

-mvis2

-mno-vis2

With -mvis2, GCC generates code that takes advantage of version 2.0 of the UltraSPARC Visual Instruction Set extensions. The default is -mvis2 when targeting a cpu that supports such instructions, such as UltraSPARC-III and later. Setting -mvis2 also sets -mvis.

-mvis3

-mno-vis3

With **-mvis3**, GCC generates code that takes advantage of version 3.0 of the UltraSPARC Visual Instruction Set extensions. The default is **-mvis3** when targeting a cpu that supports such instructions, such as niagara-3 and later. Setting **-mvis3** also sets **-mvis2** and **-mvis**.

-mcbcond

-mno-cbcond

With **-mcbcond**, GCC generates code that takes advantage of compare-and-branch instructions, as defined in the Sparc Architecture 2011. The default is **-mcbcond** when targeting a cpu that supports such instructions, such as niagara–4 and later.

-mpopc

-mno-popc

With **-mpopc**, GCC generates code that takes advantage of the UltraSPARC population count instruction. The default is **-mpopc** when targeting a cpu that supports such instructions, such as Niagara-2 and later.

-mfmaf

-mno-fmaf

With **-mfmaf**, GCC generates code that takes advantage of the UltraSPARC Fused Multiply-Add Floating-point extensions. The default is **-mfmaf** when targeting a cpu that supports such instructions, such as Niagara—3 and later.

-mfix-at697f

Enable the documented workaround for the single erratum of the Atmel AT697F processor (which corresponds to erratum #13 of the AT697E processor).

-mfix-ut699

Enable the documented workarounds for the floating-point errata and the data cache nullify errata of the UT699 processor.

These **-m** options are supported in addition to the above on SPARC-V9 processors in 64-bit environments:

-m32

-m64

Generate code for a 32-bit or 64-bit environment. The 32-bit environment sets int, long and pointer to 32 bits. The 64-bit environment sets int to 32 bits and long and pointer to 64 bits.

-mcmodel=which

Set the code model to one of

medlow

The Medium/Low code model: 64-bit addresses, programs must be linked in the low 32 bits of memory. Programs can be statically or dynamically linked.

medmid

The Medium/Middle code model: 64-bit addresses, programs must be linked in the low 44 bits of memory, the text and data segments must be less than 2GB in size and the data segment must be located within 2GB of the text segment.

medany

The Medium/Anywhere code model: 64-bit addresses, programs may be linked anywhere in memory, the text and data segments must be less than 2GB in size and the data segment must be located within 2GB of the text segment.

embmedany

The Medium/Anywhere code model for embedded systems: 64-bit addresses, the text and data segments must be less than 2GB in size, both starting anywhere in memory (determined at link time). The global register %g4 points to the base of the data segment. Programs are statically linked and PIC is not supported.

-mmemory-model=mem-model

Set the memory model in force on the processor to one of

default

The default memory model for the processor and operating system.

rmo

Relaxed Memory Order

pso Partial Store Order

tso Total Store Order

sc Sequential Consistency

These memory models are formally defined in Appendix D of the Sparc V9 architecture manual, as set in the processor's PSTATE.MM field.

-mstack-bias

-mno-stack-bias

With **-mstack-bias**, GCC assumes that the stack pointer, and frame pointer if present, are offset by -2047 which must be added back when making stack frame references. This is the default in 64-bit mode. Otherwise, assume no such offset is present.

SPU Options

These -m options are supported on the SPU:

-mwarn-reloc

-merror-reloc

The loader for SPU does not handle dynamic relocations. By default, GCC gives an error when it generates code that requires a dynamic relocation. —mno-error-reloc disables the error, —mwarn-reloc generates a warning instead.

-msafe-dma

-munsafe-dma

Instructions that initiate or test completion of DMA must not be reordered with respect to loads and stores of the memory that is being accessed. With **-munsafe-dma** you must use the volatile keyword to protect memory accesses, but that can lead to inefficient code in places where the memory is known to not change. Rather than mark the memory as volatile, you can use **-msafe-dma** to tell the compiler to treat the DMA instructions as potentially affecting all memory.

-mbranch-hints

By default, GCC generates a branch hint instruction to avoid pipeline stalls for always-taken or probably-taken branches. A hint is not generated closer than 8 instructions away from its branch. There is little reason to disable them, except for debugging purposes, or to make an object a little bit smaller.

-msmall-mem

-mlarge-mem

By default, GCC generates code assuming that addresses are never larger than 18 bits. With **-mlarge-mem** code is generated that assumes a full 32-bit address.

-mstdmain

By default, GCC links against startup code that assumes the SPU-style main function interface (which has an unconventional parameter list). With **-mstdmain**, GCC links your program against startup code that assumes a C99-style interface to main, including a local copy of argy strings.

-mfixed-range=register-range

Generate code treating the given register range as fixed registers. A fixed register is one that the register allocator cannot use. This is useful when compiling kernel code. A register range is specified as two registers separated by a dash. Multiple register ranges can be specified separated by a comma.

-mea32

-mea64

Compile code assuming that pointers to the PPU address space accessed via the __ea named address space qualifier are either 32 or 64 bits wide. The default is 32 bits. As this is an ABI-changing option, all object code in an executable must be compiled with the same setting.

-maddress-space-conversion

-mno-address-space-conversion

Allow/disallow treating the __ea address space as superset of the generic address space. This enables explicit type casts between __ea and generic pointer as well as implicit conversions of generic pointers to __ea pointers. The default is to allow address space pointer conversions.

-mcache-size=cache-size

This option controls the version of libgcc that the compiler links to an executable and selects a software-managed cache for accessing variables in the __ea address space with a particular cache size. Possible options for *cache-size* are **8**, **16**, **32**, **64** and **128**. The default cache size is 64KB.

-matomic-updates

-mno-atomic-updates

This option controls the version of libgcc that the compiler links to an executable and selects whether atomic updates to the software-managed cache of PPU-side variables are used. If you use atomic updates, changes to a PPU variable from SPU code using the __ea named address space qualifier do not interfere with changes to other PPU variables residing in the same cache line from PPU code. If you do not use atomic updates, such interference may occur; however, writing back cache lines is more efficient. The default behavior is to use atomic updates.

-mdual-nops

-mdual-nops=n

By default, GCC inserts nops to increase dual issue when it expects it to increase performance. n can be a value from 0 to 10. A smaller n inserts fewer nops. 10 is the default, 0 is the same as -mno-dual-nops. Disabled with -Os.

-mhint-max-nops=n

Maximum number of nops to insert for a branch hint. A branch hint must be at least 8 instructions away from the branch it is affecting. GCC inserts up to n nops to enforce this, otherwise it does not generate the branch hint.

-mhint-max-distance=n

The encoding of the branch hint instruction limits the hint to be within 256 instructions of the branch it is affecting. By default, GCC makes sure it is within 125.

-msafe-hints

Work around a hardware bug that causes the SPU to stall indefinitely. By default, GCC inserts the hbrp instruction to make sure this stall won't happen.

Options for System V

These additional options are available on System V Release 4 for compatibility with other compilers on those systems:

-G Create a shared object. It is recommended that -symbolic or -shared be used instead.

$-\mathbf{Q}\mathbf{y}$

Identify the versions of each tool used by the compiler, in a .ident assembler directive in the output.

-Qn

Refrain from adding .ident directives to the output file (this is the default).

-YP.dirs

Search the directories *dirs*, and no others, for libraries specified with **-1**.

-Ym,dir

Look in the directory *dir* to find the M4 preprocessor. The assembler uses this option.

TILE-Gx Options

These -m options are supported on the TILE-Gx:

-mcmodel=small

Generate code for the small model. The distance for direct calls is limited to 500M in either direction. PC-relative addresses are 32 bits. Absolute addresses support the full address range.

-mcmodel=large

Generate code for the large model. There is no limitation on call distance, pc-relative addresses, or absolute addresses.

-mcpu=name

Selects the type of CPU to be targeted. Currently the only supported type is **tilegx**.

-m32

-m64

Generate code for a 32-bit or 64-bit environment. The 32-bit environment sets int, long, and pointer to 32 bits. The 64-bit environment sets int to 32 bits and long and pointer to 64 bits.

TILEPro Options

These **-m** options are supported on the TILEPro:

-mcpu=name

Selects the type of CPU to be targeted. Currently the only supported type is **tilepro**.

-m32

Generate code for a 32-bit environment, which sets int, long, and pointer to 32 bits. This is the only supported behavior so the flag is essentially ignored.

V850 Options

These -m options are defined for V850 implementations:

-mlong-calls

-mno-long-calls

Treat all calls as being far away (near). If calls are assumed to be far away, the compiler always loads the function's address into a register, and calls indirect through the pointer.

-mno-ep

-mep

Do not optimize (do optimize) basic blocks that use the same index pointer 4 or more times to copy pointer into the ep register, and use the shorter sld and sst instructions. The **-mep** option is on by default if you optimize.

-mno-prolog-function

-mprolog-function

Do not use (do use) external functions to save and restore registers at the prologue and epilogue of a function. The external functions are slower, but use less code space if more than one function saves the same number of registers. The **-mprolog-function** option is on by default if you optimize.

-mspace

Try to make the code as small as possible. At present, this just turns on the **-mep** and **-mprolog-function** options.

-mtda=n

Put static or global variables whose size is n bytes or less into the tiny data area that register ep points to. The tiny data area can hold up to 256 bytes in total (128 bytes for byte references).

-msda=n

Put static or global variables whose size is n bytes or less into the small data area that register gp points to. The small data area can hold up to 64 kilobytes.

-mzda=n

Put static or global variables whose size is *n* bytes or less into the first 32 kilobytes of memory.

-mv850

Specify that the target processor is the V850.

-mv850e3v5

Specify that the target processor is the V850E3V5. The preprocessor constant __v850e3v5__ is defined if this option is used.

-mv850e2v4

Specify that the target processor is the V850E3V5. This is an alias for the -mv850e3v5 option.

-mv850e2v3

Specify that the target processor is the V850E2V3. The preprocessor constant __v850e2v3__ is defined if this option is used.

-mv850e2

Specify that the target processor is the V850E2. The preprocessor constant __v850e2__ is defined if this option is used.

-mv850e1

Specify that the target processor is the V850E1. The preprocessor constants __v850e1_ and __v850e_ are defined if this option is used.

-mv850es

Specify that the target processor is the V850ES. This is an alias for the -mv850e1 option.

-mv850e

Specify that the target processor is the V850E. The preprocessor constant __v850e__ is defined if this option is used.

If neither -mv850 nor -mv850e nor -mv850e1 nor -mv850e2 nor -mv850e2v3 nor -mv850e3v5 are defined then a default target processor is chosen and the relevant __v850*__ preprocessor

constant is defined.

The preprocessor constants __v850 and __v851__ are always defined, regardless of which processor variant is the target.

-mdisable-callt

-mno-disable-callt

This option suppresses generation of the CALLT instruction for the v850e, v850e1, v850e2, v850e2v3 and v850e3v5 flavors of the v850 architecture.

This option is enabled by default when the RH850 ABI is in use (see **-mrh850-abi**), and disabled by default when the GCC ABI is in use. If CALLT instructions are being generated then the C preprocessor symbol __V850_CALLT__ will be defined.

-mrelax

-mno-relax

Pass on (or do not pass on) the -mrelax command line option to the assembler.

-mlong-jumps

-mno-long-jumps

Disable (or re-enable) the generation of PC-relative jump instructions.

-msoft-float

-mhard-float

Disable (or re-enable) the generation of hardware floating point instructions. This option is only significant when the target architecture is **V850E2V3** or higher. If hardware floating point instructions are being generated then the C preprocessor symbol __FPU_OK__ will be defined, otherwise the symbol __NO_FPU__ will be defined.

-mloop

Enables the use of the e3v5 LOOP instruction. The use of this instruction is not enabled by default when the e3v5 architecture is selected because its use is still experimental.

-mrh850-abi

-mghs

Enables support for the RH850 version of the V850 ABI. This is the default. With this version of the ABI the following rules apply:

- Integer sized structures and unions are returned via a memory pointer rather than a register.
- Large structures and unions (more than 8 bytes in size) are passed by value.
- Functions are aligned to 16-bit boundaries.
- The **-m8byte-align** command line option is supported.
- The -mdisable-callt command line option is enabled by default. The -mno-disable-callt command line option is not supported.

When this version of the ABI is enabled the C preprocessor symbol __V850_RH850_ABI__ is defined.

-mgcc-abi

Enables support for the old GCC version of the V850 ABI. With this version of the ABI the following rules apply:

- Integer sized structures and unions are returned in register r10.
- Large structures and unions (more than 8 bytes in size) are passed by reference.
- Functions are aligned to 32-bit boundaries, unless optimizing for size.
- The **-m8byte-align** command line option is not supported.
- The -mdisable-callt command line option is supported but not enabled by default.

When this version of the ABI is enabled the C preprocessor symbol __V850_GCC_ABI__ is

defined.

-m8byte-align

-mno-8byte-align

Enables support for doubles and long long types to be aligned on 8-byte boundaries. The default is to restrict the alignment of all objects to at most 4-bytes. When **-m8byte-align** is in effect the C preprocessor symbol __V850_8BYTE_ALIGN__ will be defined.

-mbig-switch

Generate code suitable for big switch tables. Use this option only if the assembler/linker complain about out of range branches within a switch table.

-mapp-regs

This option causes r2 and r5 to be used in the code generated by the compiler. This setting is the default.

-mno-app-regs

This option causes r2 and r5 to be treated as fixed registers.

VAX Options

These -m options are defined for the VAX:

-munix

Do not output certain jump instructions (aobleq and so on) that the Unix assembler for the VAX cannot handle across long ranges.

-mgnu

Do output those jump instructions, on the assumption that the GNU assembler is being used.

-mg

Output code for G-format floating-point numbers instead of D-format.

VMS Options

These -m options are defined for the VMS implementations:

-mvms-return-codes

Return VMS condition codes from main. The default is to return POSIX-style condition (e.g. error) codes.

-mdebug-main=prefix

Flag the first routine whose name starts with *prefix* as the main routine for the debugger.

-mmalloc64

Default to 64-bit memory allocation routines.

-mpointer-size=size

Set the default size of pointers. Possible options for *size* are **32** or **short** for 32 bit pointers, **64** or **long** for 64 bit pointers, and **no** for supporting only 32 bit pointers. The later option disables pragma pointer_size.

VxWorks Options

The options in this section are defined for all VxWorks targets. Options specific to the target hardware are listed with the other options for that target.

-mrtp

GCC can generate code for both VxWorks kernels and real time processes (RTPs). This option switches from the former to the latter. It also defines the preprocessor macro __RTP__.

-non-static

Link an RTP executable against shared libraries rather than static libraries. The options **-static** and **-shared** can also be used for RTPs; **-static** is the default.

-Bstatic

-Bdvnamic

These options are passed down to the linker. They are defined for compatibility with Diab.

-Xbind-lazy

Enable lazy binding of function calls. This option is equivalent to **-Wl,-z,now** and is defined for compatibility with Diab.

-Xbind-now

Disable lazy binding of function calls. This option is the default and is defined for compatibility with Diab.

x86-64 Options

These are listed under

Xstormy16 Options

These options are defined for Xstormy16:

-msim

Choose startup files and linker script suitable for the simulator.

Xtensa Options

These options are supported for Xtensa targets:

-mconst16

-mno-const16

Enable or disable use of CONST16 instructions for loading constant values. The CONST16 instruction is currently not a standard option from Tensilica. When enabled, CONST16 instructions are always used in place of the standard L32R instructions. The use of CONST16 is enabled by default only if the L32R instruction is not available.

-mfused-madd

-mno-fused-madd

Enable or disable use of fused multiply/add and multiply/subtract instructions in the floating-point option. This has no effect if the floating-point option is not also enabled. Disabling fused multiply/add and multiply/subtract instructions forces the compiler to use separate instructions for the multiply and add/subtract operations. This may be desirable in some cases where strict IEEE 754–compliant results are required: the fused multiply add/subtract instructions do not round the intermediate result, thereby producing results with *more* bits of precision than specified by the IEEE standard. Disabling fused multiply add/subtract instructions also ensures that the program output is not sensitive to the compiler's ability to combine multiply and add/subtract operations.

-mserialize-volatile

-mno-serialize-volatile

When this option is enabled, GCC inserts MEMW instructions before volatile memory references to guarantee sequential consistency. The default is **-mserialize-volatile**. Use **-mno-serialize-volatile** to omit the MEMW instructions.

-mforce-no-pic

For targets, like GNU/Linux, where all user-mode Xtensa code must be position-independent code (PIC), this option disables PIC for compiling kernel code.

-mtext-section-literals

-mno-text-section-literals

Control the treatment of literal pools. The default is **-mno-text-section-literals**, which places literals in a separate section in the output file. This allows the literal pool to be placed in a data RAM/ROM, and it also allows the linker to combine literal pools from separate object files to remove redundant literals and improve code size. With **-mtext-section-literals**, the literals are interspersed in the text section in order to keep them as close as possible to their references. This may be necessary for large assembly files.

-mtarget-align

-mno-target-align

When this option is enabled, GCC instructs the assembler to automatically align instructions to reduce branch penalties at the expense of some code density. The assembler attempts to widen density instructions to align branch targets and the instructions following call instructions. If there are not enough preceding safe density instructions to align a target, no widening is performed. The default is **-mtarget-align**. These options do not affect the treatment of auto-aligned instructions like LOOP, which the assembler always aligns, either by widening density instructions or by inserting NOP instructions.

-mlongcalls

-mno-longcalls

When this option is enabled, GCC instructs the assembler to translate direct calls to indirect calls unless it can determine that the target of a direct call is in the range allowed by the call instruction. This translation typically occurs for calls to functions in other source files. Specifically, the assembler translates a direct CALL instruction into an L32R followed by a CALLX instruction. The default is **-mno-longcalls**. This option should be used in programs where the call target can potentially be out of range. This option is implemented in the assembler, not the compiler, so the assembly code generated by GCC still shows direct call instructions——look at the disassembled object code to see the actual instructions. Note that the assembler uses an indirect call for every cross-file call, not just those that really are out of range.

zSeries Options

These are listed under

Options for Code Generation Conventions

These machine-independent options control the interface conventions used in code generation.

Most of them have both positive and negative forms; the negative form of **-ffoo** is **-fno-foo**. In the table below, only one of the forms is listed——the one that is not the default. You can figure out the other form by either removing **no**— or adding it.

-fbounds-check

For front ends that support it, generate additional code to check that indices used to access arrays are within the declared range. This is currently only supported by the Java and Fortran front ends, where this option defaults to true and false respectively.

-fstack-reuse=reuse-level

This option controls stack space reuse for user declared local/auto variables and compiler generated temporaries. *reuse_level* can be **all**, **named_vars**, or **none**. **all** enables stack reuse for all local variables and temporaries, **named_vars** enables the reuse only for user defined local variables with names, and **none** disables stack reuse completely. The default value is **all**. The option is needed when the program extends the lifetime of a scoped local variable or a compiler generated temporary beyond the end point defined by the language. When a lifetime of a variable ends, and if the variable lives in memory, the optimizing compiler has the freedom to reuse its stack space with other temporaries or scoped local variables whose live range does not overlap with it. Legacy code extending local lifetime will likely to break with the stack reuse optimization.

For example,

```
int *p;
{
   int local1;

   p = &local1;
   local1 = 10;
   ....
}
```

int local2;

void bar()

{

A a(20);

foo(A(10)); // temp object's lifetime ends when foo returns

ap->i+= 10; // ap references out of scope temp whose space

// is reused with a. What is the value of ap->i?

The lifetime of a compiler generated temporary is well defined by the C++ standard. When a lifetime of a temporary ends, and if the temporary lives in memory, the optimizing compiler has the freedom to reuse its stack space with other temporaries or scoped local variables whose live range does not overlap with it. However some of the legacy code relies on the behavior of older compilers in which temporaries' stack space is not reused, the aggressive stack reuse can lead to runtime errors. This option is used to control the temporary stack reuse optimization.

-ftrapv

This option generates traps for signed overflow on addition, subtraction, multiplication operations.

-fwrapv

This option instructs the compiler to assume that signed arithmetic overflow of addition, subtraction and multiplication wraps around using twos-complement representation. This flag enables some optimizations and disables others. This option is enabled by default for the Java front end, as required by the Java language specification.

-fexceptions

Enable exception handling. Generates extra code needed to propagate exceptions. For some targets, this implies GCC generates frame unwind information for all functions, which can produce significant data size overhead, although it does not affect execution. If you do not specify this option, GCC

enables it by default for languages like C++ that normally require exception handling, and disables it for languages like C that do not normally require it. However, you may need to enable this option when compiling C code that needs to interoperate properly with exception handlers written in C++. You may also wish to disable this option if you are compiling older C++ programs that don't use exception handling.

-fnon-call-exceptions

Generate code that allows trapping instructions to throw exceptions. Note that this requires platform-specific runtime support that does not exist everywhere. Moreover, it only allows *trapping* instructions to throw exceptions, i.e. memory references or floating-point instructions. It does not allow exceptions to be thrown from arbitrary signal handlers such as SIGALRM.

-fdelete-dead-exceptions

Consider that instructions that may throw exceptions but don't otherwise contribute to the execution of the program can be optimized away. This option is enabled by default for the Ada front end, as permitted by the Ada language specification. Optimization passes that cause dead exceptions to be removed are enabled independently at different optimization levels.

-funwind-tables

Similar to **–fexceptions**, except that it just generates any needed static data, but does not affect the generated code in any other way. You normally do not need to enable this option; instead, a language processor that needs this handling enables it on your behalf.

-fasynchronous-unwind-tables

Generate unwind table in DWARF 2 format, if supported by target machine. The table is exact at each instruction boundary, so it can be used for stack unwinding from asynchronous events (such as debugger or garbage collector).

-fno-gnu-unique

On systems with recent GNU assembler and C library, the C++ compiler uses the STB_GNU_UNIQUE binding to make sure that definitions of template static data members and static local variables in inline functions are unique even in the presence of RTLD_LOCAL; this is necessary to avoid problems with a library used by two different RTLD_LOCAL plugins depending on a definition in one of them and therefore disagreeing with the other one about the binding of the symbol. But this causes dlclose to be ignored for affected DSOs; if your program relies on reinitialization of a DSO via dlclose and dlopen, you can use -fno-gnu-unique.

-fpcc-struct-return

Return "short" struct and union values in memory like longer ones, rather than in registers. This convention is less efficient, but it has the advantage of allowing intercallability between GCC-compiled files and files compiled with other compilers, particularly the Portable C Compiler (pcc).

The precise convention for returning structures in memory depends on the target configuration macros.

Short structures and unions are those whose size and alignment match that of some integer type.

Warning: code compiled with the **-fpcc-struct-return** switch is not binary compatible with code compiled with the **-freg-struct-return** switch. Use it to conform to a non-default application binary interface.

-freg-struct-return

Return struct and union values in registers when possible. This is more efficient for small structures than **-fpcc-struct-return**.

If you specify neither **-fpcc-struct-return** nor **-freg-struct-return**, GCC defaults to whichever convention is standard for the target. If there is no standard convention, GCC defaults to **-fpcc-struct-return**, except on targets where GCC is the principal compiler. In those cases, we can choose the standard, and we chose the more efficient register return alternative.

Warning: code compiled with the **-freg-struct-return** switch is not binary compatible with code compiled with the **-fpcc-struct-return** switch. Use it to conform to a non-default application binary

interface.

-fshort-enums

Allocate to an enum type only as many bytes as it needs for the declared range of possible values. Specifically, the enum type is equivalent to the smallest integer type that has enough room.

Warning: the **–fshort–enums** switch causes GCC to generate code that is not binary compatible with code generated without that switch. Use it to conform to a non-default application binary interface.

-fshort-double

Use the same size for double as for float.

Warning: the **-fshort-double** switch causes GCC to generate code that is not binary compatible with code generated without that switch. Use it to conform to a non-default application binary interface.

-fshort-wchar

Override the underlying type for **wchar_t** to be **short unsigned int** instead of the default for the target. This option is useful for building programs to run under WINE.

Warning: the **-fshort-wchar** switch causes GCC to generate code that is not binary compatible with code generated without that switch. Use it to conform to a non-default application binary interface.

-fno-common

In C code, controls the placement of uninitialized global variables. Unix C compilers have traditionally permitted multiple definitions of such variables in different compilation units by placing the variables in a common block. This is the behavior specified by **–fcommon**, and is the default for GCC on most targets. On the other hand, this behavior is not required by ISO C, and on some targets may carry a speed or code size penalty on variable references. The **–fno–common** option specifies that the compiler should place uninitialized global variables in the data section of the object file, rather than generating them as common blocks. This has the effect that if the same variable is declared (without extern) in two different compilations, you get a multiple-definition error when you link them. In this case, you must compile with **–fcommon** instead. Compiling with **–fno–common** is useful on targets for which it provides better performance, or if you wish to verify that the program will work on other systems that always treat uninitialized variable declarations this way.

-fno-ident

Ignore the #ident directive.

-finhibit-size-directive

Don't output a .size assembler directive, or anything else that would cause trouble if the function is split in the middle, and the two halves are placed at locations far apart in memory. This option is used when compiling *crtstuff.c*; you should not need to use it for anything else.

-fverbose-asm

Put extra commentary information in the generated assembly code to make it more readable. This option is generally only of use to those who actually need to read the generated assembly code (perhaps while debugging the compiler itself).

-fno-verbose-asm, the default, causes the extra information to be omitted and is useful when comparing two assembler files.

-frecord-gcc-switches

This switch causes the command line used to invoke the compiler to be recorded into the object file that is being created. This switch is only implemented on some targets and the exact format of the recording is target and binary file format dependent, but it usually takes the form of a section containing ASCII text. This switch is related to the **-fverbose-asm** switch, but that switch only records information in the assembler output file as comments, so it never reaches the object file. See also **-grecord-gcc-switches** for another way of storing compiler options into the object file.

-fpic

Generate position-independent code (PIC) suitable for use in a shared library, if supported for the target machine. Such code accesses all constant addresses through a global offset table (GOT). The

dynamic loader resolves the GOT entries when the program starts (the dynamic loader is not part of GCC; it is part of the operating system). If the GOT size for the linked executable exceeds a machine-specific maximum size, you get an error message from the linker indicating that **-fpic** does not work; in that case, recompile with **-fPIC** instead. (These maximums are 8k on the SPARC and 32k on the m68k and RS/6000. The 386 has no such limit.)

Position-independent code requires special support, and therefore works only on certain machines. For the 386, GCC supports PIC for System V but not for the Sun 386i. Code generated for the IBM RS/6000 is always position-independent.

When this flag is set, the macros __pic__ and __PIC__ are defined to 1.

-fPIC

If supported for the target machine, emit position-independent code, suitable for dynamic linking and avoiding any limit on the size of the global offset table. This option makes a difference on the m68k, PowerPC and SPARC.

Position-independent code requires special support, and therefore works only on certain machines.

When this flag is set, the macros __pic__ and __PIC__ are defined to 2.

-fpie

-fPIE

These options are similar to **-fpic** and **-fPIC**, but generated position independent code can be only linked into executables. Usually these options are used when **-pie** GCC option is used during linking.

-fpie and -fPIE both define the macros __pie__ and __PIE__. The macros have the value 1 for -fpie and 2 for -fPIE.

-fno-jump-tables

Do not use jump tables for switch statements even where it would be more efficient than other code generation strategies. This option is of use in conjunction with **-fpic** or **-fPIC** for building code that forms part of a dynamic linker and cannot reference the address of a jump table. On some targets, jump tables do not require a GOT and this option is not needed.

-ffixed-reg

Treat the register named *reg* as a fixed register; generated code should never refer to it (except perhaps as a stack pointer, frame pointer or in some other fixed role).

reg must be the name of a register. The register names accepted are machine-specific and are defined in the REGISTER_NAMES macro in the machine description macro file.

This flag does not have a negative form, because it specifies a three-way choice.

-fcall-used-reg

Treat the register named *reg* as an allocable register that is clobbered by function calls. It may be allocated for temporaries or variables that do not live across a call. Functions compiled this way do not save and restore the register *reg*.

It is an error to use this flag with the frame pointer or stack pointer. Use of this flag for other registers that have fixed pervasive roles in the machine's execution model produces disastrous results.

This flag does not have a negative form, because it specifies a three-way choice.

-fcall-saved-reg

Treat the register named *reg* as an allocable register saved by functions. It may be allocated even for temporaries or variables that live across a call. Functions compiled this way save and restore the register *reg* if they use it.

It is an error to use this flag with the frame pointer or stack pointer. Use of this flag for other registers that have fixed pervasive roles in the machine's execution model produces disastrous results.

A different sort of disaster results from the use of this flag for a register in which function values may be returned.

This flag does not have a negative form, because it specifies a three-way choice.

-fpack-struct[=n]

Without a value specified, pack all structure members together without holes. When a value is specified (which must be a small power of two), pack structure members according to this value, representing the maximum alignment (that is, objects with default alignment requirements larger than this are output potentially unaligned at the next fitting location.

Warning: the **-fpack-struct** switch causes GCC to generate code that is not binary compatible with code generated without that switch. Additionally, it makes the code suboptimal. Use it to conform to a non-default application binary interface.

-finstrument-functions

Generate instrumentation calls for entry and exit to functions. Just after function entry and just before function exit, the following profiling functions are called with the address of the current function and its call site. (On some platforms, __builtin_return_address does not work beyond the current function, so the call site information may not be available to the profiling functions otherwise.)

The first argument is the address of the start of the current function, which may be looked up exactly in the symbol table.

This instrumentation is also done for functions expanded inline in other functions. The profiling calls indicate where, conceptually, the inline function is entered and exited. This means that addressable versions of such functions must be available. If all your uses of a function are expanded inline, this may mean an additional expansion of code size. If you use **extern inline** in your C code, an addressable version of such functions must be provided. (This is normally the case anyway, but if you get lucky and the optimizer always expands the functions inline, you might have gotten away without providing static copies.)

A function may be given the attribute no_instrument_function, in which case this instrumentation is not done. This can be used, for example, for the profiling functions listed above, high-priority interrupt routines, and any functions from which the profiling functions cannot safely be called (perhaps signal handlers, if the profiling routines generate output or allocate memory).

-finstrument-functions-exclude-file-list=file,file,...

Set the list of functions that are excluded from instrumentation (see the description of -finstrument-functions). If the file that contains a function definition matches with one of *file*, then that function is not instrumented. The match is done on substrings: if the *file* parameter is a substring of the file name, it is considered to be a match.

For example:

```
-finstrument-functions-exclude-file-list=/bits/stl,include/sys
```

excludes any inline function defined in files whose pathnames contain /bits/stl or include/sys.

If, for some reason, you want to include letter ',' in one of *sym*, write ','. For example, -finstrument-functions-exclude-file-list=',,tmp' (note the single quote surrounding the option).

-finstrument-functions-exclude-function-list=sym,sym,...

This is similar to -finstrument-functions-exclude-file-list, but this option sets the list of function names to be excluded from instrumentation. The function name to be matched is its user-visible name, such as vector<int> blah(const vector<int> &), not the internal mangled name (e.g., _Z4blahRSt6vectorIiSaIiEE). The match is done on substrings: if the

sym parameter is a substring of the function name, it is considered to be a match. For C99 and C++ extended identifiers, the function name must be given in UTF-8, not using universal character names.

-fstack-check

Generate code to verify that you do not go beyond the boundary of the stack. You should specify this flag if you are running in an environment with multiple threads, but you only rarely need to specify it in a single-threaded environment since stack overflow is automatically detected on nearly all systems if there is only one stack.

Note that this switch does not actually cause checking to be done; the operating system or the language runtime must do that. The switch causes generation of code to ensure that they see the stack being extended.

You can additionally specify a string parameter: no means no checking, generic means force the use of old-style checking, specific means use the best checking method and is equivalent to bare **-fstack-check**.

Old-style checking is a generic mechanism that requires no specific target support in the compiler but comes with the following drawbacks:

- Modified allocation strategy for large objects: they are always allocated dynamically if their size exceeds a fixed threshold.
- 2. Fixed limit on the size of the static frame of functions: when it is topped by a particular function, stack checking is not reliable and a warning is issued by the compiler.
- 3. Inefficiency: because of both the modified allocation strategy and the generic implementation, code performance is hampered.

Note that old-style stack checking is also the fallback method for specific if no target support has been added in the compiler.

-fstack-limit-register=reg

-fstack-limit-symbol=sym

-fno-stack-limit

Generate code to ensure that the stack does not grow beyond a certain value, either the value of a register or the address of a symbol. If a larger stack is required, a signal is raised at run time. For most targets, the signal is raised before the stack overruns the boundary, so it is possible to catch the signal without taking special precautions.

For instance, if the stack starts at absolute address **0x80000000** and grows downwards, you can use the flags **-fstack-limit-symbol=__stack_limit** and **-Wl,--defsym,__stack_limit=0x7ffe0000** to enforce a stack limit of 128KB. Note that this may only work with the GNU linker.

-fsplit-stack

Generate code to automatically split the stack before it overflows. The resulting program has a discontiguous stack which can only overflow if the program is unable to allocate any more memory. This is most useful when running threaded programs, as it is no longer necessary to calculate a good stack size to use for each thread. This is currently only implemented for the i386 and x86_64 back ends running GNU/Linux.

When code compiled with **-fsplit-stack** calls code compiled without **-fsplit-stack**, there may not be much stack space available for the latter code to run. If compiling all code, including library code, with **-fsplit-stack** is not an option, then the linker can fix up these calls so that the code compiled without **-fsplit-stack** always has a large stack. Support for this is implemented in the gold linker in GNU binutils release 2.21 and later.

-fleading-underscore

This option and its counterpart, **-fno-leading-underscore**, forcibly change the way C symbols are represented in the object file. One use is to help link with legacy assembly code.

Warning: the -fleading-underscore switch causes GCC to generate code that is not binary

compatible with code generated without that switch. Use it to conform to a non-default application binary interface. Not all targets provide complete support for this switch.

-ftls-model=model

Alter the thread-local storage model to be used. The *model* argument should be one of global-dynamic, local-dynamic, initial-exec or local-exec.

The default without **-fpic** is initial-exec; with **-fpic** the default is global-dynamic.

-fvisibility=default/internal/hidden/protected

Set the default ELF image symbol visibility to the specified option——all symbols are marked with this unless overridden within the code. Using this feature can very substantially improve linking and load times of shared object libraries, produce more optimized code, provide near-perfect API export and prevent symbol clashes. It is **strongly** recommended that you use this in any shared objects you distribute.

Despite the nomenclature, default always means public; i.e., available to be linked against from outside the shared object. protected and internal are pretty useless in real-world usage so the only other commonly used option is hidden. The default if **-fvisibility** isn't specified is default, i.e., make every symbol public——this causes the same behavior as previous versions of GCC.

A good explanation of the benefits offered by ensuring ELF symbols have the correct visibility is given by "How To Write Shared Libraries" by Ulrich Drepper (which can be found at http://people.redhat.com/~drepper/)——however a superior solution made possible by this option to marking things hidden when the default is public is to make the default hidden and mark things public. This is the norm with DLLs on Windows and with -fvisibility=hidden and __attribute__ ((visibility("default"))) instead of __declspec(dllexport) you get almost identical semantics with identical syntax. This is a great boon to those working with cross-platform projects.

For those adding visibility support to existing code, you may find **#pragma GCC visibility** of use. This works by you enclosing the declarations you wish to set visibility for with (for example) **#pragma GCC visibility push(hidden)** and **#pragma GCC visibility pop**. Bear in mind that symbol visibility should be viewed **as part of the API interface contract** and thus all new code should always specify visibility when it is not the default; i.e., declarations only for use within the local DSO should **always** be marked explicitly as hidden as so to avoid PLT indirection overheads——making this abundantly clear also aids readability and self-documentation of the code. Note that due to ISO C++ specification requirements, operator new and operator delete must always be of default visibility.

Be aware that headers from outside your project, in particular system headers and headers from any other library you use, may not be expecting to be compiled with visibility other than the default. You may need to explicitly say **#pragma GCC visibility push(default)** before including any such headers.

extern declarations are not affected by -fvisibility, so a lot of code can be recompiled with -fvisibility-hidden with no modifications. However, this means that calls to extern functions with no explicit visibility use the PLT, so it is more effective to use __attribute ((visibility)) and/or #pragma GCC visibility to tell the compiler which extern declarations should be treated as hidden.

Note that **-fvisibility** does affect C⁺⁺ vague linkage entities. This means that, for instance, an exception class that is be thrown between DSOs must be explicitly marked with default visibility so that the **type_info** nodes are unified between the DSOs.

An overview of these techniques, their benefits and how to use them is at http://gcc.gnu.org/wiki/Visibility>.

-fstrict-volatile-bitfields

This option should be used if accesses to volatile bit-fields (or other structure fields, although the compiler usually honors those types anyway) should use a single access of the width of the field's type, aligned to a natural alignment if possible. For example, targets with memory-mapped peripheral registers might require all such accesses to be 16 bits wide; with this flag you can declare all peripheral bit-fields as unsigned short (assuming short is 16 bits on these targets) to force GCC to use 16-bit accesses instead of, perhaps, a more efficient 32-bit access.

If this option is disabled, the compiler uses the most efficient instruction. In the previous example, that

gcc-4.8 2015-06-23 230

might be a 32-bit load instruction, even though that accesses bytes that do not contain any portion of the bit-field, or memory-mapped registers unrelated to the one being updated.

If the target requires strict alignment, and honoring the field type would require violating this alignment, a warning is issued. If the field has packed attribute, the access is done without honoring the field type. If the field doesn't have packed attribute, the access is done honoring the field type. In both cases, GCC assumes that the user knows something about the target hardware that it is unaware of.

The default value of this option is determined by the application binary interface for the target processor.

-fsync-libcalls

This option controls whether any out-of-line instance of the __sync family of functions may be used to implement the C+11 __atomic family of functions.

The default value of this option is enabled, thus the only useful form of the option is **-fno-sync-libcalls**. This option is used in the implementation of the *libatomic* runtime library.

ENVIRONMENT

This section describes several environment variables that affect how GCC operates. Some of them work by specifying directories or prefixes to use when searching for various kinds of files. Some are used to specify other aspects of the compilation environment.

Note that you can also specify places to search using options such as $-\mathbf{B}$, $-\mathbf{I}$ and $-\mathbf{L}$. These take precedence over places specified using environment variables, which in turn take precedence over those specified by the configuration of GCC.

LANG

LC CTYPE

LC MESSAGES

LC_ALL

These environment variables control the way that GCC uses localization information which allows GCC to work with different national conventions. GCC inspects the locale categories **LC_CTYPE** and **LC_MESSAGES** if it has been configured to do so. These locale categories can be set to any value supported by your installation. A typical value is **en_GB.UTF-8** for English in the United Kingdom encoded in UTF-8.

The LC_CTYPE environment variable specifies character classification. GCC uses it to determine the character boundaries in a string; this is needed for some multibyte encodings that contain quote and escape characters that are otherwise interpreted as a string end or escape.

The LC_MESSAGES environment variable specifies the language to use in diagnostic messages.

If the LC_ALL environment variable is set, it overrides the value of LC_CTYPE and LC_MESSAGES; otherwise, LC_CTYPE and LC_MESSAGES default to the value of the LANG environment variable. If none of these variables are set, GCC defaults to traditional C English behavior.

TMPDIR

If **TMPDIR** is set, it specifies the directory to use for temporary files. GCC uses temporary files to hold the output of one stage of compilation which is to be used as input to the next stage: for example, the output of the preprocessor, which is the input to the compiler proper.

GCC COMPARE DEBUG

Setting GCC_COMPARE_DEBUG is nearly equivalent to passing **-fcompare-debug** to the compiler driver. See the documentation of this option for more details.

GCC_EXEC_PREFIX

If GCC_EXEC_PREFIX is set, it specifies a prefix to use in the names of the subprograms executed by the compiler. No slash is added when this prefix is combined with the name of a subprogram, but you can specify a prefix that ends with a slash if you wish.

If GCC_EXEC_PREFIX is not set, GCC attempts to figure out an appropriate prefix to use based on the

pathname it is invoked with.

If GCC cannot find the subprogram using the specified prefix, it tries looking in the usual places for the subprogram.

The default value of GCC_EXEC_PREFIX is *prefix/lib/gcc/* where *prefix* is the prefix to the installed compiler. In many cases *prefix* is the value of prefix when you ran the *configure* script.

Other prefixes specified with -B take precedence over this prefix.

This prefix is also used for finding files such as crt0.0 that are used for linking.

In addition, the prefix is used in an unusual way in finding the directories to search for header files. For each of the standard directories whose name normally begins with /usr/local/lib/gcc (more precisely, with the value of GCC_INCLUDE_DIR), GCC tries replacing that beginning with the specified prefix to produce an alternate directory name. Thus, with -Bfoo/, GCC searches foo/bar just before it searches the standard directory /usr/local/lib/bar. If a standard directory begins with the configured prefix then the value of prefix is replaced by GCC_EXEC_PREFIX when looking for header files.

COMPILER PATH

The value of **COMPILER_PATH** is a colon-separated list of directories, much like **PATH**. GCC tries the directories thus specified when searching for subprograms, if it can't find the subprograms using **GCC_EXEC_PREFIX**.

LIBRARY_PATH

The value of **LIBRARY_PATH** is a colon-separated list of directories, much like **PATH**. When configured as a native compiler, GCC tries the directories thus specified when searching for special linker files, if it can't find them using **GCC_EXEC_PREFIX**. Linking using GCC also uses these directories when searching for ordinary libraries for the **–l** option (but directories specified with **–L** come first).

LANG

This variable is used to pass locale information to the compiler. One way in which this information is used is to determine the character set to be used when character literals, string literals and comments are parsed in C and C++. When the compiler is configured to allow multibyte characters, the following values for LANG are recognized:

C-JIS

Recognize JIS characters.

C-SJIS

Recognize SJIS characters.

C-EUCJP

Recognize EUCJP characters.

If LANG is not defined, or if it has some other value, then the compiler uses mblen and mbtowc as defined by the default locale to recognize and translate multibyte characters.

Some additional environment variables affect the behavior of the preprocessor.

CPATH

C INCLUDE PATH

CPLUS_INCLUDE_PATH

OBJC_INCLUDE_PATH

Each variable's value is a list of directories separated by a special character, much like **PATH**, in which to look for header files. The special character, PATH_SEPARATOR, is target-dependent and determined at GCC build time. For Microsoft Windows-based targets it is a semicolon, and for almost all other targets it is a colon.

CPATH specifies a list of directories to be searched as if specified with $-\mathbf{I}$, but after any paths given with $-\mathbf{I}$ options on the command line. This environment variable is used regardless of which language

is being preprocessed.

The remaining environment variables apply only when preprocessing the particular language indicated. Each specifies a list of directories to be searched as if specified with **-isystem**, but after any paths given with **-isystem** options on the command line.

In all these variables, an empty element instructs the compiler to search its current working directory. Empty elements can appear at the beginning or end of a path. For instance, if the value of **CPATH** is :/special/include, that has the same effect as -I. -I/special/include.

DEPENDENCIES_OUTPUT

If this variable is set, its value specifies how to output dependencies for Make based on the non-system header files processed by the compiler. System header files are ignored in the dependency output.

The value of **DEPENDENCIES_OUTPUT** can be just a file name, in which case the Make rules are written to that file, guessing the target name from the source file name. Or the value can have the form *file target*, in which case the rules are written to file *file* using *target* as the target name.

In other words, this environment variable is equivalent to combining the options **–MM** and **–MF**, with an optional **–MT** switch too.

SUNPRO_DEPENDENCIES

This variable is the same as **DEPENDENCIES_OUTPUT** (see above), except that system header files are not ignored, so it implies **–M** rather than **–MM**. However, the dependence on the main input file is omitted.

BUGS

For instructions on reporting bugs, see <file:///usr/share/doc/gcc-4.8/README.Bugs>.

FOOTNOTES

On some systems, gcc -shared needs to build supplementary stub code for constructors to work. On
multi-libbed systems, gcc -shared must select the correct support libraries to link against. Failing to
supply the correct flags may lead to subtle defects. Supplying them in cases where they are not
necessary is innocuous.

SEE ALSO

gpl(7), gfdl(7), fsf—funding (7), cpp(1), gcov(1), as(1), ld(1), gdb(1), adb(1), dbx(1), sdb(1) and the Info entries for gcc, cpp, as, ld, binutils and gdb.

AUTHOR

See the Info entry for **gcc**, or http://gcc.gnu.org/onlinedocs/gcc/Contributors.html, for contributors to GCC.

COPYRIGHT

Copyright (c) 1988–2015 Free Software Foundation, Inc.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with the Invariant Sections being "GNU General Public License" and "Funding Free Software", the Front-Cover texts being (a) (see below), and with the Back-Cover Texts being (b) (see below). A copy of the license is included in the *gfdl* (7) man page.

(a) The FSF's Front-Cover Text is:

A GNU Manual

(b) The FSF's Back-Cover Text is:

You have freedom to copy and modify this GNU Manual, like GNU software. Copies published by the Free Software Foundation raise funds for GNU development.