How To install Nexus on Ubuntu 12.04

Version 1.4

How To install Nexus on Ubuntu 12.04	1
1 Tutorial installing Nexus on Server – Step by Step:	3
1.1 Prerequisiti – Installare java jdk per NEXUS	3
1.1.1 Download and install JDK	3
2 Nexus	5
2.1 Prerequisiti Nexus – Add user with minor privilege to Ubuntu system.	5
2.2 Download and Install Nexus:	5
2.1.1 Permessi e privilegi:	6
2.3 Configurazione	7
2.4 Using Services	9
Starting a Service	9
Stopping a Service	9
Getting a list of Services	9
Adding a Service to Default runlevels	9
2.4.1 Using service NEXUS	9
Configure security	11

1 Tutorial installing Nexus on Server - Step by Step:

1.1 Prerequisiti - Installare java jdk per NEXUS

Nexus Open Source and Nexus Professional only have one prerequisite, a Java Runtime Environment (JRE).

1.1.1 Download and install JDK

Linux x64 per ubuntu 64bit file tar.gz

Download the latest SUN JDK

http://www.oracle.com/technetwork/java/javase/downloads/index.html

Link tutorial di esempio:

http://www.liberiangeek.net/2012/04/install-oracle-java-runtime-jre-7-in-ubuntu-12-04-precise-pangolin/

Extract the tar file

Crea una nuova folder da file system oppure tramite il seguente comando:

```
sudo mkdir -p /usr/lib/jvm
```

oppure stessa cosa: Move the extracted file es jdk1.7.0_51 to the "/usr/lib/jvm/" folder

da terminale con il seguente comando:

```
sudo mv jdk1.7.0_51/usr/lib/jvm/
oppure direttamente da file system
```

Risulterà ad esempio.. /usr/lib/jvm/jdk1.7.0_51

Install SUN JDK 7 in your system:

```
sudo update-alternatives --install /usr/bin/javac javac /usr/lib/jvm/jdk1.7.0_51
/bin/javac 1
sudo update-alternatives --install /usr/bin/java java /usr/lib/jvm/jdk1.7.0_51
/bin/java 1
sudo update-alternatives --install /usr/bin/javaws javaws /usr/lib/jvm/
```

```
jdk1.7.0_51/bin/javaws 1
```

configurazione

```
sudo update-alternatives --config javac
sudo update-alternatives --config java
sudo update-alternatives --config javaws
```

Se è gia installata una versione di java, apparirà la lista delle versioni e verrà richiesto di selezionare il numero di quella da configurare, altrimenti in caso contrario apparirà un messaggio che non c'è nulla da configurare. Vedi screenshot di esempio:

```
There are 2 choices for the alternative java (providing /usr/bin/java).

Selection Path Priority Status

* 0 /usr/lib/jvm/java-6-openjdk/jre/bin/java 1061 auto mode
1 /usr/lib/jvm/java-6-openjdk/jre/bin/java 1061 manual mode
2 /usr/lib/jvm/java-6-sun/jre/bin/java 63 manual mode

Press enter to keep the current choice[*], or type selection number:
```

(Esempio press 2)

Settare le variabili d'ambiente:

Nel file .bashrc sotto /root (View→Show Hidden Files) in the end of file:

```
export JAVA_HOME=/usr/lib/jvm/jdk1.7.0_51
export PATH=.:$JAVA_HOME/bin:$PATH
```

(per casi specifici su profile Set global variables editing file /etc/profile

```
sudo gedit /etc/profile
per gli scripts in /etc/profile.d/
aggiungere le seguenti linee di codice:
export JAVA_HOME = /usr/lib/jvm/jdk1.7.0_51
export PATH = $JAVA_HOME:$PATH
```

to /etc/profile.local That way it will be set for all users)

To test your java digits:

```
java -version
```

Da qui dovrebbe apparire la versione java, se l'installazione è stata effettuata correttamente:

```
java version "1.7.0_51"
Java(TM) SE Runtime Environment (build 1.7.0_51-b13)
Java HotSpot(TM) 64-Bit Server VM (build 24.51-b03, mixed mode)
```

2 Nexus

2.1 Prerequisiti Nexus - Add user with minor privilege to Ubuntu system.

Per partire con l'installazione di Nexus, si consiglia di creare un utente differente da root che abbia permessi di lettura e scrittura per quanto riguarda le directory di nexus su cui si andrà ad operare!

Set the RUN_AS_USER to nexus or any other user with restricted rights that you want to use to run the service. You should not be running Nexus as root.

Avendo seguito la guida dal sito ufficiale di sonatype.com step by step, l'utente l'ho creato dopo gran parte della installazione, siccome nella guida non si accennava a questa cosa se non dopo varie pagine. Così facendo tutti link, folder creati come utente root poi non funzionano e bisogna rifare gran parte dei settaggi perchè il nuovo utente abbia i permessi (Vedi paragrafo sottostante)

Creazione utente

Create a user with sufficient access rights to run the service

Aggiungere un utente di sistema per nexus. As esempio:

```
adduser mynexususername
```

Immetere la pwd che si vuole abbianare a tale utente.

Per spostarsi da root nell' utente mynexususername:

```
su mynexususername
```

per tornare a root exit

2.2 Download and Install Nexus:

Download link:

http://books.sonatype.com/nexus-book/reference/install-sect-downloading.html

Estrarre il file da Ubuntu gnome file system oppure da linea di comando da terminale:

```
$ unzip nexus-2.7.1-01-bundle.zip
```

And, if you download the GZip'd TAR archive, run:

```
$ tar xvzf nexus-2.7.1-01-bundle.tar.gz
```

In modo da averlo scompattato e metterlo in /usr/local/

Oppure con comandi

```
$ sudo cp nexus-2.7.1-01-bundle.tar.gz /usr/local
$ cd /usr/local
$ sudo tar xvzf nexus-2.7.1-01-bundle.tar.gz
```

If you are installing Nexus on a server, you might want to use a directory other than your home directory. On a Unix machine, this book assumes that Nexus is installed in /usr/local/nexus-2.7.1-01 with a symbolic link /usr/local/nexus to the nexus directory. Using a generic symbolic link nexus to a specific version is a common practice which makes it easier to upgrade when a newer version of Nexus is made available.

Non il bumdle ma il contenuto (ci sono due folder una delle due)

Per creare un link simbolico:

```
\ ln -s nexus-2.7.1-01 nexus (in caso si sia sbagliato si può fare per rimuovere il link con unlink nexus )
```

Although it isn't required for Nexus to run, you may want to set an environment variable NEXUS_HOME in your environment which points to the installation directory of Nexus. This chapter will refer to this location as \$NEXUS_HOME.

http://books.sonatype.com/nexus-book/reference/_installing_nexus.html

Con questo settaggio NEXUS HOME sarà /usr/local/nexus

2.1.1 Permessi e privilegi:

Assicurarsi che l'utente creato abbia i permessi di lettura e scrittura nelle folder che vengono utilizzate da nexus. (Change the Owner and Group of your nexus directories)

Per vedere i permessi usare il comando ad esempio:

```
ls -l
```

Per abilitare i permessi:

```
chown -R mynexususername /usr/local/nexus (Nell'esempio l'utente mynexususername vine impostato come nuovo proprietario del file /usr/local/nexus e di tutte le sue sottocartelle in modo ricorsivo.)
```

```
chown -R mynexususername /usr/local/nexus-2.7.1-01-bundle
```

Altro esempio → Imposta l'utente carlo come nuovo proprietario del file /home/roberto/file e gli assegna il gruppo vendite:

2.3 Configurazione

Riporto gli steps di

http://books.sonatype.com/nexus-book/reference/install-sect-service.html# add nexus as a service on ubuntu and debian,

con integrazione perchè non bastano..

- 1. Copy either \$NEXUS_HOME/bin/nexus to /etc/init.d/nexus or create a symlink
- 2. Make the /etc/init.d/nexus script executable -

```
chmod 755 /etc/init.d/nexus
```

- 3. Edit this script changing the following variables:
 - a. Change NEXUS_HOME to the absolute folder location e.g. NEXUS HOME="/usr/local/nexus"
 - b. Set the RUN_AS_USER to nexus or any other user with restricted rights that you want to use to run the service. You should not be running Nexus as root.
 - c. If Java is not on the default path for the user running Nexus, add a JAVA_HOME variable which points to your local Java installation and add a \$JAVA_HOME/bin to the PATH.
 - d. Change PIDDIR to a directory where this user has read/write permissions. In most Linux distributions, /var/run is only writable by root. The properties you need to add to customize the PID file location is "wrapper.pid". For more information about this property and how it would be configured in wrapper.conf, see: http://wrapper.tanukisoftware.com/doc/english/properties.html

Consiglio di vedere un esempio funzionante riportato nella parte sottostante arancione!

Per editare il file, farlo da file system. Oppure con vi o con emacs o gedit command da terminale. Di seguito le modifiche che ho fatto per far funzionare lo script:

```
installation directory.
# NOTE - This will set the user which is used to run the Wrapper as well as
# the JVM and is not useful in situations where a privileged resource or
# port needs to be allocated prior to the user being changed.
#RUN_AS_USER=
#aggiunto
RUN_AS_USER=mynexususername
# Application
APP NAME="nexus"
APP LONG NAME="Nexus OSS"
#Aggiunto
#Set local path to Java
JAVA_HOME=/usr/lib/jvm/jdk1.7.0_51
PATH=$PATH:$JAVA_HOME/bin
#oppure
#JAVA HOME=/usr
#PATH=$PATH:$JAVA HOME/bin
# Priority at which to run the wrapper. See "man nice" for valid priorities.
#aggiunto
# Wrapper
WRAPPER_CMD=$NEXUS_HOME/bin/jsw/$PLATFORM/wrapper
WRAPPER_CONF=$NEXUS_HOME/conf/wrapper.conf
# nice is only used if a priority is specified.
PRIORITY=
# Location of the pid file.
#PIDDIR="."
#for root user
#PIDDIR="/var/run"
#aggiunto per prova
PIDDIR="/usr/local/nexus-2.7.1-01-bundle/sonatype-work/nexus"
# If uncommented, causes the Wrapper to be shutdown using an anchor file.
# When launched with the 'start' command, it will also ignore all INT and
# TERM signals.
#IGNORE SIGNALS=true
# The following two lines are used by the chkconfig command. Change as is
# appropriate for your application. They should remain commented.
# chkconfig: 2345 20 80
# description: Test Wrapper Sample Application
```

IMPORTANT - Make sure that the user has the required privileges to write into the Nexus

2.4 Using Services

Please note that generally, you can use either traditional sysvinit scripts and the methods of working with them as well as the new upstart configs and the command: "service" interchangeably. It is however recommended you use the new upstart methods which are both forward and backward compatible.

Starting a Service

```
# Traditional:
/etc/init.d/myservice start
# Upstart
service myservice start
```

Stopping a Service

```
# Traditional:
/etc/init.d/myservice stop
# Upstart
service myservice stop
```

Getting a list of Services

```
# Traditional:
ls /etc/init.d
# Upstart:
service --status-all
```

Adding a Service to Default runlevels

```
# Traditional
update-rc.d apache2 defaults
```

Upstart: there is no concept of runlevels, everything is event driven with dependencies. You would add an upstart config to /etc/init and potentially source a config file in /etc/default to allow users to override default behaviour.

Tutti i comandi si possono trovare al seguente link: https://help.ubuntu.com/community/UbuntuBootupHowto

2.4.1 Using service NEXUS

Rendere attivo il comando

```
user@computer:/etc/init.d$ sudo update-rc.d mystartupscript defaults
```

Quindi da folder /etc/init.d

```
update-rc.d nexus defaults
```

In caso voleste rifare l'update del comando, bisogna fare:

```
/etc/init.d$ sudo update-rc.d -f nexus remove
/etc/init.d$ sudo update-rc.d nexus defaults
```

Per far partire nexus sempre dalla stessa folder :

```
etc/init.d# service nexus start
Starting Nexus OSS...
Started Nexus OSS.
```

Per vedere i log:

\$ tail -f /usr/local/nexus/logs/wrapper.log

Per visualizzare il servizio di nexus andare da browser al seguente link:

http://localhost:8081/nexus

Per effettuare il login:

the username admin and password admin123 are the credentials of the default Nexus OSS administrator account.

Una volta effettuato il login:

By default, Nexus ships with the following configured proxy repositories:

Apache Snapshots

This repository contains snapshot releases from the Apache Software Foundation.

Codehaus Snapshots

This repository contains snapshot released from Codehaus.

Central

This is the *Central Repository* containing release artifacts. Formerly known as *Maven Central*, it is the default built-in repository for Apache Maven and directly supported in other build tools like Gradle, SBT or Ant/Ivy. For Nexus OSS the URL http://repo1.maven.org/maven2/ is used.



Vedi:

http://www.liferay.com/documentation/liferay-portal/6.1/development/-/ai/using-maven-repositories

http://books.sonatype.com/nexus-book/reference/confignx-sect-manage-repo.html

Per stoppare il service:

\$ service nexus stop

```
Stopping Nexus OSS...
Stopped Nexus OSS.
```

The start-up script nexus supports the common service commands: start, stop, restart, status, console and dump.

Configure security

a) Change default admin password:

The default administrator username and password combination is admin and admin123.

Login as admin and change the password to a secure password.

Login -> [admin, admin123] -> Left Menu -> Security -> Change Password -> click "Change Password"

If you changed these credentials for your Nexus server, make sure to update <code>settings.xml</code> with these changes. Solitamente nel file settings.xml vengono utilizzate le credenziali di un utente di tipo developer che viene creato tramite interfaccia grafica dall'utente admin.

Valutare se ci sono jar, archetype da caricare sul Nexus appena installato.

Link al backup della macchina Nexus:

http://blog.sonatype.com/2011/06/nexus-tips-and-tricks-backup-nexus/#.VMd59S5FXK8