Username: Pralay Patoria **Book:** The C++ Standard Library: A Tutorial and Reference, Second Edition. No part of any chapter or book may be reproduced or transmitted in any form by any means without the prior written permission for reprints and excerpts from the publisher of the book or chapter. Redistribution or other use that violates the fair use privilege under U.S. copyright laws (see 17 USC107) or that otherwise violates these Terms of Service is strictly prohibited. Violators will be prosecuted to the full extent of U.S. Federal and Massachusetts laws.

4.3. Error and Exception Handling

The C++ standard library is heterogeneous. It contains software from diverse sources that have different styles of design and implementation. Error and exception handling is a typical example of these differences. Parts of the library, such as string classes, support detailed error handling, checking for every possible problem that might occur and throwing an exception if there is an error. Other parts, such as the STL and valarrays, prefer speed over safety, so they rarely check for logical errors and throw exceptions only if runtime errors occur.

4.3.1. Standard Exception Classes

All exceptions thrown by the language or the library are derived from the base class exception , defined in <exception> . This class is the root of several standard exception classes, which form a hierarchy, as shown in Figure 4.1. These standard exception classes can be divided into three groups:

- 1. Language support
- 2. Logic errors
- 3. Runtime errors




Figure 4.1. Hierarchy of Standard Exceptions

Logic errors usually can be avoided because the reason is inside the scope of a program, such as a precondition violation. Runtime exceptions are caused by a reason that is outside the scope of the program, such as not enough resources.

Exception Classes for Language Support

Exceptions for language support are used by language features. So in a way they are part of the core language rather than the library. These exceptions are thrown when the following operations fail:

- An exception of class bad_cast , defined in <typeinfo> , is thrown by the dynamic_cast operator if a type conversion on a reference fails at runtime.
- An exception of class bad_typeid , defined in <typeinfo> , is thrown by the typeid operator for runtime type identification. If the argument to typeid is zero or the null pointer, this exception gets thrown.
- An exception of class bad_exception , defined in <exception> , is used to handle unexpected exceptions. It can be thrown by the function unexpected() , which is called if a function throws an exception that is not listed in an exception specification Note, however, that the use of exception specifications is deprecated since C++11 (see Section 3.1.7, page 24).

These exceptions might also be thrown by library functions. For example, bad_cast might be thrown by use_facet<> if a facet is not available in a locale (see Section 16.2.2, page 864).

Exception Classes for Logic Errors

Exception classes for logic errors are usually derived from class logic_error . Logic errors are errors that, at least in theory, could be avoided by the program; for example, by performing additional tests of function arguments. Examples of such errors are a violation of logical preconditions or a class invariant. The C++ standard library provides the following classes for logic errors:

- An exception of class invalid_argument is used to report invalid arguments, such as when a bitset (array of bits) is initialized with a char other than '0' or '1'.
- An exception of class length_error is used to report an attempt to do something that exceeds a maximum allowable size, such as appending too many characters to a string.
- An exception of class out_of_range is used to report that an argument value is not in the expected range, such as when a wrong index is used in an array-like collection or string.
- An exception of class domain error is used to report a domain error.
- Since C++11, an exception of class future_error is used to report logical errors when using asynchronous system calls (see Chapter 18). Note that runtime errors in this domain are raised via class System error.

In general, classes for logic errors are defined in <stdexcept> . However, class future_error is defined in <future> .

Exception Classes for Runtime Errors

Exceptions derived from runtime_error are provided to report events that are beyond the scope of a program and are not easily avoidable. The C++ standard library provides the following classes for runtime errors:

- An exception of class <code>range_error</code> is used to report a range error in internal computations. In the C++ standard library, the exception can occur since C++11 in conversions between wide strings and by te strings (see Section 16.4.4, page 901).
- An exception of class **overflow_error** is used to report an arithmetic overflow. In the C++ standard library the exception can occur if a bitset is converted into an integral value (see Section 12.5.1, page 652).
- An exception of class underflow_error is used to report an arithmetic underflow.
- Since C++11, an exception of class System_error is used to report errors caused by the underlying operating system. In the C++ standard library, this exception can be thrown in the context of concurrency, such as class thread, classes to control data races, and async() (see Chapter 18).
- An exception of class <code>bad_alloc</code> , defined in <code><new></code> , is thrown whenever the global operator <code>new</code> fails, except when the <code>nothrow</code> version of <code>new</code> is used. This is probably the most important runtime exception because it might occur at any time in any nontrivial program.
 - Since C++11, bad_array_new_length , derived from bad_alloc , will be thrown by new if the size passed to new is less than zero or such that the size of the allocated object would exceed the implementation-defined limit (that is, if it's a logic error rather than a runtime error).
- An exception of class <code>bad_weak_ptr</code> , defined in <memory> , is thrown whenever the creation of a weak pointer out of a shared pointer fails. See Section 5.2.2, page 89, for details.
- An exception of class bad_function_call , defined in <functional> , is thrown whenever a function wrapper object gets invoked but has no target. See Section 5.4.4, page 133, for details.

In addition, for the I/O part of the library, a special exception class called <code>ios_base::failure</code> is provided in <code><ios></code> . An exception of this class may be thrown when a stream changes its state due to an error or end-of-file. Since C++11, this class is derived from <code>system_error</code>; before C++11, it was directly derived from class <code>exception</code>. The exact behavior of this exception class is described in <code>Section 15.4.4</code>, page 762.

Conceptually, bad_alloc can be considered a system error. However, for historical reasons and because of its importance, implementations are encouraged to throw a bad_alloc rather than a system_error exception if an error represents an out-of-memory condition.

In general, classes for runtime errors are defined in <stdexcept> . Class system_error , however, is defined in <system error> .

Exceptions Thrown by the Standard Library

As the previous description shows, almost all exception classes can be thrown by the C++ standard library. In particular, bad_alloc exceptions can be thrown whenever storage is allocated.

In addition, because library features might use code provided by the application programmer, functions might throw any exception indirectly.

Any implementation of the standard library might also offer additional exception classes either as siblings or as derived classes. However, the use of these nonstandard classes makes code nonportable because you could not use another implementation of the standard library without breaking your code. So, you should always use only the standard exception classes.

Header Files for Exception Classes

The exception classes are defined in many different header files. Thus, to be able to deal with all exceptions the library might throw, you have to include:

Click here to view code image

```
#include <exception>
#include <stdexcept>
#include <system_error>
#include <new>
#include <new>
#include <ios>
#include <future>
#include <typeinfo>
#include <typeinfo>

// for classes exception and bad_exception
// for most logic and runtime error classes
// for system errors (since C++11)
// for out-of-memory exceptions
// for I/O exceptions
// for errors with async() and futures (since C++11)
// for bad_cast and bad_typeid
```

4.3.2. Members of Exception Classes

To handle an exception in a **Catch** clause, you may use the interface provided by the exception classes. For all classes, **what()** is provided; for some classes, **code()** also is provided.

The Member what ()

For all standard exception classes, only one member can be used to get additional information besides the type itself: the virtual member function what(), which returns a null-terminated byte string:

The content of the string returned by what() is implementation defined. Note that the string might be a null-terminated multiby te string that is suitable to convert and display as wstring (see Section 13.2.1, page 664). The C-string returned by what() is valid until the exception object from which it is obtained gets destroyed or a new value is assigned to the exception object.

Error Codes versus Error Conditions

For the exception classes system_error and future_error, there is an additional member to get details about the exception. However, before going into details, we have to introduce the difference between error codes and error conditions:

- Error codes are light-weight objects that encapsulate error code values that might be implementation-specific. However, some error codes also are standardized.
- Error conditions are objects that provide portable abstractions of error descriptions.

Depending on the context, for exceptions the C++ standard library sometimes specifies error code and sometimes error conditions. In fact:

- Class std::errc provides error conditions for std::system_error exceptions corresponding to standard system error numbers defined in <cerrno> or <errno.h> .
- Class std::io_errc provides an *error code* for std::ios_base::failure exceptions thrown by stream classes since C++11 (see Section 15.4.4, page 762).
- Class std::future_errc provides error codes for std::future_error exceptions thrown by the concurrency library (see Chapter 18).

Tables 4.1 and 4.2 list the error condition values that are specified by the C++ standard library for System_error exceptions. These are scoped enumerators (see Section 3.1.13, page 32), so the prefix Std::erroc:: has to be used. The values of these conditions are required to have the corresponding erron value defined in <cerno> or <erno.h> This is not the error code; the error codes usually will be implementation-specific.

Table 4.1. Error Conditions of $system_errors$, Part 1

techbus.safaribooksonline.com/print?xmlid=9780132978286%2Fch04lev1sec3	
Error Condition	Enum Value
address_family_not_supported	EAFNOSUPPORT
address_in_use	EADDRINUSE
address_not_available	EADDRNOTAVAIL
already_connected	EISCONN
argument_list_too_long	E2BIG
argument_out_of_domain	EDOM
bad_address	EFAULT
bad_file_descriptor	EBADF
bad_message	EBADMSG
broken_pipe	EPIPE
connection_aborted	ECONNABORTED
connection_already_in_progress	EALREADY
connection_refused	ECONNREFUSED
connection_reset	ECONNRESET
cross_device_link	EXDEV
destination_address_required	EDESTADDRREQ
device_or_resource_busy	EBUSY
directory_not_empty	ENOTEMPTY
executable_format_error	ENOEXEC
file_exists	EEXIST
file_too_large	EFBIG
filename_too_long	ENAMETOOLONG
function_not_supported	ENOSYS
host_unreachable	EHOSTUNREACH
identifier_removed	EIDRM
illegal_byte_sequence	EILSEQ
inappropriate_io_control_operation	ENOTTY
interrupted	EINTR

techbus.safaribooksonline.com/print?xmiid=9/801329/8286%2Fch04lev1sec3		
invalid_argument	EINVAL	
invalid_seek	ESPIPE	
io_error	EIO	
is_a_directory	EISDIR	
message_size	EMSGSIZE	
network_down	ENETDOWN	
network_reset	ENETRESET	
network_unreachable	ENETUNREACH	
no_buffer_space	ENOBUFS	
no_child_process	ECHILD	
no_link	ENOLINK	
no_lock_available	ENOLCK	
no_message_available	ENODATA	
no_message	ENOMSG	
no_protocol_option	ENOPROTOOPT	
no_space_on_device	ENOSPC	
no_stream_resources	ENOSR	
no_such_device_or_address	ENXIO	
no_such_device	ENODEV	
no_such_file_or_directory	ENOENT	
no_such_process	ESRCH	
not_a_directory	ENOTDIR	
not_a_socket	ENOTSOCK	

Table 4.2. Error Conditions of $system_errors$, Part 2

Error ConditionEnum Valuenot_a_streamENOSTRnot_connectedENOTCONNnot_enough_memoryENOMEMnot_supportedENOTSUPoperation_canceledECANCELEDoperation_in_progressEINPROGRESSoperation_not_supportedEOPNOTSUPPoperation_would_blockEWOULDBLOCKowner_deadEACCESprotocol_errorEPROTOprotocol_not_supportedEPROTONOSUPPORTread_only_file_systemEROFSresource_deadlock_would_occurEDEADLKresource_unavailable_try_againEAGAINresult_out_of_rangeERANGEstate_not_recoverableENOTRECOVERABLEstream_timeoutETIMEtext_file_busyETIMEtimed_outETIMEtoo_many_files_open_in_systemENFILEtoo_many_files_openEMFILEtoo_many_linksEMLINKtoo_many_symbolic_link_levelsELOOPvalue_too_largeEOVERFLOWwrong_protocol_typeEPROTOTYPE	techbus.sataribooksoniine.com/print?xmiid=	9780132978286%2FCN04leV1SeC3
not_connected not_enough_memory not_supported operation_canceled operation_not_permitted operation_mot_supported operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_links too_many_symbolic_link_levels value_too_large ENOTCONN ENOMEM ENOTSUP ECANCELED ECANCEL ECANCELED ECANCEL ECA	Error Condition	Enum Value
not_enough_memory not_supported operation_canceled operation_not_permitted operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open too_many_files_open too_many_symbolic_link_levels value_too_large ECANCELED ENOTSUPP ECUNCTUPP EVOULDBLOCK EOWNERDEAD EROCES EPROTO EPROTONOSUPPORT ERANGE ERANGE ENOTRECOVERABLE ETIME ETIME EMLINK EMLINK EMLINK ELOOP EOVERFLOW	not_a_stream	ENOSTR
not_supported operation_canceled operation_in_progress operation_not_permitted operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open too_many_files_open too_many_symbolic_link_levels value_too_large ECANCELED ECANCELED ECANCELED ENPROGRESS EPERM EOPNOTSUPP EWOULDBLOCK EOWNERDEAD EROCES EPROTO EVOULDBLOCK EOWNERDEAD ENOUTSUPP EWOULDBLOCK EOWNERDEAD ENOTOSUPPORT ERANGE ERANGE ENOTRECOVERABLE ETIME ETIME EMLINK EMLINK EMLINK ELOOP EOVERFLOW	not_connected	ENOTCONN
operation_canceled operation_in_progress operation_not_permitted operation_not_supported operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_links too_many_symbolic_link_levels value_too_large ECANCELED ECANCELED EINPROGRESS EPRM EOPNOTSUPP EWOULDBLOCK EOWNERDEAD EROCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO ENTOTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EROCES ENOTS EROFS EACCES EPROTO EVOULDBLOCK ENOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EROCES EPRM ENOULDBLOCK EOWNERDEAD EACCES EPRM EOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES EPRM EOULDBLOCK EOWNERDEAD EACCES EPRM EOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES EPRM EOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES EPROTO EVOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES EPROTO EVOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES EPROTO EVOULDBLOCK EOWNERDEAD EROCES ENOTOSUPPORT EROFS EACCES ENOTOSUPPORT EROFS ENOTOSUPPORT	not_enough_memory	ENOMEM
operation_in_progress operation_not_permitted operation_not_supported operation_would_block owner_dead permission_denied permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_links too_many_symbolic_link_levels value_too_large EINPROGRESS EPERM EOPNOTSUPP EWOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EVOULDBLOCK EOWNERDEAD EACCES EPROTO EACCES EPROTO ENOTECOS EPROTO ENTOTO ENTOTO ENTOTO ENTILE ETIME ETIMEDOUT ENFILE EMLINK EMLINK EDOOP EOVERFLOW	not_supported	ENOTSUP
operation_not_permitted operation_not_supported operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_links too_many_symbolic_link_levels value_too_large EPERM EOPNOTSUPP EWOULDBLOCK EOWNERDEAD ERROTO EPROTO EPROTONOSUPPORT EROFS EERAGE ERANGE ERANGE ENOTRECOVERABLE ETIME ETIME ENTILE EMLINK EMLINK ELOOP EVERFLOW	operation_canceled	ECANCELED
operation_not_supported operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_too_many_files_open too_many_symbolic_link_levels value_too_large EOPNOTSUPP EWOULDBLOCK EOWNERDEAD EROCES EPROTO EPROTONOSUPPORT EROFS ERANGE ENOTRECOVERABLE ETIME ETXTBSY ETXTBSY ETIMEDOUT ENFILE EMLINK EMLINK ELOOP EOVERFLOW	operation_in_progress	EINPROGRESS
operation_would_block owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_symbolic_link_levels value_too_large EWOULDBLOCK EOWNERDEAD EACCES EPROTO EPROTONOSUPPORT EROFS EEDEADLK EAGAIN ERANGE ENOTRECOVERABLE ETIME ETIME ETIME ETIME EMFILE EMFILE EMLINK ELOOP EOVERFLOW	operation_not_permitted	EPERM
owner_dead permission_denied protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large EOWNERDEAD EACCES EPROTO EPROTONOSUPPORT EROFS EDEADLK ERANGE ENOTRECOVERABLE ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMFILE EMLINK ELOOP EOVERFLOW	operation_not_supported	EOPNOTSUPP
permission_denied	operation_would_block	EWOULDBLOCK
protocol_error protocol_not_supported read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large EPROTO EPROTONOSUPPORT EROFS EDEADLK EAGAIN ERANGE ENOTRECOVERABLE ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMLINK ELOOP EOVERFLOW	owner_dead	EOWNERDEAD
protocol_not_supported	permission_denied	EACCES
read_only_file_system resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large EROFS EDEADLK EAGAIN ERANGE ENOTRECOVERABLE ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMLINK EMLINK ELOOP EOVERFLOW	protocol_error	EPROTO
resource_deadlock_would_occur resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large EDEADLK EAGAIN ERANGE ENOTRECOVERABLE ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMLINK EMLINK ELOOP EOVERFLOW	protocol_not_supported	EPROTONOSUPPORT
resource_unavailable_try_again result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large EAGAIN ERANGE ENOTRECOVERABLE ENOTRECOVERABLE ETIME ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMLINK EMLINK ELOOP EOVERFLOW	read_only_file_system	EROFS
result_out_of_range state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large ERANGE ENOTRECOVERABLE ETIME ETIMEDOUT ENFILE EMFILE EMLINK EMLINK ELOOP EOVERFLOW	resource_deadlock_would_occur	EDEADLK
state_not_recoverable stream_timeout text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large ENOTRECOVERABLE ETIME ETXTBSY ETIMEDOUT ENFILE EMFILE EMFILE EMLINK ELOOP EOVERFLOW	resource_unavailable_try_again	EAGAIN
stream_timeout ETIME text_file_busy ETXTBSY timed_out ETIMEDOUT too_many_files_open_in_system ENFILE too_many_files_open EMFILE too_many_links EMLINK too_many_symbolic_link_levels ELOOP value_too_large EOVERFLOW	result_out_of_range	ERANGE
text_file_busy timed_out too_many_files_open_in_system too_many_files_open too_many_links too_many_symbolic_link_levels value_too_large ETXTBSY ETIMEDOUT ENFILE EMFILE EMLINK EMLINK	state_not_recoverable	ENOTRECOVERABLE
timed_out ETIMEDOUT too_many_files_open_in_system too_many_files_open EMFILE too_many_links EMLINK too_many_symbolic_link_levels ELOOP value_too_large EOVERFLOW	stream_timeout	ETIME
too_many_files_open_in_system	text_file_busy	ETXTBSY
too_many_files_open EMFILE too_many_links EMLINK too_many_symbolic_link_levels ELOOP value_too_large EOVERFLOW	timed_out	ETIMEDOUT
too_many_links EMLINK too_many_symbolic_link_levels ELOOP value_too_large EOVERFLOW	too_many_files_open_in_system	ENFILE
too_many_symbolic_link_levels	too_many_files_open	EMFILE
value_too_large EOVERFLOW	too_many_links	EMLINK
	too_many_symbolic_link_levels	EL00P
wrong_protocol_type	value_too_large	EOVERFLOW
	wrong_protocol_type	EPROTOTYPE

1 Note that in the C++11 standard, the error codes of future errors are defined explicitly with future_errc::broken_promise having the value 0 . But because error code 0 usually stands for "no error," this was a design mistake. The fix is that all future error code values are now defined to be implementation-specific.

Table 4.3. Error Codes of future_errors

Error Code	Meaning
broken_promise	shared state abandoned
future_already_retrieved	get_future() already called
promise_already_satisfied	Shared state already has a value/exception or already invoked
no_state	No shared state

The only error code specified for <code>ios_base::failure</code> exceptions is <code>std::io_errc::stream</code> .

Dealing with Error Codes and Error Conditions

For error codes and error conditions, two different types are provided by the C++ standard library: class <code>std::error_code</code> and class <code>std::error_codition</code>. This might lead to the impression that dealing with errors is pretty complicated. However, the library is designed so that you can always compare error codes with error conditions using both the objects or enumeration values. For example, for any error object <code>ec</code> of type <code>std::error_code</code> or <code>std::error_condition</code> the following is possible:

Click here to view code image

if (ec == std::errc::invalid argument) { // check for specific error condition

Thus, when dealing with errors only to check for specific error codes or conditions, the difference between codes and conditions doesn't matter.

```
To be able to deal with error codes and error conditions, class std::system_error , including its derived class std::ios_base::failure , and class std::_future_error provide the additional nonvirtual member function code() returning an object of class std::error_code :2

namespace std {
    class system_error : public runtime_error {
        public:
            virtual const char* what() const noexcept;
            const error_code& code() const noexcept;
            ...
    };

class future_error : public logic_error {
    public:
        virtual const char* what() const noexcept;
        const error_code& code() const noexcept;
        ...
};
```

² Strictly speaking, these declarations are in different header files, and what() is not declared as virtual here but derives its virtuality from its base class.

 ${\tt Class} \quad {\tt error_code} \quad {\tt then} \ {\tt provides} \ {\tt member} \ {\tt functions} \ {\tt to} \ {\tt get} \ {\tt some} \ {\tt details} \ {\tt of} \ {\tt the} \ {\tt error}.$

Click here to view code image

This interface is driven by the following design:

- Different libraries might use the same integral values for different error codes. So, each error has a category and a value. Only inside a category is each value distinct and has a clear specified meaning.
- message() yields a corresponding message, which usually is part of what what() yields in general for all exceptions, although this is not required.
- operator bool() yields whether an error code is set (0 is the value that stands for "no error"). When exceptions are caught, this operator usually should yield true .
- default_error_condition() returns the corresponding error_condition , again providing category() , value() , message() , and operator bool() :

Click here to view code image

Class Std::error_category provides the following interface:

Click here to view code image

Here, name() yields the name of the category. message() and default_error_condition() return the message and the default error condition according to the passed value (this is what the corresponding error_code member functions call). Operators == and != allow you to compare error categories.

The following category names are defined by the C++ standard library:

- "iostream" for I/O stream exceptions of type ios_base::failure
- "generic" for system exceptions of type System_error , where the value corresponds to a POSIX errno value
- "system" for system exceptions of type system_error , where the value does not correspond to a POSIX errno value
- "future" for exceptions of type future_error

For each category, global functions are provided that return the category:

 $\frac{3}{2}$ It's probably an oversight that iostream_category() is not declared with noexcept .

Thus, for an error code object e , you can also call the following to find out whether it is an I/O failure:

```
if (e.code().category() == std::iostream_category())
```

The following code demonstrates how to use a generic function to process (here, print) different exceptions:

Click here to view code image

```
// util/exception.hpp
```

```
#include <exception>
#include <system error>
#include <future>
#include <iostream>
template <typename T>
void processCodeException (const T& e)
    using namespace std;
    auto c = e.code();
    cerr << "- category:</pre>
                                   " << c.category().name() << endl;
    cerr << "- walue:
cerr << "- msg:
                                   " << c.value() << endl;
                                   " << c.message() << endl;
    cerr << "- def category: "</pre>
          << c.default_error_condition().category().name() << endl;
    cerr << "- def value:</pre>
         << c.default_error_condition().value() << endl;
cerr << "- def msg: "</pre>
           << c.default error condition().message() << endl;
}
void processException()
    using namespace std;
         throw; // rethrow exception to deal with it here
    catch (const ios_base::failure& e) {
    cerr << "I/O EXCEPTION: " << e.what() << endl;</pre>
         processCodeException(e);
```

```
catch (const system_error& e) {
    cerr << "SYSTEM_EXCEPTION: " << e.what() << endl;
    processCodeException(e);
}
catch (const future_error& e) {
    cerr << "FUTURE_EXCEPTION: " << e.what() << endl;
    processCodeException(e);
}
catch (const bad_alloc& e) {
    cerr << "BAD_ALLOC_EXCEPTION: " << e.what() << endl;
}
catch (const exception& e) {
    cerr << "EXCEPTION: " << e.what() << endl;
}
catch (...) {
    cerr << "EXCEPTION (unknown)" << endl;
}
</pre>
```

This allows to handle exceptions as follows:

```
try {
    ...
} catch (...) {
    processException();
}
```

Other Members

The remaining members of the standard exception classes create, copy, assign, and destroy exception objects.

Note that besides what() and code(), for any of the standard exception classes, no additional member is provided that describes the kind of exception. For example, there is no portable way to find out the context of an exception or the faulty index of a range error. Thus, a portable evaluation of an exception could print only the message returned from what():

```
try {
    ...
} catch (const std::exception& error) {
    // print implementation-defined error message
    std::cerr << error.what() << std::endl;
    ...
}</pre>
```

The only other possible evaluation might be an interpretation of the exact type of the exception. For example, when a <code>bad_alloc</code> exception is thrown, a program might try to get more memory.

4.3.3. Passing Exceptions with Class exception ptr

Since C++11, the C++ standard library provides the ability to store exceptions into objects of type **exception_ptr** to process them later or in other contexts:

Click here to view code image

```
current_exception() returns an exception_ptr object that refers to the currently handled exception. The value
returned by current_exception() is valid as long as an exception_ptr refers to it.
rethrow_exception() rethrows the stored exception so that bar() behaves as the initial exception thrown in
foo() would have occured inside bar().
```

This feature is especially useful to pass exception between threads (see Section 18.2.1, page 964).

4.3.4. Throwing Standard Exceptions

You can throw standard exceptions inside your own library or program. All logic error and runtime error standard exception classes that provide the what() interface have only a constructor for std::string and (since C++11) for const char*. The value passed here will become the description returned by what(). For example, the class logic_error is defined as follows:

Click here to view code image

Class Std::System_error provides the ability to create an exception object by passing an error code, a what() string, and an optional category:

Click here to view code image

To provide an error_code object, make_error_code() convenience functions are provided that take only the error code value.

Class std::ios_base::failure provides constructors taking a what() string and (since C++11) an optional error_code object. Class std::future_error provides only a constructor taking a single error_code object.

Thus, throwing a standard exception is pretty easy:

Click here to view code image

You can't throw exceptions of the base class exception and any exception class that is provided for language support (bad_cast , bad_typeid , bad_exception).

4.3.5. Deriving from Standard Exception Classes

Another possibility for using the standard exception classes in your code is to define a special exception class derived directly or indirectly from class exception. To do this, you must ensure that the what() mechanism or code() mechanism works, which is possible because what() is virtual. For an example, see class Stack in Section 12.1.3, page 635.