Username: Pralay Patoria **Book:** Pro .NET Performance. No part of any chapter or book may be reproduced or transmitted in any form by any means without the prior written permission for reprints and excerpts from the publisher of the book or chapter. Redistribution or other use that violates the fair use privilege under U.S. copyright laws (see 17 USC107) or that otherwise violates these Terms of Service is strictly prohibited. Violators will be prosecuted to the full extent of U.S. Federal and Massachusetts laws.

File I/O

Normally, file I/O goes through the filesystem cache, which has some performance benefits: caching of recently accessed data, read-ahead (speculative pre-fetching data from disk), write-behind (asynchronously writing data to disk), and combining of small writes. By hinting Windows about your expected file access pattern, you can gain a bit more performance. If your application does overlapped I/O and can intelligently handle buffers facing some complexities, then by passing caching entirely can be more efficient.

Cache Hinting

When creating or opening a file, you specify flags and attributes to the CreateFile Win32 API function, some of which influence caching behavior:

- FILE_FLAG_SEQUENTIAL_SCAN hints to the Cache Manager that the file is accessed sequentially, possibly skipping some parts, but is seldom accessed randomly. The cache will read further ahead.
- FILE_FLAG_RANDOM_ACCESS hints that the file is accessed in random order, so the Cache Manager reads less ahead, since it is
 unlikely that this data will actually be requested by the application.
- FILE ATTRIBUTE TEMPORARY hints that the file is temporary, so flushing writes to disk (to prevent data loss) can be delay ed.

NET exposes these options (except the last one) through a FileStream constructor overload that accepts a FileOptions enumeration parameter.

Caution Random access is bad for performance, especially on disk media since the read/write head has to physically move. Historically, disk throughput has improved with increasing aereal storage density, but latency has not. Modern disks can intelligently (taking disk rotation into account) re-order random-access I/O so that the total time the head spends travelling is minimized. This is called Native Command Queuing (NCQ). For this to work effectively, the disk controller must be aware of several I/O requests ahead. In other words, if possible, you should have several asynchronous I/O requests pending.

Unbuffered I/O

Unbuffered I/O by passes the Windows cache entirely. This has both benefits and drawbacks. Like with cache hinting, unbuffered I/O is enabled through the "flags and attributes" parameter during file creation, but .NET does not expose this functionality:

- FILE_FLAG_NO_BUFFERING prevents the data read or written from being cached but has no effect on hardware caching by the disk
 controller. This avoids a memory copy (from user buffer to cache) and prevents cache pollution (filling the cache with useless data
 at the expense of more important data). However, reads and writes must obey alignment requirements. The following parameters
 must be aligned to or have a size that is an integer multiple of the disk sector size: I/O transfer size, file offset, and memory buffer
 address. Typically, the sector size is 512 bytes long. Recent high-capacity disk drives have 4,096 byte sectors (known as
 "Advanced Format"), but they can run in a compatibility mode that emulates 512 byte sectors (at the expense of performance).
- FILE_FLAG_WRITE_THROUGH instructs the Cache Manager to flush cached writes (if FILE_FLAG_NO_BUFFERING is not specified) and
 instructs the disk controller to commit writes to physical media immediately, rather than storing them in the hardware cache.

Read-ahead improves performance by keeping the disk utilized, even if the application makes synchronous reads, and has delays between reads. This depends on Windows correctly predicting what part of the file the application will request next. By disabling buffering, you also disable read-ahead and should keep the disk busy by having multiple overlapped I/O operations pending.

Write-behind also improves performance for applications making synchronous writes by giving the illusion that disk-writes finish very quickly. The application can better utilize the CPU, because it blocks for less time. When you disable buffering, writes complete in the actual amount of time it takes to write them to disk. Therefore, doing asynchronous I/O becomes even more important when using unbuffered I/O.