EXECUTABLE FILE FORMATS

Executable File Formats

- Portable Executable (PE)
 - Executable file format of choice for Windows
- Executable and Linkable Format (ELF)
 - Executable file format of choice for Linux

PE

- Portable Executable
 - Executable file format of choice for Windows
 - Including Windows CE
 - Modified version of Unix COFF (Common Object File Format)
 - .cpl, .exe, .dll, .ocx, .sys, .scr, .drv, .tlb

PE Addressing

- Virtual Address (VA)
 - Virtual address of an object once it is loaded into memory
- Relative Virtual Address (RVA)
 - Offset from the beginning of the loaded image

PE Tables

- Import Table
- Export Table
- Resource Table
- Exception Table
- Certificate Table
- Base Relocation Table
- Thread Local Storage Table
- ...


PE Import and Export Tables

- Import Table (.idata)
 - Used as a lookup table for external function addresses
 - Import by ordinal or name
- Export Table (.edata)
 - Used as a lookup table for internal function addresses
 - Export by ordinal or name


PE Resource Table

- Resource Table (.rsrc)
 - Multi-level binary-sorted tree
 - Windows typically uses 3 levels
 - Type
 - 2. Name
 - 3. Language
 - Leaves contain a description and raw data


msfpescan



Click on the "Modules" button




Find where the PE header is mapped



Double-click to view the PE Header dump

```
OllyDbg - pq.exe - [Dump - pq:00400000..00400FFF]
                                                                                                   _ _ _ X
 D File View Debug Trace Options Windows Help
                                                                                                              ₽ ×
                                                   L E M T C ...
                                                                           B M H
Address Hex dump
                                                   Comments
                                                   IMAGE_NT_SIGNATURE[4] = "PE "
Machine = IMAGE_FILE_MACHINE_I386
               50 45 0 ASCII "PE",0,0
00400128
                        DW 14C
0040012
               4C01
00400120
               0800
                        DW
                                                   NumberOfSections
00400130
               195E422|DD 2A425E19
                                                   TimeDateStamp = 2A425E19
0040013
               00000000 DD 00000000
                                                   PointerToSymbolTable = 0
00400138
               0000000i DD 00000000
                                                   NumberOfSymbols = 0
                                                   SizeOfOptionalHeader = 224.
Characteristics = EXECUTABLE_IMAGE:32BIT_MACHINE:LINE_NU
MagicNumber = IMAGE_NT_OPTIONAL_HDR32_MAGIC
00400130
              E000
                        DW 0E0
0040013E
               8E81
                        DW 818E
                       DW 10B
00400140
               0B01
0040014
                        DB
                                                   MajorLinkerVersion = 2
MinorLinkerVersion = 25.
                           02
0040014
                        DB 19
0040014
               00B6080( DD
                           0008B600
                                                   SizeOfCode = 570880.
00400148
               0034040(DD 00043400
                                                   SizeOfInitializedData = 275456.
00400140
               0000000i DD 00000000
                                                   SizeOfUninitializedData =
00400150
               42500D01 DD 000D5042
                                                   AddressOfEntryPoint = 0D5042
                                                   BaseOfCode = 1000
BaseOfData = 80000
0040015
               0010000iDD 00001000
0040015
               00D0080i DD 0008D000
               0000400 DD 00400000
                                                   ImageBase = 400000
                                                   SectionAlignment = 1000
FileAlignment = 200
0040016
               0010000|DD 00001000
0040016
               0002000|DD 00000200
0040016
               0400
                                                   MajorOSVersion = 4
0040016F
               0000
                                                   MinorOSVersion = 0
0040016
               0000
                        D₩
                           ø
                                                   MajorImageVersion = 0
               0000
00400168
                                                   MinorImageVersion = 0
                                                   MajorSubsystemVersion =
00400170
               0400
004001
               ดีดีดีดี
                                                   MinorSubsystemVersion = 0
                        DM
0040017
               0000000 DD 00000000
                                                   Win32VersionValue = 0
                                                   SizeOfImage = 876544.
0040017
0040017
               0004000 DD 00000400
                                                   SizeOfHeaders = 1024.
00400180
               0000000( DD
                           00000000
                                                   CheckSum = 0
0040018
                                                   Subsystem = IMAGE_SUBSYSTEM_WINDOWS_GUI
00400186
               0000
                                                   DLLCharacteristics = 0
               0000100 DD 00100000
                                                   SizeOfStackReserve = 1048576.
0040018
0040018
               0040000 DD 00004000
                                                   SizeOfStackCommit = 16384.
SizeOfHeapReserve = 1048576.
00400190
               0000100iDD 00100000
0040019
                                                   SizeOfHeapCommit = 4096.
               0010000|DD 00001000
0040019
               0000000| DD 00000000
                                                   LoaderFlags = 0
00400190
               1000000|DD 00000010
                                                   NumberOfRvaAndSizes = 16.
004001A0
               0000000| DD 00000000
                                                   Export Table address = 0
               00000000 DD 00000000
                                                   Export Table size = 0
004001A
                                                                                                          Paused
```

 In this case, the compressor left behind some identifying information




ELF

- Executable and Linkable Format
 - Executable file format of choice for Linux
 - none, .o, .so, .elf, .exe

ELF Construction

- ELF Header
- Program Header Table
 - Describes segments
- Section Header Table
 - Describes sections

readelf



Questions/Comments?