
IP addressing & Subnet

Dr. Md. Shohrab Hossain Professor, CSE, BUET

Slide Source: Cisco Networking


- •IP addressing
- Public / Private IP address
- Network Address Translation
- Subnetting

Binary Number System




Network Portion and Host Portion of an IPv4 Address

 The subnet mask just says where to look for the network portion in a given IPv4 address



Bitwise AND Operation



IPv4 Subnet masks

Valid Subnet Masks

| Subnet Value |
|-----------------|
| 255 |
| 254 |
| 252 |
| 248 |
| 240 |
| 224 |
| 192 |
| 128 |
| |

| Bit V | 'alue | | | | | | |
|-------|-------|----|----|---|---|---|---|
| 128 | 64 | 32 | 16 | 8 | 4 | 2 | 1 |
| 1 | 1 | 1 | 1 | 1 | 1 | 1 | 1 |
| 1 | 1 | 1 | 1 | 1 | 1 | 1 | 0 |
| 1 | 1 | 1 | 1 | 1 | 1 | 0 | 0 |
| 1 | 1 | 1 | 1 | 1 | 0 | 0 | 0 |
| 1 | 1 | 1 | 1 | 0 | 0 | 0 | 0 |
| 1 | 1 | 1 | 0 | 0 | 0 | 0 | 0 |
| 1 | 1 | 0 | 0 | 0 | 0 | 0 | 0 |
| 1 | 0 | 0 | 0 | 0 | 0 | 0 | 0 |
| 0 | 0 | 0 | 0 | 0 | 0 | 0 | 0 |

Network Address and Broadcast address

• For a network, 192.168.10.0/24 network There are 8-bit allocated for host part.

Network Address:

- All 0's in the host part: 0000 0000 = 0
- So, network address = 192.168.10.0

Broadcast address:

- All 1's in the host part: 1111 1111 = 255
- So, broadcast address = 192.168.10.255
- IP range: 1- 254


Types of IPv4 Address

Legacy Classful Addressing

IP Address Classes

| Address Class | 1st octet range (decimal) | 1st octet bits (green bits do not change) | Network(N) and Host(H) parts of address | Default subnet mask (decimal and binary) | Number of possible networks and hosts per network |
|------------------|---------------------------------|---|---|--|---|
| A | 1-127** | 00000000- 01111111 | N.H.H.H | 255.0.0.0 | 128 nets (2^7) 16,777,214 hosts per net (2^24-2) |
| В | 128-191 | 10000000- 10111111 | N.N.H.H | 255.255.0.0 | 16,384 nets (2^14) 65,534 hosts per net (2^16-2) |
| С | 192-223 | 11000000- 11011111 | N.N.N.H | 255.255.255.0 | 2,097,150 nets (2^21) 254 hosts per net (2^8-2) |
| D | 224-239 | 11100000- 11101111 | NA (multicast) | | |
| E | 240-255 | 11110000- 11111111 | NA (experimental) | | |

Classful Addressing



Classless Addressing

- Formal name is Classless Inter-Domain Routing (CIDR)
- Created a new set of standards that allowed service providers to allocate IPv4 addresses on any address bit boundary (prefix length) instead of only by a class A, B, or C address
- Example: 192.168.10.0/23

Examining the Prefix Length

| | Dotted Decimal Significant bits show in binary | | | | |
|----------------------------|--|-------------------------|--|--|--|
| Network Address | 10.1.1.0/24 | 10.1.1. 00000000 | | | |
| First Host Address | 10.1.1.1 | 10.1.1.00000001 | | | |
| Last Host Address | 10.1.1.254 | 10.1.1.11111110 | | | |
| Broadcast Address | 10.1.1.255 | 10.1.1.11111111 | | | |
| Number of hosts: 2^8 – 2 = | 254 hosts | | | | |

| Network Address | 10.1.1.0/25 | 10.1.1.00000000 |
|----------------------------|--------------------------|-----------------|
| First Host Address | 10.1.1 <mark>.1</mark> | 10.1.1.00000001 |
| Last Host Address | 10.1.1 <mark>.126</mark> | 10.1.1.01111110 |
| Broadcast Address | 10.1.1 <mark>.127</mark> | 10.1.1.01111111 |
| Number of hosts: 2^7 – 2 = | 126 hosts | |

| Network Address | 10.1.1.0/26 | 10.1.1.00 000000 |
|--------------------------|-------------------------|-------------------------|
| First Host Address | 10.1.1 <mark>.1</mark> | 10.1.1.00000001 |
| Last Host Address | 10.1.1 <mark>.62</mark> | 10.1.1.00111110 |
| Broadcast Address | 10.1.1 <mark>.63</mark> | 10.1.1.00111111 |
| Number of hosts: 2^6 – 2 | = 62 hosts | |

Examining the Prefix Length (cont.)

| | Dotted Decimal Significant bits s in binary 10.1.1.0/27 10.1.1.000000000 10.1.1.1 10.1.1.000000001 | | | |
|----------------------------|--|-------------------------|--|--|
| Network Address | 10.1.1.0/27 | 10.1.1.000 00000 | | |
| First Host Address | 10.1.1 <mark>.1</mark> | 10.1.1.00000001 | | |
| Last Host Address | 10.1.1.30 | 10.1.1.00011110 | | |
| Broadcast Address | 10.1.1 <mark>.31</mark> | 10.1.1.00011111 | | |
| Number of hosts: 2^5 - 2 = | 30 hosts | | | |

| Network Address | 10.1.1.0/28 | 10.1.1.0000 0000 |
|----------------------------|-------------------------|-------------------------|
| First Host Address | 10.1.1 <mark>.1</mark> | 10.1.1.00000001 |
| Last Host Address | 10.1.1 <mark>.14</mark> | 10.1.1.00001110 |
| Broadcast Address | 10.1.1 <mark>.15</mark> | 10.1.1.00001111 |
| Number of hosts: 2^4 - 2 = | 14 hosts | |

Private IP address

Public and Private IPv4 Addresses

Private address blocks are:

- Hosts that do not require access to the Internet can use private addresses
 - **10**.0.0.0 to 10.255.255.255 (10.0.0.0/8)
 - **172.16**.0.0 to **172.31**.255.255 (172.16.0.0/12)
 - **192.168**.0.0 to 192.168.255.255 (192.168.0.0/16)
- Not globally routable
- Address translation is done at Router to convert private IP into Public IP address and vice versa

What is NAT?


- NAT is a process used to translate network addresses.
- NAT's primary use is to conserve public IPv4 addresses.
- NAT is usually implemented at border network devices, such as firewalls or routers.
- NAT allows the networks to use private addresses internally, only translating to public addresses when needed.
- Devices within the organization can be assigned private addresses and operate with locally unique addresses.
- When traffic must be sent or received to or from other organizations or the Internet, the border router translates the addresses to a public and globally unique address.

NAT Characteristics


IPv4 Address Space

- Networks are commonly implemented using private IPv4 addresses, as defined in RFC 1918.
- Private IPv4 addresses cannot be routed over the internet and are used within an organization or site to allow devices to communicate locally.
- To allow a device with a private IPv4 address to access devices and resources outside of the local network, the private address must first be translated to a public address.
- NAT provides the translation of private addresses to public addresses.

| Class | Activity Type | Activity Name |
|-------|----------------------------------|----------------------|
| А | 10.0.0.0 – 10.255.255.255 | 10.0.0.0/8 |
| В | 172.16.0.0 – 172.31.255.255 | 172.16.0.0/12 |
| С | 192.168.0.0 – 192.168.255.255 | 192.168.0.0/16 |




NAT



NAT Characteristics What is NAT


- The primary use of NAT is to conserve public IPv4 addresses.
- NAT allows networks to use private IPv4 addresses internally and translates them to a public address when needed.
- A NAT router typically operates at the border of a stub network.
- When a device inside the stub network wants to communicate with a device outside of its network, the packet is forwarded to the border router which performs the NAT process, translating the internal private address of the device to a public, outside, routable address.



How NAT Works

PC1 wants to communicate with an outside web server with public address 209.165.201.1.


- 1. PC1 sends a packet addressed to the web server.
- 2. R2 receives the packet and reads the source IPv4 address to determine if it needs translation.
- 3. R2 adds mapping of the local to global address to the NAT table.
- 4. R2 sends the packet with the translated source address toward the destination.
- 5. The web server responds with a packet addressed to the inside global address of PC1 (209.165.200.226).
- 6. R2 receives the packet with destination address 209.165.200.226. R2 checks the NAT table and finds an entry for this mapping. R2 uses this information and translates the inside global address (209.165.200.226) to the inside local address (192.168.10.10), and the packet is forwarded toward PC1.



Port Address Translation (PAT)

Port Address Translation (PAT), also known as NAT overload, maps multiple private IPv4 addresses to a single public IPv4 address or a few addresses.

- With PAT, when the NAT router receives a packet from the client, it uses the source port number to uniquely identify the specific NAT translation.
- PAT ensures that devices use a different TCP port number for each session with a server on the internet.



Subnetting

Network Segmentation

Reasons for Subnetting

Subnetting is the process of segmenting a network into multiple smaller network spaces called subnetworks or subnets.

- Large networks must be segmented into smaller subnetworks, creating smaller groups of devices and services to:
 - Control traffic by containing broadcast traffic within each subnetwork.
 - Reduce overall network traffic and improve network performance.


Communication Between Subnets


- A router is necessary for devices on different networks and subnets to communicate.
- Devices on a network and subnet use the router interface attached to their LAN as their default gateway.


Different networks for different groups

Planning the Network










Planning requires decisions on each subnet in terms of size, the number of hosts per subnet, and how host addresses will be assigned.

Basic Subnetting

- Borrowing Bits to Create Subnets
- Borrowing 1 bit $2^1 = 2$ subnets




Subnets in Use

Subnets in Use

Subnet 0

Network 192.168.1.0-127/25

192.168.1.0/25



Subnet 1

Network 192.168.1.128-255/25

Address Range for 192.168.1.0/25 Subnet

Network Address

192. 168. 1. 0 000 0000 = 192.168.1.0

First Host Address

192. 168. 1. 0 000 0001 = 192.168.1.1

Last Host Address

192. 168. 1. 0 111 1110 = 192.168.1.126

Broadcast Address

192. 168. 1. 0 111 1111 = 192.168.1.127

Address Range for 192.168.1.128/25 Subnet

Network Address

192. 168. 1. 1 000 0000 = 192.168.1.128

First Host Address

192. 168. 1. 1 000 0001 = 192.168.1.129


Last Host Address

192. 168. 1. 1 111 1110 = 192.168.1.254

Broadcast Address


192. 168. 1. 1 111 1111 = 192.168.1.255

Subnetting Formulas



Creating 4 Subnets

Borrowing 2 bits to create 4 subnets. $2^2 = 4$ subnets



Creating Eight Subnets


Borrowing 3 bits to Create 8 Subnets. 23 = 8 subnets

| | Network | 192. | 168. | 1. | 000 | 0 0000 | 192.168.1.0 |
|---------------------|-----------|------|------|----|-----|--------|---------------|
| Net 0 | First | 192. | 168. | 1. | 000 | 0 0001 | 192.168.1.1 |
| | Last | 192. | 168. | 1. | 000 | 1 1110 | 192.168.1.30 |
| | Broadcast | 192. | 168. | 1. | 000 | 1 1111 | 192.168.1.31 |
| | Network | 192. | 168. | 1. | 001 | 0 0000 | 192.168.1.32 |
| Net 1 | First | 192. | 168. | 1. | 001 | 0 0001 | 192.168.1.33 |
| | Last | 192. | 168. | 1. | 001 | 1 1110 | 192.168.1.62 |
| | Broadcast | 192. | 168. | 1. | 001 | 1 1111 | 192.168.1.63 |
| | Network | 192. | 168. | 1. | 010 | 0 0000 | 192.168.1.64 |
| Net 2 | First | 192. | 168. | 1. | 010 | 0 0001 | 192.168.1.65 |
| Sale Series Service | Last | 192. | 168. | 1. | 010 | 1 1110 | 192.168.1.94 |
| | Broadcast | 192. | 168. | 1. | 010 | 1 1111 | 192.168.1.95 |
| | Network | 192. | 168. | 1. | 011 | 0 0000 | 192.168.1.96 |
| Net 3 | First | 192. | 168. | 1. | 011 | 0 0001 | 192.168.1.97 |
| | Last | 192. | 168. | 1. | 011 | 1 1110 | 192.168.1.126 |
| | Broadcast | 192. | 168. | 1. | 011 | 1 1111 | 192.168.1.127 |

Creating Eight Subnets (Cont.)

| | Network | 192. | 168. | 1. | 100 | 0 0000 | 192.168.1.128 |
|-------|-----------|------|------|----|-----|--------|---------------|
| Net 4 | Fist | 192. | 168. | 1. | 100 | 0 0001 | 192.168.1.129 |
| | Last | 192. | 168. | 1. | 100 | 1 1110 | 192.168.1.158 |
| | Broadcast | 192. | 168. | 1. | 100 | 1 1111 | 192.168.1.159 |
| | Network | 192. | 168. | 1. | 101 | 0 0000 | 192.168.1.160 |
| Net 5 | Fist | 192. | 168. | 1. | 101 | 0 0001 | 192.168.1.161 |
| | Last | 192. | 168. | 1. | 101 | 1 1110 | 192.168.1.190 |
| | Broadcast | 192. | 168. | 1. | 101 | 1 1111 | 192.168.1.191 |
| | Network | 192. | 168. | 1. | 110 | 0 0000 | 192.168.1.192 |
| Net 6 | Fist | 192. | 168. | 1. | 110 | 0 0001 | 192.168.1.193 |
| | Last | 192. | 168. | 1. | 110 | 1 1110 | 192.168.1.222 |
| | Broadcast | 192. | 168. | 1. | 110 | 1 1111 | 192.168.1.223 |
| | Network | 192. | 168. | 1. | 111 | 0 0000 | 192.168.1.224 |
| Net 7 | Fist | 192. | 168. | 1. | 111 | 0 0001 | 192.168.1.225 |
| | Last | 192. | 168. | 1. | 111 | 1 1110 | 192.168.1.254 |
| | Broadcast | 192. | 168. | 1. | 111 | 1 1111 | 192.168.1.255 |

Creating Eight Subnets (Cont.)



Subnetting Based on Host Requirements

Two considerations when planning subnets:


- Number of subnets required
- Number of host addresses required

Formula to determine number of usable hosts: 2ⁿ-2

- 2ⁿ (where n is the number of remaining host bits) is used to calculate the number of hosts.
- -2 (The subnetwork ID and broadcast address cannot be used on each subnet.)


Traditional Subnetting: Equal Addresses

- Subnets that require fewer addresses have unused (wasted) addresses
- For example, WAN links only need two addresses.




Variable Length Subnet Masks (VLSM)


- The variable-length subnet mask (VLSM) or subnetting a subnet provides more efficient use of addresses.
- VLSM allows a network space to be divided in unequal parts.
- Subnet mask varies, depending on how many bits have been borrowed for a particular subnet.
- Network is first subnetted, and then the subnets are resubnetted.



Benefits of Variable Length Subnet Masking Basic VLSM



Creating Eight Subnets (Cont.)



Let us do another example...