# CHAPTER 5 CENTRAL PROCESSING UNIT Rolisha Sthapit

Er. Rolisha Sthapit

### CONTENTS

- **5.1 Introduction:** Major Components of CPU, CPU Organizations (Accumulator Based Organization, General Register Organization, Stack Based Organization)
- **5.2 CPU Instructions:** Instruction Formats, Addressing Modes, Types of Instructions (on the basis of numbers of addresses, on the basis of type of operation: data transfer instructions, data manipulation instructions, program control instructions), Program Control, Subroutine Call and Return, Types of Interrupt
- **5.3 RISC and CISC:** RISC vs CISC, Pros and Cons of RISC and CISC, Overlapped Register Windows

### 5.1 INTRODUCTION

- The part of the computer that performs the bulk of data processing operation is called central processing unit (CPU) which consists of ALU, control unit and register array.
- CPU performs a variety of functions dictated by the type of instructions that are incorporated in the computer.
- The register set stores intermediate data used during the execution of the instructions. The arithmetic logic unit (ALU) performs the required microoperations for executing the instructions. The control (CU) unit supervises the transfer of information among the registers and instructs the ALU as to which operation to be performed.





Fig: Major components of CPU

### General Register Organization


• A bus organization of seven CPU registers is shown below:



- All registers are connected to two multiplexers (MUX) that select the registers for bus A and bus B. Registers selected by multiplexers are sent to ALU. Another selector (OPR) connected to ALU selects the operation for the ALU. Output produced by ALU is stored in some register and this destination register for storing the result is activated by the destination decoder (SELD).
- Example: R1 ← R2 + R3
- MUX selector (SELA): BUS A← R2
- MUX selector (SELB): BUS B ← R3
- ALU operation selector (OPR): ALU to ADD
- Decoder destination selector (SELD): R1 ← Out Bus

#### **Control word:**

Combination of all selection bits of a processing unit is called control word. Control Word for above CPU is as below:



 The 14 bit control word when applied to the selection inputs specify a particular microoperation. Encoding of the register selection fields and ALU operations is given below:

Binary Code	SELA	SELB	SELD
000	Input	Input	None
001	R1	R1	R1
010	R2	R2	R2
011	R3	R3	R3
100	R4	R4	R4
101	R5	R5	R5
110	R6	R6	R6
111	R7	R7	R7

OPR Select	Operation	Symbol
00000	Transfer A	TSFA
00001	Increment A	INCA
00010	Add A + B	ADD
00101	Subtract $A - B$	SUB
00110	Decrement A	DECA
01000	AND A and B	AND
01010	OR A and B	OR
01100	XOR A and B	XOR
01110	Complement A	COMA
10000	Shift right A	SHRA
11000	Shift left A	SHLA

Example:  $R1 \leftarrow R2 - R3$ 

This microoperation specifies R2 for A input of the ALU, R3 for the B input of the ALU, R1 for the destination register and ALU operation to subtract A-B. Binary control word for this microoperation statement is:

Field:	SELA	SELB	SELD	OPR
Symbol:	R2	R3	R1	SUB
Control word:	010	011	001	00101

### Examples of different microoperations are shown below: Symbolic Designation

Microoperation	SELA	SELB	SELD	OPR	Control Word
R1 ← R2 − R3	R2	R3	R1	SUB	010 011 001 00101
$R4 \leftarrow R4 \lor R5$	R4	R5	R4	OR	100 101 100 01010
$R6 \leftarrow R6 + 1$	R6	201.05	R6	INCA	110 000 110 00001
$R7 \leftarrow R1$	R1		R7	TSFA	001 000 111 00000
Output $\leftarrow R2$	R2	200 1130	None	TSFA	010 000 000 00000
Output ← Input	Input	<u>u-u</u>	None	<b>TSFA</b>	000 000 000 00000
R4 ← sh1 R4	R4	0.39	R4	SHLA	100 000 100 11000
R5←0	R5	R5	R5	XOR	101 101 101 01100

# Stack Organization

• This is useful *last-in, first-out* (LIFO) list (actually storage device) included in most CPU's. Stack in digital computers is essentially a memory unit with a stack pointer (SP). SP is simply an address register that points stack top. Two operations of a stack are the insertion (push) and deletion (pop) of items. In a computer stack, nothing is pushed or popped; these operations are simulated by incrementing or decrementing the SP register.

# Register stack

• It is the collection of finite number of registers. Stack pointer (SP) points to the register that is currently at the top of stack.





Fig: Block diagram of a 64-word stack

# Memory stack

A portion of memory can be used as a stack with a processor register as a SP.
 Figure below shows a portion of memory partitioned into 3 parts: program, data and stack.



PC: used during fetch phase to read an instruction.

AR: used during execute phase to read an operand.

SP: used to push or pop items into or from the stack.

Here, initial value of SP is 4001 and stack grows with decreasing addresses. First item is stored at 4000, second at 3999 and last address that can be used is 3000. No provisions are available for stack limit checks.

PUSH:POP:
$$SP \leftarrow SP - 1$$
 $DR \leftarrow M[SP]$  $M[SP] \leftarrow DR$  $SP \leftarrow SP + 1$ 

# 5.2 CPU Organizations/Processor Organization

There are three types of CPU organization based on the instruction format:

- 1. Single accumulator organization
- 2. General register organization
- 3. Stack Organization

### 1. Single accumulator organization:

- In this type of organization all the operations are performed with an implied accumulator register.
- Basic computer is the good example of single accumulator organization.
- The instruction of this type of organization has an address field

where X and Y is the address of the operand

### 2. General register organization:

- When a large number of processor registers are included in the CPU, it is most efficient to connect them through a common bus system. The registers communicate with each other not only for direct data transfer, but also while performing various microoperations. Hence, it is necessary to provide a common unit that can perform all the arithmetic, logic and shift microoperations in the processor.
- In this type of organization the instruction has two or three address field

### 3. Stack organization:

- Last-in, first-out (LIFO) mechanism.
- A stack is a storage device that stores information in such a manner that the item stored last is the first item retrieved.
- In this type of organization of CPU, all the operations are performed with stack.
- The PUSH and POP instruction only need address field. The operation-type instructions do not need address field.

This ADD instruction in the stack organization performs addition of two top of the stack element and stores the result in the top of the stack. First pops two operands from the top of the stack; adds them and stores the result in the top of the stack.

### **Instruction Formats**

Most common field found in register are:

- a) Mode bit: It specifies the way the operand or the effective address is determined.
- b) Op-code field: It specifies the operation to be performed.
- c) Address field: It designates a memory address or a processor register.

The number of address fields in the instruction format depends on the internal organization of CPU. On the basis of no. of address field we can categorize the instruction as below:

#### 1. Three-Address Instruction:

- Computer with three address instruction can use each address field to specify either processor register or memory operand.
- Advantage –it minimize the size of program
- Disadvantage —binary coded instruction requires too many bits to specify three address fields

### Example

```
Program to evaluate the following arithmetic statement X = (A+B) * (C+D) using three address fields instruction
```

```
ADD R1, A, B / R1 \leftarrow M[A] + M[B]
ADD R2, C, D / R2 \leftarrow M[C] + M[D]
MUL X, R1, R2 / M[X] \leftarrow R1*R2
```

#### **2.**Two-Address Instruction:

- Computer with two address instruction can use each address field to specify either processer register or memory operand
- Advantage –it minimize the size of instruction
- Disadvantage –the size of program is relatively larger

# Example

```
Program to evaluate the following arithmetic statement
X = (A+B)*(C+D) using two address field instruction
      MOV R1, A / R1 \leftarrow M[A]
      ADD R1, B / R1 - R1 + M[B]
      MOV R2, C / R2\leftarrow M[C]
      ADD R2, D / R2 \leftarrow R2 + M[D]
      MUL R1, R2 / R1←R1*R2
      MOV X, R1 /M[X] \leftarrow R1
```

#### **3.**One-Address Instruction:

- Execution of one address field instruction use an implied accumulator register for all data manipulation
- Advantage –relatively small instruction size
- Disadvantage –relatively large program size

# Example

STORE X

```
Program to evaluate the following arithmetic statement
X = (A+B)*(C+D) using one address field instruction
      LOAD A /AC \leftarrow M[A]
      ADD B /AC \leftarrow AC + M[B]
      STORE T / M[T] ← AC
      LOAD C / AC \leftarrow M[C]
                  /AC \leftarrow AC+M[D]
      ADD D
      MULT
                  /AC \leftarrow AC*M[T]
```

/ M[X] ← AC

#### **4.**Zero-Address Instruction:

- This type of instruction is used in stack organization computer. There is no address field in this type of instruction except PUSH and POP.
- Advantage –small instruction size
- Disadvantages –large the program size

# Example

Program to evaluate the following arithmetic statement X = (A+B)\*(C+D) using zero address field instruction

```
/ TOS \leftarrow M[A]
PUSH A
                   / TOS \leftarrow M[B]
PUSH B
                   / TOS \leftarrow (A+B)
ADD
                   / TOS \leftarrow M[C]
PUSH C
                   / TOS \leftarrow M[D]
PUSH D
                  / TOS \leftarrow (C+D)
ADD
                 / TOS \leftarrow (A+B)*(C+D)
MUL
                 /M[X] \leftarrow TOS
POP X
```

# X=A-B+C+(D/E)

Three Address	Two Address	One Address	Zero Address
DIV R1,D,E	MOV R1,D	LOAD D	PUSH D
ADD R2,R1,C	DIV R1,E	DIV E	PUSH E
ADD R3,R2,A	ADD R1,C	ADD C	DIV
SUB X,R3,B	ADD R1,A	ADD A	PUSH C
	SUB R1,B	SUB B	ADD
	MOV X,R1	STORE X	PUSH A
			ADD
			PUSH B
			SUB
			POP X

# Y=A+B(CD+EF-G/H)

Three address	Two address	One address	Zero address
DIV R1,G,H	MOV R1,G	LOAD G	PUSH G
MUL R2,E,F	DIV R1,H	DIV H	PUSH H
MUL R3,C,D	MOV R2,E	STORE T	DIV
ADD R4,R2,R3	MUL R2,F	LOAD E	PUSH E
SUB Y,R4,R1	MOV R3,C	MUL F	PUSH F
MUL Y,Y,B	MUL R3,D	SUB T	MUL
ADD Y,Y,A	ADD R2,R3	STORE T	SUB
	SUB R2,R1	LOAD C	PUSH C
	MUL R2,B	MUL D	PUSH D
	ADD R2,A	ADD T	MUL
	MOV Y,R2	MUL B	ADD
		ADD A	PUSH B
		STORE Y	MUL
			PUSH A
			ADD
			POP Y

# 6.3 Addressing Modes

The method of calculating or finding the effective address of the operand in the instruction is called addressing mode. The way operands (data) are chosen during program execution depends on the addressing mode of the instruction. So, addressing mode specifies a rule for interpreting or modifying the address field of the instruction before the operand is actually referenced.

#### Why Addressing modes?

- To give programming versatility to the user (by providing facilities as: pointers to memory, counters for loop control, indexing of data and program relocation)
- To use the bits in the address field of the instruction efficiently

# Types of Addressing Modes

#### The various addressing modes are:

- i. Implied Mode
- ii. Immediate Mode
- iii. Register Mode
- iv. Register Indirect Mode
- v. Auto increment or Auto decrement Mode
- vi. Direct Address Mode
- vii. Indirect Address Mode
- viii. Relative Address Mode
- ix. Indexed Addressing Mode
- x. Base Register Addressing Mode

### i. Implied Mode:

- In this type of addressing mode, operands specified implicitly in the definition of instruction.
- All the register reference instructions that use an accumulator and zero-address instruction in a stack organized computer are implied mode instruction.
- No need to specify the address in the instruction.
- E.g. CMA (complement accumulator), CLA, CME, etc.

#### ii. Immediate Mode:

- In this addressing mode, the operand is specified in the instruction itself i.e. there is no any address field to represent the operand
- Immediate mode instructions are useful for initializing register to a constant value.
- Instead of specifying the address of the operand, operand itself is specified in the instruction.

### iii. Register Mode:

- In this type of addressing mode, the operands are in the register which is within the CPU.
- Faster to acquire an operand than the memory addressing

### iv. Register Indirect Mode:

- In this addressing mode, the content of register present in the instruction specifies the effective address of operand.
- The advantage of this addressing mode is that the address field of the instruction uses fewer bits to select a register.
- EA = content of R

  AC← M[R1]

#### v. Auto Increment or Auto decrement mode:

• In auto increment mode, the content of CPU register is incremented by 1, which gives the effective address of the operand in memory.

$$AC \leftarrow M[R1], R1 \leftarrow R1 + 1$$

• In auto decrement mode, the content of CPU register is decremented by 1, which gives the effective address of the operand in memory.

$$AC \leftarrow M[R1 - 1]$$

#### vi. Direct Address Mode

In this addressing mode, the address field of an instruction gives the effective address of operand.

#### vii. Indirect Address Mode

In this addressing mode, the address field of the instruction gives the address of effective address.

#### viii. Relative Address Mode:

In this addressing mode, the content of program counter is added to the address part of the instruction which gives the effective address of the operand.

$$AC \leftarrow M[PC + ADR]$$

### ix. Indexed Addressing Mode:

In this addressing mode, the content of index register is added to the address field of the instruction which gives the effective address of operand.

$$AC \leftarrow M[ADR + XR]$$

### x. Base Register Addressing Mode:

In this addressing mode, the content of the base register is added to the address part of the instruction which gives the effective address of the operand.

 $AC \leftarrow M[ADR + BR]$ 

# Numerical Example

	Address	Memory		Addressing	Effective	Conten
PC = 200	200	Load to AC	Mode	Mode	Address	of AC
	201	Address = 50	0	Direct address	500	800
R1 = 400	202	Next instructi	on	Immediate operand	201	500
				Indirect address	800	300
				Relative address	702	325
XR = 100	_			Indexed address	600	900
	399	450		Register	horien	400
AC	400	700		Register indirect	400	700
AC	-	1.00		Autoincrement	400	700
	500	800		Autodecrement	399	450
	-		$\neg$	Fig: Content of AC after	er each addres	ssing mod
	600	900				
	702	325				
	-					

## Data Transfer and Manipulation

- Computers give extensive set of instructions to give the user the flexibility to carryout various computational tasks. The actual operations in the instruction set are not very different from one computer to another although binary encodings and symbol name (operation) may vary. So, most computer instructions can be classified into 3 categories:
- 1. Data transfer instructions
- 2. Data manipulation instructions
- 3. Program control instructions

#### **Data Transfer Instructions:**

Data transfer instructions causes transfer of data from one location to another without modifying the binary information content. The most common transfers are:

- between memory and processor registers
- between processor registers and I/O
- between processor register themselves

Example: Load, store, exchange, move, push, pop, etc

LD
ST
MOV
XCH
IN
OUT
<b>PUSH</b>
POP

Load: denotes transfer from memory to registers (usually AC)
Store: denotes transfer from a processor registers into memory
Move: denotes transfer between registers, between memory
words or memory & registers.

Exchange: swaps information between two registers or register and a memory word.

Input & Output: transfer data among registers and I/O terminals.

Push & Pop: transfer data among registers and memory stack.

• Instructions described above are often associated with the variety of addressing modes. Assembly language uses special character to designate the addressing mode. E.g. # sign placed before the operand to recognize the immediate mode. (Some other assembly languages modify the mnemonics symbol to denote various addressing modes, e.g. for load immediate: LDI). Example: consider load to accumulator instruction when used with 8 different addressing modes:

Mode	Assembly Convention	Register Transfer
Direct address	LD ADR	$AC \leftarrow M[ADR]$
Indirect address	LD @ADR	$AC \leftarrow M[M[ADR]]$
Relative address	LD SADR	$AC \leftarrow M[PC + ADR]$
Immediate operand	LD #NBR	$AC \leftarrow NBR$
Index addressing	LD ADR(X)	$AC \leftarrow M[ADR + XR]$
Register	LD R1	$AC \leftarrow R1$
Register indirect	LD (R1)	$AC \leftarrow M[R1]$
Autoincrement	LD (R1)+	$AC \leftarrow M[R1], R1 \leftarrow R1 + 1$

Table: Recommended assembly language conventions for load instruction in different addressing modes

### **Data manipulation Instructions:**

Data manipulation Instructions perform operations on data and provide the computational capabilities for the computer. These instructions perform arithmetic, logic and shift operations.

Example: increment, decrement, add, subtract, add with carry, subtract with borrow, 2's complement.

### **Arithmetic instructions:**

• Typical arithmetic instructions are listed below:

Name	Mnemonic		
Increment	INC	• Incremen	t (decrement) instr. adds 1 to
Decrement	DEC		s 1 from) the register or memory
Add	ADD	word valu	[[[[[[[] [[] [[] [[] [[] [[] [[] [[] [[
Subtract	SUB	Add, su	btract, multiply and divide
Multiply	MUL	instructio	ons may operate on different
Divide	DIV	data type	s (fixed-point or floating-point,
Add with carry	ADDC	binary or	decimal).
Subtract with borrow	SUBB		
Negate (2's complement)	NEG		

### Logical and bit manipulation instructions:

• Logical instructions perform binary operations on strings of bits stored in registers and are useful for manipulating individual or group of bits representing binary coded information. Logical instructions each bit of the operand separately and treat it as a Boolean variable

Name	Mnemonic	
Clear	CLR	
Complement	COM	Clear instr. causes specified operand to be
AND	AND	replaced by 0's.
OR	OR	Complement instr. produces the 1's
Exclusive-OR	XOR	complement.
Clear carry	CLRC	AND, OR and XOR instructions produce
Set carry	SETC	the corresponding logical operations on
Complement carry	COMC	individual bits of the operands.
Enable interrupt	EI	
Disable interrupt	DI	

Er. Rolisha Sthapit

### **Shift instructions**

 Instructions to shift the content of an operand are quite useful and are often provided in several variations (bit shifted at the end of word determine the variation of shift). Shift instructions may specify 3 different shifts:

□ Logical shifts

☐ Arithmetic shifts

☐ Rotate-type operations

Name	Mnemonic	
Logical shift right	SHR	
Logical shift left	SHL	
Arithmetic shift right	SHRA	
Arithmetic shift left	SHLA	
Rotate right	ROR	
Rotate left	ROL	
Rotate right through carry	RORC	
Rotate left through carry	ROLC	

- Table lists 4 types of shift instructions.
- Logical shift inserts 0 at the end position
- Arithmetic shift left inserts 0 at the end (identical to logical left shift) and arithmetic shift right leave the sign bit unchanged (should preserve the sign).
- Rotate instructions produce a circular shift.
- Rotate left through carry instruction transfers carry bit to right and so is for rotate shift right.

## 5.3 RISC and CISC characteristics

#### RISC (reduced instruction set computer) characteristics

- > Relatively few instructions
- > Relatively few addressing modes
- ➤ Memory access limited to load and store instructions
- > All operations done within the registers of the CPU
- Fixed-length, easily decoded instruction format
- Single-cycle instruction execution
- > The control unit is hardwired rather than micro programmed
- > Relatively large number of registers in the processor unit
- > Efficient instruction pipeline

The main concept of RISC is to reduce execution time by simplifying the instruction set of the computer. Example: MIPS(Microprocessor without Interlocked Pipeline Stages), ARM (Advanced RISC Machine)

### CISC (complex instruction set computer) characteristics

- >A large number of instructions typically from 100 to 250 instructions
- ➤ Some instructions that perform specialized tasks and are used infrequently
- ➤ A large variety of addressing modes typically from 5 to 20 different modes
- ➤ Variable-length instruction format
- >Uses memory to load and store instruction and operand as well
- >Instructions that manipulate operands in memory

### Principle of CISC:

To provide single machine instruction for each statement that is written in a higher level language. One reason to provide a complex instruction set is to simplify the compilation and improve the overall computer performance.

Example: IBM computer, desktop computer, Digital equipment corporation.

Assignment: Write any 8 differences between RISC and CISC.

### Reverse Polish Notation

A+B – Infix Notation

+AB – Prefix or Polish Notation

AB+ - Postfix or Reverse Polish Notation

### **Infix Notation:**

the notation where the operator is in between the operands.

#### **Prefix Notation:**

the notation where the operator lies before the operand.

### **Postfix Notation:**

the notation where the operator lies after the operand.

### • Example:

$$(A+B)*[C*(D+E)+F]$$

## Program control instructions

 Instructions are always stored in successive memory locations and are executed accordingly. But sometimes it is necessary to condition the data processing instructions which change the PC value accidently causing a break in the instruction execution and branching to different program segments.

Name Branch Jump Skip Call Return Compare (by subtraction)	Mnemonic BR JMP SKP CALL RET CMP	<ul> <li>Branch (usually one address instruction) and jump instructions can be changed interchangeably.</li> <li>Skip is zero address instruction and may be conditional &amp; unconditional.</li> <li>Call and return instructions are used in conjunction with subroutine calls.</li> </ul>	
Test (by ANDing)	TST	Conjunction with subroutine cans.	

It is sometimes convenient to supplement the ALU circuit in the CPU with a status register where status bit conditions can be stored for further analysis. Status bits are also called condition-code bits or flag bits. Figure 8-8 shows the block diagram of an 8-bit ALU with a 4-bit status register. The four status bits are symbolized by C, S, Z, and V. The bits are set or cleared as a result of an operation performed in the ALU.

- 1. Bit C (carry) is set to 1 if the end carry C<sub>8</sub> is 1. It is cleared to 0 if the carry is 0.
- **2.** Bit S (sign) is set to 1 if the highest-order bit  $F_7$  is 1. It is set to 0 if the bit is 0.
- 3. Bit Z (zero) is set to 1 if the output of the ALU contains all 0's. It is cleared to 0 otherwise. In other words, Z = 1 if the output is zero and Z = 0 if the output is not zero.
- 4. Bit V (overflow) is set to 1 if the exclusive-OR of the last two carries is equal to 1, and cleared to 0 otherwise. This is the condition for an overflow when negative numbers are in 2's complement. For the 8-bit ALU, V = 1 if the output is greater than +127 or less than -128.




Figure 8-8 Status register bits.

TABLE 8-11 Conditional Branch Instructions

Mnemonic	Branch condition	Tested condition	
BZ	Branch if zero	Z = 1	
BNZ	Branch if not zero	Z = 0	
BC	Branch if carry	C = 1	
BNC	Branch if no carry	C = 0	
BP	Branch if plus	s = 0	
BM	Branch if minus	S = 1	
BV	Branch if overflow	$\nu = 1$	
BNV	Branch if no overflow	V = 0	
Unsigned	d compare conditions $(A - B)$		
BHI	Branch if higher	A > B	
BHE	Branch if higher or equal	$A \geq B$	
BLO	Branch if lower	A < B	
BLOE	Branch if lower or equal	$A \leq B$	
BE	Branch if equal	A = B	
BNE	Branch if not equal	$A \neq B$	
Signed o	compare conditions $(A - B)$		
BGT	Branch if greater than	A > B	
BGE	Branch if greater or equal	$A \geq B$	
BLT	Branch if less than	A < B	
BLE	Branch if less or equal	$A \leq B$	
BE	Branch if equal	A = B	
BNE	Branch if not equal	$A \neq B$	

## Subroutine Call and Return

A subroutine is a self-contained sequence of instructions that performs a given computational task. During the execution of a program, a subroutine may be called to perform its function many times at various points in the main program. Each time a subroutine is called, a branch is executed to the beginning of the subroutine to start executing its set of instructions. After the subroutine has been executed, a branch is made back to the main program.

A call subroutine instruction consists of an operation code together with an address that specifies the beginning of the subroutine. The instruction is executed by performing two operations: (1) the address of the next instruction available in the program counter (the return address) is stored in a temporary location so the subroutine knows where to return, and (2) control is transferred to the beginning of the subroutine. The last instruction of every subroutine, commonly called return from subroutine, transfers the return address from the temporary location into the program counter. This results in a transfer of program control to the instruction whose address was originally stored in the temporary location.

Different computers use a different temporary location for storing the return address. Some store the return address in the first memory location of the subroutine, some store it in a fixed location in memory, some store it in a processor register, and some store it in a memory stack. The most efficient way is to store the return address in a memory stack. The advantage of using a stack for the return address is that when a succession of subroutines is called, the sequential return addresses can be pushed into the stack. The return from

subroutine instruction causes the stack to pop and the contents of the top of the stack are transferred to the program counter. In this way, the return is always to the program that last called a subroutine. A subroutine call is implemented with the following microoperations:

 $SP \leftarrow SP - 1$  Decrement stack pointer

 $M[SP] \leftarrow PC$  Push content of PC onto the stack

 $PC \leftarrow$  effective address Transfer control to the subroutine

If another subroutine is called by the current subroutine, the new return address is pushed into the stack, and so on. The instruction that returns from the last subroutine is implemented by the microoperations:

 $PC \leftarrow M[SP]$  Pop stack and transfer to PC

 $SP \leftarrow SP + 1$  Increment stack pointer

## Program Interrupt

- The concept of program interrupt is to handle a variety of problems that arise out of normal program sequence.
- Program interrupt refers to the transfer of program control from a currently running program to another service program as a result of an external or internal generated request. Control returns to the original program after the service program is executed.
- After a program has been interrupted and the service routine has been executed, the CPU must return to exactly the same state that it was when the interrupt occurred.

- The state of the CPU at the end of the execute cycle ( when the interrupt is recognised) is determined from:
  - 1. The content of program counter
  - 2. The content of all processor registers
  - 3. The content of certain status conditions

The collection of all status bit conditions in the CPU is sometimes called a *program status word* or PSW. The PSW is stored in a separate hardware register and contains the status information that characterizes the state of the CPU.

## Types of Interrupt

There are three major types of interrupts that cause a break in the normal execution of a program. They can be classified as:

- 1. External interrupts
- 2. Internal interrupts
- 3. Software interrupts

## 1. External Interrupt

External interrupts come from input-output (I/O) devices, from a timing device, from a circuit monitoring the power supply, or from any other external source. Examples that cause external interrupts are I/O device requesting transfer of data, I/O device finished transfer of data, elapsed time of an event, or power failure. Timeout interrupt may result from a program that is in an endless loop and thus exceeded its time allocation. Power failure interrupt may have as its service routine a program that transfers the complete state of the CPU into a nondestructive memory in the few milliseconds before power ceases.

## 2. Internal Interrupt

Internal interrupts arise from illegal or erroneous use of an instruction or data. Internal interrupts are also called *traps*. Examples of interrupts caused by internal error conditions are register overflow, attempt to divide by zero, an invalid operation code, stack overflow, and protection violation. These error conditions usually occur as a result of a premature termination of the instruction execution. The service program that processes the internal interrupt determines the corrective measure to be taken.

## 3. Software Interrupt


A software interrupt is initiated by executing an instruction. Software interrupt is a special call instruction that behaves like an interrupt rather than a subroutine call. It can be used by the programmer to initiate an interrupt procedure at any desired point in the program. The most common use of software interrupt is associated with a supervisor call instruction. This instruction provides means for switching from a CPU user mode to the supervisor mode. Certain operations in the computer may be assigned to the supervisor mode only, as for example, a complex input or output transfer procedure. A program written by a user must run in the user mode. When an input or output transfer is required, the supervisor mode is requested by means of a supervisor call instruction. This instruction causes a software interrupt that stores the old CPU state and brings in a new PSW that belongs to the supervisor mode. The calling program must pass information to the operating system in order to specify the particular task requested.

The difference between internal and external interrupts is that the internal interrupt is initiated by some exceptional condition caused by the program itself rather than by an external event. Internal interrupts are synchronous with

the program while external interrupts are asynchronous. If the program is rerun, the internal interrupts will occur in the same place each time. External interrupts depend on external conditions that are independent of the program being executed at the time.

## Overlapped Register Windows

- Procedure call and return occurs quite often in high-level programming languages.
- When translated into machine language, procedure call produces a sequence of instructions that save register values, pass parameters needed for the procedure and then calls a subroutine to execute the body of the procedure.
- After a procedure return, the program restores the old register values, passes results to the calling program and returns from the subroutine. Saving & restoring registers and passing of parameters & results involve time consuming operations.
- A characteristic of some RISC processors is use of overlapped register windows to provide the passing of parameters and avoid need for saving & restoring register values. The concept of overlapped register windows is illustrated below:



There are three classes of registers:

– Global Registers:

Available to all functions

Window local registers:

Variables local to the function

– Window shared registers:

Permit data to be shared without actually needing to copy it

Only one register window is active at a time. The active register window is indicated by a pointer. When a function is called, a new register window is activated. This is done by incrementing the pointer. When a function calls a new function, the high numbered registers of the calling function window are shared with the called function as the low numbered registers in its register window. This way the caller's high and the called function's low registers overlap and can be used to pass parameters and results

The advantage of overlapped register windows is that the processor does not have to push registers on a stack to save values and to pass parameters when there is a function call.

#### This saves:

- Accesses to memory to access the stack.
- The cost of copying the register contents at all

And, since function calls and returns are so common, this results in a significant savings relative to a stack-based approach

## Description of Diagram

System has a total of 74 registers (Just an example)

- R0 R9 = global registers (hold parameters shared by all procedures)
- Other 64 registers are divided into 4 windows to accommodate procedures A, B, C and D.
- Each register window consists of 10 local registers and two sets of 6 registers common to adjacent windows.
- Common overlapped registers permit parameters to be passed without the actual movement of data
- Only one register window is activated at any time with a pointer indicating the active window.
- Four windows have a circular organization with A being adjacent to D.

### Example: Procedure A calls B

- Registers R26 to R31 are common to both procedures and therefore procedure A stores the parameters for procedure B in these registers.
- B uses local registers R32 through R41 for local variable storage.
- When B is ready to return at the end of its computation, programs stores results in registers R26-R31 and transfers back to the register window of procedure A.

In general, the organization of register windows will have following relationships:

Number of global registers = G

Number of local register in each window = L

Number of registers common to windows = C

Number of windows = W

Now,

Window size = L + 2C + G

Register file = (L+C)W + G (total number of register needed in the processor)

Example: In above fig, G = 10, L = 10, C = 6 and W = 4. Thus window size = 10+12+10 = 32 registers and register file consists of (10+6)\*4+10 = 74 registers.

A two-word instruction is stored in memory at an address designated by the 8-14. symbol W. The address field of the instruction (stored at W + 1) is designing nated by the symbol Y. The operand used during the execution of the instruction is stored at an address symbolized by Z. An index register contains the value X. State how Z is calculated from the other addresses if the addressing mode of the instruction is

- a. direct
- b. indirect
- c. relative
- d. indexed


Z = Effective address

(a) Direct:

(b) Indirect: Z = M[Y] (c) Relative: Z = Y + W + 2

Z = Y

(d) Indexed: Z = Y + X




8-18. An instruction is stored at location 300 with its address field at location 301. The address field has the value 400. A processor register R1 contains the number 200. Evaluate the effective address if the addressing mode of the

instruction is (a) direct; (b) immediate; (c) relative; (d) register indirect; (e) index with R1 as the index register.

#### Effective address

- (a) Direct: 400
- (b) Immediate: 301
- (c) Relative: 302 + 400 = 702
- (d) Reg. Indirect: 200
- (e) Indexed: 200 + 400 = 600



Consider the following figure:

PC = 300

R1 = 500

What is the value in AC if the instruction is


LDA 300 if the modes are:

- Direct addressing
- ii. immediate
- iii. Indirect addressing
- Indirect addressing 200
  Register indirect if LDA (R1) is used 100 iv.

Address	Memory	
300	450	
450	200	
500	100	1

14.

Consider the following memory and the instruction LDA 250:



R (250)

PC 325

Write the value loaded into AC when the addressing mode is

- Indirect b) Register Indirect
- c) Immediate
- d) Direct

**Solution:** 

a) Indirect: 432

b)Register Indirect: 511

c) Immediate: 250

d) Direct: 511

#### CISC and RISC architecture Microcontrollers:

CISC Processors	RISC Processors	
Complex Instruction Set Computer	Reduced Instruction Set Computer	
When an MCU supports many addressing modes for arithmetic and logical instructions and for memory accesses and data transfer instructions, the MCU is said to of CISC architecture.	When an MCU has an instruction set that supports one or two addressing modes for arithmetic and logical instructions and few for memory accesses and data transfer instructions, the MCU is said to of RISC architecture	
Large number of complex instructions	Small number of instructions	
Instructions are of variable number of bytes	Instructions are of fixed number of bytes	
Instructions take varying amounts of time for execution	Instructions take fixed amount of time for execution	